



# CHAPTER 13

## Managing Reports

---

At scheduled intervals, you can configure the Cisco Mobile Wireless Transport Manager (MWTM) to gather critical information from network objects that it detects. The MWTM uses that information to calculate statistics (accounting statistics, performance statistics, and so on) and generates reports based on those statistics.

You can view reports in several ways:

- From the MWTM web navigation tree, in **Reports** or **File Archive**, click the type of report you want to view in the web navigation tree; for example, if you want to view current link reports, select **Reports > ITP Statistics > Link**. All link reports appear. See [Displaying Status and Summary Reports, page 11-21](#) for more information about accessing reports from the web interface.
- For a single object of a specified type do one of the following. From the MWTM:
  - Web navigation tree, in **DEFAULT View**, click a node select an object in a node. In the content area in the right pane, click the **Reports** tab. Reports appear for the active object only.
  - Client, right-click an object and click **Latest Reports**. The Reports tab in the MWTM web interface opens for the active object only.

This chapter contains:

- [Using the Reports Page, page 13-1](#)
- [Enabling Automatic Reports Using the CLI, page 13-2](#)
- [Viewing Reports, page 13-4](#)
- [Viewing Graph Series Editor Details, page 13-397](#)
- [Locating Stored Reports, page 13-399](#)
- [Customizing ITP Reports, page 13-400](#)
- [Generating Custom ITP Statistics Reports Using the CLI, page 13-400](#)

## Using the Reports Page

To access the main Reports page:

---

**Step 1** Do one of the following:

- In a web browser, launch the MWTM web interface (see [Accessing the MWTM Web Interface, page 11-2](#)). In the navigation tree, click **Reports**.

- From the MWTM client, in the MWTM main window, choose **View > MWTM Web Links > Reports**.

The Reports page in the content area shows the Report Type and the status (enabled or disabled). If you have generated a report, a green status ball and the word “Enabled” appear in the Status column. If you have not generated a report, a red status ball and the word “Disabled” appears.



**Note** Clicking a Report Type takes you directly to the report data page.

The Status column indicates whether you have enabled or disabled data gathering for the specified report type.

- Step 2** To enable a report in the MWTM Web interface, click “Disabled” in the Status column. The Status changes “Enabled” and a green status ball appears.

## Enabling Automatic Reports Using the CLI

Using CLI commands, there are two types of reports that you can generate:

- Continuous reports that run at specified intervals. You enable automatic generation of these reports with the **mwtm statreps** commands (see [Generating Custom ITP Statistics Reports Using the CLI, page 13-400](#)). After you enable generation of a continuous report, it will run at the specified intervals until you disable it with the appropriate CLI command.
- Custom ITP reports that you create one-time on demand. You generate these reports with the **mwtm abcstats** commands where *abc* is the type of command (see [Generating Custom ITP Statistics Reports Using the CLI, page 13-400](#)). They run at custom intervals or on demand at the specified times. Custom reports are *custom* because you can specify that they run at custom time intervals. The content of custom ITP reports is the same as the regularly scheduled reports. This option is only available for ITP reports listed in [Table 13-1](#).

Enabling continuous reports using the CLI is the same as enabling and disabling reports from the Reports page.

To enable continuous reports using the CLI:

- Step 1** Log in as the root user, as described in [Starting the MWTM Client, page 3-3](#), or as a superuser, as described in [Specifying a Super User \(Server Only\), page 2-21](#).

- Step 2** Enter:

```
cd /opt/CSCOsgrm/bin
```

- Step 3** Enter the following CLI command to enable all report types:

```
./mwtm statreps all
```

You can enable and disable specific reports using specific CLI commands. For example, to generate continuous GTT statistics, enter:

```
./mwtm statreps gtt
```

To see a list of all report-related CLI commands, enter the following command:

```
./mwtm rephelp
```

To determine which CLI command generates which report, see [Generating Custom ITP Statistics Reports Using the CLI, page 13-400](#).

- Step 4** (Optional) View the generated report in the MWTM web interface by clicking **Reports** in the navigation pane as described in [Viewing Reports, page 13-4](#).



**Note**

After you issue the CLI to generate a continuous report, the report is not immediately available for viewing. It takes approximately two times the report interval before the report is available.

## Customized Report Disabling

Using the below steps you can individually disable the reports:

- Step 1** Copy ReportsDisableMaster.conf file into ReportDisable.conf file. The ReportsDisableMaster.conf file exists in the report directory. By default, this file will be available in */CSCOs/gm/reports/etc* directory. The ReportsDisable.conf file is used to disable individual reports.

- Step 2** Remove the # sign from the line in the report to be disabled. The syntax is report name followed by the colon(:) symbol followed by 0 or 1. 0 represents report to be disabled and 1 represents report to be enabled.



**Note**

The report name will have a value that map to the individual report names as listed in the README-ExportFiles.txt file.

- Step 3** Now, restart the server. It may take an hour for the reports to get disabled.

## Customized Report Aging

Using the below steps you can mention the number of days a specific report has to be retained in the report folders:

- Step 1** Copy ReportsAgingMaster.conf file into ReportsAging.conf file. The ReportsAgingMaster.conf file exists in the report directory. By default, this file will be available in */CSCOs/gm/reports/etc* directory. The ReportsAging.conf file is used to age the individual reports.

- Step 2** Remove the # sign from the line to enable a report.

The syntax is *<report name>:<DBTableName>:<export report folder>:<Aging Value>*. For example, *AaaAccounting:DBTableName:export15min:3*. The Aging value can be changed to customize the value.

**Note**

The `<DBTableName>` is not currently used but may be used in the future. The `<Aging Value>` mentions the number of days for which a specific report has to be restored in `<export report folder>` (export15min, exporthourly, exportdaily or exportmonthly).

## Viewing Reports

After you generate reports, you can view them using the MWTM web interface. You can view historical reports for all objects of a specific type (for example, all link reports for all links) or, you can view reports for a specific object (for example, all link reports for a specific link).

**Note**

For the reports having output type as Graph, the Graph Series Editor window is displayed when you click the Custom series icon. See [Viewing Graph Series Editor Details, page 13-397](#).

**Note**

For the reports having output type as Graph, the Sort Parameter option is available to select the criteria for including a top set of series and for ordering of the corresponding graphs displayed.




You can access reports in the MWTM web interface through these categories:

Category	Report Type	Related Content
Reports> Dashboards	CPU/Memory	<a href="#">CPU / Memory Reports, page 13-8</a>
	Interface	<a href="#">Interface Reports, page 13-8</a>
Reports > Common Statistics	AAA	<a href="#">AAA Reports, page 13-10</a>
	CPU	<a href="#">CPU Reports, page 13-13</a>
	IP Local Pool	<a href="#">IP Local Pool Reports, page 13-18</a>
	Interface	<a href="#">Interface Reports, page 13-21</a>
	Memory	<a href="#">Memory Reports, page 13-40</a>
Reports > ITP Statistics	AS	<a href="#">AS Reports, page 13-46</a>
	ASP	<a href="#">ASP Reports, page 13-53</a>
	GTT Rates	<a href="#">GTT Rates Reports, page 13-66</a>
	Link	<a href="#">Link Reports, page 13-70</a>
	Link Multi-Day	<a href="#">Link Multi-Day Report, page 13-80</a>
	Linkset	<a href="#">Linkset Reports, page 13-81</a>
	MLR	<a href="#">MLR Reports, page 13-91</a>
	MSU Rates	<a href="#">MSU Rates Reports, page 13-96</a>
	SCTP	<a href="#">SCTP Reports, page 13-100</a>

Category	Report Type	Related Content
Reports > Mobile Statistics	CSG	<a href="#">CSG Reports, page 13-104</a>
	GGSN	<a href="#">GGSN Reports, page 13-129</a>
	PDNGW	<a href="#">PDNGW Reports, page 13-160</a>
	PDSN	<a href="#">PDSN Reports, page 13-190</a>
	SGW	<a href="#">SGW Reports, page 13-203</a>
	SPGW	<a href="#">SPGW Reports, page 13-226</a>
Reports > RAN Statistics	PWE3	<a href="#">PWE3 Reports, page 13-278</a>
	QOS	<a href="#">QOS Reports, page 13-284</a>
	RAN-Optimized	<a href="#">RAN-Optimized Reports, page 13-290</a>
Reports > ITP Accounting	AS	<a href="#">AS Accounting Reports, page 13-304</a>
	GTT	<a href="#">GTT Accounting Reports, page 13-305</a>
	MTP3	<a href="#">MTP3 Accounting Reports, page 13-306</a>
Reports > Mobile Subscribers	BWG	<a href="#">BWG Subscribers Reports, page 13-308</a>
	CSG	<a href="#">CSG Subscribers Reports, page 13-309</a>
	GGSN	<a href="#">GGSN Subscribers Reports, page 13-315</a>
	HA	<a href="#">HA Subscribers Reports, page 13-317</a>
	PDNGW	<a href="#">PDNGW Subscribers Reports, page 13-318</a>
	PDSN	<a href="#">PDSN Subscribers Reports, page 13-324</a>
	SGW	<a href="#">SGW Subscribers Reports, page 13-326</a>
	SPGW	<a href="#">SPGW Subscribers Reports, page 13-332</a>
File Archive > Events	Events	You can find information on archived event reports in the “Managing Events” chapter (see <a href="#">Viewing Archived Event Files on the Web, page 9-24</a> ).
File Archive > Inventory	Chassis	<a href="#">Chassis Inventory Archived Reports, page 13-339</a>
	Element	<a href="#">Element Inventory Archived Reports, page 13-339</a>
File Archive > Common Statistics	AAA	<a href="#">AAA Archived Reports, page 13-340</a>
	CPU	<a href="#">CPU Archived Reports, page 13-342</a>
	IP Local Pool	<a href="#">IP Local Pool Archived Reports, page 13-343</a>
	Interface	<a href="#">Interface Archived Reports, page 13-344</a>
	Memory	<a href="#">Memory Archived Reports, page 13-345</a>

Category	Report Type	Related Content
File Archive > ITP Statistics	Custom	<a href="#">Custom Archived Reports, page 13-348</a>
	Rolling	<a href="#">Rolling Archived Reports, page 13-350</a>
	AS	<a href="#">Application Server Archived Reports, page 13-351</a>
	ASP	<a href="#">Application Server Process Archived Reports, page 13-352</a>
	GTT Rates	<a href="#">GTT Rates Archived Reports, page 13-353</a>
	Link	<a href="#">Link Archived Reports, page 13-353</a>
	Linkset	<a href="#">Linkset Archived Reports, page 13-354</a>
	MLR	<a href="#">MLR Archived Reports, page 13-355</a>
	MSU	<a href="#">MSU Archived Reports, page 13-356</a>
	MTP3/AS Events	<a href="#">MTP3/AS Events Archived Reports, page 13-357</a>
	Point Code	<a href="#">Point Code Archived Reports, page 13-358</a>
	Q752	<a href="#">Q752 Archived Reports, page 13-359</a>
	SCTP	<a href="#">SCTP Archived Reports, page 13-360</a>
File Archive > Mobile Statistics	CSG	<a href="#">CSG Archived Reports, page 13-361</a>
	GGSN	<a href="#">GGSN Archived Reports, page 13-363</a>
	HA	<a href="#">HA Archived Reports, page 13-365</a>
	PDNGW	<a href="#">PDNGW Archived Reports, page 13-366</a>
	PDSN	<a href="#">PDSN Archived Reports, page 13-369</a>
	SGW	<a href="#">SGW Archived Reports, page 13-370</a>
	SPGW	<a href="#">SPGW Archived Reports, page 13-373</a>
	SLB	<a href="#">SLB Archived Reports, page 13-372</a>
File Archive > RAN Statistics	Ethernet	<a href="#">Ethernet Archived Reports, page 13-378</a>
	PWE3	<a href="#">PWE3 Archived Reports, page 13-378</a>
	QOS	<a href="#">QOS Archived Reports, page 13-379</a>
	RAN-Optimized	<a href="#">RAN-Optimized Archived Reports, page 13-380</a>
File Archive > ITP Accounting	GTT Accounting	<a href="#">GTT Accounting Archived Reports, page 13-382</a>
	MTP3/AS Acct	<a href="#">MTP3/AS Accounting Archived Reports, page 13-383</a>
File Archive > Mobile Subscribers	BWG	<a href="#">BWG Subscriber Statistics Archived Reports, page 13-384</a>
	CSG	<a href="#">CSG Subscriber Statistics Archived Reports, page 13-385</a>
	GGSN	<a href="#">GGSN Subscriber Statistics Archived Reports, page 13-386</a>
	HA	<a href="#">HA Subscriber Statistics Archived Reports, page 13-387</a>
	PDNGW	<a href="#">PDNGW Subscriber Statistics Archived Reports, page 13-388</a>
	PDSN	<a href="#">PDSN Subscriber Statistics Archived Reports, page 13-389</a>
	SGW	<a href="#">SGW Subscriber Statistics Archived Reports, page 13-390</a>
	SPGW	<a href="#">SPGW Subscriber Statistics Archived Reports, page 13-391</a>
File Archive > PCRF	Host	<a href="#">Host Resources Statistics Reports, page 13-392</a>

To view a Web report:

- 
- Step 1** For all objects of a specified type:
- From the MWTM web navigation tree, in **Reports** or **File Archive**, click the type of report you want to view in the web navigation tree; for example, if you want to view current link reports, select **Reports > ITP Statistics > Link**. All link reports appear.
- For a single object of a specified type do one of the following. From the MWTM:
- Web navigation tree, in **DEFAULT View**, click a node to select an object in a node. In the content area in the right pane, click the **Reports** tab. Reports appear for the active object only.
  - Client, right-click an object and click **Latest Reports**. The Reports tab in the MWTM web interface opens for the active object only.
- Step 2** Choose the **Type** and **Duration** from the drop-down lists; for example, if you wanted to view hourly link reports for the last 12 hours, choose **Link Hourly** from the Type list and **Last 12 Hours** from the Duration list.
- Step 3** (Optional) For most Statistics and Accounting reports, to customize the date or time range (or both) click the Customize the date and time range icon. . Note that these dates are the dates with server time zone.
- Step 4** Click the green arrow to run the report. If you change the Type or Duration, an information message appears:
- Click the green arrow to show the selected report.
- Step 5** To disable this error message, click **Hide Message**. To display the message again, click the **Information** icon. 
- Step 6** (Optional) For Statistics and Accounting reports, to export the report as a .csv file, click the **Export** icon. 



**Note** For information about all File Archive export reports in *csv.zip* format, refer to the MWTM readme file by clicking **Administrative** on the navigation pane, then under System Information, click **Export Reports README**. The readme contains documentation on every field in each export report, description of the report fields, and in most cases, the SNMP MIB variables used to generate the field values.

---



**Note** To navigate to the Details tab for an object, click the underlined object in the report; for example, to go to the Details tab for a node, click the underlined node in the reports table.

---



**Tip** For details on web toolbars and icons, see [Using the Toolbar, page 11-6](#).

---

## Viewing Dashboard Reports


Dashboard Reports are located within **Reports > Dashboards** in the MWTM web interface. You can also find archived reports in the `/opt/CSCOs/gm/reports` directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in .csv format.

You can view any of the following Dashboard reports:

- [CPU / Memory Reports, page 13-8](#)
- [Interface Reports, page 13-8](#)

### CPU / Memory Reports

The MWTM interface provides **CPU Average/Peak Utilization Summary and Memory Average/Peak Utilization summary** report of nodes over a duration. To generate a CPU Average/CPU Peak/Memory Average/Memory Peak Utilization Daily reports:

- 
- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Dashboards > CPU/Memory**.
- Step 2** In the tool bar of the right pane, choose a report type from the **Type** drop-down menu.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.

The CPU/Memory reports display the following summary table with the hide and show link options to view the specific report type you have selected:


- **CPU Average Utilization Summary:** Displays the average ten CPU values gathered during the specified period. This report is similar to the [CPU Average Utilization Daily Reports, page 13-16](#), except that it displays the output data in a table format without the graph output.
  - **CPU Peak Utilization Summary:** Displays the ten CPU values with the maximum CPU utilization over the specified time period. This report is similar to the [CPU Peak Utilization Daily Reports, page 13-14](#), except that it displays the output data in a table format without the graph output.
  - **Memory Average Utilization Summary:** Displays the ten average memory values gathered during the specified period. This report is similar to the [Memory Average Utilization Daily Reports, page 13-43](#), except that it displays the output data in a table format without the graph output.
  - **Memory Peak Utilization Summary:** Displays the ten CPU values with the highest memory utilization over the specified time period. This report is similar to the [Memory Peak Utilization Daily Reports, page 13-41](#), except that it displays the output data in a table format without the graph output.
- 

### Interface Reports

The MWTM web interface provides a dashboard of interface reports. To generate Interface Dashboard reports:

- 
- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Dashboards > Interface**.



- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.).

The Type drop-down menu contains the following reports:

- [Interface Utilization/Errors Percentage Daily, page 13-9](#)
- [Interface Utilization/Discards Percentage Daily, page 13-9](#)
- [Interface Errors/Discards Percentage Daily, page 13-9](#)
- [Interface Broadcast/Multicast Packets Percentage Daily, page 13-9](#)
- [Interface Total Packets / Errors-Discards Daily, page 13-10](#)

### Interface Utilization/Errors Percentage Daily

MWTM displays the summary tables of Interface Utilization / Errors Percentage Daily reports during a specified period in a single page with the hide and show options to display a specific report. This report is similar to the [Interface Utilization Daily Reports, page 13-21](#) and [Interface Errors Percentage Daily Reports, page 13-38](#), except that it displays the output data in a table format without the graph output.

The Interface Utilization/Errors Percentage Daily report type display a set of Send/Receive Interface Utilization Percentage Summary and Send/Receive Interface Errors Percentage Summary values.

### Interface Utilization/Discards Percentage Daily

MWTM display the summary tables of Interface Utilization / Discards Percentage Daily reports during a specified period in a single page with the hide and show options to display a specific report. This report is similar to the [Interface Utilization Daily Reports, page 13-21](#) and [Interface Discards Percentage Daily Reports, page 13-35](#), except that it displays the output data in a table format without the graph output.

The Interface Utilization/Discards Percentage Daily report type display a set of Send/Receive Interface Utilization Percentage Summary and Send/Receive Interface Discards Percentage Summary values.

### Interface Errors/Discards Percentage Daily

MWTM display the summary tables of Interface Errors / Discards Percentage Daily reports during a specified period in a single page with the hide and show options to display a specific report. This report is similar to the [Interface Errors/Discards Daily Report, page 13-26](#) except that it displays the output data in a table format without the graph output.

The Interface Errors/Discards Percentage Daily report type display a set of Send/Receive Interface Errors Percentage Summary and Send/Receive Interface Discards Percentage Summary values.

### Interface Broadcast/Multicast Packets Percentage Daily

MWTM display the summary tables of Interface Broadcast / Multicast Packets Percentage Daily reports during a specified period in a single page with the hide and show options to display a specific report. This report is similar to the [Interface Broadcast Packets Percentage Daily Reports, page 13-29](#) and [Interface Multicast Packets Percentage Daily Reports, page 13-30](#) except that it displays the output data in a table format without the graph output.

The Interface Broadcast/Multicast Packets Percentage Daily report type display a set of Send/Receive Interface Broadcast Packets Percentage Summary and Send/Receive Interface Multicast Packets Percentage Summary values.

### Interface Total Packets / Errors-Discards Daily

MWTM displays the Interface Total Packets / Errors-Discards Daily during a specified period at node level in a single summary table. This report is similar to the [Interface Total Packets Daily Reports, page 13-23](#) and [Interface Errors/Discards Daily Report, page 13-26](#) except that it displays the output data in a table format without the graph output.

The Interface Total Packets / Errors-Discards Daily report type display a set of Send/Receive Interface Total Packets Summary and Send/Receive Interface Errors Discards Summary values.

## Viewing Common Statistics Reports



Common Statistics Reports are located within **Reports > Common Statistics** in the MWTM web interface. You can also find archived reports in the `/opt/CSCOsgm/reports` directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in .csv format.

You can view any of the following Common statistics reports:

- [AAA Reports, page 13-10](#)
- [CPU Reports, page 13-13](#)
- [Interface Reports, page 13-21](#)
- [Memory Reports, page 13-40](#)

### AAA Reports

The MWTM web interface provides node-level and network wide AAA reports for monitoring communications and status of AAA Server operation. To generate a network wide AAA reports:

- 
- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > AAA**.
  - Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
  - Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
  - Step 4** Choose an output format (Table or CSV) from the Output drop-down menu for contents of each output type.
  - Step 5** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [AAA Accounting Statistics Daily Report, page 13-11](#)
  - [AAA Authentication Statistics Daily Report, page 13-11](#)
-

### AAA Accounting Statistics Daily Report

MWTM displays the AAA accounting statistics daily report obtained during the specified period.


**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > AAA**.


**Note**

The 15-minute and hourly AAA accounting statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the AAA reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose AAA Accounting Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node for the object
Server Name	Name of the Server.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Requests	The number of accounting requests sent to the server during the system reinitialization.
Request Timeouts	The number of accounting requests timed out during the system reinitialization.
Transaction Completed	<ul style="list-style-type: none"> <li>Count—Total number of accounting transactions with the server which succeeded during the system reinitialization.</li> <li>Rate—Rate at which the accounting transactions succeeded during the system reinitialization.</li> </ul>
Transaction Failures	The number of accounting transactions with this server which failed during the system reinitialization.
Error Responses	The number of server ERROR accounting responses received from the server during the system reinitialization.
Incorrect Responses	The number of accounting responses which could not be processed during the system reinitialization.

### AAA Authentication Statistics Daily Report

MWTM displays the AAA authentication statistics daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1**

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > AAA**.

**Note**

The 15-minute and hourly AAA authentication statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the AAA reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose AAA Authentication Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node for the object
Server Name	Name of the Server.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Requests	The number of authentication requests sent to the server during the system reinitialization.
Request Timeouts	The number of authentication requests which have timed out since the server is in active state.
Transaction Completed	<ul style="list-style-type: none"> <li>Count—Total number of authentication transactions with the server which succeeded during the system reinitialization.</li> <li>Rate—Rate at which the authentication transactions succeeded during the system reinitialization.</li> </ul>
Transaction Failures	The number of authentication transactions occurred when the server which failed since the server is in active state.
Error Responses	The number of server ERROR authentication responses received from the server since the server is in active state.
Incorrect Responses	The number of authentication responses which could not be processed since the server is in active state.

## CPU Reports

The MWTM web interface provides node-level CPU reports. The information is available in graphical, tabular, and CSV formats. There are two types of utilization reports:

- **Peak utilization**—Displays the maximum (or peak) values obtained during the specified period (for example, 15 minutes, hourly, daily).
- **Average utilization**—Displays the average values obtained during the specified period (for example, 15 minutes, hourly, daily).





**Note** The 15-minute and hourly CPU reports are available from the node level only; they are not available from the top level or the network level.

In addition to generating network-wide CPU reports as explained in the following steps, you can also generate node-level CPU reports as explained in [Generating Node-Level CPU/Memory Reports, page 13-303](#).

To generate a network-wide CPU reports:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > CPU**.

- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** To generate the report, click the Run icon (green arrow ).
- The Type drop-down menu contains the following reports:
- [CPU Peak Utilization Daily Reports, page 13-14](#)
  - [CPU Average Utilization Daily Reports, page 13-16](#)

## CPU Peak Utilization Daily Reports

The CPU Peak Utilization Daily reports display the CPUs with the highest maximum CPU utilization over the specified time period.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > CPU**. You can access node-level CPU/Memory reports by clicking on a node name, then clicking the **Performance** tab.
- Step 2** From the Type menu, select one of the following CPU utilization reports:
- CPU Peak Utilization Daily
  - CPU Average Utilization Daily



**Note** The 15-minute and hourly CPU reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CPU reports to navigate to a specific node to view hourly and 15 minute reports for that node.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Slot/CPU	Slot number (if known) and CPU number.
CPU Description	Type of CPU.
Average Utilization	Average utilization across the chosen time range.
Maximum Utilization	Maximum utilization during the specified time range.
Maximum Date ( <i>time zone</i> )	Timestamp when the maximum utilization occurred.
Warning Threshold	Threshold setting beyond which a warning is issued.
Overload Threshold	Threshold setting beyond which is considered overloaded.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

GUI Element	Description
<i>Graph</i>	If you select <b>Graph</b> from the Output menu, the graph displays the 12 CPUs with the highest maximum CPU utilization over the specified time period.
<i>Table or CSV</i>	<p>If you select <b>Table</b> from the Output menu, the table contains all CPUs monitored by MWTM. By default, the CPUs are sorted by maximum CPU utilization. The table includes:</p> <ul style="list-style-type: none"> <li>• Node—Name of the node.</li> <li>• Slot/CPU—Slot number (if known) and CPU number.</li> <li>• CPU Description—Type of CPU.</li> <li>• Timestamp (<i>time zone</i>)—Timestamp at which the maximum utilization rate occurred.</li> <li>• Average Utilization—Average of the data across the chosen time range.</li> <li>• Maximum Utilization—Maximum utilization during the specified time range.</li> <li>• Minimum Utilization—Minimum utilization during the specified time range.</li> <li>• Warning Threshold—Threshold setting beyond which a warning is issued.</li> <li>• Overload Threshold—Threshold setting beyond which is considered overloaded.</li> </ul> <p><b>Note</b> If you select <b>CSV</b> from the Output menu, the same data is presented in the excel format.</p>
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Percentage Utilization	If Output Type is Graph, the Y-axis label shows percentage of CPU utilization over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

## CPU Average Utilization Daily Reports

The CPU Average Utilization Daily reports display the average CPU values gathered during the specified period.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > CPU**. You can access node-level CPU/Memory reports by clicking on a node name, then clicking the **Performance** tab.
- Step 2** In the tool bar of the right pane, from the Type menu, select **CPU Average Utilization Daily**.  
A summary table displays the following information:

Field	Description
Node	Name of the node.
Slot/CPU	Name of the CPU.
CPU Description	Description of the CPU.
Average Utilization	Average utilization across the chosen time range.
Maximum Utilization	Highest utilization of the average values during the specified time range.
Maximum Date ( <i>time zone</i> )	Timestamp for when the maximum utilization value occurred.
Warning Threshold	Threshold setting beyond which a warning is issued.
Overload Threshold	Threshold setting beyond which is considered overloaded.





**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

GUI Element	Description
<i>Graph</i>	If you select <b>Graph</b> from the Output menu, the graph displays the average daily CPU utilization over the specified time period.
<i>Table or CSV</i>	<p>If you select <b>Table</b> from the Output menu, the table contains all CPUs monitored by MWTM. By default, the CPUs are sorted by maximum CPU utilization. The table includes:</p> <ul style="list-style-type: none"> <li>• Node—Name of the node.</li> <li>• Slot/CPU—Slot number (if known) and CPU number.</li> <li>• CPU Description—Type of CPU.</li> <li>• Timestamp (<i>time zone</i>)—Timestamp at which the maximum utilization rate occurred.</li> <li>• Average Utilization—Average of the data across the chosen time range.</li> <li>• Maximum Utilization—Maximum utilization during the specified time range.</li> <li>• Minimum Utilization—Minimum utilization during the specified time range.</li> <li>• Warning Threshold—Threshold setting beyond which a warning is issued.</li> <li>• Overload Threshold—Threshold setting beyond which is considered overloaded.</li> </ul> <p><b>Note</b> If you select <b>CSV</b> from the Output menu, the same data is presented in the excel format.</p>
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Percentage Utilization	If Output Type is Graph, the Y-axis label shows percentage of CPU utilization over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

## IP Local Pool Reports

The MWTM web interface provides node-level and network wide IP local pool reports. To generate a network wide IP local pool reports:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > IP Local Pool**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [IP Local Pool Statistics Daily Reports, page 13-18](#)



### Note

If MWTM detects an utilization percentage that it considers to be impossible, the GUI displays ‘Out of Range’ in the corresponding table cells.

## IP Local Pool Statistics Daily Reports

MWTM displays the IP Local Pool Statistics Daily report during the specified period.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > IP Local Pool**.



### Note

The 15-minute and hourly IP Local Pool reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the IP Local Pool reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose IP Local Pool Statistics Daily from Type drop-down menu.

The Free Addresses and the In Use Addresses tables contain summary information as described below:

Field	Description
Node	Name of the node.
Pool Name	Name of an IP local pool.
Total Addresses	Total number of IP Addresses in the IP Local Pool.



Field	Description
Free Addresses	<ul style="list-style-type: none"><li>• Average—Average number of IP addresses available for use in the IP local pool.</li><li>• Minimum—Minimum number of IP addresses available for use in the IP local pool.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li><li>• Maximum—Maximum number of IP addresses available for use in the IP local pool.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li></ul>
In Use Addresses	<ul style="list-style-type: none"><li>• Average—Average number of IP addresses being used in the IP local pool.</li><li>• Minimum—Minimum number of IP addresses being used in the IP local pool.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li><li>• Maximum—Maximum number of IP addresses being used in the IP local pool.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li></ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
IP Local Pool Statistics Daily	Table, CSV	Node	Name of the node.
		Pool Name	Name of an IP local pool.
		Timestamp ( <i>time zone</i> )	Timestamp that shows time bits-per second value occurred.
		Total Addresses	Total number of IP Addresses in the IP Local Pool.
		Free Addresses	<ul style="list-style-type: none"> <li>• Average—Average number of IP addresses available for use in the IP local pool.</li> <li>• Maximum—Maximum number of IP addresses available for use in the IP local pool.</li> <li>• Minimum—Minimum number of IP addresses available for use in the IP local pool.</li> </ul>
		In Use Addresses	<ul style="list-style-type: none"> <li>• Average—Average number of IP addresses being used in the IP local pool.</li> <li>• Maximum—Maximum number of IP addresses being used in the IP local pool.</li> <li>• Minimum—Minimum number of IP addresses being used in the IP local pool.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Min Addresses/ Avg Addresses/ Max Addresses	If Output Type is Graph, the Y-axis label shows Minimum/Average/Maximum addresses available IP addresses that are Free/In use.
		Server Time	Name of the node for the link.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for Minimum/Average/Maximum addresses available IP addresses that are Free/In use.

## Interface Reports

The MWTM web interface provides node-level and network wide interface reports. To generate a network wide interface reports:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [Interface Utilization Daily Reports, page 13-21](#)
- [Interface Total Packets Daily Reports, page 13-23](#)
- [Interface Errors/Discards Daily Report, page 13-26](#)
- [Interface Broadcast Packets Percentage Daily Reports, page 13-29](#)
- [Interface Multicast Packets Percentage Daily Reports, page 13-30](#)
- [Interface Unicast Packets Percentage Daily Reports, page 13-32](#)
- [Interface Discards Percentage Daily Reports, page 13-35](#)
- [Interface Errors Percentage Daily Reports, page 13-38](#)



### Note

If MWTM detects an utilization percentage that it considers to be impossible, the GUI displays ‘Out of Range’ in the corresponding table cells.

## Interface Utilization Daily Reports

MWTM displays the Interface Utilization Daily report during the specified period.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.



### Note

The 15-minute and hourly Interface Utilization reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the Interface Utilization reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose Interface Utilization Daily from Type drop-down menu.

The Interface Utilization table contains summary information as described below:

Field	Description
Node	Name of the node.
Interface	Name of the interface.
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
Interface Utilization Daily	Table, CSV	Node	Name of the node for the link.
		Interface	Name of the interface.
		Timestamp ( <i>time zone</i> )	Timestamp that shows time bits-per second value occurred.
		Average Utilization%	<ul style="list-style-type: none"> <li>Send—Average of the data sent across the chosen time range.</li> <li>Receive—Average of the data received across the chosen time range.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Utilization %	If Output Type is Graph, the Y-axis label shows Utilization in percentage.
		Server Time	Name of the node for the link.
		<i>Legend</i>	Device allows the user to interact with the operating system.

## Interface Total Packets Daily Reports

MWTM displays the Interface Total Packets Daily report during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.



### Note

The 15-minute and hourly Interface Total Packets reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the Interface Total Packets reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose Interface Total Packets Daily from Type drop-down menu.

The Interface Total Packets table contains summary information as described below:

Field	Description
Node	Name of the node.
Interface	Name of the interface.
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>



**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	GUI Element	Field	Description
Interface Total Packets Daily	Table, CSV		Node	Name of the node for the link.
			Interface	Device allows the user to interact with the operating system.
			Time stamp (time zone)	Timestamp of the report.
		Send	Total Packets	The total number of packets sent by the Interface.
			Unicast Packets %	The number packets sent from a single source to a specified destination by the interface.
			Multicast Packets %	The number of packets sent from the single source to multiple destinations by the interface.
			Broadcast Packets %	The number of packets sent from multiple source to multiple destinations.
		Receive	Total Packets	The total number of packets received by the Interface.
			Unicast Packets %	The number of unicast packets received by the interface.
			Multicast Packets %	The number of multicast packets received by the interface.
			Broadcast Packets %	The number of broadcast packets received by the interface.
	Graph		Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
			Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
			Total Packets	If Output Type is Graph, the Y-axis label shows total packets.
			Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
			Legend	If Output Type is Graph, a color-coded legend shows labels for total packets.

### Interface Performance Reports

The 15-minute, hourly, and daily Interface Performance reports are available from the interface level only; they are not available from the node level or the network level. Click on a interface name in the navigation tree and then click the Reports tab to view 15 minute, hourly, and daily Interface Performance reports for that interface.

The Graph and Table/CSV output of these reports display the combined output of the fields of Interface Utilization reports and Interface Total Packets reports. At the interface level, the summary table contains the additional column Data Type.

See [Interface Utilization Daily Reports](#) and [Interface Total Packets Daily Reports](#) for information on column names.

### Interface Errors/Discards Daily Report

MWTM displays the Interface failed during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.



#### Note

The 15-minute and hourly Interface Errors/Discards reports are available from the node and interface level only; they are not available from the top level or the network level. Click on a node or interface name in the Interface Errors/Discards reports to navigate to a specific node or interface to view hourly and 15 minute reports for that node or interface.

- Step 2** Choose Interface Errors/Discards from Type drop-down menu.

The Interface Errors+Discards table contains summary information as described below:

Field	Description
Node	Name of the node.
Interface	Name of the interface.

Field	Description
Send	<ul style="list-style-type: none"><li>• Average—Average Send for the statistic for the specified time.</li><li>• Minimum—Minimum Send for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li><li>• Maximum—Maximum Send for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li></ul>
Receive	<ul style="list-style-type: none"><li>• Average—Average Receive for the statistic for the specified time.</li><li>• Minimum—Minimum Receive for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li><li>• Maximum—Maximum Receive for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li></ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
Interface Errors/ Discards Daily	Table, CSV	Node	Name of the node for the link.
		Interface	Device allows the user to interact with the operating system.
		Time stamp ( <i>time zone</i> )	Timestamp of the report.
		Send	<ul style="list-style-type: none"> <li>Packets—Total number of outbound packets.</li> <li>Errors—Number of outbound packets that contained errors.</li> <li>Error %—Percentage of outbound packets that contained errors.</li> <li>Discards—Number of outbound packets that were discarded.</li> <li>Discard %—Percentage of outbound packets that were discarded.</li> </ul>
		Receive	<ul style="list-style-type: none"> <li>Packets—Total number of inbound packets.</li> <li>Errors—Number of inbound packets that contained errors.</li> <li>Error %—Percentage of inbound packets that contained errors.</li> <li>Discards—Number of inbound packets that were discarded.</li> <li>Discard %—Percentage of inbound packets that were discarded.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Errors+ Discards	If Output Type is Graph, the Y-axis label shows Errors+Discards.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for Errors+Discards.

## Interface Broadcast Packets Percentage Daily Reports

MWTM displays the Interface Broadcast Packets Percentage Daily report during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.



### Note

The 15-minute and hourly Interface Broadcast Packets Percentage reports are available from the node and interface level only; they are not available from the top level or the network level. Click on a node or the interface name in the Interface Broadcast Packets Percentage reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose Interface Broadcast Packets Percentage Daily from Type drop-down menu.

The Interface Broadcast Packets Percentage table contains summary information as described below:

Field	Description
Node	Name of the node.
Interface	Name of the interface.
Send	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Minimum—Minimum Send for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Minimum—Minimum Receive for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
Interface Broadcast Packets Percentage Daily	Table, CSV	Node	Name of the node for the link.
		Interface	Name of the interface.
		Timestamp ( <i>time zone</i> )	Timestamp that shows time bits-per second value occurred.
		Send	<ul style="list-style-type: none"> <li>Total Packets—The total number of packets sent by the Interface.</li> <li>Unicast Packets %—The number of packets sent from a single source to a specified destination by the interface.</li> <li>Multicast Packets %—The number of packets sent from the single source to multiple destinations by the interface.</li> <li>Broadcast Packets %—The number of packets sent from multiple source to multiple destinations. This is the default sortable column.</li> </ul>
		Receive	<ul style="list-style-type: none"> <li>Total Packets—The total number of packets received by the Interface.</li> <li>Unicast Packets %—The number of unicast packets received by the interface.</li> <li>Multicast Packets %—The number of multicast packets received by the interface.</li> <li>Broadcast Packets %—The number of broadcast packets received by the interface.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Packets %	If Output Type is Graph, the Y-axis label shows packets in percentage.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for packets.

### Interface Multicast Packets Percentage Daily Reports

MWTM displays the Interface Multicast Packets Percentage Daily report during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.

**Note**

The 15-minute and hourly Interface Multicast Packets Percentage reports are available from the node and interface level only; they are not available from the top level or the network level. Click on a node or the interface name in the Interface Multicast Packets Percentage reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose Interface Multicast Packets Percentage Daily from Type drop-down menu.

The Interface Multicast Packets Percentage table contains summary information as described below:

Field	Description
Node	Name of the node.
Interface	Name of the interface.
Send	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Minimum—Minimum Send for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Minimum—Minimum Receive for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
Interface Multicast Packets Percentage Daily	Table, CSV	Node	Name of the node for the link.
		Interface	Name of the interface.
		Timestamp ( <i>time zone</i> )	Timestamp that shows time bits-per second value occurred.
		Send	<ul style="list-style-type: none"> <li>Total Packets—The total number of packets sent by the Interface.</li> <li>Unicast Packets %—The number of packets sent from a single source to a specified destination by the interface.</li> <li>Multicast Packets %—The number of packets sent from the single source to multiple destinations by the interface.</li> </ul> <p>This is the default sortable column.</p> <ul style="list-style-type: none"> <li>Broadcast Packets %—The number of packets sent from multiple source to multiple destinations.</li> </ul>
		Receive	<ul style="list-style-type: none"> <li>Total Packets—The total number of packets received by the Interface.</li> <li>Unicast Packets %—The number of unicast packets received by the interface.</li> <li>Multicast Packets %—The number of multicast packets received by the interface.</li> <li>Broadcast Packets %—The number of broadcast packets received by the interface.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Packets %	If Output Type is Graph, the Y-axis label shows packets in percentage.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for packets.

### Interface Unicast Packets Percentage Daily Reports

MWTM displays the Interface Unicast Packets Percentage Daily report during the specified period.



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.

**Note**

The 15-minute and hourly Interface Unicast Packets Percentage reports are available from the node and interface level only; they are not available from the top level or the network level. Click on a node or the interface name in the Interface Unicast Packets Percentage reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose Interface Unicast Packets Percentage Daily from Type drop-down menu.

The Interface Unicast Packets Percentage table contains summary information as described below:

Field	Description
Node	Name of the node.
Interface	Name of the interface.
Send	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Minimum—Minimum Send for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Minimum—Minimum Receive for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
Interface Unicast Packets Percentage Daily	Table, CSV	Node	Name of the node for the link.
		Interface	Name of the interface.
		Timestamp ( <i>time zone</i> )	Timestamp that shows time bits-per second value occurred.
		Send	<ul style="list-style-type: none"> <li>Total Packets—The total number of packets sent by the Interface.</li> <li>Unicast Packets %—The number of packets sent from a single source to a specified destination by the interface. This is the default sortable column.</li> <li>Multicast Packets %—The number of packets sent from the single source to multiple destinations by the interface.</li> <li>Broadcast Packets %—The number of packets sent from multiple source to multiple destinations.</li> </ul>
		Receive	<ul style="list-style-type: none"> <li>Total Packets—The total number of packets received by the Interface.</li> <li>Unicast Packets %—The number of unicast packets received by the interface.</li> <li>Multicast Packets %—The number of multicast packets received by the interface.</li> <li>Broadcast Packets %—The number of broadcast packets received by the interface.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Packets %	If Output Type is Graph, the Y-axis label shows packets in percentage.
		Server Time	Name of the node for the link.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for packets.

### Interface Packets Percentage Reports

The 15-minute, hourly, and daily Interface Packets Percentage reports are available from the interface level only; they are not available from the node level or the network level. Click on a interface name in the navigation tree and then click the Reports tab to view 15 minute, hourly, and daily Interface Packets Percentage reports for that interface.

The Graph and Table/CSV output of these reports display the combined output of the fields of Interface Broadcast Packets Percentage reports, Interface Multicast Packets Percentage, and Interface Unicast Packets Percentage. At the interface level, the summary table contains the additional column Data Type.

See [Interface Broadcast Packets Percentage Daily Reports](#), [Interface Multicast Packets Percentage Daily Reports](#), and [Interface Unicast Packets Percentage Daily Reports](#) for information on column names.

### Interface Discards Percentage Daily Reports

MWTM displays the Interface Discards Percentage Daily report during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.



#### Note

The 15-minute and hourly Interface Discards Percentage reports are available from the node and interface level only; they are not available from the top level or the network level. Click on a node or the interface name in the Interface Discards Percentage reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose Interface Discards Percentage Daily from Type drop-down menu.

The Interface Discards Percentage table contains summary information as described below:

Field	Description
Node	Name of the node.
Interface	Name of the interface.

Field	Description
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
Interface Discards Percentage Daily	Table, CSV	Node	Name of the node for the link.
		Interface	Name of the interface.
		Timestamp ( <i>time zone</i> )	Timestamp that shows time bits-per second value occurred.
		Send	<ul style="list-style-type: none"> <li>Packets—Total number of outbound packets.</li> <li>Errors—Number of outbound packets that contained errors.</li> <li>Error %—Percentage of outbound packets that contained errors.</li> <li>Discards—Number of outbound packets that were discarded.</li> <li>Discard %—Percentage of outbound packets that were discarded.</li> </ul>
		Receive	<ul style="list-style-type: none"> <li>Packets—Total number of inbound packets.</li> <li>Errors—Number of inbound packets that contained errors.</li> <li>Error %—Percentage of inbound packets that contained errors.</li> <li>Discards—Number of inbound packets that were discarded.</li> <li>Discard %—Percentage of inbound packets that were discarded.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Discards %	If Output Type is Graph, the Y-axis label shows discards in percentage.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for discards.

## Interface Errors Percentage Daily Reports

MWTM displays the Interface Errors Percentage Daily report during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Interface**.



### Note

The 15-minute and hourly Interface Errors Percentage reports are available from the node and interface level only; they are not available from the top level or the network level. Click on a node or the interface name in the Interface Errors Percentage reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose Interface Errors Percentage Daily from Type drop-down menu.

The Interface Errors Percentage table contains summary information as described below:

Field	Description
Node	Name of the node.
Interface	Name of the interface.
Send	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Minimum—Minimum Send for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Minimum—Minimum Receive for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp that shows time when the minimum value occurred.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
Interface Errors Percentage Daily	Table, CSV	Node	Name of the node for the link.
		Interface	Name of the interface.
		Timestamp ( <i>time zone</i> )	Timestamp that shows time bits-per second value occurred.
		Send	<ul style="list-style-type: none"> <li>Packets—Total number of outbound packets.</li> <li>Errors—Number of outbound packets that contained errors.</li> <li>Error %—Percentage of outbound packets that contained errors.</li> <li>Discards—Number of outbound packets that were discarded.</li> <li>Discard %—Percentage of outbound packets that were discarded.</li> </ul>
		Receive	<ul style="list-style-type: none"> <li>Packets—Total number of inbound packets.</li> <li>Errors—Number of inbound packets that contained errors.</li> <li>Error %—Percentage of inbound packets that contained errors.</li> <li>Discards—Number of inbound packets that were discarded.</li> <li>Discard %—Percentage of inbound packets that were discarded.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Errors %	If Output Type is Graph, the Y-axis label shows errors in percentage.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for errors.

### Interface Errors/Discards Percentage Reports

The 15-minute, hourly, and daily Interface Errors/Discards Percentage reports are available from the interface level only; they are not available from the node level or the network level. Click on a interface name in the navigation tree and then click the Reports tab to view 15 minute, hourly, and daily Interface Errors/Discards Percentage reports for that interface.

The Graph and Table/CSV output of these reports display the combined output of the fields of Interface Discards Percentage reports and Interface Errors Packets Percentage. At the interface level, the summary table contains the additional column Data Type.

See [Interface Discards Percentage Daily Reports](#) and [Interface Errors Percentage Daily Reports](#) for information on column names.

## Memory Reports

The MWTM web interface provides node-level Memory reports. The information is available in graphical, tabular, and CSV formats. There are three types of utilization reports:



- Peak utilization—Displays the maximum (or peak) values obtained during the specified period (for example, 15 minutes, hourly, daily).
- Average utilization—Displays the average values obtained during the specified period (for example, 15 minutes, hourly, daily).
- Buffer utilization—Displays the buffer values obtained during the specified period (for example, 15 minutes, hourly, daily).



**Note** The 15-minute and hourly Memory reports are available from the node level only; they are not available from the top level or the network level.

In addition to generating network-wide Memory reports as explained in the following steps, you can also generate node-level CPU reports as explained in [Generating Node-Level CPU/Memory Reports](#), page 13-303.

To generate a network-wide Memory reports:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Memory**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [Memory Peak Utilization Daily Reports](#), page 13-41
- [Memory Average Utilization Daily Reports](#), page 13-43
- [Memory Buffer Utilization Daily Reports](#), page 13-44



## Memory Peak Utilization Daily Reports

The Memory Peak Utilization Daily reports display the CPUs with the highest memory utilization over the specified time period.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Memory**. You can access node-level CPU/Memory reports by clicking on a node name, then clicking the **Performance** tab.

**Step 2** From the Type menu, select one of the following Memory utilization reports:

- Memory Peak Utilization 15 minutes
- Memory Peak Utilization Hourly
- Memory Peak Utilization Daily



**Note**

The 15-minute and hourly Memory reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the Memory reports to navigate to a specific node to view hourly and 15 minute reports for that node.

A summary table displays the following information:

Field	Description
Node	Name of the node.
Slot/CPU	Name of the CPU.
CPU Description	Description of the CPU.
Memory Description	Type of memory.
Average Utilization	Average memory utilization during the specified time range.
Maximum Utilization	Maximum memory utilization during the specified time range
Maximum Date ( <i>time zone</i> )	Timestamp for when the maximum utilization value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

GUI Element	Description
<i>Graph</i>	If you select <b>Graph</b> from the Output menu, the graph displays the CPUs with the highest memory utilization over the specified time period.
<i>Table or CSV</i>	<p>If you select <b>Table</b> from the Output menu, the table contains all CPUs monitored by MWTM. By default, the CPUs are sorted by maximum CPU utilization. The table includes:</p> <ul style="list-style-type: none"> <li>• Node—Name of the node.</li> <li>• Slot/CPU—Slot number (if known) and CPU number.</li> <li>• CPU Description—Type of CPU.</li> <li>• Timestamp (<i>time zone</i>)—Timestamp at which the maximum utilization rate occurred.</li> <li>• Memory Description—Type of memory, which can be processor, I/O, Fast, etc.</li> <li>• Average Utilization—Average of the data across the chosen time range.</li> <li>• Maximum Utilization—Maximum utilization during the specified time range.</li> <li>• Minimum Utilization—Minimum utilization during the specified time range.</li> <li>• Total—Average Used plus Average Free memory during the specified time frame.</li> <li>• Average Used—Average memory used during the specified time range.</li> <li>• Average Free—Average memory available during the specified time range.</li> </ul> <p><b>Note</b> If you select <b>CSV</b> from the Output menu, the same data is presented in the excel format.</p>
Percentage Utilization	If Output Type is Graph, the Y-axis label shows percentage of memory utilization over time.
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

## Memory Average Utilization Daily Reports

The Memory Average Utilization Daily reports display the average memory values gathered during the specified period.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Memory**. You can access node-level CPU/Memory reports by clicking on a node name, then clicking the **Performance** tab.

**Step 2** From the Type menu, select one of the following Memory utilization reports:

- Memory Average Utilization 15 minutes
- Memory Average Utilization Hourly
- Memory Average Utilization Daily



**Note** The 15-minute and hourly Memory reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the Memory reports to navigate to a specific node to view hourly and 15 minute reports for that node.

A summary table displays the following information:

Field	Description
Node	Name of the node.
Slot/CPU	Name of the CPU.
CPU Description	Description of the CPU.
Memory Description	Type of memory.
Average Utilization	Average memory utilization during the specified time range.
Maximum Utilization	Highest memory utilization of the average values during the specified time range.
Maximum Date ( <i>time zone</i> )	Timestamp for when the maximum utilization value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

GUI Element	Description
<i>Graph</i>	If you select <b>Graph</b> from the Output menu, the graph displays the average memory utilization over the specified time period.
<i>Table or CSV</i>	<p>If you select <b>Table</b> from the Output menu, the table contains all CPUs monitored by MWTM. By default, the CPUs are sorted by maximum CPU utilization. The table includes:</p> <ul style="list-style-type: none"> <li>• Node—Name of the node.</li> <li>• Slot/CPU—Slot number (if known) and CPU number.</li> <li>• CPU Description—Type of CPU.</li> <li>• Timestamp (<i>time zone</i>)—Timestamp at which the maximum utilization rate occurred.</li> <li>• Memory Description—Type of memory, which can be processor, I/O, Fast, etc.</li> <li>• Average Utilization—Average of the data across the chosen time range.</li> <li>• Maximum Utilization—Maximum utilization during the specified time range.</li> <li>• Minimum Utilization—Minimum utilization during the specified time range.</li> <li>• Total—Average Used plus Average Free memory during the specified time frame.</li> <li>• Average Used—Average memory used during the specified time range.</li> <li>• Average Free—Average memory available during the specified time range.</li> </ul> <p><b>Note</b> If you select <b>CSV</b> from the Output menu, the same data is presented in the excel format.</p>
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Percentage Utilization	If Output Type is Graph, the Y-axis label shows percentage of memory utilization over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

## Memory Buffer Utilization Daily Reports

The Memory Buffer Utilization Daily reports display the CPUs with the memory buffer utilization over the specified time period.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Common Statistics > Memory**. You can access node-level CPU/Memory reports by clicking on a node name, then clicking the **CPU/Mem** tab.

**Step 2** From the Type menu, select one of the following Memory utilization reports:

- Memory Buffer Utilization 15 minutes
- Memory Buffer Utilization Hourly
- Memory Buffer Utilization Daily



**Note**

The 15-minute and hourly Memory Buffer Utilization reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the Memory Buffer Utilization reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

GUI Element	Description
<i>Table or CSV</i>	<p>The table includes:</p> <ul style="list-style-type: none"> <li>• Node—Name of the node.</li> <li>• Timestamp (<i>time zone</i>)—Timestamp at which the maximum utilization rate occurred.</li> <li>• Buffer Name—Displays the buffer type.</li> <li>• Buffer Failures—Displays the number of failures to grant a buffer due to reasons other than insufficient memory.</li> <li>• Buffer No Storage—Displays the number of times the system tried to create new buffers, but could not due to insufficient free memory in the system.</li> </ul> <p><b>Note</b> If you select <b>CSV</b> from the Output menu, the same data is presented in the excel format.</p>

## Viewing ITP Statistics Reports

ITP Statistics Reports are located within **Reports > ITP Statistics** in the MWTM web interface. You can also find ITP statistics reports in the `/opt/CSCOs/gm/reports` directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All reports are saved as export files in .csv format.



You can view any of the following ITP statistics reports:

- [AS Reports, page 13-46](#)
- [ASP Reports, page 13-53](#)
- [GTT Rates Reports, page 13-66](#)
- [Link Reports, page 13-70](#)

- [Link Multi-Day Report, page 13-80](#)
- [Linkset Reports, page 13-81](#)
- [MLR Reports, page 13-91](#)
- [MSU Rates Reports, page 13-96](#)
- [SCTP Reports, page 13-100](#)

## AS Reports

The MWTM web interface provides node-level Application Server (AS) reports. The information is available in graphical, tabular, and CSV formats. To generate a network-wide AS report:

- 
- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > AS**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [AS Statistics Hourly Reports, page 13-46](#)
  - [AS Statistics Daily Reports, page 13-48](#)
  - [AS Peaks Statistics Daily Reports, page 13-51](#)
- 

### AS Statistics Hourly Reports

MWTM displays the AS Statistics Hourly report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

---

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > AS**.
- Step 2** Choose AS Statistics Hourly from the Type drop-down menu.

The Send Packets and Receive Packets tables contain summary information as described below:

Field	Description
Node	Name of the node for the application server.
Signaling Point	Name of the signaling point for the application server.

Field	Description
Application Server	Name of the application server.
Send	<ul style="list-style-type: none"><li>• Average—Average Send for the statistic for the specified time.</li><li>• Minimum—Minimum Send for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum Send for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>
Receive	<ul style="list-style-type: none"><li>• Average—Average Receive for the statistic for the specified time.</li><li>• Minimum—Minimum Receive for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum Receive for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
AS Statistics Hourly Report	Table, CSV	Node	Name of the node.
		Signaling Point	Name of the signaling point for the application server.
		AS	Name of the application server.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Packets From MTP3	Total number of packets that the application server received, sent from the MTP3 layer.
		Packets To ASPs	Total number of packets that the application server sent to the application server processes.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Packets	If Output Type is Graph, the Y-axis label shows hourly statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.

## AS Statistics Daily Reports

MWTM displays the AS Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > AS**.
- Step 2** Choose AS Statistics Daily from the Type drop-down menu.



The Send Packets and Receive Packets tables contain summary information as described below:

Field	Description
Node	Name of the node for the application server.
Signaling Point	Name of the signaling point for the application server.
Application Server	Name of the application server.
Send	<ul style="list-style-type: none"><li>• Average—Average Send for the statistic for the specified time.</li><li>• Minimum—Minimum Send for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum Send for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>
Receive	<ul style="list-style-type: none"><li>• Average—Average Receive for the statistic for the specified time.</li><li>• Minimum—Minimum Receive for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum Receive for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
AS Statistics Daily Report	Table, CSV	Node	Name of the node.
		Signaling Point	Name of the signaling point for the application server.
		AS	Name of the application server.
		Timestamp (time zone)	Timestamp of the report.
		Send	<ul style="list-style-type: none"> <li>Packets To ASPs—Total number of packets that the application server sent to the application server processes for the specified date.</li> <li>Peak To ASPs—Highest hourly Packets To ASPs for the application server for the specified date.</li> <li>Peak To Hour—Hour in which the Peak To ASPs for the application server occurred for the specified date.</li> </ul>
		Receive	<ul style="list-style-type: none"> <li>Packets From MTP3—Total number of packets that the application server receives from the MTP3 layer for the specified date.</li> <li>Peak From MTP3—Highest hourly Packets From MTP3 for the application server for the specified date.</li> <li>Peak From Hour—Hour in which the Peak From MTP3 for the application server occurred for the specified date.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Packets	If Output Type is Graph, the Y-axis label shows daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		Legend	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.

## AS Peaks Statistics Daily Reports

MWTM displays the AS Peaks Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > AS**.

**Step 2** Choose AS Peaks Statistics Daily from the Type drop-down menu.

The Send Peak Packets and Receive Peak Packets tables contain summary information as described below:



Field	Description
Node	Name of the node for the application server.
Signaling Point	Name of the signaling point for the application server.
Application Server	Name of the application server.
Send	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Minimum—Minimum Send for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Minimum—Minimum Receive for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
AS Peaks Statistics Daily Report	Table, CSV	Node	Name of the node for the application server.
		SP Name	Name of the signaling point for the application server.
		AS	Name of the application server that recorded the peak value.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Send	<ul style="list-style-type: none"> <li>Peak To ASPs—Highest hourly Packets To ASPs for the application server for the specified date.</li> <li>Peak To Hour—Hour in which the Peak To ASPs for the application server occurred for the specified date.</li> </ul>
		Receive	<ul style="list-style-type: none"> <li>Peak From MTP3—Highest hourly Packets From MTP3 for the application server for the specified date.</li> <li>Peak From Hour—Hour in which the Peak From MTP3 for the application server occurred for the specified date.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Peaks	If Output Type is Graph, the Y-axis label shows peaks daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## ASP Reports

The MWTM web interface provides node-level Application Server Process (ASP) reports. The information is available in graphical, tabular, and CSV formats. To generate a network-wide ASP report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > ASP**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow ).

The Type drop-down menu contains the following reports:

- [ASP Statistics Hourly Reports, page 13-53](#)
- [ASP Statistics Daily Reports, page 13-56](#)
- [ASP Peaks Statistics Daily Reports, page 13-58](#)
- [ASP MTP3 Statistics Daily Reports, page 13-61](#)
- [ASP MTP3 Peaks Statistics Daily Reports, page 13-63](#)

### ASP Statistics Hourly Reports

MWTM displays the ASP Statistics Hourly report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > ASP**.
- Step 2** Choose ASP Statistics Hourly from the Type drop-down menu.

The Send Packets and Receive Packets tables contain summary information as described below:

Field	Description
Node	Name of the node for the application server process.
Signaling Point	Name of the signaling point for the application server.
Application Server	Name of the application server.
ASP	Name of the application server process.

Field	Description
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
ASP Statistics Hourly	Table, CSV	Node	Name of the node.
		Signaling Point	Name of the signaling point for the application server.
		AS	Name of the application server.
		ASP	Name of the application server process.
		Timestamp (time zone)	Timestamp of the report.
		Packets From ASP	Total number of packets that the application server process send for the specified date and hour.
		Packets To ASP	Total number of packets sent to the application server process for the specified date and hour.
		Packets From MTP3	Total number of packets that the application server process received from the MTP3 layer for the specified date and hour.
		Packets To MTP3	Total number of packets the application server process sent to the MTP3 layer for the specified date and hour.
		Send Errors	Total number of errors that occurred when sending packets to the application server process for the specified date and hour.
		Receive Errors	Total number of errors that occurred when receiving packets from the application server process for the specified date and hour.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Packets	If Output Type is Graph, the Y-axis label shows hourly statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## ASP Statistics Daily Reports

MWTM displays the ASP Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > ASP**.

**Step 2** Choose ASP Statistics Daily from the Type drop-down menu.

The Send Packets and Receive Packets tables contain summary information as described below:

Field	Description
Node	Name of the node for the application server process.
Signaling Point	Name of the signaling point for the application server.
Application Server	Name of the application server.
ASP	Name of the application server process.
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>



**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
ASP Statistics Daily	Table, CSV	Node	Name of the node.
		Signaling Point	Name of the signaling point for the application server.
		AS	Name of the application server.
		ASP	Name of the application server process.
		Timestamp (time zone)	Timestamp of the report.
		Packets From ASP	Total number of packets that the application server process sent for the specified date.
		Peak From ASP	Highest hourly Packets From ASP for the application server process for the specified date.
		Peak From Hour	Hour in which the Peak From ASP for the application server process occurred for the specified date.  Click the hour to see the ASP Hourly Report for the chosen application server process and hour.
		Packets To ASP	Total number of packets that the application server sent to the application server processes for the specified date.
		Peak To ASP	Highest hourly Packets To ASP for the application server process for the specified date.
		Peak To Hour	Hour in which the Peak To ASP for the application server process occurred for the specified date.
		Send Errors	Total number of errors that occurred when sending packets to the application server processes for the specified date.
		Peak Send Errors	Highest hourly Send Errors for the application server process for the specified date.
		Peak Send Hour	Hour in which the Peak Send Errors for the application server process occurred for the specified date.
		Receive Errors	Total number of errors that occurred when receiving packets from the application server processes for the specified date.
		Peak Receive Errors	Highest hourly receive errors for the application server process for the specified date.
		Peak Receive Hour	Hour in which the peak receive errors for the application server process occurred for the specified date.

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Packets	If Output Type is Graph, the Y-axis label shows hourly statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## ASP Peaks Statistics Daily Reports

MWTM displays the ASP Peaks Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > ASP**.

**Step 2** Choose ASP Peaks Statistics Daily from the Type drop-down menu.

The Send Peak Packets and Receive Peak Packets tables contain summary information as described below:

Field	Description
Node	Name of the node for the application server process.
Signaling Point	Name of the signaling point for the application server.
Application Server	Name of the application server.
ASP	Name of the application server process.

Field	Description
Send	<ul style="list-style-type: none"><li>• Average—Average Send for the statistic for the specified time.</li><li>• Minimum—Minimum Send for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum Send for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>
Receive	<ul style="list-style-type: none"><li>• Average—Average Receive for the statistic for the specified time.</li><li>• Minimum—Minimum Receive for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum Receive for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
ASP Peaks Statistics Daily	Table, CSV	Node	Name of the node.
		SP Name	Name of the signaling point for the application server.
		AS	Name of the application server.
		ASP	Name of the application server process.
		Timestamp ( <i>timestamp</i> )	Timestamp of the report.
		Peak From ASP	Highest hourly Packets From ASP for the application server process for the chosen day.
		Peak From Hour	Hour in which the Peak From ASP for the application server process occurred for the chosen day.
		Peak To ASP	Highest hourly Packets To ASP for the application server process for the chosen day.
		Peak To Hour	Hour in which the Peak To ASP for the application server process occurred for the chosen day.
		Peak Send Errors	Highest hourly Send Errors for the application server process for the last 30 days.
		Peak Send Hour	Hour in which the Peak Send Errors for the application server process occurred for the chosen day.
		Peak Receive Errors	Highest hourly Receive Errors for the application server process or the last 30 days.
		Peak Receive Hour	Hour in which the Peak Receive Errors for the application server process occurred for the chosen day.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Peaks	If Output Type is Graph, the Y-axis label shows daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## ASP MTP3 Statistics Daily Reports

MWTM displays the ASP MTP3 Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > ASP**.

**Step 2** Choose ASP MTP3 Statistics Daily from the Type drop-down menu.

The Send Packets and Receive Packets tables contain summary information as described below:

Field	Description
Node	Name of the node for the application server process.
Signaling Point	Name of the signaling point for the application server.
Application Server	Name of the application server.
ASP	Name of the application server process.
Send	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Minimum—Minimum Send for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Minimum—Minimum Receive for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
ASP MTP3 Statistics Daily	Table, CSV	Node	Name of the node.
		Signaling Point	Name of the signaling point for the application server.
		AS	Name of the application server.
		ASP	Name of the application server process.
		Timestamp (time zone)	Timestamp of the report.
		Packets From MTP3	Total number of packets that the application server process receives from the MTP3 layer for the specified date.
		Peak From MTP3	Highest hourly Packets From MTP3 for the application server process for the specified date.
		Peak From Hour	Hour in which the Peak From MTP3 for the application server process occurred for the specified date.  Click the hour to see the ASP Hourly Report for the chosen application server process and hour.
		Packets To MTP3	Total number of packets sent to the MTP3 layer by the application server process for the specified date.
		Peak To MTP3	Highest hourly Packets To MTP3 for the application server process for the specified date.
		Peak To Hour	Hour in which the Peak To MTP3 for the application server process occurred for the specified date.
		Send Errors	Total number of errors that occurred when sending packets to the MTP3 layer for the specified date.
		Peak Send Errors	Highest hourly Send Errors for the application server process for the specified date.
		Peak Send Hour	Hour in which the Peak Send Errors for the application server process occurred for the specified date.
		Receive Errors	Total number of errors that occurred when receiving packets from the MTP3 layer for the specified date.
		Peak Receive Errors	Highest hourly Receive Errors for the application server process for the specified date.
		Peak Receive Hour	Hour in which the Peak Receive Errors for the application server process occurred for the specified date.  Click the hour to see the ASP Hourly Report for the chosen application server process and hour.

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Packets	If Output Type is Graph, the Y-axis label shows hourly statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

### ASP MTP3 Peaks Statistics Daily Reports

MWTM displays the ASP MTP3 Peaks Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > ASP**.

**Step 2** Choose ASP MTP3 Peaks Statistics Daily from the Type drop-down menu.

The Send Peak Packets and Receive Peak Packets tables contain summary information as described below:

Field	Description
Node	Name of the node for the application server process.
Signaling Point	Name of the signaling point for the application server.
Application Server	Name of the application server.
ASP	Name of the application server process.

Field	Description
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:



Report Type	Output	Field	Description
ASP MTP3 Peaks Statistics Daily	Table, CSV	Node	Name of the node.
		Signaling Point	Name of the signaling point for the application server.
		AS	Name of the application server.
		ASP	Name of the application server process.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Peak From MTP3	Highest hourly Packets From MTP3 for the application server process for the specified date.
		Peak From Hour	Hour in which the Peak From MTP3 for the application server process occurred for the specified date.
		Peak To MTP3	Highest hourly Packets To MTP3 for the application server process for the specified date.
		Peak To Hour	Hour in which the Peak To MTP3 for the application server process occurred for the specified date.
		Peak Send Errors	Highest hourly Send Errors for the application server process for the specified date.
		Peak Send Hour	Hour in which the Peak Send Errors for the application server process occurred for the specified date.
		Peak Receive Errors	Highest hourly Receive Errors for the application server process for the specified date.
		Peak Receive Hour	Hour in which the Peak Receive Errors for the application server process occurred for the specified date.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Peaks	If Output Type is Graph, the Y-axis label shows peaks daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## GTT Rates Reports


You can view peak GTT rates or average GTT rates. The information is available in graphical, tabular, and CSV formats. There are two types of GTT rates reports:

- Peak utilization—Displays the maximum (or peak) GTT rates obtained during the specified period (for example, 15 minutes, hourly, daily).
- Average utilization—Displays the average values obtained during the specified period (for example, 15 minutes, hourly, daily).

**Note**


The 15-minute and hourly reports for GTT Rates are available from the node level only; they are not available from the top level or the network level.

To generate a network-wide GTT reports:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > GTT Rates**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.

**Note**

The Graph output displays up to twelve GTT Rates data streams based on traffic and/or number of errors. To view all GTT Rates data streams, choose Graph, Table, or CSV.

- Step 5** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [GTT Rate Peak Daily Reports, page 13-67](#)
- [GTT Rate Average Daily Reports, page 13-68](#)

## GTT Rate Peak Daily Reports

GTT Rate Peak Daily Report displays the maximum (or peak) GTT rates obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > GTT Rates**.

**Step 2** Choose GTT Rate Peak Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Slot/CPU	Slot number (if known) and CPU number.
CPU Description	Type of CPU.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Average GTT Rate	Average GTT rate for the specified duration.
Maximum GTT Rate	Maximum GTT rate during the specified duration.
Minimum GTT Rate	Minimum GTT rate during the specified duration.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTT Rate Peak Daily Report	Table	Node	Name of the node for the object. You can click on a node name to see node-specific reports.
		Slot/CPU	Slot number (if known) and CPU number.
		CPU Description	Type of CPU.
		Average GTT Rate	Average GTT rate for the specified duration.
		Maximum GTT Rate	Maximum GTT rate during the specified duration.
		Maximum Date ( <i>time zone</i> )	Timestamp when the maximum GTT rate occurred.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Global Title Translations /Sec	If Output Type is Graph, Y-axis label that shows the Global Title Translations per second.  <b>Note</b> If no data exists between any two data points, the graph displays a color-coded vertical bar to show the period for which no data is available.
		Server Time	If Output Type is Graph, X-axis label that shows a historical time scale and the server time zone.
		Legend	If Output Type is Graph, color-coded legend that shows labels for output.

## GTT Rate Average Daily Reports

GTT Rate Average Daily Report displays the average values obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > GTT Rates**.

- Step 2** Choose GTT Rate Average Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Slot/CPU	Slot number (if known) and CPU number.
CPU Description	Type of CPU.
Average GTT Rate	Average GTT rate for the specified duration.
Maximum GTT Rate	Maximum GTT rate during the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp when the maximum utilization occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTT Rate Average Daily Report	Table	Node	Name of the node for the object. You can click on a node name to see node-specific reports.
		Slot/CPU	Slot number (if known) and CPU number.
		CPU Description	Type of CPU.
		Average GTT Rate	Average GTT rate for the specified duration.
		Maximum GTT Rate	Maximum GTT rate during the specified duration.
		Maximum Date ( <i>time zone</i> )	Timestamp when the maximum GTT rate occurred.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Global Title Translations /Sec	If Output Type is Graph, Y-axis label that shows the Global Title Translations per second. <b>Note</b> If no data exists between any two data points, the graph displays a color-coded vertical bar to show the period for which no data is available.
		Server Time	If Output Type is Graph, X-axis label that shows a historical time scale and the server time zone.
		Legend	If Output Type is Graph, color-coded legend that shows labels for output.

## Link Reports

You can view summary reports of hourly and daily statistics for links, and export the reports.

This section covers:

- [Link Statistics Hourly Reports, page 13-70](#)
- [Link Statistics Daily Reports, page 13-73](#)
- [Link Peaks Statistics Daily Reports, page 13-77](#)


### Link Statistics Hourly Reports

You can view hourly summaries of statistics for all links or a specific link that the MWTM detected on the specified date and hour. The Link Hourly Report page shows summary reports of hourly link statistics by date and hour. You can also graph the results.

The Link Hourly Report table is sorted based on the information in the Send Average Utilization column; however, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns](#), page 4-24).

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > Link**.
- Step 2** In the tool bar of the right pane, from the Type drop-down menu, select Link Hourly Statistics. (See [Table 13-1](#) for a list of report types and their contents).
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu (see [Table 13-1](#) for contents of each output type).
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.

The Send Utilization and Receive Utilization tables contain summary information as described below:

Field or Column	Description
Node	Name of the node for the link.
Signaling Point	Name of the signaling point for the link.
Linkset	Linkset for the object.
SLC	ID of the link.
Send	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Minimum—Minimum Send for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Minimum—Minimum Receive for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 6** Depending on what you select from the Output pulldown menu, the following information is displayed:

Field or Column	Description
<b>Graph</b>	
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Utilization %	If Output Type is Graph, the Y-axis label shows hourly statistics over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.
<b>Table, CSV</b>	
Node	Name of the node for the link.
SP Name	Name of the signaling point for the link.
Linkset Name	Linkset for the object.
SLC	ID of the link.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Type	Type of link. Possible link types are: <ul style="list-style-type: none"> <li>• <b>HSL</b>—Uses the SS7-over-ATM (Asynchronous Transfer Mode) high-speed protocol.</li> <li>• <b>SCTP</b>—Uses the Stream Control Transmission Protocol (SCTP) IP transport protocol.</li> <li>• <b>Serial</b>—Uses the serial SS7 signaling protocol.</li> <li>• <b>Virtual</b>—A virtual link that connects signaling point instances that run on the same node. The MWTM does not poll virtual links; nor does it display real-time data or accounting statistics for virtual links.</li> </ul>
Hourly In-Service (%)	Percentage of time the link was in service on the specified date and hour.
Long Term In-Service (%)	Average percentage of time the link was in service since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.
Congestion %	Percentage of time the link was congested on the specified date and hour.



Field or Column	Description
Send	<ul style="list-style-type: none"> <li>• <b>Average Utilization %</b>—Average Send for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned send capacity for the SCTP link, then <b>NoCap</b> appears in the field.</li> <li>• <b>Long Term Average Utilization %</b>—Long-term average Send for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for the SCTP link, then <b>NoCap</b> appears in the field.</li> <li>• <b>MSUs</b>—Total number of MTP3 message signal units (MSUs) sent on the specified date and hour.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• <b>Average Utilization %</b>—Average Receive for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned send capacity for the SCTP link, then <b>NoCap</b> appears in the field.</li> <li>• <b>Long Term Average Utilization %</b>—Long-term average Receive for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for the SCTP link, then <b>NoCap</b> appears in the field.</li> <li>• <b>MSUs</b>—Total number of MTP3 message signal units (MSUs) received on the specified date and hour.</li> </ul>

## Link Statistics Daily Reports

You can view daily summaries of statistics for all links or for a specific link that the MWTM detected on the specified date and hour. The Link Daily Report page shows summary reports of daily link statistics by date and hour.


The Link Daily Report table is sorted based on the information in the Avg Send or Avg Send Erlangs column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then **MathError** appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > Link**.

- Step 2** In the tool bar of the right pane, from the Type drop-down menu, select Link Daily Statistics. (See [Table 13-1](#) for a list of report types and their contents).
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu (see [Table 13-1](#) for contents of each output type).
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.

The Send Utilization and Receive Utilization tables contain summary information as described below:

Field or Column	Description
Node	Name of the node for the link.
Signaling Point	Name of the signaling point for the link.
Linkset	Linkset for the object.
SLC	ID of the link.
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 6** Depending on what you select from the Output pulldown menu, the following information is displayed:

Field or Column	Description
<b>Graph</b>	
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Utilization Percentage	If Output Type is Graph, the Y-axis label shows daily link statistics over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.
<b>Table, CSV</b>	
Node	Name of the node for the link.
SP Name	Name of the signaling point for the link.
Linkset Name	Linkset for the object.
SLC	ID of the link.
Timestamp ( <i>time zone</i> )	Timestamp of the report
Type	Type of link. Possible link types are: <ul style="list-style-type: none"> <li>• <b>HSL</b>—Uses the SS7-over-ATM (Asynchronous Transfer Mode) high-speed protocol.</li> <li>• <b>SCTP</b>—Uses the Stream Control Transmission Protocol (SCTP) IP transport protocol.</li> <li>• <b>Serial</b>—Uses the serial SS7 signaling protocol.</li> <li>• <b>Virtual</b>—A virtual link that connects signaling point instances that run on the same node. The MWTM does not poll virtual links; nor does it display real-time data or accounting statistics for virtual links.</li> </ul>
Daily In-Service %	Percentage of time the link was in service on the specified date.
Long Term In-Service %	Average percentage of time the link was in service since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.
Daily Low In-Service %	Lowest hourly in-service percentage for the link for the specified date.
Low Service Hour	Hour in which the lowest in-service percentage occurred for the specified date.
Avg Congestion %	Average percentage of time the link was congested on the specified date.

Field or Column	Description
Send	<ul style="list-style-type: none"> <li>• <b>Average Utilization %</b>—Average Send for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>Peak Utilization %</b>—Highest Send for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>Peak Hour</b>—Hour in which the Peak Send for the link occurred for the specified date.  Click the hour to see the Link Hourly Report for the chosen link and hour.</li> <li>• <b>Long Term Average Utilization %</b>—Long-term average Send for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>MSUs</b>—Total number of MTP3 message signal units (MSUs) sent on the specified date and hour.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• <b>Average Utilization %</b>—Average Receive for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>Peak Utilization %</b>—Highest Receive for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>Peak Hour</b>—Hour in which the Peak Receive for the link occurred for the specified date.  Click the hour to see the Link Hourly Report for the chosen link and hour.</li> <li>• <b>Long Term Average Utilization %</b>—Long-term average Receive for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>MSUs</b>—Total number of MTP3 message signal units (MSUs) received on the specified date and hour.</li> </ul>

## Link Peaks Statistics Daily Reports


You can view a daily link statistics peaks report using the Link Peaks Daily Report page. The peaks report shows peak values for each day and the hour in which each peak value occurred.

The Link Peaks Daily table is sorted based on the information in the Peak Send or Peak Send Erlangs column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > Link**.
- Step 2** In the tool bar of the right pane, from the Type drop-down menu, select Link Peaks Daily Statistics. (See [Table 13-1](#) for a list of report types and their contents).
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu (see [Table 13-1](#) for contents of each output type).
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.

The Send Utilization and Receive Utilization tables contain summary information as described below:

Field or Column	Description
Node	Name of the node for the link.
Signaling Point	Name of the signaling point for the link.
Linkset	Linkset for the object.
SLC	ID of the link.

Field or Column	Description
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 6** Depending on what you select from the Output pulldown menu, the following information is displayed:

Field or Column	Description
<b>Graph</b>	
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Utilization %	If Output Type is Graph, the Y-axis label shows daily link statistics over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.
<b>Table, CSV</b>	
Node	Name of the node for the link.
SP Name	Name of the signaling point for the link.
Linkset Name	Linkset for the object.
SLC	ID of the link.
Timestamp ( <i>time zone</i> )	Timestamp of the report
Type	Type of link. Possible link types are: <ul style="list-style-type: none"> <li>• <b>HSL</b>—Uses the SS7-over-ATM (Asynchronous Transfer Mode) high-speed protocol.</li> <li>• <b>SCTP</b>—Uses the Stream Control Transmission Protocol (SCTP) IP transport protocol.</li> <li>• <b>Serial</b>—Uses the serial SS7 signaling protocol.</li> <li>• <b>Virtual</b>—A virtual link that connects signaling point instances that run on the same node. The MWTM does not poll virtual links; nor does it display real-time data or accounting statistics for virtual links.</li> </ul>

Field or Column	Description
Send	<ul style="list-style-type: none"> <li>• <b>Peak Utilization</b>—Highest Send for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>Peak Hour</b>—Hour in which the Peak Send for the link occurred for the specified date.  Click the hour to see the Link Hourly Report for the chosen link and hour.</li> <li>• <b>Long Term Average Utilization</b>—Long-term average Send for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>MSUs</b>—Total number of MTP3 message signal units (MSUs) sent on the specified date and hour.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• <b>Peak Utilization</b>—Highest Receive for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>Peak Hour</b>—Hour in which the Peak Receive for the link occurred for the specified date.  Click the hour to see the Link Hourly Report for the chosen link and hour.</li> <li>• <b>Long Term Average Utilization</b>—Long-term average Receive for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for the SCTP link, then NoCap appears in the field.</li> <li>• <b>MSUs</b>—Total number of MTP3 message signal units (MSUs) received on the specified date and hour.</li> </ul>

## Link Multi-Day Report

The Link Multi-Day Report page shows send and receive percentages for all links for the last three or five days.

The Link Multi-Day table is sorted based on the information in the Avg Send column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > Link Multi-Day**.

**Step 2** In the tool bar of the right pane, from the Type pulldown menu, select Link Statistics Multi-Day. (See [Table 13-1](#) for a list of report types and their contents).

**Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.

The information described in the following table is displayed for the duration you selected.

**Note**

If there are less than five days of data available, the Link Multi-Day Report displays N/A for the days for which there is no data.

Field or Column	Description
Node	Name of the node for the link.
Network Name	Name of the network for the link.
Signaling Point	Name of the signaling point for the link.
Link	Name of the link.
Avg. Send Utilization (%)	Send for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for each of the last five days. If you do not set the planned send capacity for the SCTP link, then <code>NoCap</code> appears in the field.
Avg. Receive Utilization (%)	Receive for the link, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for each of the last five days. If you do not set the planned receive capacity for the SCTP link, then <code>NoCap</code> appears in the field.

## Linkset Reports

You can view summary reports of hourly and daily statistics for linksets, and export the reports.

This section covers:

- [Linkset Statistics Hourly Reports, page 13-82](#)
- [Linkset Statistics Daily Reports, page 13-85](#)
- [Linkset Peaks Statistics Daily Reports, page 13-88](#)

## Linkset Statistics Hourly Reports


You can view hourly summaries of statistics for all linksets or for a specific linkset that the MWTM detected on the specified date and hour. The Linkset Hourly Report page shows summary reports for all archived MWTM hourly linkset statistics by date and hour.

The Linkset Hourly Report table is sorted based on the information in the Send Utilization column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns](#), page 4-24).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > Linkset**.
- Step 2** In the tool bar of the right pane, from the Type drop-down menu, select Linkset Hourly Statistics. (See [Table 13-1](#) for a list of report types and their contents).
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu (see [Table 13-1](#) for contents of each output type).
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.

The Send Utilization and Receive Utilization tables contain summary information as described below:

Field or Column	Description
Node	Name of the node for the linkset.
Signaling Point	Name of the signaling point for the linkset.
Linkset	Linkset for the object.

Field or Column	Description
Send	<ul style="list-style-type: none"><li>• Average—Average Send for the statistic for the specified time.</li><li>• Minimum—Minimum Send for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum Send for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>
Receive	<ul style="list-style-type: none"><li>• Average—Average Receive for the statistic for the specified time.</li><li>• Minimum—Minimum Receive for the statistic for the specified time.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum Receive for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>

**Step 6** Depending on what you select from the Output pulldown menu, the following information is displayed:

Field or Column	Description
<b>Graph</b>	
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Utilization Percentage	If Output Type is Graph, the Y-axis label shows hourly linkset utilization over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.
<b>Table, CSV</b>	
Node	Name of the node for the linkset.
SP Name	Name of the signaling point for the linkset.
Linkset Name	Linkset for the object.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Hourly In-Service (%)	Percentage of time the linkset was in service on the specified date.
Long Term In-Service (%)	Average percentage of time the linkset was in service since MWTM polling began for the link, or since the MWTM last reset the averages as a result of bad data.
Send Utilization (%)	<p>Average Send for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.</p> <p>If you do not set the planned send capacity for one or more of the SCTP links associated with the linkset, then NoCap appears in the field.</p>
Long Term Send Utilization (%)	<p>Long-term average Send for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the linkset, or since the MWTM last reset the averages as a result of bad data.</p> <p>If you do not set the planned send capacity for one or more of the SCTP links associated with the linkset, then NoCap appears in the field.</p>
Receive Utilization (%)	<p>Average Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.</p> <p>If you do not set the planned receive capacity for one or more of the SCTP links associated with the linkset, then NoCap appears in the field.</p>
Long Term Receive Utilization (%)	<p>Long-term average Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the linkset, or since the MWTM last reset the averages as a result of bad data.</p> <p>If you do not set the planned receive capacity for one or more of the SCTP links associated with the linkset, then NoCap appears in the field.</p>

## Linkset Statistics Daily Reports


You can view daily summaries of statistics for all linksets or for a specific linkset that the MWTM detected on the specified date and hour. The Linkset Daily Report page shows summary reports of all archived MWTM daily linkset statistics by date and hour.

The Linkset Daily Report table is sorted based on the information in the Send Average column. You can sort the table based on the information in one of the other columns (see [Navigating Table Columns](#), page 4-24).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > Linkset**.
- Step 2** In the tool bar of the right pane, from the Type drop-down menu, select Linkset Daily Statistics. (See [Table 13-1](#) for a list of report types and their contents).
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu (see [Table 13-1](#) for contents of each output type).
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.

The Send Utilization and Receive Utilization tables contain summary information as described below:

Field or Column	Description
Node	Name of the node for the linkset.
Signaling Point	Name of the signaling point for the linkset.
Linkset	Linkset for the object.

Field or Column	Description
Send	<ul style="list-style-type: none"> <li>• Average—Average Send for the statistic for the specified time.</li> <li>• Minimum—Minimum Send for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Send for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• Average—Average Receive for the statistic for the specified time.</li> <li>• Minimum—Minimum Receive for the statistic for the specified time.</li> <li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>• Maximum—Maximum Receive for the statistic for the specified time.</li> <li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 6** Depending on what you select from the Output pulldown menu, the following information is displayed:

Field or Column	Description
<b>Graph</b>	
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Utilization Percentage	If Output Type is Graph, the Y-axis label shows daily linkset statistics over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.
<b>Table, CSV</b>	
Date	Date of the report.
Node	Name of the node for the linkset.
SP Name	Name of the signaling point for the linkset.
Linkset Name	Linkset for the object.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Daily In-Service (%)	Percentage of time the linkset was in service on the specified date.
Long Term In-Service (%)	Average percentage of time the linkset was in service since MWTM polling began for the linkset, or since the MWTM last reset the averages as a result of bad data.
Daily Low In-Service (%)	Lowest hourly in-service percentage for the linkset for the specified date.
Low Service Hour	Hour in which the lowest in-service percentage occurred for the specified date.

Field or Column	Description
Send	<ul style="list-style-type: none"> <li>• <b>Average Utilization (%)</b>—Average Send for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned receive capacity for one or more of the SCTP links associated with the linkset, then <b>NoCap</b> appears in the field.</li> <li>• <b>Peak Utilization (%)</b>—Highest Send for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.</li> <li>• <b>Peak Hour</b>—Hour in which the Peak Send for the linkset occurred for the specified date.  Click the hour to see the Link Hourly Report for all links associated with the chosen linkset for the chosen hour.</li> <li>• <b>Long Term Average Utilization (%)</b>—Long-term average Send for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the linkset, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for one or more of the SCTP links associated with the linkset, then <b>NoCap</b> appears in the field.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• <b>Average Utilization (%)</b>—Average Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.  If you do not set the planned receive capacity for one or more of the SCTP links associated with the linkset, then <b>NoCap</b> appears in the field.</li> <li>• <b>Peak Utilization (%)</b>—Highest Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.</li> <li>• <b>Peak Hour</b>—Hour in which the Peak Receive for the linkset occurred for the specified date.  Click the hour to see the Link Hourly Report for all links associated with the chosen linkset for the chosen hour.</li> <li>• <b>Long Term Average Utilization (%)</b>—Long-term average Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the linkset, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for one or more of the SCTP links associated with the linkset, then <b>NoCap</b> appears in the field.</li> </ul>

### Linkset Peaks Statistics Daily Reports


You can view a linkset daily statistics peaks report using the Linkset Peaks Daily Report page. The peaks report shows peak values for each day and the hour in which each peak value occurred.



The Linkset Peaks Daily Report table is sorted based on the information in the Peak Send or Peak Send Erlangs column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns](#), page 4-24).

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > Linkset**.
- Step 2** In the tool bar of the right pane, from the Type drop-down menu, select Linkset Peaks Daily Statistics. (See [Table 13-1](#) for a list of report types and their contents).
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu (see [Table 13-1](#) for contents of each output type).
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.

The Send Utilization and Receive Utilization tables contain summary information as described below:

Field or Column	Description
Node	Name of the node for the linkset.
Signaling Point	Name of the signaling point for the linkset.
Linkset	Linkset for the object.
Send	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Minimum—Minimum Send for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Minimum—Minimum Receive for the statistic for the specified time.</li> <li>Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li> </ul>

**Step 6** Depending on what you select from the Output pulldown menu, the following information is displayed:

Field or Column	Description
<b>Graph</b>	
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Utilization Percentage	If Output Type is Graph, the Y-axis label shows daily linkset statistics over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.
<b>Table, CSV</b>	
Node	Name of the node for the linkset.
SP Name	Name of the signaling point for the linkset.
Linkset Name	Linkset for the object.
Timestamp ( <i>time zone</i> )	Timestamp of the report.

Field or Column	Description
Send	<ul style="list-style-type: none"> <li>• <b>Peak Utilization %</b>—Highest Send or Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.</li> <li>• <b>Peak Hour</b>—Hour in which the Peak Send or Peak Receive for the linkset occurred for the specified date. Click the hour to see the Link Hourly Report for all links associated with the chosen linkset for the chosen hour.</li> <li>• <b>Long Term Average Utilization %</b>—Long-term average Send or Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the linkset, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for one or more of the SCTP links associated with the linkset, then <b>NoCap</b> appears in the field.</li> </ul>
Receive	<ul style="list-style-type: none"> <li>• <b>Peak Utilization %</b>—Highest Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command) for the specified date and hour.</li> <li>• <b>Peak Hour</b>—Hour in which the Peak Receive for the linkset occurred for the specified date. Click the hour to see the Link Hourly Report for all links associated with the chosen linkset for the chosen hour.</li> <li>• <b>Long Term Average Utilization %</b>—Long-term average Receive for the linkset, expressed as a percentage or number of Erlangs (E) (as set with the <b>mwtm webutil</b> command), since MWTM polling began for the linkset, or since the MWTM last reset the averages as a result of bad data.  If you do not set the planned send capacity for one or more of the SCTP links associated with the linkset, then <b>NoCap</b> appears in the field.</li> </ul>

## MLR Reports

Multi-Layer SMS Routing, or MLR, is a routing scheme that enables intelligent routing of Short Message Service (SMS) mobile originated (MO) messages based on the application or service from which they originated or to which they are destined. The MLR feature can make SMS message routing decisions based on information found in the TCAP, MAP, and MAP-user layers; MAP operation codes MAP-MT-FORWARD-SM and SEND-ROUTING-INFO-FOR-SM; and ANSI TCAP and IS-41 MAP operations.

You can view a summary report of daily statistics for MLR. You can also export the reports.

## Daily MLR Reports

You can view a summary report of MLR processed, aborts, continues, result invokes, rule matches, subtriggers, and triggers statistics for the MWTM on a specified date. The MLR *type* Daily Report page shows reports of all archived MWTM daily MLR processed, aborts, continues, result invokes, rule matches, subtriggers, and triggers by date.

These archived daily MLR reports are available:

- [MLR Aborts Statistics Daily Reports, page 13-92](#)
- [MLR Continues Statistics Daily Reports, page 13-93](#)
- [MLR Processed Statistics Daily Reports, page 13-93](#)
- [MLR ResultInvokes Statistics Daily Reports, page 13-94](#)
- [MLR RuleMatches Statistics Daily Reports, page 13-95](#)
- [MLR SubTriggers Statistics Daily Reports, page 13-95](#)
- [MLR Triggers Statistics Daily Reports, page 13-96](#)

## MLR Aborts Statistics Daily Reports

The MLR Aborts Statistics Custom Report table is sorted based on the information in the Total Aborted column. However, you can sort the table based on the information in one of the columns (see [Navigating Table Columns, page 4-24](#)).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the signaling point.
Network Name	Name of the network for the signaling point.
Signaling Point	Name of the signaling point.
Total Aborted	Total number of MSUs aborted by MLR on the specified date.
No Resources	Number of MSUs aborted by MLR because of a shortage of resources on the specified date.
Results Blocked	Number of MSUs aborted by MLR with a result of <b>block</b> on the specified date.
GTI Mismatches	Number of MSUs aborted by MLR because of mis-matched GTIs on the specified date.
Address Conversion Failures	Number of MSUs aborted by MLR because of a failed GTA address conversion on the specified date.
Destination Unavailables	Number of MSUs aborted by MLR because the destination was unavailable on the specified date.
No Server Aborted	Number of MSUs aborted by MLR because no server was available on the specified date.

## MLR Continues Statistics Daily Reports

The MLR Continues Statistics Custom Report table is sorted based on the information in the Total Continued column. However, you can sort the table based on the information in one of the columns (see [Navigating Table Columns, page 4-24](#)).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the signaling point.
Network Name	Name of the network for the signaling point.
Signaling Point	Name of the signaling point.
Total Continued	Total number of MSUs returned to SCCP by MLR with a result of <b>continue</b> on the specified date.
Unsupported Message Type	Number of MSUs returned to SCCP by MLR because of unsupported message types on the specified date.
Unsupported Seg SCCP	Number of MSUs returned to SCCP by MLR because of unsupported SCCP segments on the specified date.
Unsupported Messages	Number of MSUs returned to SCCP by MLR because of parse failures resulting from unsupported messages on the specified date.
Parse Errors	Number of MSUs returned to SCCP by MLR because of parse errors on the specified date.
No Results	Number of MSUs returned to SCCP by MLR with no results on the specified date.
Result Continueds	Number of MSUs returned to SCCP by MLR with a result of <b>continue</b> on the specified date.
No Server Continueds	Number of MSUs returned to SCCP by MLR because no server was available on the specified date.
Result GTTs	Number of MSUs returned to SCCP by MLR with a result of <b>GTT</b> on the specified date.
Failed Triggers	Number of MSUs returned to SCCP by MLR because of no trigger match on the specified date.

## MLR Processed Statistics Daily Reports

The MLR Processed Statistics Custom Report table is sorted based on the information in the Routed column. However, you can sort the table based on the information in one of the columns (see [Navigating Table Columns, page 4-24](#)).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the signaling point.
Network Name	Name of the network for the signaling point.
Signaling Point	Name of the signaling point.
Routed	Total number of packets routed by MLR on the specified date.
Total Continued	Total number of MSUs passed back to SCCP processing by MLR on the specified date.
Total Aborted	Total number of MSUs not processed by MLR because of invalid data or a blocked MSU.
MAP SMS-MOs	Number of MSUs of type GSM-MAP SMS-MO processed by MLR on the specified date.
MAP SMS-MTs	Number of MSUs of type GSM-MAP SMS-MT processed by MLR on the specified date.
MAP SRI-SMs	Number of MSUs of type GSM-MAP SRI-SM processed by MLR on the specified date.
MAP AlertScs	Number of MSUs of type GSM-MAP AlertSc processed by MLR on the specified date.
ANSI-41 SMD-PPs	Number of MSUs of type ANSI-41 SMD-PP processed by MLR on the specified date.
ANSI-41 SMS-Requests	Number of MSUs of type ANSI-41 SMSRequest processed by MLR on the specified date.
ANSI-41 SMS-Notifys	Number of MSUs of type ANSI-41 SMSNotify processed by MLR on the specified date.
Links	Contains links to related MLR reports (Aborts, Continues, Triggers, SubTriggers, RuleMatches, and ResultInvokes). The target report is filtered by the signaling point.

### MLR ResultInvokes Statistics Daily Reports

The MLR ResultInvokes Statistics Custom Report table is sorted based on the information in the Invokes column. However, you can sort the table based on the information in one of the columns (see [Navigating Table Columns](#), page 4-24).



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the signaling point.
Network Name	Name of the network for the signaling point.

Field or Column	Description
Signaling Point	Name of the signaling point.
ResultSet	Name of the result set of which this result is a member.
Result Number	Number of this result in the result set.
Invokes	Total number of times this result was invoked.

### MLR RuleMatches Statistics Daily Reports

The MLR RuleMatches Statistics Custom Report table is sorted based on the information in the Matches column. However, you can sort the table based on the information in one of the columns (see [Navigating Table Columns](#), page 4-24).



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the signaling point.
Network Name	Name of the network for the signaling point.
Signaling Point	Name of the signaling point.
RuleSet	Name of the rule set of which this rule is a member.
Rule Number	Number of this rule in the rule set.
Matches	Total number of times this rule was matched.

### MLR SubTriggers Statistics Daily Reports

The MLR SubTriggers Statistics Custom Report table is sorted based on the information in the Matches column. However, you can sort the table based on the information in one of the columns (see [Navigating Table Columns](#), page 4-24).



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the signaling point.
Network Name	Name of the network for the signaling point.
Signaling Point	Name of the signaling point.
Trigger Index	Index number associated with the trigger.
Sub Trigger Index	Index number associated with the subtrigger.

Field or Column	Description
Action	Action taken by the subtrigger. Clicking on the ruleset name highlights the signaling point in the navigation tree and opens the MLR Trigger Config tab for the chosen ruleset.
Parameters	Parameters that control the behavior of the subtrigger.
Matches	Number of subtrigger matches with result <b>Action Performed</b> .

## MLR Triggers Statistics Daily Reports

The MLR Triggers Statistics Custom Report table is sorted based on the information in the Matches column. However, you can sort the table based on the information in one of the columns (see [Navigating Table Columns, page 4-24](#)).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the signaling point.
Network Name	Name of the network for the signaling point.
Signaling Point	Name of the signaling point.
Trigger Index	Index number associated with the trigger.
Action	Action taken by the trigger. Clicking on the ruleset name highlights the signaling point in the navigation tree and opens the MLR Trigger Config tab for the chosen ruleset.
Parameters	Parameters that control the behavior of the trigger.
Preliminary Matches	Preliminary count of trigger matches.
Matches	Number of trigger matches with result <b>Action Performed</b> .
Links	Contains links to related MLR SubTrigger reports. The target report is filtered by the signaling point.

## MSU Rates Reports

You can view 15 minute, hourly, and daily MSU rates reports. You can also export the reports in CSV format.

This section covers:

- [MSU Load Statistics Reports, page 13-96](#)
- [MSU Peaks Statistics Reports, page 13-98](#)

## MSU Load Statistics Reports

The MSU Load Report provides the distribution of send and receive MSU packets, pertaining to overload thresholds for every CPU.



The MSU Load Report tables are sorted based on the information in the Date column. However, you can sort the tables based on the information in one of the columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > MSU Rates**.



**Note** The 15-minute and hourly reports for MSU Load are available from the node level only; they are not available from the top level or the network level. Click on a node name in the MSU Load reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose MSU Load Statistics Daily from Type drop-down menu.

The Send Average MSU Rate and Receive Average MSU Rate tables contain summary information as described below:

Field or Column	Description
Node	You can click on a node name to go to node-specific reports.
Processor Slot/Bay	Number of the processor and the number of the bay containing the processor. This number is set to zero when the platform does not support processors in multiple slots or bays.
Send Average MSU Rate	Average MSU rate sent over the last duration.
Receive Average MSU Rate	Average MSU rate received over the last duration.
Maximum Date ( <i>time zone</i> )	Time when the maximum MSU load received value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

GUI Element	Description
<i>Graph</i>	If you select <b>Graph</b> from the Output menu, the graph displays the SCTP send and receive packets rates over the specified time period.
<i>Table</i>	
Date	Date of the report.
Node	Name of the node.
Processor Slot/Bay	Number of the processor and the number of the bay containing the processor. This number is set to zero when the platform does not support processors in multiple slots or bays.
Overloaded Threshold	Over this rate of traffic, MSU traffic handling may be impacted.
Duration % Send	Duration of time the send MSU rate is in the specified percentage.
Duration % Receive	Duration in time the receive MSU rate is in the specified percentage.
Send Average MSU Rate	Average MSU rate sent over the last duration.
Receive Average MSU Rate	Average MSU rate received over the last duration.
Total MSU Send	Total MSU sent over the last duration.
Total MSU Receive	Total MSU received over the last duration.

## MSU Peaks Statistics Reports

You can view a 15 minute, hourly, or daily report of MSU peak rates for all nodes that the MWTM detected in that time. The MSU Peaks Report page provides information that helps you analyze the maximum send and receive rates for each processor in MSU units per second.



### Note

A cron job needs to be implemented at device level to reset the MSU Peak Rate every hour. This has to be done in the config mode as follows:

```
kron occurrence resetMsuPeaks in 1:0 recurring
policy-list resetMsuPeaks
kron policy-list resetMsuPeaks
cli clear cs7 msu-rates peak
```

This is applicable only for ITP devices having 12.2(33)IRG.

The MSU Peaks Report tables are sorted based on the information in the Send column. However, you can sort the tables based on the information in one of the columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > MSU Rates**.



**Note** The 15-minute and hourly reports for MSU Peak are available from the node level only; they are not available from the top level or the network level. Click on a node name in the MSU Peak reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose MSU Peak Statistics Daily from Type drop-down menu.

The Send Max Rate and Receive Max Rate tables contain summary information as described below:

Field or Column	Description
Node	You can click on a node name to go to node-specific reports.
Processor Slot/Bay	Number of the processor and the number of the bay containing the processor. This number is set to zero when the platform does not support processors in multiple slots or bays.
Send Max Rate	Maximum MSU rate sent over the last duration.
Receive Max Rate	Maximum MSU rate received over the last duration.
Maximum Date ( <i>time zone</i> )	Time when the maximum MSU load received value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

GUI Element	Description
<i>Graph</i>	If you select <b>Graph</b> from the Output menu, the graph displays the SCTP send and receive packets rates over the specified time period.
<i>Table</i>	
Date	Date of the report.
Node	Name of the node.
Processor Slot/Bay	Number of the processor and the number of the bay containing the processor. This number is set to zero when the platform does not support processors in multiple slots or bays.
Max Rate (MSU/sec) Send	This value records the highest rate of MSUs per second sent by the processor since the measurement was cleared.
Max Rate (MSU/sec) Receive	This value records the highest rate of MSU per second received by the processor since the measurement was cleared.
Threshold (MSU/sec) Acceptable	Specifies a level of traffic below which traffic is considered to be acceptable. Once the traffic rate exceeds the Warning threshold, it is not Acceptable until traffic falls below this threshold.
Threshold (MSU/sec) Warning	Specifies a level of traffic that should be avoided, but is below a level that impacts MSU routing. Once the traffic rate exceeds the Overloaded threshold, it is not considered non-impacting until the traffic falls below this threshold.
Threshold (MSU/sec) Overloaded	Specifies a level of traffic indicating a rate that might impact MSU routing.
Duration in Acceptable Threshold (Seconds) Send	Rate of traffic (in seconds) sent by this processor considered as acceptable.
Duration in Acceptable Threshold (Seconds) Receive	Rate of traffic (in seconds) received by this processor considered as acceptable.
Duration in Overloaded Threshold (Seconds) Send	Rate of traffic (in seconds) sent by this processor at a level that might impact MSU routing.
Duration in Overloaded Threshold (Seconds) Receive	Rate of traffic (in seconds) received by this processor at a level that might impact MSU routing.

## SCTP Reports

The MWTM web interface provides node-level SCTP reports for performance and error statistics. The information is available in graphical, tabular, and CSV formats.



### Note

SCTP Reports are supported on ITP platforms only.

To generate a network-wide SCTP report:

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > SCTP**. You can also click on a node name, then select the Reports tab.

**Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu:

- [SCTP Performance Daily Reports, page 13-101](#)
- [SCTP Errors Daily Reports, page 13-102](#)



**Note** The 15-minute and hourly reports for SCTP are available from the node level only; they are not available from the top level or the network level.

## SCTP Performance Daily Reports

MWTM displays the SCTP performance rates obtained during the specified period.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > ITP Statistics > SCTP**.



**Note** The 15-minute and hourly reports for SCTP are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SCTP reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose SCTP Performance Daily from Type drop-down menu.

The Sent Packets and Receive Packets tables contain summary information as described below:

Field or Column		Description
Node		You can click on a node name to go to node-specific reports.
Send	Average Packets	Average SCTP packets sent.
	Maximum Packets	Maximum SCTP packets sent.
	Maximum Date ( <i>time zone</i> )	Time when the maximum SCTP packets sent value occurred.
Receive	Average Packets	Average SCTP packets received.
	Maximum Packets	Maximum SCTP packets received.
	Maximum Date ( <i>time zone</i> )	Time when the maximum SCTP packets received value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

GUI Element	Description
<i>Graph</i>	If you select <b>Graph</b> from the Output menu, the graph displays the SCTP send and receive packets rates over the specified time period.
<i>Table</i>	<p>If you select <b>Table</b> from the Output menu, the table contains:</p> <ul style="list-style-type: none"> <li>• Node—Name of the node.</li> <li>• Timestamp (<i>time zone</i>)—Timestamp of the report.</li> <li>• Send <ul style="list-style-type: none"> <li>– SCTP Packets—Number of SCTP packets sent to peers.</li> <li>– Control Chunks—Number of SCTP control chunks sent to peers (no transmissions included).</li> <li>– Ordered Chunks—Number of SCTP ordered data chunks sent to peers (no transmissions included).</li> <li>– Unordered Chunks—Number of SCTP unordered chunks (which are data chunks in which the U bit is set to one) sent to peers (no transmissions included).</li> </ul> </li> <li>• Receive <ul style="list-style-type: none"> <li>– SCTP Packets—Number of SCTP packets received from peers.</li> <li>– Control Chunks—Number of SCTP control chunks received from peers (no transmissions included).</li> <li>– Ordered Chunks—Number of SCTP ordered data chunks received from peers (no transmissions included).</li> <li>– Unordered Chunks—Number of SCTP unordered chunks (which are data chunks in which the U bit is set to one) received from peers (no transmissions included).</li> </ul> </li> </ul>
Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
Packets	If Output Type is Graph, the Y-axis label shows percentage of utilization over time.
Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

## SCTP Errors Daily Reports

MWTM displays the SCTP error rates obtained during the specified period.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Statistics > SCTP**.

**Note**

The 15-minute and hourly reports for SCTP are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SCTP reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose SCTP Errors Daily from Type drop-down menu.

The summary table displays the following information:

Field or Column	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Unassociated Packets	Number of SCTP packets received by the host which are correctly formed but for which the receiver is not able to identify the association to which the packet belongs.
Checksum Errors	Number of SCTP packets received from peers with an invalid checksum.
Fragmented User Messages	Number of user messages that have to be fragmented because of the MTU.
Reassembled User Messages	Number of user messages reassembled.
Retransmitted Chunks	Number of SCTP chunks retransmitted due to the T3 timers expiring before the packet is acknowledged.
Retransmitted Chunks (Fast Recovery)	Number of SCTP chunks retransmitted using the fast-recovery retransmission mechanism specified in SCTP.
Destination Address Failures	Number of times a destination IP address was marked unavailable since the start of the association. The IP destination address will be marked unavailable when the specified number of retransmissions have failed.

## Viewing Mobile Statistics Reports

Mobile Statistics Reports are located within **Reports > Mobile Statistics** in the MWTM web interface. You can also find Mobile statistics reports in the `/opt/CSCOs/gm/reports` directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All reports are saved as export files in .csv format.



You can view any of the following Mobile statistics reports:

- [CSG Reports, page 13-104](#)
- [GGSN Reports, page 13-129](#)
- [PDNGW Reports, page 13-160](#)
- [PDSN Reports, page 13-190](#)
- [SGW Reports, page 13-203](#)
- [SPGW Reports, page 13-226](#)

## CSG Reports

The MWTM web interface provides node-level Content services reports. Content Service is a capability to examine IP/TCP/UDP headers, payload and enable billing based on the content being provided.

To generate a network-wide Content services report:

- 
- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Table or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [CSG BMA Statistics Daily Reports, page 13-105](#)
- [CSG Global Peak Rates Daily Reports, page 13-106](#)
- [CSG Gx Global Statistics Daily Reports, page 13-108](#)
- [CSG Protocol Rates Daily Reports, page 13-109](#)
- [CSG Load Session Rates Daily Reports, page 13-110](#)
- [CSG Load Radius Rates Daily Reports, page 13-111](#)
- [CSG Load BMA Rates Daily Reports, page 13-112](#)
- [CSG Load User DB Rates Daily Reports, page 13-113](#)
- [CSG Load Gx Event Rates Daily Reports, page 13-114](#)
- [CSG Quota Manager Statistics Daily Reports, page 13-115](#)
- [CSG Billing Plan Statistics Daily Reports, page 13-116](#)
- [CSG Gx Global Message Statistics Daily Reports, page 13-117](#)
- [CSG Gx Global Message Errors Daily Reports, page 13-118](#)
- [CSG Gx PCRF Method List Message Statistics Daily Reports, page 13-119](#)
- [CSG Gx PCRF Method List Message Errors Daily Reports, page 13-120](#)
- [CSG Gx Policy Preload Statistics Daily Reports, page 13-121](#)



- [CSG Gx Policy Preload Errors Daily Reports, page 13-122](#)
- [CSG Gx Policy Preload Accounting Policy Statistics Daily Reports, page 13-123](#)
- [CSG Gx Policy Preload Billing Plan Statistics Daily Reports, page 13-124](#)
- [CSG Gx Policy Preload Billing Services Statistics Daily Reports, page 13-125](#)
- [CSG Gx Policy Preload Content Policy Statistics Daily Reports, page 13-126](#)
- [CSG Gx Policy Preload Service Content Statistics Daily Reports, page 13-127](#)
- [CSG Load Quota Manager Rates Daily, page 13-128](#)

## CSG BMA Statistics Daily Reports

MWTM displays the CSG BMA Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



### Note

The 15-minute and hourly CSG BMA Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG BMA Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose CSG BMA Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Server	Name of the Server.
Port	Name of the Port.
VRF Name	Name of the VRF.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Sent	Number of records sent to the billing mediation agent.
Sent Per Second	Number of records sent per second to the billing mediation agent.
Retransmits	Number of messages retransmitted to the billing mediation agent.
Failed Acks	Number of acknowledgments received from the billing mediation agent for which there are no outstanding requests.
Lost Records	Number of lost records since system initialization or the last time the counter wrapped.
Bad Records	Number of bad records received. These are records in which an error was detected while attempting to decode the contents.

### CSG Global Peak Rates Daily Reports

MWTM displays the CSG Global Peaks Rates Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Global Peaks Rates reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Global Peaks Rates reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Global Peaks Rates Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Users	<ul style="list-style-type: none"><li>• Average—Average CSG rate for the specified duration.</li><li>• Minimum—Minimum CSG rate during the specified duration.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum CSG rate during the specified duration.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>
Sessions	<ul style="list-style-type: none"><li>• Average—Average CSG rate for the specified duration.</li><li>• Minimum—Minimum CSG rate during the specified duration.</li><li>• Minimum Date (<i>time zone</i>)—Timestamp when the minimum value occurred.</li><li>• Maximum—Maximum CSG rate during the specified duration.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
CSG Global Peak Rates Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Time value occurred.
		Average Users	The average number of users using the network.
		Peak Users	The maximum number of users using the network.
		Average Sessions	The average number of sessions in the network.
		Peak Sessions	The maximum number of sessions in the network.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Peak Users/ Peak Sessions	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		Utilization	If Output Type is Graph, a color-coded legend shows labels for utilization.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## CSG Gx Global Statistics Daily Reports

MWTM displays the CSG Gx Global Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



### Note

The 15-minute and hourly CSG Gx Global Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Global Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Gx Global Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Time value occurred.
Gx Rule Activation Failure	<ul style="list-style-type: none"> <li>Count—Number of Gx rule activation failures.</li> <li>Rate—Rate of Gx rule activation failures.</li> </ul>
Gx Rule Deactivation Failure	<ul style="list-style-type: none"> <li>Count—Number of Gx rule deactivation failures.</li> <li>Rate—Rate of Gx rule deactivation failures.</li> </ul>
Gx Revalidation Success	<ul style="list-style-type: none"> <li>Count—Number of Gx revalidation success.</li> <li>Rate—Rate of Gx revalidation success.</li> </ul>
Gx Revalidation Failure	<ul style="list-style-type: none"> <li>Count—Number of Gx revalidation failures.</li> <li>Rate—Rate of Gx revalidation failures.</li> </ul>

### CSG Protocol Rates Daily Reports

MWTM displays the CSG Protocol Rates Daily report obtained during the specified period.



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



**Note**

The 15-minute and hourly CSG Protocol Rates reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Protocol Rates reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Protocol Rates Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Protocol	Name of the protocol.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Inspection Method	The type of inspection method applied in the network.
Transactions	<ul style="list-style-type: none"> <li>Count—Total number of transactions occurred in the network.</li> <li>Rate—Number of transactions occurred in the network per second.</li> <li>Peak—The highest number of transactions occurred in the network per second.</li> </ul>
Subscriber Send Packets	<ul style="list-style-type: none"> <li>Count—Total number of outgoing subscriber packets.</li> <li>Rate—Number of outgoing subscriber packets per second.</li> <li>Peak—The highest number of outgoing subscriber packets per second.</li> </ul>
Subscriber Send Bits	<ul style="list-style-type: none"> <li>Count—Total number of outgoing subscriber bits.</li> <li>Rate—Number of outgoing subscriber bits per second.</li> <li>Peak—The highest number of outgoing subscriber bits per second.</li> </ul>
Network Send Packets	<ul style="list-style-type: none"> <li>Count—Total number of outgoing network packets.</li> <li>Rate—Number of outgoing network packets per second.</li> <li>Peak—The highest number of outgoing network packets per second.</li> </ul>
Network Send Bits	<ul style="list-style-type: none"> <li>Count—Total number of outgoing network bits.</li> <li>Rate—Number of outgoing network bits per second.</li> <li>Peak—The highest number of outgoing network bits per second.</li> </ul>

### CSG Load Session Rates Daily Reports

MWTM displays the CSG Load Session Rates Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Load Session Rates reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Load Session Rates reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Load Session Rates Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
IPC Queue Depth Tolerance	Maximum queue depth for Radius Start requests in the IPC queue.
Allowed	Number of outgoing Radius Start requests allowed.
Allowed Rate	Number of outgoing Radius Start requests allowed per second.
Allowed Peak	Number of outgoing Radius Start maximum requests allowed.
Denied	Number of outgoing Radius Start requests denied.
Denied Rate	Number of outgoing Radius Start requests denied per second.
Denied Peak	Number of outgoing Radius Start maximum requests denied.

### CSG Load Radius Rates Daily Reports

MWTM displays the CSG Load Radius Rates Daily report obtained during the specified period.



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



**Note**

The 15-minute and hourly CSG Load Radius Rates reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Load Radius Rates reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Load Radius Rates Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
IPC Queue Depth Tolerance	Maximum queue depth for Radius Start requests in the IPC queue.
Allowed	Number of outgoing Radius Start requests allowed.
Allowed Rate	Number of outgoing Radius Start requests allowed per second.
Allowed Peak	Number of outgoing Radius Start maximum requests allowed.
Denied	Number of outgoing Radius Start requests denied.
Denied Rate	Number of outgoing Radius Start requests denied per second.
Denied Peak	Number of outgoing Radius Start maximum requests denied.

### CSG Load BMA Rates Daily Reports

MWTM displays the CSG Load BMA Rates Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Load BMA Rates reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Load BMA Rates reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Load BMA Rates Daily from the Type drop-down menu.



A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
IPC Queue Depth Tolerance	Maximum queue depth for Radius Start requests in the IPC queue.
Allowed	Number of outgoing Radius Start requests allowed.
Allowed Rate	Number of outgoing Radius Start requests allowed per second.
Allowed Peak	Number of outgoing Radius Start maximum requests allowed.
Denied	Number of outgoing Radius Start requests denied.
Denied Rate	Number of outgoing Radius Start requests denied per second.
Denied Peak	Number of outgoing Radius Start maximum requests denied.

### CSG Load User DB Rates Daily Reports

MWTM displays the CSG Load User DB Rates Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Load User DB Rates reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Load User DB Rates reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose CSG Load User DB Rates Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
IPC Queue Depth Tolerance	Maximum queue depth for Radius Start requests in the IPC queue.
Allowed	Number of outgoing Radius Start requests allowed.
Allowed Rate	Number of outgoing Radius Start requests allowed per second.
Allowed Peak	Number of outgoing Radius Start maximum requests allowed.
Denied	Number of outgoing Radius Start requests denied.
Denied Rate	Number of outgoing Radius Start requests denied per second.
Denied Peak	Number of outgoing Radius Start maximum requests denied.

### CSG Load Gx Event Rates Daily Reports

MWTM displays the CSG Load Gx Event Rates Daily report, obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Load Gx Event Rates reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Load Gx Event Rates reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Load Gx Event Rates Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
IPC Queue Depth Tolerance	Maximum queue depth for Radius Start requests in the IPC queue.
Allowed	<ul style="list-style-type: none"> <li>Count—Number of outgoing Radius Start requests allowed.</li> <li>Rate—Number of outgoing Radius Start requests allowed per second.</li> <li>Peak—Number of outgoing Radius Start maximum requests allowed.</li> </ul>
Denied	<ul style="list-style-type: none"> <li>Count—Number of outgoing Radius Start requests denied.</li> <li>Rate—Number of outgoing Radius Start requests denied per second.</li> <li>Peak—Number of outgoing Radius Start maximum requests denied.</li> </ul>

### CSG Quota Manager Statistics Daily Reports

MWTM displays the CSG Quota Manager Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Quota Manager Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Quota Manager Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose CSG Quota Manager Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Server	Name of the Server.
Port	Name of the Port.
VRF Name	Name of the VRF.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Sent	Number of records sent to the billing mediation agent.
Sent Per Second	Number of records sent per second to the billing mediation agent.
Retransmits	Number of messages retransmitted to the billing mediation agent.
Failed Acks	Number of acknowledgments received from the billing mediation agent for which there are no outstanding requests.
Lost Records	Number of lost records since system initialization or the last time the counter wrapped.
Bad Records	Number of bad records received. These are records in which an error was detected while attempting to decode the contents.

### CSG Billing Plan Statistics Daily Reports

MWTM displays the CSG Billing Plan Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Billing Plan Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Billing Plan Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Billing Plan Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Billing Plan Name	Name of the billing plan.
Subscriber Count	Number of subscribers associated with a given Billing Plan.
Peak Subscriber Count	The highest number of subscribers associated with a given Billing Plan.

### CSG Gx Global Message Statistics Daily Reports

MWTM displays the CSG Gx Global Message Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Gx Global Message Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Global Message Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose CSG Gx Global Message Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Active Sessions	Number of sessions which are in active state.
Credit Control Request	<p><b>Initial Messages Sent</b></p> <ul style="list-style-type: none"> <li>Count—Number of CCR-Initial messages sent.</li> <li>Rate—Rate at which the CCR-Initial messages are sent.</li> </ul> <p><b>Update Messages Sent</b></p> <ul style="list-style-type: none"> <li>Count—Number of CCR-Update messages sent.</li> <li>Rate—Rate at which the CCR-Update messages are sent.</li> </ul> <p><b>Final Messages Sent</b></p> <ul style="list-style-type: none"> <li>Count—Number of CCR-Final messages sent.</li> <li>Rate—Rate at which the CCR-Final messages are sent.</li> </ul>
Credit Control Answer Messages Received	<ul style="list-style-type: none"> <li>Count—Number of CCA received.</li> <li>Rate—Rate at which the CCA are received.</li> </ul>
Reauthorization	<p><b>Request Messages Received</b></p> <ul style="list-style-type: none"> <li>Count—Number of RRR received.</li> <li>Rate—Rate at which the RRR are received.</li> </ul> <p><b>Answer Messages Sent</b></p> <ul style="list-style-type: none"> <li>Count—Number of RAR sent.</li> <li>Rate—Rate at which the RAR sent.</li> </ul>

## CSG Gx Global Message Errors Daily Reports

MWTM displays the CSG Gx Global Message Errors Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



### Note

The 15-minute and hourly CSG Gx Global Message Errors reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Global Message Errors reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Gx Global Message Errors Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Invalid Message Type Errors	Number of invalid message type errors.
Duplicate Request Errors	Number of duplicate request type errors.
Credit Control	<ul style="list-style-type: none"> <li>Response Failures—Number of Failures to send CCR.</li> <li>Answer Errors—Number of errors occurred in CCA.</li> </ul>
Reauthorization Answer Failures	<ul style="list-style-type: none"> <li>Answer Failures—Number of failures to send CCA.</li> <li>Response Errors—Number of failures occurred in RAR</li> </ul>
Invalid Request	<ul style="list-style-type: none"> <li>Type Errors—Number of errors due to invalid request type.</li> <li>Number Errors—Number of errors due to invalid request number.</li> <li>Status Errors—Number of errors due to invalid request status.</li> </ul>
Invalid Session ID Errors	Number of times the session id received does not exist.

### CSG Gx PCRF Method List Message Statistics Daily Reports

MWTM displays the CSG Gx PCRF Method List Message Statistics Daily report obtained during the specified period.



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



**Note**

The 15-minute and hourly CSG Gx PCRF Method List Message Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx PCRF Method List Message Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Gx PCRF Method List Message Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Method List Name	Method list name.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Active Sessions	Number of sessions which are in active state.
Credit Control Request	<b>Initial Messages Sent</b> <ul style="list-style-type: none"> <li>Count—Number of CCR-Initial messages sent.</li> <li>Rate—Rate at which the CCR-Initial messages are sent.</li> </ul> <b>Update Messages Sent</b> <ul style="list-style-type: none"> <li>Count—Number of CCR-Update messages sent.</li> <li>Rate—Rate at which the CCR-Update messages are sent.</li> </ul> <b>Final Messages Sent</b> <ul style="list-style-type: none"> <li>Count—Number of CCR-Final messages sent.</li> <li>Rate—Rate at which the CCR-Final messages are sent.</li> </ul>
Credit Control Answer Messages Received	<ul style="list-style-type: none"> <li>Count—Number of CCA received.</li> <li>Rate—Rate at which the CCA are received.</li> </ul>
Reauthorization	<b>Request Messages Received</b> <ul style="list-style-type: none"> <li>Count—Number of RRR received.</li> <li>Rate—Rate at which the RRR are received.</li> </ul> <b>Answer Messages Sent</b> <ul style="list-style-type: none"> <li>Count—Number of RAR sent.</li> <li>Rate—Rate at which the RAR sent.</li> </ul>

### CSG Gx PCRF Method List Message Errors Daily Reports

MWTM displays the CSG Gx PCRF Method List Message Errors Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



**Note**

The 15-minute and hourly CSG Gx PCRF Method List Message Errors reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx PCRF Method List Message Errors reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Gx PCRF Method List Message Statistics Daily from the Type drop-down menu. A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Method List Name	Method list name.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
PCRF Reboots	Number of times PCRF reboots.
Invalid Message Type Errors	Number of invalid message type errors.
Duplicate Request Errors	Number of duplicate request type errors.
Credit Control Response	<ul style="list-style-type: none"> <li>Response Failures—Number of Failures to send CCR.</li> <li>Answer Errors—Number of errors occurred in CCA.</li> </ul>
Reauthorization	<ul style="list-style-type: none"> <li>Answer Failures—Number of failures to send CCA.</li> <li>Response Errors—Number of failures occurred in RAR</li> </ul>
Invalid Request	<ul style="list-style-type: none"> <li>Type Errors—Number of errors due to invalid request type.</li> <li>Number Errors—Number of errors due to invalid request number.</li> <li>Status Errors—Number of errors due to invalid request status.</li> </ul>
Invalid Session ID Errors	Number of times the session id received does not exist.

## CSG Gx Policy Preload Statistics Daily Reports

MWTM displays the CSG Gx Policy Preload Statistics Daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.

**Note**

The 15-minute and hourly CSG Gx Policy Preload Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the Gx Policy Preload Daily Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Gx Policy Preload Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
PCEF Initiated Preloading	Number of PCEF initiated preloading
PCRF Initiated Preloading	Number of PCRF initiated preloading
Policy Preload Requests	Number of Policy Preload requests.
Policy Preload Responses	Number of Policy Preload responses.
Global Policy Push Count	Number of Global Policy Push.
Global Policy Push Acknowledgement	Number of Global Policy Push Acknowledgements.

### CSG Gx Policy Preload Errors Daily Reports

MWTM displays the CSG Gx Policy Preload Errors Daily report obtained during the specified period.



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



**Note**

The 15-minute and hourly CSG Gx Policy Preload Errors Daily Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Policy Preload Errors Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Gx Policy Preload Errors Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Preload Data Inconsistent	Number of times the preload data is inconsistent.
Attribute Value Pairs Missing	Number of times the mandatory AVPs are missing
Wrong Order Failures	Number of failures due to wrong order.
Enforcement Failures	Number of failures to enforce.
Static Configuration Conflicts	Number of conflicts with static config.
Invalid Message Type Errors	Number of invalid message type errors.
Credit Control	<ul style="list-style-type: none"> <li>Request Failures—Number of times failed to send CCR.</li> <li>Answer Errors—Number of errors occurred in CCA.</li> </ul>
Reauthorization	<ul style="list-style-type: none"> <li>Answer Failures—Number of times failed to send RAA.</li> <li>Response Errors—Number of errors occurred in RAR.</li> </ul>
Invalid Request	<ul style="list-style-type: none"> <li>Type Errors—Number of errors due to invalid request type.</li> <li>Number Errors—Number of errors due to invalid request number.</li> <li>Status Errors—Number of errors due to invalid request status.</li> </ul>
Invalid Session ID Errors	Number of times the session id received does not exist.
Preload Timeout Errors	Number of times the preload timeout occurs.

### CSG Gx Policy Preload Accounting Policy Statistics Daily Reports

MWTM displays the CSG Gx Policy Preload Accounting Policy Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Gx Policy Preload Accounting Policy Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Policy Preload Accounting Policy Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Gx Policy Preload Errors Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Accounting Policy	<ul style="list-style-type: none"> <li>Inserted—Number of accounting policy-maps inserted during preload.</li> <li>Deleted—Number of accounting policy-maps deleted during preload.</li> <li>Rolled Back—Number of times rollback is successful on insertion/deletion of accounting policy-maps during preload.</li> <li>Insert Failed —Number of times insertion of accounting policy-maps has failed.</li> <li>Delete Failed—Number of times deletion of accounting policy-maps has failed.</li> <li>Roll Back Failed—Number of times rollback has failed on insertion/deletion of accounting policy-maps during preload.</li> </ul>

### CSG Gx Policy Preload Billing Plan Statistics Daily Reports

MWTM displays the CSG Gx Policy Preload Billing Plan Statistics Daily report obtained during the specified period.



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



**Note**

The 15-minute and hourly CSG Gx Policy Preload Billing Plan Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Policy Preload Billing Plan Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose CSG Gx Policy Preload Billing Plan Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Billing Plans	<ul style="list-style-type: none"> <li>• Inserted—Number of billing-plans inserted during preload.</li> <li>• Deleted—Number of billing-plans deleted during preload.</li> <li>• Rolled Back—Number of times rollback is successful on insertion/deletion of billing-plans during preload.</li> <li>• Insert Failed —Number of times insertion of billing-plans has failed.</li> <li>• Delete Failed—Number of times deletion of billing-plans has failed.</li> <li>• Roll Back Failed—Number of times rollback has failed on insertion/deletion of billing-plans during preload.</li> </ul>

### CSG Gx Policy Preload Billing Services Statistics Daily Reports

MWTM displays the CSG Gx Policy Preload Billing Services Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Gx Policy Preload Billing Services Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Policy Preload Billing Services Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose CSG Gx Policy Preload Billing Services Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Billing Services	<ul style="list-style-type: none"> <li>Inserted—Number of billing-services inserted during preload.</li> <li>Deleted—Number of billing-services deleted during preload.</li> <li>Rolled Back—Number of times rollback is successful on insertion/deletion of billing-services during preload.</li> <li>Insert Failed —Number of times insertion of billing-services has failed.</li> <li>Delete Failed—Number of times deletion of billing-services has failed.</li> <li>Roll Back Failed—Number of times rollback has failed on insertion/deletion of billing-services during preload.</li> </ul>

### CSG Gx Policy Preload Content Policy Statistics Daily Reports

MWTM displays the CSG Gx Policy Preload Content Policy Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Gx Policy Preload Content Policy Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Policy Preload Content Policy Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose CSG Gx Policy Preload Content Policy Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Content Policies	<ul style="list-style-type: none"> <li>Inserted—Number of content-policies inserted during preload.</li> <li>Deleted—Number of content-policies deleted during preload.</li> <li>Rolled Back—Number of times rollback is successful on insertion/deletion of content-policies during preload.</li> <li>Insert Failed —Number of times insertion of content-policies has failed.</li> <li>Delete Failed—Number of times deletion of content-policies has failed.</li> <li>Roll Back Failed—Number of times rollback has failed on insertion/deletion of billing-services during preload.</li> </ul>

### CSG Gx Policy Preload Service Content Statistics Daily Reports

MWTM displays the CSG Gx Policy Preload Service Content Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Gx Policy Preload Service Content Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Gx Policy Preload Service Content Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose CSG Gx Policy Preload Service Content Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Service Contents	<ul style="list-style-type: none"> <li>Inserted—Number of service-contents inserted during preload.</li> <li>Deleted—Number of service-contents deleted during preload.</li> <li>Rolled Back—Number of times rollback is successful on insertion/deletion of service-contents during preload.</li> <li>Insert Failed —Number of times insertion of service-contents has failed.</li> <li>Delete Failed—Number of times deletion of service-contents has failed.</li> <li>Roll Back Failed—Number of times rollback has failed on insertion/deletion of service-contents during preload.</li> </ul>

### CSG Load Quota Manager Rates Daily

MWTM displays the CSG Load Quota Manager Rates Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > CSG**.



#### Note

The 15-minute and hourly CSG Load Quota Manager Rates Daily report are available from the node level only; they are not available from the top level or the network level. Click on a node name in the CSG Load Quota Manager Rates Daily report to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose CSG Load Quota Manager Rates Daily from the Type drop-down menu.



A summary table displays the information described in the following table:



Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
IPC Queue Depth Tolerance	Maximum queue depth for Quota Manager requests in the IPC queue.
Allowed	Number of outgoing Quota Manager requests allowed.
Allowed Rate	Number of outgoing Quota Manager requests allowed per second.
Allowed Peak	Number of outgoing Quota Manager maximum requests allowed.
Denied	Number of outgoing Quota Manager requests denied.
Denied Rate	Number of outgoing Quota Manager requests denied per second.
Denied Peak	Number of outgoing Quota Manager maximum requests denied.

## GGSN Reports

The MWTM web interface provides node-level GGSN reports. To generate a network-wide GGSN report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** If available, choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow ).

The Type drop-down menu contains the following reports:

- [APN Aggregate Miscellaneous Statistics Daily Reports, page 13-130](#)
- [APN Aggregate PDP/Bearer Statistics Daily Reports, page 13-133](#)
- [APN Aggregate PDP/Bearer Extended Statistics Daily Reports, page 13-136](#)
- [APN Aggregate Throughput Statistics Daily Reports, page 13-139](#)
- [APN Instance Miscellaneous Statistics Daily Reports, page 13-143](#)
- [APN Instance PDP/Bearer Statistics Daily Reports, page 13-143](#)
- [APN Instance PDP/Bearer Extended Statistics Daily Reports, page 13-143](#)
- [APN Instance Throughput Statistics Daily Reports, page 13-143](#)
- [APN Instance DHCP V6 Proxy Server Statistics Daily Reports, page 13-143](#)

- [GTP Active Statistics Daily Reports, page 13-146](#)
- [GTP Charging Statistics Daily Reports, page 13-149](#)
- [GTP Error Statistics Daily Reports, page 13-151](#)
- [GTP PDP Statistics Daily Reports, page 13-152](#)
- [GTP Throughput Statistics Daily Reports, page 13-153](#)
- [Charging Group Statistics Daily Reports, page 13-156](#)
- [Charging Gateway Group Statistics Daily, page 13-157](#)

**Note**

The 15-minute and hourly reports for GGSN are available from the node level only; they are not available from the top level or the network level.

## APN Aggregate Miscellaneous Statistics Daily Reports

MWTM displays the APN Aggregate Miscellaneous Statistics Daily report obtained during the specified period.

**Note**

The same column names are displayed for **APN Instance Miscellaneous Statistics Daily Reports** with the addition of the column Node. Also, the same column names are displayed for APN Aggregate Miscellaneous Statistics Daily Reports of GGSN and PDNGW reports.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1**

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN, SPGW or PDNGW**

**Note**

The 15-minute and hourly reports for APN Aggregate Miscellaneous Statistics and APN Instance Miscellaneous Statistics are available from the node level only; they are not available from the top level or the network level. Click on a node name in the APN Aggregate Miscellaneous Statistics or in the APN Instance Miscellaneous Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2**

Choose APN Aggregate Miscellaneous Statistics Daily (or APN Instance Miscellaneous Statistics Daily) from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
APN	The name of the Access Point Name (APN).
Average Redirected Inter Mobile Traffic	Average of packets, pertaining to inter mobile communication, that have been redirected to device specified by cgprsAccPtRedirInterMobilAddr.
Maximum Redirected Inter Mobile Traffic	Maximum number of packets, pertaining to inter mobile communication, that have been redirected to device specified by cgprsAccPtRedirInterMobilAddr.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
APN Aggregate Miscellaneous Statistics Daily  (or APN Instance Miscellaneous Statistics Daily)	Table, CSV	APN Name	The name of the Access Point Name (APN).
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		DHCP Requests Success	<ul style="list-style-type: none"> <li>Count—Number of DHCP request packets.</li> <li>Rate—Rate at which DHCP packets are requested.</li> <li>Ratio—Ratio of DHCP successful request packets.</li> </ul>
		DHCP Requests Failure	<ul style="list-style-type: none"> <li>Count—Number of DHCP failure packets.</li> <li>Rate—Rate at which DHCP packets are declined.</li> </ul>
		DHCP Releases	<ul style="list-style-type: none"> <li>Count—Number of DHCP released packets.</li> <li>Rate—Rate at which DHCP packets released.</li> </ul>
		COA Message Success	<ul style="list-style-type: none"> <li>Count—Number of COA messages received at GGSN or PDNGW.</li> <li>Rate—Rate at which COA messages received at GGSN or PDNGW.</li> <li>Ratio—Ratio of COA messages received at GGSN or PDNGW.</li> </ul>
		COA Message Failure	<ul style="list-style-type: none"> <li>Count—Number of Error indication messages received on the GGSN or PDNGW.</li> <li>Rate—Rate at which Error indication messages received on the GGSN or PDNGW.</li> </ul>
		Direct Tunnels Enabled	<ul style="list-style-type: none"> <li>Count—Direct tunnels enabled for the PDP contexts in the GGSN or PDNGW.</li> <li>Rate—Rate at which the direct tunnels are enabled for the PDP contexts in the GGSN or PDNGW.</li> </ul>
		Redirected Inter Mobile Traffic	<ul style="list-style-type: none"> <li>Count—Total number of packets, pertaining to inter mobile communication, that have been redirected to device specified by cgprsAccPtRedirInterMobilAddr.</li> <li>Rate—Rate of packets, pertaining to inter mobile communication, that have been redirected to device specified by cgprsAccPtRedirInterMobilAddr.</li> </ul>
		DHCP Message Sent Error	<ul style="list-style-type: none"> <li>Count—Number of error messages sent.</li> <li>Rate—Rate at which error messages sent.</li> </ul>
		DHCP Message Receive IP Allocation Error	<ul style="list-style-type: none"> <li>Count—Number of error messages received.</li> <li>Rate—Rate at which error messages received.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Redirected Inter Mobile Traffic	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

### APN Aggregate PDP/Bearer Statistics Daily Reports

MWTM displays the APN Aggregate PDP/Bearer Statistics Daily report obtained during the specified period.



#### Note

The same column names are displayed for **APN Instance PDP/Bearer Statistics Daily Reports** with the addition of the column **Node**. Also, the same column names are displayed for APN Aggregate PDP/Bearer Statistics Daily Reports of GGSN and PDNGW reports.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN, SPGW or PDNGW**.



#### Note

The 15-minute and hourly reports for APN Aggregate PDP/Bearer Statistics and APN Instance PDP/Bearer Statistics are available from the node level only; they are not available from the top level or the network level. Click on a node name in the APN Aggregate PDP/Bearer Statistics reports or in the APN Instance PDP/Bearer Statistics to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose APN Aggregate PDP/Bearer Statistics Daily (or APN Instance PDP/Bearer Statistics Daily) from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
APN	The name of the Access Point Name (APN).
APN Index	A unique numerical identifier for the APN.
Average Active PDP/Bearer Contexts	Average Number of PDP/Bearer contexts that are currently established on the GGSN or PDNGW devices.
Maximum Active PDP/Bearer Contexts	Maximum Number of PDP/Bearer contexts that are currently established on the GGSN or PDNGW devices.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.
Average PDP/Bearer Activation Success Ratio	Average ratio of PDP/Bearer context request messages received by the GGSN or PDNGW devices.
Maximum PDP/Bearer Activation Success Ratio	Maximum ratio of PDP/Bearer context request messages received by the GGSN or PDNGW devices.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.
Average PDP/Bearer Retainability Ratio	Average ratio of PDP/Bearer context messages retained by the GGSN or PDNGW devices.
Maximum PDP/Bearer Retainability Ratio	Maximum ratio of PDP/Bearer context messages retained by the GGSN or PDNGW devices.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
APN Aggregate PDP/Bearer Statistics Daily (or APN Instance PDP/Bearer Statistics Daily)	Table, CSV	APN Name	The name of the Access Point Name (APN).
		APN Index	A unique numerical identifier for the APN.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Active PDP/Bearers	<ul style="list-style-type: none"> <li>Count—Number of active PDP contexts or Bearers on this APN.</li> </ul>
		PDP/Bearer Activation by MS Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed PDP context/Bearer activation procedures by the MS on this APN.</li> <li>Rate—Rate (per second) of successfully completed PDP context/Bearer activation procedures by the MS on this APN.</li> <li>Ratio—Number of successful activations for every 100 activation attempts.</li> </ul>
		PDP/Bearer Activation by MS Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed PDP context/Bearer activation procedures by the MS on this APN.</li> <li>Rate—Rate (per second) of failed PDP context/Bearer activation procedures by the MS on this APN.</li> </ul>
		PDP/Bearer Deactivations by Network Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed PDP context/Bearer deactivation procedures by the GGSN or PDNGW on this APN.</li> <li>Rate—Rate (per second) of successfully completed PDP context/Bearer deactivation procedures by the GGSN or PDNGW on this APN.</li> </ul>
		PDP/Bearer Deactivations by Network Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed PDP context/Bearer deactivation procedures by the GGSN or PDNGW on this APN.</li> <li>Rate—Rate (per second) of failed PDP context/Bearer deactivation procedures by the GGSN or PDNGW on this APN.</li> </ul>
		PDP/Bearer Retainability	<ul style="list-style-type: none"> <li>Ratio—For every 100 PDP contexts/Bearers, the number of activations whose deactivation was not completed by the network.</li> </ul>

Report Type	Output	Field	Description
		PDP/Bearer Deactivations by MS Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed PDP context/Bearer deactivation procedures by the MS on this APN.</li> <li>Rate—Rate (per second) of successfully completed PDP context/Bearer deactivation procedures by the MS on this APN.</li> <li>Ratio—Number of successful deactivations for every 100 deactivation attempts.</li> </ul>
		PDP/Bearer Deactivations by MS Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed PDP context/Bearer deactivation procedures by the MS on this APN.</li> <li>Rate—Rate (per second) of failed PDP context/Bearer deactivation procedures by the MS on this APN.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Active PDP/Bearer Contexts/ PDP/Bearer Activation Success Ratio PDP/Bearer Retainability Ratio	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

### APN Aggregate PDP/Bearer Extended Statistics Daily Reports

MWTM displays the APN Aggregate PDP/Bearer Extended Statistics Daily report obtained during the specified period.



#### Note

The same column names are displayed for **APN Instance PDP/Bearer Extended Statistics Daily Reports** with the addition of the column Node. Also, the same column names are displayed for APN Aggregate PDP/Bearer Extended Statistics Daily Reports of GGSN and PDNGW reports.



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN**.

**Note**

The 15-minute and hourly reports for APN Aggregate PDP/Bearer Extended Statistics and APN Instance PDP/Bearer Extended Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the APN Aggregate PDP/Bearer Extended Statistics reports or in the APN Instance PDP/Bearer Extended Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose APN Aggregate PDP/Bearer Extended Statistics Daily (or APN Instance PDP/Bearer Extended Statistics Daily) from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
APN	The name of the Access Point Name (APN).
Node	Name of the node.
APN Index	A unique numerical identifier for the APN.
Successful Dynamic PDP/Bearer Activations by MS Ratio	<ul style="list-style-type: none"> <li>Average—Average number of successful dynamic activations for every 100 dynamic activation attempts.</li> <li>Maximum—Maximum number of successful dynamic activations for every 100 dynamic activation attempts.</li> <li>Maximum Date (<i>time zone</i>)—Time the maximum value occurred.</li> </ul>
Successful PDP/Bearer Activations By Network Ratio	<ul style="list-style-type: none"> <li>Average—Average number of successful activations for every 100 dynamic activation attempts.</li> <li>Maximum—Maximum number of successful activations for every 100 dynamic activation attempts.</li> <li>Maximum Date (<i>time zone</i>)—Time the maximum value occurred.</li> </ul>
Successful Dedicated Bearer Activations Ratio	<ul style="list-style-type: none"> <li>Average—Average number of successful dedicated activations for every 100 dynamic activation attempts.</li> <li>Maximum—Maximum number of successful dedicated activations for every 100 dynamic activation attempts.</li> <li>Maximum Date (<i>time zone</i>)—Time the maximum value occurred.</li> </ul>

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
APN Aggregate PDP/Bearer Extended Statistics Daily	Table, CSV	APN Name	The name of the Access Point Name (APN).
		APN Index	A unique numerical identifier for the APN.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Dynamic PDP/Bearer Activations By MS Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed dynamic PDP/Bearer context activation procedures initiated by MS on this APN.</li> <li>Rate—Rate (per second) of successfully completed dynamic PDP/Bearer context activation procedures initiated by MS on this APN.</li> <li>Ratio—Number of successful dynamic activations for every 100 dynamic activation attempts.</li> </ul>
		Dynamic PDP/Bearer Activations By MS Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed dynamic PDP/Bearer context activation procedures initiated by MS on this APN.</li> <li>Rate—Rate (per second) of failed dynamic PDP/Bearer context activation procedures initiated by MS on this APN.</li> </ul>
		PDP/Bearer Activations By Network Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed network initiated PDP/Bearer context activation procedures.</li> <li>Rate—Rate (per second) of successfully completed network initiated PDP/Bearer context activation procedures.</li> <li>Ratio—Number of successful network initiated activations for every 100 activation attempts.</li> </ul>
		PDP/Bearer Activations By Network Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed network initiated PDP/Bearer context activation procedures.</li> <li>Rate—Rate (per second) of failed network initiated PDP/Bearer context activation procedures.</li> </ul>
		PDP/Bearer Updates By Network Success	<ul style="list-style-type: none"> <li>Count—Total number of successful update responses received from the SGSN for GGSN or PDNGW initiated update requests on this APN.</li> <li>Rate—Rate (per second) of successful update responses received from the SGSN for GGSN or PDNGW initiated update requests on this APN.</li> <li>Ratio—Number of successful update responses received for every 100 update attempts.</li> </ul>

Report Type	Output	Field	Description
		PDP/Bearer Updates By Network Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed update responses received from the SGSN for GGSN or PDNGW initiated update requests on this APN.</li> <li>Rate—Rate (per second) of failed update responses received from the SGSN for GGSN or PDNGW initiated update requests on this APN.</li> </ul>
		Dedicated Bearer Activations Success	<ul style="list-style-type: none"> <li>Count—Total number of successful dedicated bearer activation procedures received on this APN.</li> <li>Rate—Rate (per second) of successful dedicated bearer activation procedures received on this APN.</li> <li>Ratio—Number of successful dedicated bearer activation procedures for every 100 activation attempts.</li> </ul>
		Dedicated Bearer Activations Failure	<ul style="list-style-type: none"> <li>Count—Total number of unsuccessful dedicated bearer activation procedures received on this APN.</li> <li>Rate—Rate (per second) of unsuccessful dedicated bearer activation procedures received on this APN.</li> </ul>
	Graph	Successful Dynamic PDP/Bearer Activations by MS Ratio	Number of successful dynamic activations for every 100 dynamic activation attempts.
		Successful PDP/Bearer Activations By Network Ratio	Number of successful activations for every 100 dynamic activation attempts.
		Successful Dedicated Bearer Activations Ratio	Number of successful dedicated activations for every 100 dynamic activation attempts.

### APN Aggregate Throughput Statistics Daily Reports

MWTM displays the APN Aggregate Throughput Statistics Daily report obtained during the specified period.



#### Note

The same column names are displayed for **APN Instance Throughput Statistics Daily Reports** with the addition of the column Node. Also, the same column names are displayed for APN Aggregate Throughput Statistics Daily Reports of GGSN, PDNGW, and SGW reports.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN, PDNGW, SGW, or SPGW**.



**Note** The 15-minute and hourly reports for APN Aggregate Throughput Statistics and APN Instance Throughput Statistics are available from the node level only; they are not available from the top level or the network level. Click on a node name in the APN Aggregate Throughput Statistics reports or in the APN Instance Throughput Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose APN Aggregate Throughput Statistics Daily (APN Instance Throughput Statistics Daily) from the Type drop-down menu.

A summary table displays the information described in the following table:

GUI Element	Field	Description
	APN	The name of the Access Point Name (APN).
	APN Index	A unique numerical identifier for the APN.
Upstream Bits	Average Rate	Average Rate during the specified duration.
	Maximum Rate	Maximum Rate during the specified duration.
	Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum bits-per-second value occurred.
Downstream Bits	Average Rate	Average Rate during the specified duration.
	Maximum Rate	Maximum Rate during the specified duration.
	Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum bits-per-second value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
APN Aggregate Throughput Statistics Daily (or APN Instance Throughput Statistics Daily)	Table, CSV	APN Name	The name of the Access Point Name (APN).
		APN Index	The Unique identifier for the Access Point Name.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Upstream Bits	<ul style="list-style-type: none"> <li>Count—Number of upstream bytes sent on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of upstream bytes sent on this APN during the last sampling period.</li> </ul>
		Downstream Bits	<ul style="list-style-type: none"> <li>Count—Number of downstream bytes sent on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of downstream bytes sent on this APN during the last sampling period.</li> </ul>
		Upstream Packets	<ul style="list-style-type: none"> <li>Count—Number of upstream packets sent on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of upstream packets sent on this APN during the last sampling period.</li> </ul>
		Downstream Packets	<ul style="list-style-type: none"> <li>Count—Number of downstream packets sent on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of downstream packets sent on this APN during the last sampling period.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Upstream Throughput Rate/Downstream Throughput Rate	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

### APN Instance Miscellaneous Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Miscellaneous Statistics Daily report with the addition of the column Node. See [APN Aggregate Miscellaneous Statistics Daily Reports, page 13-130](#).

### APN Instance PDP/Bearer Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate PDP/Bearer Statistics Daily report with the addition of the column Node. See [APN Aggregate PDP/Bearer Statistics Daily Reports, page 13-133](#).

### APN Instance PDP/Bearer Extended Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate PDP/Bearer Extended Statistics Daily report with the addition of the column Node. See [APN Aggregate PDP/Bearer Extended Statistics Daily Reports, page 13-136](#).

### APN Instance Throughput Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Throughput Statistics Daily report with the addition of the column Node. See [APN Aggregate Throughput Statistics Daily Reports, page 13-139](#).

### APN Instance DHCP V6 Proxy Server Statistics Daily Reports

MWTM displays the APN Instance DHCP V6 Proxy Server Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN, SPGW**.



#### Note

The 15-minute and hourly reports for APN Instance DHCP V6 Proxy Server Statistics is available from the node level only; they are not available from the top level or the network level. Click on a node name in the APN Aggregate DHCP V6 Proxy Server Statistics reports or in the APN Instance DHCP V6 Proxy Server Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose APN Instance DHCP V6 Proxy Server Statistics Daily from the Type drop-down menu. A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Information Request Received	Information request received on this APN during the last sampling period.

Field	Description
Information Request Sent	Information request sent on this APN during the last sampling period.
Information Request Location Sent	Information request location sent on this APN during the last sampling period.
IP Allocation Success	IP allocation successes on this APN during the last sampling period.
IP Release	IP releases on this APN during the last sampling period.
Maximum Date (EST)	Timestamp when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:



Report Type	Output	Field	Description
APN Instance DHCP V6 Proxy Server Statistics Daily	Table, CSV	Node	Name of the node for the object.
		APN	The name of the Access Point Name (APN).
		Timestamp EDT( <i>time zone</i> )	Timestamp of the report.
		Information Request Received/Sent	<ul style="list-style-type: none"> <li>Count—Number of information request received/sent on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of information request received/sent on this APN during the last sampling period.</li> </ul>
		Information Request Location Sent	<ul style="list-style-type: none"> <li>Count—Number of location request sent on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of location request sent on this APN during the last sampling period.</li> </ul>
		IP Allocation Success/Fail	<ul style="list-style-type: none"> <li>Count—Number of IP allocation success/fail on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of IP allocation success/fail on this APN during the last sampling period.</li> </ul>
		IP Release	<ul style="list-style-type: none"> <li>Count—Number of IP release on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of IP release on this APN during the last sampling period.</li> </ul>
		IP Renew Fail	<ul style="list-style-type: none"> <li>Count—Number of IP renew fails on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of IP renew fails on this APN during the last sampling period.</li> </ul>
		Unknown Message	<ul style="list-style-type: none"> <li>Count—Number of unknown messages on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of unknown messages on this APN during the last sampling period.</li> </ul>

Report Type	Output	Field	Description
		Errors	<ul style="list-style-type: none"> <li>Count—Number of errors on this APN during the last sampling period.</li> <li>Rate—Rate (per second) of errors on this APN during the last sampling period.</li> </ul>
	Graph	APN Instance DHCP V6 Proxy Server Statistics Daily Information Request Received	Displays the graph of information request received on this APN during the last sampling period.
		APN Instance DHCP V6 Proxy Server Statistics Daily Information Request Sent	Displays the graph of information request sent on this APN during the last sampling period.
		APN Instance DHCP V6 Proxy Server Statistics Daily Information Request Location Sent	Displays the graph of information request location sent on this APN during the last sampling period.
		APN Instance DHCP V6 Proxy Server Statistics Daily IP Allocation Success	Displays the graph of IP allocation success on this APN during the last sampling period.
		APN Instance DHCP V6 Proxy Server Statistics Daily IP Release	Displays the graph of IP releases on this APN during the last sampling period.

## GTP Active Statistics Daily Reports

MWTM displays the GTP Active Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN**.



### Note

The 15-minute and hourly GTP Active Statistics (GGSN) reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Active Statistics (GGSN) reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTP Active Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Average Active Sessions	Average sessions which are in active state.
Maximum Active Sessions	Maximum sessions which are in active state.
Maximum Date (time zone)	Timestamp when the maximum value occurred.
Average GTP v0 PDP Contexts	Average PDP contexts (GTP version 0) that are active.
Maximum GTP v0 PDP Contexts	Maximum PDP contexts (GTP version 0) that are active.
Maximum Date (time zone)	Timestamp when the maximum value occurred.
Average GTP v1 PDP Contexts	Average PDP contexts (GTP version 1) that are active.
Maximum GTP v1 PDP Contexts	Maximum PDP contexts (GTP version 1) that are active.
Maximum Date (time zone)	Timestamp when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Active Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Active Sessions	Total number of sessions currently established with the system.
		Direct Tunnel PDP Contexts	Direct tunnels enabled for the PDP contexts in the GGSN.
		GTP v0 PDP Contexts	PDP contexts (GTP version 0) that are active.
		GTP v1 PDP Contexts	PDP contexts (GTP version 1) that are active.
		PPP Regen PDPs	Device-specific interfaces created for association with PDP contexts regenerated to a Point-to-Point (PPP) session.
		PPP PDPs	Total number of point to point PDP contexts.
		Total Direct Tunnel	Enabled—Total number of direct tunnels enabled.  PDP Error Indications—Total number of PDP error indications.  PDP Deleted—Total number of direct tunnel PDPs deleted.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Active Sessions/ GTP v0 PDP Contexts/ GTP v1 PDP Contexts	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.

## GTP Charging Statistics Daily Reports

MWTM displays the GTP Charging Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.



### Note

The same column names are displayed for GTP Throughput Statistics Daily Reports of GGSN, PDNGW, and SGW reports.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN, PDNGW, SGW, or SPGW**.



### Note

The 15-minute and hourly GTP Charging Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Charging Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node. At the Node level, the summary table contains the additional columns - Data Type, Minimum, and Minimum Date (*time zone*).

### Step 2

Choose GTP Charging Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
CDR Messages Pending	<ul style="list-style-type: none"> <li>Average—Average Send for the statistic for the specified time.</li> <li>Maximum—Maximum Send for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>
CDR Messages Sent	<ul style="list-style-type: none"> <li>Average—Average Receive for the statistic for the specified time.</li> <li>Maximum—Maximum Receive for the statistic for the specified time.</li> <li>Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li> </ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Charging Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp (time zone)	Timestamp of the report.
		Current Containers	The number of currently open or closed charging containers.
		Current CDRs	<ul style="list-style-type: none"> <li>Open—The number of currently opened G-CDRs on the GGSN, PDNGW, SGW, or SPGW.</li> <li>Closed—The number of currently closed G-CDRs on the GGSN, PDNGW, SGW, or SPGW which have not been sent to the CG.</li> </ul>
		CDR Messages Pending	<ul style="list-style-type: none"> <li>Count—The number of currently pending G-CDR output messages.</li> </ul>
		CDR Messages Sent	<ul style="list-style-type: none"> <li>Count—The number of transmitted G-CDR output messages since the charging service is enabled.</li> <li>Rate—Rate of transmitted G-CDR output messages since the charging service is enabled.</li> </ul>
		CDRs Opened	<ul style="list-style-type: none"> <li>Count—Total number of CDRs opened on the GGSN, PDNGW, SGW, or SPGW either since system startup or since the last time the charging statistics was cleared.</li> <li>Rate—Rate of CDRs opened on the GGSN, PDNGW, SGW, or SPGW either since system startup or since the last time the charging statistics was cleared.</li> </ul>
		Containers Created	<ul style="list-style-type: none"> <li>Count—Total number of containers created on the GGSN, PDNGW, SGW, or SPGW either since system startup or since the last time the charging statistics was cleared.</li> <li>Rate—Rate of containers created on the GGSN, PDNGW, SGW, or SPGW either since system startup or since the last time the charging statistics was cleared.</li> </ul>
		Service Records Created	<ul style="list-style-type: none"> <li>Count—Total number of service records created on the GGSN, PDNGW, SGW, or SPGW either since the system startup or since the time the service aware feature is enabled.</li> <li>Rate—Rate of service records created on the GGSN, PDNGW, SGW, or SPGW either since the system startup or since the time the service aware feature is enabled.</li> </ul>

Report Type	Output	Field	Description
		Total Unique APNs	<ul style="list-style-type: none"> <li>Count—The number of access points for which charging data is being collected.</li> <li>Rate—Rate of access points for which charging data is being collected.</li> </ul>
		Charging Gateway Down Times	<ul style="list-style-type: none"> <li>Count—The number of occurrences of cgprsCgAlarmEchoFailure traps state transitions since system startup.</li> <li>Rate—Rate of occurrences of cgprsCgAlarmEchoFailure traps state transitions since system startup.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		CDR Messages Pending/CDR Messages Sent	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.

## GTP Error Statistics Daily Reports

MWTM displays the GTP Error Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN**.



### Note

The 15-minute and hourly GTP Error Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Error Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTP Error Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
PDP Context Activations	<ul style="list-style-type: none"> <li>Insufficient Resources Rejection—Number of PDP context requests rejected due to insufficient resources.</li> </ul>
PDP Context Requests	<ul style="list-style-type: none"> <li>PPP Regeneration Insufficient Resources Rejection—PDP context requests rejected due to insufficient resources for PPP regeneration.</li> <li>PPP Regeneration Threshold Limit Drops—Number of PDP context requests dropped due to the PPP regeneration threshold limit.</li> </ul>
PDP Context Messages	<ul style="list-style-type: none"> <li>TFT Semantic Errors—Total number of received PDP context messages that had Traffic Flow Templates (TFT) with semantic errors.</li> <li>TFT Syntax Errors—Total number of received PDP context messages that had TFTs with syntax errors.</li> <li>Packet Filter Semantic Errors—Total number of received PDP context messages that had packet filters with semantic errors.</li> <li>Packet Filter Syntax Errors—Total number of received PDP context messages that had packet filters with syntax errors.</li> </ul>
Signaling Messages	<ul style="list-style-type: none"> <li>Unexpected—Number of unexpected GTP signaling messages sent or received.</li> <li>GTP Message Parsers Errors—Number of GTP messages received with wrong value.</li> </ul>

## GTP PDP Statistics Daily Reports



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN**.



### Note

The 15-minute and hourly GTP PDP Statistics (GGSN) reports are available from the node level only; they are not available from the top level or the network level. Choose GTP PDP Statistics Daily from the Type drop-down menu.

### Step 2

Choose GTP PDP Statistics Daily (GTP PDP/Bearer Statistics Daily or GTP Bearer Statistics Daily) from the Type drop-down menu.

A summary table displays the information described in the following table:



Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Activation Failure Ratio	Failure ratio.
Created	<ul style="list-style-type: none"> <li>Count—Number of PDP/Bearer contexts created.</li> <li>Rate—Rate at which the PDP/Bearer contexts are created.</li> </ul>
Rejected	<ul style="list-style-type: none"> <li>Count—Number of PDP/Bearer contexts rejected.</li> <li>Rate—Rate at which the PDP/Bearer contexts are rejected.</li> </ul>
Deleted	<ul style="list-style-type: none"> <li>Count—Number of PDP/Bearer contexts deleted.</li> <li>Rate—Rate at which the PDP/Bearer contexts are deleted.</li> </ul>

### GTP Throughput Statistics Daily Reports

MWTM displays the GTP Throughput Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.



#### Note

The same column names are displayed for GTP Throughput Statistics Daily Reports of GGSN, PDNGW, and SGW reports.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN, PDNGW, SGW, or SPGW**.



#### Note

The 15-minute and hourly GTP Throughput Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Throughput Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node. At the Node level, the summary table contains the additional columns - Data Type, Minimum, and Minimum Date (*time zone*).

#### Step 2

Choose GTP Throughput Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Send	<ul style="list-style-type: none"><li>• Average—Average Send for the statistic for the specified time.</li><li>• Maximum—Maximum Send for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li></ul>
Receive	<ul style="list-style-type: none"><li>• Average—Average Receive for the statistic for the specified time.</li><li>• Maximum—Maximum Receive for the statistic for the specified time.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp that shows time when the maximum value occurred.</li></ul>

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Throughput Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		GTP Signaling Messages	<p><b>Sent</b></p> <ul style="list-style-type: none"> <li>Count—GTP signaling messages sent between the Serving GPRS Support Node (SGSN) and GGSN, PDNGW, SGW, or SPGW.</li> <li>Rate—Rate at which the GTP signaling messages are sent between SGSN and GGSN.</li> </ul> <p><b>Received</b></p> <ul style="list-style-type: none"> <li>Count—GTP signaling messages received between the Serving GPRS Support Node (SGSN) and GGSN, PDNGW, SGW, or SPGW</li> <li>Rate—Rate at which the GTP signaling messages are received between SGSN and GGSN.</li> </ul>
		G-PDU Messages	<p><b>Sent</b></p> <ul style="list-style-type: none"> <li>Count—Number of GTP Packet Data Unit (G-PDU) messages sent on a SGSN path.</li> <li>Rate—Rate at which the G-PDU messages are sent on a SGSN path.</li> </ul> <p><b>Received</b></p> <ul style="list-style-type: none"> <li>Count—Number of G-PDU messages received on a SGSN path.</li> <li>Rate—Rate at which the G-PDU messages are received on a SGSN path.</li> </ul>
		G-PDU Bits	<p><b>Sent</b></p> <ul style="list-style-type: none"> <li>Count—Number of G-PDU bits sent on a SGSN path.</li> <li>Rate—Rate at which the G-PDU bits are sent on a SGSN path.</li> </ul> <p><b>Received</b></p> <ul style="list-style-type: none"> <li>Count—Number of G-PDU bits received on a SGSN path.</li> <li>Rate—Rate at which the G-PDU bits are received on a SGSN path.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		GTP Signaling Messages Sent/ GTP Signaling Messages Received	If Output Type is Graph, the Y-axis label shows daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.

## Charging Group Statistics Daily Reports

MWTM displays the Charging Group Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN, SPGW**.



### Note

The 15-minute and hourly GTP Charging Group Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Charging Group Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose Charging Group Statistics Daily from the Type drop-down menu. Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
Charging Group Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp EDT ( <i>time zone</i> )	Timestamp of the report.
		Index	Shows the index number.
		ISCSI	Shows the ISCSI.
		Service Mode	Displays the mode of the service.
		Switch Over Priority	Shows the priority of the switch over.
		Row Status	Shows the number of rows in the table, prior to the first visible row;

### Charging Gateway Group Statistics Daily

MWTM displays the Charging Gateway Group Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > GGSN, SPGW**.



#### Note

The 15-minute and hourly Charging Gateway Group Statistics Daily reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the Charging Gateway Group Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
CDR Messages Pending	Average—The average currently pending G-CDR output messages. Maximum—The maximum currently pending G-CDR output messages.
CDR Messages Sent	Average—The average currently sent G-CDR output messages. Maximum—The maximum currently sent G-CDR output messages.
Maximum Date (EST)	Timestamp when the maximum value occurred.

**Step 3** Choose Charging Gateway Group Statistics Daily from the Type drop-down menu. Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:



Report Type	Output	Field	Description
Charging Gateway Group Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp (time zone)	Timestamp of the report.
		Current Containers	The number of currently open or closed charging containers.
		Current CDRs	<ul style="list-style-type: none"> <li>Open—The number of currently opened G-CDRs on the GGSN, PDNGW, SGW, or SPGW.</li> <li>Closed—The number of currently closed G-CDRs on the GGSN, PDNGW, SGW, or SPGW which have not been sent to the CG.</li> </ul>
		CDR Messages Pending	<ul style="list-style-type: none"> <li>Count—The number of currently pending G-CDR output messages.</li> </ul>
		CDR Messages ISCSI Pending	<ul style="list-style-type: none"> <li>Count—The number of currently pending ISCI output messages.</li> </ul>
		CDR Messages CG Pending	<ul style="list-style-type: none"> <li>Count—The number of currently pending CG output messages.</li> </ul>
		CDR Messages Maintenance Pending	<ul style="list-style-type: none"> <li>Count—The number of currently pending maintenance output messages.</li> </ul>
		CDR Messages Sent	<ul style="list-style-type: none"> <li>Count—The number of transmitted G-CDR output messages since the charging service is enabled.</li> <li>Rate—Rate of transmitted G-CDR output messages since the charging service is enabled.</li> </ul>
		CDR Messages ISCI Sent	<ul style="list-style-type: none"> <li>Count—The number of transmitted ISCI output messages since the charging service is enabled.</li> <li>Rate—Rate of transmitted ISCI output messages since the charging service is enabled.</li> </ul>

Report Type	Output	Field	Description
		CDR Messages CG Sent	<ul style="list-style-type: none"> <li>Count—The number of transmitted CG output messages since the charging service is enabled.</li> <li>Rate—Rate of transmitted CG output messages since the charging service is enabled.</li> </ul>
		CDRs Opened	<ul style="list-style-type: none"> <li>Count—Total number of CDRs opened on the GGSN, PDNGW, SGW, or SPGW either since system startup or since the last time the charging statistics was cleared.</li> <li>Rate—Rate of CDRs opened on the GGSN, PDNGW, SGW, or SPGW either since system startup or since the last time the charging statistics was cleared.</li> </ul>
		Containers Created	<ul style="list-style-type: none"> <li>Count—Total number of containers created on the GGSN, PDNGW, SGW, or SPGW either since system startup or since the last time the charging statistics was cleared.</li> <li>Rate—Rate of containers created on the GGSN, PDNGW, SGW, or SPGW either since system startup or since the last time the charging statistics was cleared.</li> </ul>
		Service Records Created	<ul style="list-style-type: none"> <li>Count—Total number of service records created on the GGSN, PDNGW, SGW, or SPGW either since the system startup or since the time the service aware feature is enabled.</li> <li>Rate—Rate of service records created on the GGSN, PDNGW, SGW, or SPGW either since the system startup or since the time the service aware feature is enabled.</li> </ul>
		Total Unique APNs	<ul style="list-style-type: none"> <li>Count—The number of access points for which charging data is being collected.</li> <li>Rate—Rate of access points for which charging data is being collected.</li> </ul>
		Charging Gateway Down Times	<ul style="list-style-type: none"> <li>Count—The number of occurrences of cgprsCgAlarmEchoFailure traps state transitions since system startup.</li> <li>Rate—Rate of occurrences of cgprsCgAlarmEchoFailure traps state transitions since system startup.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		CDR Messages Pending/CDR Messages Sent	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## PDNGW Reports

The MWTM web interface provides node-level PDNGW reports for bearer performance statistics. To generate a network wide PDNGW report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** If available, choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [APN Aggregate Miscellaneous Statistics Daily Reports, page 13-161](#)
- [APN Aggregate PDP/Bearer Statistics Daily Reports, page 13-161](#)
- [APN Aggregate PDP/Bearer Extended Statistics Daily Reports, page 13-161](#)
- [APN Aggregate Throughput Statistics Daily Reports, page 13-161](#)
- [APN Instance Miscellaneous Statistics Daily Reports, page 13-161](#)
- [APN Instance PDP/Bearer Statistics Daily Reports, page 13-162](#)
- [APN Instance PDP/Bearer Extended Statistics Daily Reports, page 13-162](#)
- [APN Instance Throughput Statistics Daily Reports, page 13-162](#)



- [EPC Gateway Protection Statistics Daily Reports, page 13-162](#)
- [EPC Gateway Buffering Statistics Daily Reports, page 13-164](#)
- [GTP Active Statistics Daily Reports, page 13-167](#)
- [GTP Charging Statistics Daily Reports, page 13-168](#)
- [GTP Error Statistics Daily Reports, page 13-169](#)
- [GTP Path PDP Statistics Daily Reports, page 13-171](#)
- [GTP Path Errors Daily Reports, page 13-171](#)
- [GTP PDP/Bearer Statistics Daily Reports, page 13-173](#)
- [GTP Throughput Statistics Daily Reports, page 13-175](#)
- [GTPv2 Bearer Statistics Daily Reports, page 13-175](#)
- [GTPv2 Session Statistics Daily Reports, page 13-178](#)
- [GTPv2 Path Bearer Requests Statistics Daily Reports, page 13-181](#)
- [GTPv2 Path Bearer Responses Statistics Daily Reports, page 13-184](#)
- [GTPv2 Path Session Statistics Daily Reports, page 13-187](#)

**Note**

The 15-minute and hourly reports for PDNGW are available from the node level only; they are not available from the top level or the network level.

### APN Aggregate Miscellaneous Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Miscellaneous Statistics Daily report of GGSN Reports. See [APN Aggregate Miscellaneous Statistics Daily Reports, page 13-130](#).

### APN Aggregate PDP/Bearer Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate PDP/Bearer Statistics Daily report of GGSN Reports. See [APN Aggregate PDP/Bearer Statistics Daily Reports, page 13-133](#).

### APN Aggregate PDP/Bearer Extended Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate PDP/Bearer Extended Statistics Daily report of GGSN Reports. See [APN Aggregate PDP/Bearer Extended Statistics Daily Reports, page 13-136](#).

### APN Aggregate Throughput Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Throughput Statistics Daily report of GGSN Reports. See [APN Aggregate Throughput Statistics Daily Reports, page 13-139](#).

### APN Instance Miscellaneous Statistics Daily Reports

The GUI displays the same fields as that of APN Instance Miscellaneous Statistics Daily report of GGSN Reports. See [APN Instance Miscellaneous Statistics Daily Reports, page 13-143](#).

### APN Instance PDP/Bearer Statistics Daily Reports

The GUI displays the same fields as that of APN Instance PDP/Bearer Statistics Daily report of GGSN Reports. See [APN Instance PDP/Bearer Statistics Daily Reports, page 13-143](#).

### APN Instance PDP/Bearer Extended Statistics Daily Reports

The GUI displays the same fields as that of APN Instance PDP/Bearer Extended Statistics Daily report of GGSN Reports. See [APN Instance PDP/Bearer Extended Statistics Daily Reports, page 13-143](#).

### APN Instance Throughput Statistics Daily Reports

The GUI displays the same fields as that of APN Instance Throughput Statistics Daily report of GGSN Reports. See [APN Instance Throughput Statistics Daily Reports, page 13-143](#).

### EPC Gateway Protection Statistics Daily Reports

MWTM displays the EPC Gateway Protection Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.



#### Note

The same column names are displayed for EPC Gateway Protection Statistics Daily Reports of PDNGW and SGW reports.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW, SPGW or SGW**.



#### Note

The 15-minute and hourly EPC Gateway Protection Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the EPC Gateway Protection Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose EPC Gateway Protection Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Call Request Dropped	Total number of dropped call requests.
Times Low Congestion Reached	Times when the low congestion reached.

Field	Description
Times High Congestion Reached	Times when the high congestion reached.
Maximum Date (time zone)	Timestamp when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
EPC Gateway Protection Statistics Daily Reports	Table, CSV	Node	Name of the node.
		Timestamp (time zone)	Timestamp of the report.
		Call Requests Dropped	<ul style="list-style-type: none"> <li>Count—Total number of incoming calls dropped at the gateway.</li> <li>Rate—Rate at which the incoming calls are dropped at the gateway.</li> </ul>
		Times Low Congestion Reached	<ul style="list-style-type: none"> <li>Count—The number of times low congestion occurred on the gateway.</li> <li>Rate—Rate at which the low congestion are occurred on the gateway.</li> </ul>
		Times High Congestion Reached	<ul style="list-style-type: none"> <li>Count—The number of times high congestion occurred on the gateway.</li> <li>Rate—Rate at which the high congestion occurred on the gateway.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Call Requests Dropped/ Times Low Congestion Reached/ Times High Congestion Reached	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## EPC Gateway Buffering Statistics Daily Reports

MWTM displays the EPC Gateway Buffering Statistics Daily report obtained during the specified period.


**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.


**Note**

The same column names are displayed for EPC Gateway Buffering Statistics Daily Reports of PDNGW and SGW reports.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW, SPGW or SGW**.


**Note**

The 15-minute and hourly EPC Gateway Buffering Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the EPC Gateway Buffering Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose EPC Gateway Buffering Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Total In Use Buffers	Total number of buffers currently in use.
Total Buffered Bits	Total number of bytes buffered at present in the buffer.
Total Buffers Available	Current available buffer size.
Maximum Date (time zone)	Timestamp when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
EPC Gateway Buffering Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Total In Use Buffers	Total number of buffers currently in use.
		Total Buffered Packets	Total number of packets buffered at present in the buffer.
		Total Buffered Bits	Total number of bytes buffered at present in the buffer.
		Total Buffers Available	Current available buffer size.
		Buffers Created	<ul style="list-style-type: none"> <li>Count—Total number of buffers created.</li> <li>Rate—Rate at which the buffers are created.</li> </ul>
		Buffers Deleted	<ul style="list-style-type: none"> <li>Count—Total number of buffers deleted.</li> <li>Rate—Rate at which the buffers are deleted.</li> </ul>
		Buffers Timed Out	<ul style="list-style-type: none"> <li>Count—Total number of buffers that got timed out.</li> <li>Rate—Rate at which the buffers got timed out.</li> </ul>
		Buffer Packets Enqueued	<ul style="list-style-type: none"> <li>Count—Total number of packets enqueued to the buffering agent.</li> <li>Rate—Rate at which the packets are enqueued to the buffering agent.</li> </ul>
		Buffer Packets Dequeued	<ul style="list-style-type: none"> <li>Count—Total number of packets dequeued from the buffering agent.</li> <li>Rate—Rate at which the packets are dequeued from the buffering agent.</li> </ul>
		Buffer Bits Enqueued	<ul style="list-style-type: none"> <li>Count—Total bytes of data enqueued to the buffering agent.</li> <li>Rate—Rate at which the bits of data are enqueued to the buffering agent.</li> </ul>
		Buffer Bits Dequeued	<ul style="list-style-type: none"> <li>Count—Total bytes of data dequeued from the buffering agent.</li> <li>Rate—Rate at which the bits of data are dequeued from the buffering agent.</li> </ul>

Report Type	Output	Field	Description
		Buffer Rejected Memory Unavailable	<ul style="list-style-type: none"> <li>Count—Total number of times the buffer allocation is rejected by gateway due to requested memory is greater than the total available buffers.</li> <li>Rate—Rate at which the buffer allocation is rejected by gateway due to requested memory is greater than the total available buffers.</li> </ul>
		Buffer Rejected Low Memory	<ul style="list-style-type: none"> <li>Count—Total number of times the buffer allocation is rejected due to low memory availability in the gateway.</li> <li>Rate—Rate at which the buffer allocation is rejected due to low memory availability in the gateway.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Total In Use Buffers/Total Buffered Bits/Total Buffers Available	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTP Active Statistics Daily Reports

MWTM displays the GTP Active Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW**.



### Note

The 15-minute and hourly GTP Active Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Active Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTP Active Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Average Active Sessions	Average sessions which are in active state.
Maximum Active Sessions	Maximum sessions which are in active state.
Maximum Date (time zone)	Timestamp when the maximum value occurred.
Average GTP v2 EPS Bearers	Average GTP v2 EPS bearers.
Maximum GTP v2 EPS Bearers	Maximum GTP v2 EPS bearers.
Maximum Date (time zone)	Timestamp when the maximum value occurred.

### Step 3

Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Active Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Active Sessions	Total number of sessions currently established with the system.
		Direct Tunnel PDP Contexts	Direct tunnels enabled for the PDP contexts in the GGSN.
		GTP v0 PDP Contexts	PDP contexts (GTP version 0) that are active.
		GTP v1 PDP Contexts	PDP contexts (GTP version 1) that are active.
		GTP v2 EPS Bearers	EPS bearers (GTP version 2) that are active.
		PPP Regen PDPs	Device-specific interfaces created for association with PDP contexts regenerated to a Point-to-Point (PPP) session.
		PPP PDPs	Total number of point to point PDP contexts.
		Total Direct Tunnel	<ul style="list-style-type: none"> <li>Enabled—Total number of enabled direct tunnels.</li> <li>PDP Error Indications—Total number of PDP error indicated direct tunnels.</li> <li>PDP Deleted—Number of deleted tunnels.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Active Sessions/ GTP v2 EPS Bearers	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTP Charging Statistics Daily Reports

The GUI displays the same fields as that of GTP Charging Statistics Daily report of GGSN Reports. See [GTP Charging Statistics Daily Reports, page 13-149](#).



## GTP Error Statistics Daily Reports

MWTM displays the GTP Error Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW**.



### Note

The 15-minute and hourly GTP Error Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Error Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTP Error Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Average Unexpected Signaling Messages	The average unexpected GTP signaling messages sent or received
Maximum Unexpected Signaling Messages	The maximum unexpected GTP signaling messages sent or received
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.
Average Dropped Signaling Messages	The average dropped GTP signaling messages sent or received
Maximum Dropped Signaling Messages	The maximum dropped GTP signaling messages sent or received
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

### Step 3

Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Error Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp (time zone)	Timestamp of the report.
		PDP Context Activations	<ul style="list-style-type: none"> <li>Insufficient Resources Rejection—Number of PDP context requests rejected due to insufficient resources.</li> </ul>
		PDP Context Requests	<ul style="list-style-type: none"> <li>PPP Regeneration Insufficient Resources Rejection—PDP context requests rejected due to insufficient resources for PPP regeneration.</li> <li>PPP Regeneration Threshold Limit Drops—Number of PDP context requests dropped due to the PPP regeneration threshold limit.</li> </ul>
		PDP Context Messages	<ul style="list-style-type: none"> <li>TFT Semantic Errors—Total number of received PDP context messages that had Traffic Flow Templates (TFT) with semantic errors.</li> <li>TFT Syntax Errors—Total number of received PDP context messages that had TFTs with syntax errors.</li> <li>Packet Filter Semantic Errors—Total number of received PDP context messages that had packet filters with semantic errors.</li> <li>Packet Filter Syntax Errors—Total number of received PDP context messages that had packet filters with syntax errors.</li> </ul>
		Signaling Messages	<ul style="list-style-type: none"> <li>Unexpected—Number of unexpected GTP signaling messages sent or received.</li> <li>Dropped—Number of GTP messages received with wrong value.</li> </ul>
		GTP Message Parsers Errors	<ul style="list-style-type: none"> <li>Unexpected—Number of unexpected GTP parser error messages sent or received.</li> <li>Dropped—Number of GTP parser error messages received with wrong value.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Average Unexpected Signaling Messages/Maximum Unexpected Signaling Messages/Average Dropped Signaling Messages/Maximum Dropped Signaling Messages	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTP Path PDP Statistics Daily Reports

The GUI displays the same fields as that of GTP Path PDP Statistics Daily report of SPGW Reports. See [GTP Path PDP Statistics Daily Reports, page 13-245](#).

### GTP Path Errors Daily Reports

MWTM displays the GTP Path Errors Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW, SPGW**.

**Note**

The 15-minute and hourly GTP Path Error (PDNGW) reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path Error (PDNGW) reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTP Path Errors Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Dropped Signaling Messages	The signaling messages are dropped.
Unexpected Signaling Messages	The unexpected GTP signaling messages are sent or received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Path Errors Daily	Table, CSV	Node	Name of the node.
		GTP Path	Path of the GTP.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Signaling Messages	<b>Unexpected</b> <ul style="list-style-type: none"> <li>Count—Number of unexpected GTP signaling messages sent or received.</li> <li>Rate—Rate at which the unexpected GTP signaling messages are sent or received.</li> </ul> <b>Dropped</b> <ul style="list-style-type: none"> <li>Count—Number of signaling messages that are dropped.</li> <li>Rate—Rate at which the signaling messages are dropped.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Dropped Signaling Messages/ Unexpected Signaling Messages	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTP PDP/Bearer Statistics Daily Reports

The GUI displays the GTP PDP/Bearer Statistics Daily report of PDNGW report.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW, SPGW**.

**Note**

The 15-minute and hourly GTP PDP/Bearer Statistics (PDNGW) reports are available from the node level only; they are not available from the top level or the network level. Choose GTP PDP/Bearer Statistics Daily from the Type drop-down menu.

**Step 2** Choose GTP PDP/Bearer Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
PDP Context Activation Failure Ratio	The failure ratio.
Activation Rejected	The PDP/Bearer contexts are rejected.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP PDP/Bearer Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Activation Failure Ratio	Failure ratio.
		Created	<ul style="list-style-type: none"> <li>Count—Number of PDP/Bearer contexts created.</li> <li>Rate—Rate at which the PDP/Bearer contexts are created.</li> </ul>
		Rejected	<ul style="list-style-type: none"> <li>Count—Number of PDP/Bearer contexts rejected.</li> <li>Rate—Rate at which the PDP/Bearer contexts are rejected.</li> </ul>
		Deleted	<ul style="list-style-type: none"> <li>Count—Number of PDP/Bearer contexts deleted.</li> <li>Rate—Rate at which the PDP/Bearer contexts are deleted.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		PDP Context Activation Failure Ratio/Activation Rejected	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTP Throughput Statistics Daily Reports

The GUI displays the same fields as that of GTP Throughput Statistics Daily report of GGSN Reports. See [GTP Throughput Statistics Daily Reports, page 13-153](#).

### GTPv2 Bearer Statistics Daily Reports

MWTM displays the GTPv2 Bearer Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW**.

**Note**

The 15-minute and hourly GTPv2 Bearer Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SGW GTPv2 Bearer Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTPv2 Bearer Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Bearer Requests Sent	The create bearer request messages are sent.
Create Bearer Requests Received	The create bearer request messages are received.
Delete Bearer Requests Sent	The delete bearer request messages are sent.
Delete Bearer Requests Received	The delete bearer request messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:



Report Type	Output	Field	Description
GTPv2 Bearer Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp (time zone)	Timestamp shows the time bits-per second value occurred.
		Create Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages sent.</li> <li>Rate—Rate at which the create bearer request messages are sent.</li> </ul>
		Create Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Create Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>
		Modify Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages sent.</li> <li>Rate—Rate at which the modify bearer request messages are sent.</li> </ul>
		Modify Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
		Modify Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
		Update Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages sent.</li> <li>Rate—Rate at which the update bearer request messages are sent.</li> </ul>
		Update Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>
		Update Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages rejected.</li> <li>Rate—Rate at which the update bearer request messages are rejected.</li> </ul>
		Delete Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages sent.</li> <li>Rate—Rate at which the delete bearer response messages are sent.</li> </ul>

Report Type	Output	Field	Description
		Delete Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages received.</li> <li>Rate—Rate at which the delete bearer response messages are received.</li> </ul>
		Delete Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages rejected.</li> <li>Rate—Rate at which the delete bearer response messages are rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Bearer Requests Sent/Create Bearer Requests Received/Delete Bearer Requests Sent/Delete Bearer Requests Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTPv2 Session Statistics Daily Reports

MWTM displays the GTPv2 Session Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW**

**Note**

The 15-minute and hourly GTPv2 Session Daily (PDNGW) reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Session Daily (PDNGW) reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTPv2 Session Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Session Requests Sent	The create session request messages are sent.
Create Session Requests Received	The create session request messages are received.
Delete Session Requests Sent	The delete session request messages are sent.
Delete Session Requests Received	The delete session request messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Session Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Create Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create session request messages received.</li> <li>Rate—Rate at which the create session request messages are received.</li> </ul>
		Create Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session request messages rejected.</li> <li>Rate—Rate at which the create session request messages are rejected.</li> </ul>
		Delete Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages received.</li> <li>Rate—Rate at which the delete session request messages are received.</li> </ul>
		Delete Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages rejected.</li> <li>Rate—Rate at which the delete session request messages are rejected.</li> </ul>
		Create Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of create session response messages sent.</li> <li>Rate—Rate at which the create session response messages are sent.</li> </ul>
		Delete Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages sent.</li> <li>Rate—Rate at which the delete session response messages are sent.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Session Requests Sent/Create Session Requests Received/Delete Session Requests Sent/Delete Session Requests Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTPv2 Path Bearer Requests Statistics Daily Reports

MWTM displays the GTPv2 Path Bearer Requests Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW**.



#### Note

The 15-minute and hourly GTPv2 Path Bearer Requests Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Path Bearer Requests Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose GTPv2 Path Bearer Requests Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Bearer Requests Sent	The create bearer request messages are sent.
Create Bearer Requests Received	The create bearer request messages are received.
Delete Bearer Requests Sent	The delete bearer request messages are sent.
Delete Bearer Requests Received	The delete bearer request messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Path Bearer Requests Statistics Daily	Table, CSV	Node	Name of the node.
		GTP Path	Path of GTP.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Create Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages sent.</li> <li>Rate—Rate at which the create bearer request messages are sent.</li> </ul>
		Create Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Create Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>
		Modify Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages sent.</li> <li>Rate—Rate at which the modify bearer request messages are sent.</li> </ul>
		Modify Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
		Modify Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
		Update Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages sent.</li> <li>Rate—Rate at which the update bearer request messages are sent.</li> </ul>
		Update Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>
		Update Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages rejected.</li> <li>Rate—Rate at which the update bearer request messages are rejected.</li> </ul>

Report Type	Output	Field	Description
		Delete Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of delete bearer request messages sent.</li> <li>Rate—Rate at which the delete bearer request messages are sent.</li> </ul>
		Delete Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete bearer request messages received.</li> <li>Rate—Rate at which the delete bearer request messages are received.</li> </ul>
		Delete Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete bearer request messages rejected.</li> <li>Rate—Rate at which the delete bearer request messages are rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Bearer Requests Sent/Create Bearer Requests Received/Delete Bearer Requests Sent/Delete Bearer Requests Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTPv2 Path Bearer Responses Statistics Daily Reports

MWTM displays the GTPv2 Path Bearer Responses Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.



- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW**.



**Note** The 15-minute and hourly GTPv2 Path Bearer Responses Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Path Bearer Responses Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose GTPv2 Path Bearer Responses Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Bearer Responses Sent	The create bearer responses messages are sent.
Create Bearer Responses Received	The create bearer responses messages are received.
Delete Bearer Responses Sent	The delete bearer responses messages are sent.
Delete Bearer Responses Received	The delete bearer responses messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Path Bearer Responses Statistic	Table, CSV	Node	Name of the node.
		GTP Path	Path of GTP.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Create Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer response messages sent.</li> <li>Rate—Rate at which the create bearer response messages are sent.</li> </ul>
		Create Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer response messages received.</li> <li>Rate—Rate at which the create bearer response messages are received.</li> </ul>
		Create Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer response messages rejected.</li> <li>Rate—Rate at which the create bearer response messages are rejected.</li> </ul>
		Modify Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer response messages sent.</li> <li>Rate—Rate at which the modify bearer response messages are sent.</li> </ul>
		Modify Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer response messages received.</li> <li>Rate—Rate at which the modify bearer response messages are received.</li> </ul>
		Modify Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of modify bearer response messages rejected.</li> <li>Rate—Rate at which the modify bearer response messages are rejected.</li> </ul>
		Update Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of update bearer response messages sent.</li> <li>Rate—Rate at which the update bearer response messages are sent.</li> </ul>
		Update Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of update bearer response messages received.</li> <li>Rate—Rate at which the update bearer response messages are received.</li> </ul>
		Update Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer response messages rejected.</li> <li>Rate—Rate at which the update bearer response messages are rejected.</li> </ul>

Report Type	Output	Field	Description
		Delete Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages sent.</li> <li>Rate—Rate at which the delete bearer response messages are sent.</li> </ul>
		Delete Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages received.</li> <li>Rate—Rate at which the delete bearer response messages are received.</li> </ul>
		Delete Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages rejected.</li> <li>Rate—Rate at which the delete bearer response messages are rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Bearer Responses Sent/Create Bearer Responses Received/Delete Bearer Responses Sent/Delete Bearer Responses Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTPv2 Path Session Statistics Daily Reports

MWTM displays the GTPv2 Path Session Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW**.

**Note**

The 15-minute and hourly GTPv2 Path Session Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Path Session Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTPv2 Path Session Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:



Field	Description
Node	The name of the node.
Create Session Requests Received	The create session request messages are received.
Delete Session Responses Sent	The delete session response messages are sent.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Path Session Statistics Daily	Table, CSV	Node	Name of the node.
		GTP Path	Path of GTP.
		Timestamp (time zone)	Timestamp shows the time bits-per second value occurred.
		Create Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create session request messages received.</li> <li>Rate—Rate at which the create session request messages are received.</li> </ul>
		Create Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session request messages rejected.</li> <li>Rate—Rate at which the create session request messages are rejected.</li> </ul>
		Delete Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages received.</li> <li>Rate—Rate at which the delete session request messages are received.</li> </ul>
		Delete Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages rejected.</li> <li>Rate—Rate at which the delete session request messages are rejected.</li> </ul>
		Create Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of create session response messages sent.</li> <li>Rate—Rate at which the create session response messages are sent.</li> </ul>
		Delete Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages sent.</li> <li>Rate—Rate at which the delete session response messages are sent.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Session Requests Received/ Delete Session Responses Sent	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## PDSN Reports

The MWTM web interface provides node-level PDSN reports. To generate a network-wide PDSN report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDSN**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** If available, choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [PDSN Session Statistics Daily Reports, page 13-190](#)
- [PDSN Session Bandwidth Statistics Daily Reports, page 13-193](#)
- [PDSN Flow Statistics Daily Reports, page 13-195](#)
- [PDSN Flow Extended Statistics Daily Reports, page 13-197](#)
- [PDSN Packet Control Function Statistics Daily Reports, page 13-199](#)
- [PDSN Traffic Statistics Daily Reports, page 13-200](#)
- [PDSN Traffic Extended Statistics Daily Reports, page 13-202](#)

### PDSN Session Statistics Daily Reports

MWTM displays the PDSN Session Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDSN**.



#### Note

The 15-minute and hourly PDSN Session reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PDSN Session reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose PDSN Session Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Total Sessions	Total number of sessions currently established with the system.
Maximum Allowed Session	Maximum number of sessions allowed by the system.
Average Session Utilization	Average session utilization during the specified duration.
Maximum Session Utilization	Maximum session utilization during the specified duration.
Maximum Date (time zone)	Timestamp when the maximum value occurred

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PDSN Session Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Total Sessions	Total number of sessions currently established with the system.
		Maximum Allowed Sessions	Maximum number of sessions allowed by the system.
		Session Utilization	Total session utilization.
		Total Active Sessions	Total number of sessions in active state.
		Total Dormant Sessions	Total number of sessions in dormant state.
		Total PPP over GRE Sessions	Total number of PPPoGRE sessions currently established with the system.
		Total HDLC over GRE Sessions	Total number of HDLCoGRE sessions currently established with the system.
		Total Sessions Established	Total number of sessions established since system was last restarted.
		Total Sessions Established Rate	Rate at which the sessions were established since system was last restarted.
		Total Sessions Released	Total number of sessions released since system was last restarted.
		Total Sessions Released Rate	Rate at which the sessions were released since system was last restarted.
		Total Session Failures	Number of A10/A11 session failures occurring since PDSN agent restarted.
		Session Failure Ratio	Ratio of session failures.



Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Maximum Allowed Sessions/ Total Sessions/ Session Utilization	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		Utilization	If Output Type is Graph, a color-coded legend shows labels for utilization.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

### PDSN Session Bandwidth Statistics Daily Reports

MWTM displays the PDSN Session Bandwidth Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDSN**.



#### Note

The 15-minute and hourly PDSN Session Bandwidth reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PDSN Session Bandwidth reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose PDSN Session Bandwidth Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Total Allocated Bandwidth	Total bandwidth allocated for sessions currently established on the PDSN.
Total Configured Bandwidth	Total bandwidth value configured via the CLI that would be supported by PDSN system.
Average Bandwidth Utilization	Average bandwidth utilization during the specified duration.
Maximum Bandwidth Utilization	Maximum bandwidth utilization during the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp when the maximum value occurred

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PDSN Session Bandwidth Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Total Available Bandwidth	Bandwidth available on the PDSN system for creation of new sessions.
		Total Allocated Bandwidth	Total bandwidth allocated for sessions currently established on the PDSN.
		Total Configured Bandwidth	Total bandwidth value configured via the CLI that would be supported by PDSN system.
		Bandwidth Utilization	Total bandwidth that has been utilized.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Total Allocated Bandwidth/ Total Configured Bandwidth/ Bandwidth Utilization	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		Utilization	If Output Type is Graph, a color-coded legend shows labels for utilization.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

### PDSN Flow Statistics Daily Reports

MWTM displays the PDSN Flow Statistics Daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1**

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDSN**.

**Note**

The 15-minute and hourly PDSN Flow reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PDSN Flow reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2**

Choose PDSN Flow Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Total Simple IP Flows	Total number of flows currently using simple IP service.
Total Mobile IP Flows	Total number of flows currently using MoIP services.
Maximum Date ( <i>time zone</i> )	Timestamp when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PDSN Flow Statistics Daily Reports	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Total Simple IP Flows	Total number of flows currently using simple IP service.
		Total Mobile IP Flows	Total number of flows currently using MoIP services.
		Total Proxy Mobile IP Flows	Total number of flows currently using proxy MoIP service.
		Total MSID Flows	Total number of flows currently using MSID service.
		Total VPDN Flows	The total number of flows currently using VPDN service.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Total Simple IP Flows/ Total Mobile IP Flows	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

### PDSN Flow Extended Statistics Daily Reports

MWTM displays the PDSN Flow Extended Statistics Daily report obtained during the specified period.



**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDSN**.

**Note**

The 15-minute and hourly PDSN Flow Extended Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PDSN Flow Extended Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose PDSN Flow Extended Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Total Simple IP Flows Established	<ul style="list-style-type: none"> <li>Count—Total number of Simple IP flow that has been established successfully since system reboot.</li> <li>Rate—Rate at which the Simple IP flow is established successfully since system reboot.</li> </ul>
Total Mobile IP Flows Established	<ul style="list-style-type: none"> <li>Count—Total number of mobile IP flow that has been established successfully since system reboot.</li> <li>Rate—Rate at which the mobile IP flow is established successfully since system reboot.</li> </ul>
Total Proxy Mobile IP Flows Established	<ul style="list-style-type: none"> <li>Count—Total number of proxy mobile IP flow that has been established successfully since system reboot.</li> <li>Rate—Rate at which the proxy mobile IP flow is established successfully since system reboot.</li> </ul>
Total VPDN Flows Established	<ul style="list-style-type: none"> <li>Count—Total number of VPDN flow that has been established successfully since system reboot.</li> <li>Rate—Rate at which the VPDN flow is established successfully since system reboot.</li> </ul>
Total Simple IP Flow Failures	<ul style="list-style-type: none"> <li>Count—Total number of simple IP flow setup request failed since last system reboot.</li> <li>Rate—Rate at which the simple IP flow setup request is failed since last system reboot.</li> </ul>
Total Mobile IP Flow Failures	<ul style="list-style-type: none"> <li>Count—Total number of mobile IP flow setup request failed since system reboot.</li> <li>Rate—Rate at which the mobile IP flow setup request is failed since system reboot.</li> </ul>
Total Proxy Mobile IP Flow Failures	<ul style="list-style-type: none"> <li>Count—Total number of proxy mobile IP flow setup request failed since system reboot.</li> <li>Rate—Rate at which the proxy mobile IP flow setup request is failed since system reboot.</li> </ul>

Field	Description
Total VPDN Flow Failures	<ul style="list-style-type: none"> <li>Count—Total number of VPDN flow setup request failed since last system reboot.</li> <li>Rate—Rate at which the VPDN flow setup request is failed since last system reboot.</li> </ul>
Total Unknown Type Flow Failures	<ul style="list-style-type: none"> <li>Count—Total number of unknown type flow setup request failed since last system reboot.</li> <li>Rate—Rate at which the unknown type flow setup request is failed since last system reboot.</li> </ul>
Flow Failure Ratio	Ratio of flow failures.

### PDSN Packet Control Function Statistics Daily Reports

MWTM displays the PDSN Packet Control Function Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDSN**.



#### Note

The 15-minute and hourly PDSN PCF Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PDSN PCF reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose PDSN Packet Control Function Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Total PCFs	Total number of PCF currently interacting with the system.
Maximum Allowed PCFs	Maximum number of PCF allowed by the system.
Average PCF Utilization	Average PCF utilization during the specified duration.
Maximum PCF Utilization	Maximum PCF utilization during the specified duration.
Maximum Date (time zone)	Timestamp for when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PDSN Packet Control Function Statistics Daily Reports	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Total PCFs	Total number of PCF currently interacting with the system.
		Maximum Allowed PCFs	Maximum number of PCF allowed by the system.
		PCF Utilization	PCF utilization.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Total PCFs/ PCF Utilization/ Maximum Allowed PCFs	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

### PDSN Traffic Statistics Daily Reports

MWTM displays the PDSN Traffic Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDSN**.



**Note**

The 15-minute and hourly PDSN Traffic Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PDSN Traffic Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose PDSN Traffic Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Simple IP Bits Sent	<ul style="list-style-type: none"> <li>Count—Total number of simple IP data octets (in unit of 1024 octets) sent to mobile stations from PDSN since system was last restarted.</li> <li>Rate—Rate at which the simple IP data octets (in unit of 1024 octets) are sent to mobile stations from PDSN since system was last restarted.</li> </ul>
Simple IP Bits Received	<ul style="list-style-type: none"> <li>Count—Total number of simple IP data octets (in unit of 1024 octets) received from mobile stations by PDSN since system was last restarted.</li> <li>Rate—Rate at which the simple IP data octets (in unit of 1024 octets) are received from mobile stations by PDSN since system was last restarted.</li> </ul>
Simple IP Packets Sent	<ul style="list-style-type: none"> <li>Count—Total number of simple IP data packets sent to mobile stations since system was last restarted.</li> <li>Rate—Rate at which the simple IP data packets are sent to mobile stations since system was last restarted.</li> </ul>
Simple IP Packets Received	<ul style="list-style-type: none"> <li>Count—Total number of simple IP data packets received from mobile stations since system was last restarted.</li> <li>Rate—Rate at which the simple IP data packets are received from mobile stations since system was last restarted.</li> </ul>
Mobile IP Bits Sent	<ul style="list-style-type: none"> <li>Count—Total number of mobile IP data octets (in unit of 1024 octets) sent to mobile stations from PDSN since system was last restarted.</li> <li>Rate—Rate at which the mobile IP data octets (in unit of 1024 octets) are sent to mobile stations from PDSN since system was last restarted.</li> </ul>
Mobile IP Bits Received	<ul style="list-style-type: none"> <li>Count—Total number of mobile IP data octets (in unit of 1024 octets) received from mobile stations by PDSN since system was last restarted.</li> <li>Rate—Rate at which the mobile IP data octets (in unit of 1024 octets) are received from mobile stations by PDSN since system was last restarted.</li> </ul>
Mobile IP Packets Sent	<ul style="list-style-type: none"> <li>Count—Total number of mobile IP data packets sent to mobile stations from PDSN since system was last restarted.</li> <li>Rate—Rate at which the mobile IP data packets are sent to mobile stations from PDSN since system was last restarted.</li> </ul>
Mobile IP Packets Received	<ul style="list-style-type: none"> <li>Count—Total number of mobile IP data packets received from mobile stations since system was last restarted.</li> <li>Rate—Rate at which the mobile IP data packets are received from mobile stations since system was last restarted.</li> </ul>

Field	Description
Proxy Mobile IP Bits Sent	<ul style="list-style-type: none"> <li>Count—Total number of proxy mobile IP data octets (in unit of 1024 octets) sent to mobile stations from PDSN since system was last restarted.</li> <li>Rate—Rate at which the proxy mobile IP data octets (in unit of 1024 octets) are sent to mobile stations from PDSN since system was last restarted.</li> </ul>
Proxy Mobile IP Bits Received	<ul style="list-style-type: none"> <li>Count—Total number of proxy mobile IP data octets (in unit of 1024 octets) received from mobile stations since system was last restarted.</li> <li>Rate—Rate at which the proxy mobile IP data octets (in unit of 1024 octets) are received from mobile stations since system was last restarted.</li> </ul>
Proxy Mobile IP Packets Sent	<ul style="list-style-type: none"> <li>Count—Total number of proxy mobile IP data packets sent to mobile stations from PDSN since system was last restarted.</li> <li>Rate—Rate at which the proxy mobile IP data packets are sent to mobile stations from PDSN since system was last restarted.</li> </ul>
Proxy Mobile IP Packets Received	<ul style="list-style-type: none"> <li>Count—Total number of mobile IP data packets received from mobile stations since system was last restarted.</li> <li>Rate—Rate at which the mobile IP data packets are received from mobile stations since system was last restarted.</li> </ul>

## PDSN Traffic Extended Statistics Daily Reports

MWTM displays the PDSN Traffic Extended Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDSN**.



### Note

The 15-minute and hourly PDSN Traffic Extended Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PDSN Traffic Extended Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2


Choose PDSN Traffic Extended Statistics Daily from the Type drop-down menu.


A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Short Data Burst Packets Sent	<ul style="list-style-type: none"> <li>Count—Total number of SDB marked data packets sent to PCF from PDSN since system was last restarted.</li> <li>Rate—Rate at which the SDB marked data packets are sent to PCF from PDSN since system was last restarted.</li> </ul>
Short Data Burst Bits Sent	<ul style="list-style-type: none"> <li>Count—Total number of SDB marked data octets sent to PCF from PDSN since system was last restarted.</li> <li>Rate—Rate at which the SDB marked data octets are sent to PCF from PDSN since system was last restarted.</li> </ul>
No GRE Key Packet Discards	<ul style="list-style-type: none"> <li>Count—Total number of packets discarded from PCF because of the missing GRE Keying since system was last restarted.</li> <li>Rate—Rate at which the packets are discarded from PCF because of the missing GRE Key since system was last restarted.</li> </ul>
No Session Packet Discards	<ul style="list-style-type: none"> <li>Count—Total number of packets discarded from PCF because of missing session since system was last restarted.</li> <li>Rate—Rate at which the packets are discarded from PCF because of missing session since system was last restarted.</li> </ul>
Invalid GRE Protocol Packet Discards	<ul style="list-style-type: none"> <li>Count—Total number of packets discarded from PCF because of invalid GRE protocol since system was last restarted.</li> <li>Rate—Rate at which the packets are discarded from PCF because of invalid GRE protocol since system was last restarted.</li> </ul>
Invalid Checksum Packet Discards	<ul style="list-style-type: none"> <li>Count—Total number of packets discarded from PCF because of invalid checksum since system was last restarted.</li> <li>Rate—Rate at which the packets are discarded from PCF because of invalid checksum since system was last restarted.</li> </ul>

## SGW Reports

The MWTM web interface provides node-level SGW reports for bearer performance statistics. To generate a network wide PDNGW report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.

- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** If available, choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [APN Aggregate Bearer Statistics Daily Reports, page 13-204](#)
- [APN Aggregate Throughput Statistics Daily Reports, page 13-208](#)
- [APN Instance Bearer Statistics Daily Reports, page 13-208](#)
- [APN Instance Throughput Statistics Daily Reports, page 13-208](#)
- [EPC Gateway Protection Statistics Daily Reports, page 13-208](#)
- [EPC Gateway Buffering Statistics Daily Reports, page 13-208](#)
- [GTP Active Statistics Daily Reports, page 13-208](#)
- [GTP Charging Statistics Daily Reports, page 13-210](#)
- [GTP Error Statistics Daily Reports, page 13-210](#)
- [GTP Path PDP Statistics Daily Reports, page 13-212](#)
- [GTP Path Errors Daily Reports, page 13-212](#)
- [GTP Bearer Statistics Daily Reports, page 13-214](#)
- [GTP Throughput Statistics Daily Reports, page 13-215](#)
- [GTPv2 Bearer Statistics Daily Reports, page 13-215](#)
- [GTPv2 Session Statistics Daily Reports, page 13-217](#)
- [GTPv2 Path Bearer Requests Statistics Daily Reports, page 13-218](#)
- [GTPv2 Path Bearer Responses Statistics Daily Reports, page 13-221](#)
- [GTPv2 Path Session Statistics Daily Reports, page 13-224](#)



**Note** The 15-minute and hourly reports for SGW are available from the node level only; they are not available from the top level or the network level.

## APN Aggregate Bearer Statistics Daily Reports

MWTM displays the APN Aggregate Bearer Statistics Daily report obtained during the specified period.



**Note** The same column names are displayed for **APN Instance Bearer Statistics Daily Reports** with the addition of the column Node.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.

**Note**

The 15-minute and hourly reports for APN Aggregate Bearer Statistics are available from the node level only; they are not available from the top level or the network level. Click on a node name in the APN Aggregate Bearer Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose APN Aggregate Bearer Statistics Daily (or APN Instance Bearer Statistics Daily) from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
APN	The name of the Access Point Name (APN).
APN Index	A unique numerical identifier for the APN.
Average Active Bearers	Average Number of bearer contexts that are currently established on the SGW devices.
Maximum Active Bearers	Maximum Number of bearer contexts that are currently established on the SGW devices.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.
Average Bearer Activation Success Ratio	Average ratio of bearer context request messages received by the SGW devices.
Maximum Bearer Activation Success Ratio	Maximum ratio of bearer context request messages received by the SGW devices.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
APN Aggregate Bearer Statistics Daily (or APN Instance Bearer Statistics Daily)	Table, CSV	APN Name	The name of the Access Point Name (APN).
		APN Index	A unique numerical identifier for the APN.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Active Bearers	<ul style="list-style-type: none"> <li>Count—Number of active Bearer contexts on this APN.</li> </ul>
		Total Bearers (Only for SPGW)	<ul style="list-style-type: none"> <li>Count—Number of total Bearer on this APN.</li> </ul>
		Bearer Activations Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed Bearer activation procedures by MS.</li> <li>Rate—Rate (per second) of successfully completed Bearer activation procedures by the MS Total number of unsuccessful bearer modify initiated by MME or SGSN.</li> <li>Ratio—Number of successful activations for every 100 activation attempts.</li> </ul>
		Bearer Activations Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed Bearer activation procedures by the MS on this APN.</li> <li>Rate—Rate (per second) of failed Bearer activation procedures by the MS on this APN.</li> </ul>
		Bearer Deactivations Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed Bearer deactivation procedures by the SGW on this APN.</li> <li>Rate—Rate (per second) of successfully completed Bearer deactivation procedures by the SGW on this APN.</li> </ul>
		Bearer Updates Success	<ul style="list-style-type: none"> <li>Count—Total number of successful bearer update initiated by network.</li> <li>Rate—Rate (per second) of successful bearer update initiated by network.</li> <li>Ratio—Number of successful bearer update initiated by network for every 100 attempts.</li> </ul>
		Bearer Updates Failure	<ul style="list-style-type: none"> <li>Count—Total number of unsuccessful bearer update initiated by MME or SGSN.</li> <li>Rate—Rate at which the unsuccessful bearer update initiated by MME or SGSN.</li> </ul>

Report Type	Output	Field	Description
		Bearer Modifications Success	<ul style="list-style-type: none"> <li>Count—Total number of successful bearer modify initiated by MME or SGSN.</li> <li>Rate—Rate (per second) of successful bearer modify initiated by MME or SGSN.</li> <li>Ratio—Number of successful bearer modify initiated by MME or SGSN for every 100 initiation attempts.</li> </ul>
		Bearer Modifications Failure	<ul style="list-style-type: none"> <li>Count—Total number of unsuccessful bearer modify initiated by MME or SGSN.</li> <li>Rate—Rate at which the unsuccessful bearer modify initiated by MME or SGSN.</li> </ul>
		Dedicated Bearer Activations Success	<ul style="list-style-type: none"> <li>Count—Total number of successful dedicated bearer creation initiated by network.</li> <li>Rate—Rate (per second) of successful dedicated bearer creation initiated by network.</li> <li>Ratio—Number of successful dedicated bearer creation for every 100 bearer creation attempts.</li> </ul>
		Dedicated Bearer Activations Failure	<ul style="list-style-type: none"> <li>Count—Total number of unsuccessful dedicated bearer activation procedures received on this APN.</li> <li>Rate—Rate (per second) of unsuccessful dedicated bearer activation procedures received on this APN.</li> </ul>
		Dedicated Bearer Deactivations Success	<ul style="list-style-type: none"> <li>Count—Total number of successful dedicated bearer deactivation initiated by network.</li> <li>Rate—Rate (per second) of successful dedicated bearer deactivation initiated by network.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Active Bearers/ Bearer Activation Success Ratio	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, a color-coded legend shows labels for utilization.

## APN Aggregate Throughput Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Throughput Statistics Daily report of GGSN Reports. See [APN Aggregate Throughput Statistics Daily Reports, page 13-139](#).

## APN Instance Bearer Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Bearer Statistics Daily report of SGW reports. See [APN Aggregate Bearer Statistics Daily Reports, page 13-204](#).

## APN Instance Throughput Statistics Daily Reports

The GUI displays the same fields as that of APN Instance Throughput Statistics Daily report of GGSN Reports. See [APN Instance Throughput Statistics Daily Reports, page 13-143](#).

## EPC Gateway Protection Statistics Daily Reports

The GUI displays the same fields as that of EPC Gateway Protection Statistics Daily report of PDNGW Reports. See [EPC Gateway Protection Statistics Daily Reports, page 13-162](#).

## EPC Gateway Buffering Statistics Daily Reports

The GUI displays the same fields as that of EPC Gateway Buffering Statistics Daily report of PDNGW Reports. See [EPC Gateway Buffering Statistics Daily Reports, page 13-164](#).

## GTP Active Statistics Daily Reports

MWTM displays the GTP Active Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.



### Note

The 15-minute and hourly GTP Active Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Active Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTP Active Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Average Active Sessions	Average sessions which are in active state.



Field	Description
Maximum Active Sessions	Maximum sessions which are in active state.
Maximum Date (time zone)	Timestamp when the maximum value occurred.
Average Active Users	Average users that are active.
Maximum Active Users	Maximum users that are active.
Maximum Date (time zone)	Timestamp when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Active Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Active Bearers	Total number of active bearers on this GTP.
		Active Sessions	Total number of sessions currently established with the system.
		Active Users	Number of active users.
		Idle Users	Total number of users currently in Idle state in the gateway.
		Suspended Users	Total number of users suspended by the gateway.
		Total Direct Tunnel	<ul style="list-style-type: none"> <li>Enabled—Total number of enabled direct tunnels.</li> <li>PDP Error Indications—Total number of PDP error indicated direct tunnels.</li> <li>PDP Deleted—Number of deleted tunnels.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Active Sessions/ Active Users	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTP Charging Statistics Daily Reports

The GUI displays the same fields as that of GTP Charging Statistics Daily report of GGSN Reports. See [GTP Charging Statistics Daily Reports, page 13-149](#).

## GTP Error Statistics Daily Reports

MWTM displays the GTP Error Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.



**Note** The 15-minute and hourly GTP Error Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Error Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose GTP Error Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Average Unexpected Signaling Messages	The average unexpected GTP signaling messages sent or received
Maximum Unexpected Signaling Messages	The maximum unexpected GTP signaling messages sent or received
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.
Average Dropped Signaling Messages	The average dropped GTP signaling messages sent or received
Maximum Dropped Signaling Messages	The maximum dropped GTP signaling messages sent or received
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Error Statistics Daily report	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Signaling Messages	<ul style="list-style-type: none"> <li>Unexpected—Number of unexpected GTP signaling messages sent or received.</li> <li>Dropped—Number of dropped GTP signaling messages.</li> </ul>
		GTP Message Parsers Errors	Number of GTP messages received with wrong value.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Average Unexpected Signaling Messages/ Maximum Unexpected Signaling Messages/ Average Dropped Signaling Messages/ Maximum Dropped Signaling Messages	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTP Path PDP Statistics Daily Reports

The GUI displays the same fields as that of GTP Path PDP Statistics Daily report of SPGW Reports. See [GTP Path PDP Statistics Daily Reports, page 13-245](#).

### GTP Path Errors Daily Reports

MWTM displays the GTP Path Errors Daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.

**Note**

The 15-minute and hourly GTP Path Errors reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path Errors reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose GTP Path Errors Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
GTP Path	Path of the GTP.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Signaling Messages	<p><b>Unexpected</b></p> <ul style="list-style-type: none"> <li>Count—Number of unexpected GTP signaling messages sent or received.</li> <li>Rate—Rate at which the unexpected GTP signaling messages are sent or received.</li> </ul> <p><b>Dropped</b></p> <ul style="list-style-type: none"> <li>Count—Number of signaling messages dropped.</li> <li>Rate—Rate at which the signaling messages are dropped.</li> </ul>

## GTP Bearer Statistics Daily Reports

The GUI displays the GTP Bearer Statistics Daily Reports.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.



### Note

The 15-minute and hourly GTP Bearer Statistics reports are available from the node level only; they are not available from the top level or the network level. Choose GTP Bearer Statistics Daily from the Type drop-down menu.

- Step 2** Choose GTP Bearer Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
PDP Context Activation Failure Ratio	The failure ratio.
Activation Rejected	The PDP/Bearer contexts are rejected.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Bearer Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp (time zone)	Timestamp of the report.
		Activation Failure Ratio	Failure ratio.
		Created	<ul style="list-style-type: none"> <li>Count—Number of Bearer contexts created.</li> <li>Rate—Rate at which the Bearer contexts are created.</li> </ul>
		Rejected	<ul style="list-style-type: none"> <li>Count—Number of Bearer contexts rejected.</li> <li>Rate—Rate at which the Bearer contexts are rejected.</li> </ul>
		Deleted	<ul style="list-style-type: none"> <li>Count—Number of Bearer contexts deleted.</li> <li>Rate—Rate at which the Bearer contexts are deleted.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		PDP Context Activation Failure Ratio/Activation Rejected	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTP Throughput Statistics Daily Reports

The GUI displays the same fields as that of GTP Throughput Statistics Daily reports of GGSN Reports. See [GTP Throughput Statistics Daily Reports, page 13-153](#).

### GTPv2 Bearer Statistics Daily Reports

MWMT displays the GTPv2 Bearer Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.



**Note** The 15-minute and hourly GTPv2 Bearer Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SGW GTPv2 Bearer Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose GTPv2 Bearer Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Create Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages sent.</li> <li>Rate—Rate at which the create bearer request messages are sent.</li> </ul>
Create Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
Create Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>
Modify Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages sent.</li> <li>Rate—Rate at which the modify bearer request messages are sent.</li> </ul>
Modify Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
Modify Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
Update Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages sent</li> <li>Rate—Rate at which the update bearer request messages are sent.</li> </ul>
Update Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>
Update Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages rejected.</li> <li>Rate—Rate at which the update bearer request messages are rejected.</li> </ul>
Delete Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages sent</li> <li>Rate—Rate at which the delete bearer response messages are sent.</li> </ul>
Delete Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages received.</li> <li>Rate—Rate at which the delete bearer response messages are received.</li> </ul>
Delete Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages rejected.</li> <li>Rate—Rate at which the delete bearer response messages are rejected.</li> </ul>



## GTPv2 Session Statistics Daily Reports

MWTM displays the GTPv2 Session Statistics Daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1**

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.

**Note**

The 15-minute and hourly GTPv2 Session Statistics Daily reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Session Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2**

Choose GTPv2 Session Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Create Session Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create session request messages sent.</li> <li>Rate—Rate at which the create session request messages are sent.</li> </ul>
Create Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create session request messages received.</li> <li>Rate—Rate at which the create session request messages are received.</li> </ul>
Create Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session request messages rejected.</li> <li>Rate—Rate at which the create session request messages are rejected.</li> </ul>
Delete Session Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages sent.</li> <li>Rate—Rate at which the delete session request messages are sent.</li> </ul>
Delete Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages received.</li> <li>Rate—Rate at which the delete session request messages are received.</li> </ul>
Delete Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages rejected.</li> <li>Rate—Rate at which the delete session request messages are rejected.</li> </ul>
Create Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of create session response messages sent.</li> <li>Rate—Rate at which the create session response messages are sent.</li> </ul>
Create Session Responses Received	<ul style="list-style-type: none"> <li>Count—Number of create session response messages received.</li> <li>Rate—Rate at which the create session response messages are received.</li> </ul>
Create Session Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session response messages rejected.</li> <li>Rate—Rate at which the create session response messages are rejected.</li> </ul>
Delete Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages sent.</li> <li>Rate—Rate at which the delete session response messages are sent.</li> </ul>
Delete Session Responses Received	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages received.</li> <li>Rate—Rate at which the delete session response messages are received.</li> </ul>
Delete Session Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages rejected.</li> <li>Rate—Rate at which the delete session response messages are rejected.</li> </ul>

### GTPv2 Path Bearer Requests Statistics Daily Reports

MWTM displays the GTPv2 Path Bearer Requests Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW, SPGW**.



**Note** The 15-minute and hourly GTPv2 Path Bearer Requests Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Path Bearer Requests Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose GTPv2 Path Bearer Requests Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Bearer Requests Sent	The create bearer request messages are sent.
Create Bearer Requests Received	The create bearer request messages are received.
Delete Bearer Requests Sent	The delete bearer request messages are sent.
Delete Bearer Requests Received	The delete bearer request messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Path Bearer Requests Statistics Daily	Table, CSV	Node	Name of the node.
		GTP Path	Path of GTP.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Create Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages sent.</li> <li>Rate—Rate at which the create bearer request messages are sent.</li> </ul>

Report Type	Output	Field	Description
		Create Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Create Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>
		Modify Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages sent.</li> <li>Rate—Rate at which the modify bearer request messages are sent.</li> </ul>
		Modify Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
		Modify Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
		Update Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages sent.</li> <li>Rate—Rate at which the update bearer request messages are sent.</li> </ul>
		Update Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>
		Update Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages rejected.</li> <li>Rate—Rate at which the update bearer request messages are rejected.</li> </ul>
		Delete Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of delete bearer request messages sent.</li> <li>Rate—Rate at which the update bearer request messages are sent.</li> </ul>
		Delete Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete bearer request messages received.</li> <li>Rate—Rate at which the delete bearer request messages are received.</li> </ul>
		Delete Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete bearer request messages rejected.</li> <li>Rate—Rate at which the delete bearer request messages are rejected.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Bearer Requests Sent/Create Bearer Requests Received/Delete Bearer Requests Sent/Delete Bearer Requests Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTPv2 Path Bearer Responses Statistics Daily Reports

MWTM displays the GTPv2 Path Bearer Responses Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW, SPGW**.



#### Note

The 15-minute and hourly GTPv2 Path Bearer Responses Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Path Bearer Responses Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose GTPv2 Path Bearer Responses Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Bearer Responses Sent	The create bearer responses messages are sent.
Create Bearer Responses Received	The create bearer responses messages are received.
Delete Bearer Responses Sent	The delete bearer responses messages are sent.
Delete Bearer Responses Received	The delete bearer responses messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Path Bearer Responses Statistics Daily	Table, CSV	Node	Name of the node.
		GTP Path	Path of GTP.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Create Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer response messages sent.</li> <li>Rate—Rate at which the create bearer response messages are sent.</li> </ul>
		Create Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer response messages received.</li> <li>Rate—Rate at which the create bearer response messages are received.</li> </ul>
		Create Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer response messages rejected.</li> <li>Rate—Rate at which the create bearer response messages are rejected.</li> </ul>
		Modify Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer response messages sent.</li> <li>Rate—Rate at which the modify bearer response messages are sent.</li> </ul>
		Modify Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer response messages received.</li> <li>Rate—Rate at which the modify bearer response messages are received.</li> </ul>
		Modify Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of modify bearer response messages rejected.</li> <li>Rate—Rate at which the modify bearer response messages are rejected.</li> </ul>
		Update Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of update bearer response messages sent.</li> <li>Rate—Rate at which the update bearer response messages are sent.</li> </ul>
		Update Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of update bearer response messages received.</li> <li>Rate—Rate at which the update bearer response messages are received.</li> </ul>

Report Type	Output	Field	Description
		Update Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer response messages rejected.</li> <li>Rate—Rate at which the update bearer response messages are rejected.</li> </ul>
		Delete Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete bearer responses messages sent.</li> <li>Rate—Rate at which the update bearer responses messages are sent.</li> </ul>
		Delete Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages received.</li> <li>Rate—Rate at which the delete bearer response messages are received.</li> </ul>
		Delete Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete bearer response messages rejected.</li> <li>Rate—Rate at which the delete bearer response messages are rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Bearer Responses Sent/Create Bearer Responses Received/Delete Bearer Responses Sent/Delete Bearer Responses Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTPv2 Path Session Statistics Daily Reports

MWTM displays the GTPv2 Path Session Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.



- 
- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SGW**.



**Note** The 15-minute and hourly GTPv2 Path Session Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Path Session Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

---

- Step 2** Choose GTPv2 Path Session Statistics Daily from the Type drop-down menu.



A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
GTP Path	Path of GTP.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Create Session Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create session request messages sent.</li> <li>Rate—Rate at which the create session request messages are sent.</li> </ul>
Create Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create session request messages received.</li> <li>Rate—Rate at which the create session request messages are received.</li> </ul>
Create Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session request messages rejected.</li> <li>Rate—Rate at which the create session request messages are rejected.</li> </ul>
Delete Session Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages sent.</li> <li>Rate—Rate at which the delete session request messages are sent.</li> </ul>
Delete Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages received.</li> <li>Rate—Rate at which the delete session request messages are received.</li> </ul>
Delete Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages rejected.</li> <li>Rate—Rate at which the delete session request messages are rejected.</li> </ul>
Create Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of create session response messages sent.</li> <li>Rate—Rate at which the create session response messages are sent.</li> </ul>
Create Session Responses Received	<ul style="list-style-type: none"> <li>Count—Number of create session response messages received.</li> <li>Rate—Rate at which the create session response messages are received.</li> </ul>
Create Session Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session response messages rejected.</li> <li>Rate—Rate at which the create session response messages are rejected.</li> </ul>
Delete Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages sent.</li> <li>Rate—Rate at which the delete session response messages are sent.</li> </ul>
Delete Session Responses Received	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages received.</li> <li>Rate—Rate at which the delete session response messages are received.</li> </ul>
Delete Session Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages rejected.</li> <li>Rate—Rate at which the delete session response messages are rejected.</li> </ul>

## SPGW Reports

The MWTM web interface provides node-level SPGW reports for bearer performance statistics. To generate a network wide SPGW report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.

- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** If available, choose a sort parameter from the Sort Parameter drop-down menu.
- Step 6** To generate the report, click the Run icon (green arrow ).

The Type drop-down menu contains the following reports:

- [APN Aggregate Miscellaneous Statistics Daily Reports, page 13-228](#)
- [APN Aggregate PDP/Bearer Statistics Daily Reports, page 13-228](#)
- [APN Aggregate Bearer Statistics Daily Reports, page 13-228](#)
- [APN Aggregate Bearer QOS Statistics Daily Reports, page 13-228](#)
- [APN Aggregate PDP/Bearer Extended Statistics Daily Reports, page 13-232](#)
- [APN Aggregate Throughput Statistics Daily Reports, page 13-235](#)
- [APN Instance Miscellaneous Statistics Daily Reports, page 13-235](#)
- [APN Instance PDP/Bearer Statistics Daily Reports, page 13-235](#)
- [APN Instance PDP/Bearer Extended Statistics Daily Reports, page 13-235](#)
- [APN Instance Bearer Statistics Daily Reports, page 13-235](#)
- [APN Instance Bearer QOS Statistics Daily Reports, page 13-235](#)
- [APN Instance Throughput Statistics Daily Reports, page 13-235](#)
- [APN Instance DHCP V6 Proxy Server Statistics Daily Reports, page 13-235](#)
- [Charging Group Statistics Daily Reports, page 13-235](#)
- [Charging Gateway Group Statistics Daily Reports, page 13-235](#)
- [EPC Gateway Protection Statistics Daily Reports, page 13-235](#)
- [EPC Gateway Session Statistics Daily Reports, page 13-236](#)
- [EPC Gateway Buffering Statistics Daily Reports, page 13-238](#)
- [GTP Active Statistics Daily Reports, page 13-238](#)
- [GTP Charging Statistics Daily Reports, page 13-240](#)
- [GTP Error Statistics Daily Reports, page 13-240](#)
- [GTP Path Data PDU Statistics Daily Reports, page 13-242](#)
- [GTP Path Signaling Statistics Daily Reports, page 13-243](#)
- [GTP Path PDP Roaming Statistics Daily Reports, page 13-244](#)
- [GTP Path PDP Statistics Daily Reports, page 13-245](#)
- [GTP Path PDP Update Statistics Daily Reports, page 13-246](#)
- [GTP Path PDP Version Statistics Daily Reports, page 13-247](#)
- [GTP Path PDP Miscellaneous Statistics Daily Reports, page 13-248](#)
- [GTP Path Errors Daily Reports, page 13-249](#)

- [GTP PDP/Bearer Statistics Daily Reports, page 13-250](#)
- [GTP Throughput Statistics Daily Reports, page 13-251](#)
- [GTPv2 Bearer Statistics Daily Reports, page 13-251](#)
- [GTPv2 Session Statistics Daily Reports, page 13-251](#)
- [GTPv2 Path Bearer Requests Statistics Daily Reports, page 13-253](#)
- [GTPv2 Path Bearer Responses Statistics Daily Reports, page 13-253](#)
- [GTPv2 Path Session Statistics Daily Reports, page 13-253](#)
- [GTPv2 Downlink Statistics Daily Reports, page 13-256](#)
- [GTPv2 Tunnel Statistics Daily Reports, page 13-259](#)
- [GTPv2 Notification Statistics Daily Reports, page 13-263](#)
- [GTPv2 Echo Statistics Daily Reports, page 13-265](#)
- [GTPv2 Miscellaneous Statistics Daily Reports, page 13-268](#)
- [GTPv2 Bearer Commands Statistics Daily Reports, page 13-271](#)
- [GTPv2 Bearer Resource Commands Statistics Daily Reports, page 13-274](#)
- [SGSN Throughput Statistics Daily Reports, page 13-277](#)



**Note** The 15-minute and hourly reports for PDNGW are available from the node level only; they are not available from the top level or the network level.

### APN Aggregate Miscellaneous Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Miscellaneous Statistics Daily report of GGSN Reports. See [APN Aggregate Miscellaneous Statistics Daily Reports, page 13-130](#).

### APN Aggregate PDP/Bearer Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate PDP/Bearer Statistics Daily report of GGSN Reports. See [APN Aggregate PDP/Bearer Statistics Daily Reports, page 13-133](#).

### APN Aggregate Bearer Statistics Daily Reports

MWTM displays the APN Aggregate Bearer Statistics Daily report obtained during the specified period. See [APN Aggregate Bearer Statistics Daily Reports, page 13-204](#).

### APN Aggregate Bearer QOS Statistics Daily Reports

MWTM displays the APN Aggregate Bearer QOS Statistics Daily report obtained during the specified period.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.

**Note**

The 15-minute and hourly reports for APN Aggregate Bearer QOS Statistics are available from the node level only; they are not available from the top level or the network level. Click on a node name in the APN Aggregate Bearer QOS Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose APN Aggregate Bearer QOS Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
APN	The name of the Access Point Name (APN).
Average Successful Dedicated Bearer QOS Modifications	The average successful dedicated bearer creation initiated by network.
Maximum Successful Dedicated Bearer QOS Modifications	The maximum successful dedicated bearer creation initiated by network.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.
Average Successful Dedicated Bearer NonQOS Modifications	The average successful dedicated bearer creation initiated by network.
Maximum Successful Dedicated Bearer NonQOS Modifications	The maximum successful dedicated bearer creation initiated by network.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
APN Aggregate Bearer QOS Statistics Daily (or APN Instance Bearer Statistics Daily)	Table, CSV	APN Name	The name of the Access Point Name (APN).
		APN Index	A unique numerical identifier for the APN.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Active Bearers	<ul style="list-style-type: none"> <li>Count—Number of active Bearer contexts on this APN.</li> </ul>
		Bearer Activations Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed Bearer activation procedures by MS.</li> <li>Rate—Rate (per second) of successfully completed Bearer activation procedures by the MS Total number of unsuccessful bearer modify initiated by MME or SGSN.</li> <li>Ratio—Number of successful activations for every 100 activation attempts.</li> </ul>
		Bearer Activations Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed Bearer activation procedures by the MS on this APN.</li> <li>Rate—Rate (per second) of failed Bearer activation procedures by the MS on this APN.</li> </ul>
		Bearer Deactivations Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed Bearer deactivation procedures by the SGW on this APN.</li> <li>Rate—Rate (per second) of successfully completed Bearer deactivation procedures by the SGW on this APN.</li> </ul>
		Bearer Updates Success	<ul style="list-style-type: none"> <li>Count—Total number of successful bearer update initiated by network.</li> <li>Rate—Rate (per second) of successful bearer update initiated by network.</li> <li>Ratio—Number of successful bearer update initiated by network for every 100 attempts.</li> </ul>
		Bearer Updates Failure	<ul style="list-style-type: none"> <li>Count—Total number of unsuccessful bearer update initiated by MME or SGSN.</li> <li>Rate—Rate at which the unsuccessful bearer update initiated by MME or SGSN.</li> </ul>

Report Type	Output	Field	Description
		Bearer Modifications Success	<ul style="list-style-type: none"> <li>Count—Total number of successful bearer modify initiated by MME or SGSN.</li> <li>Rate—Rate (per second) of successful bearer modify initiated by MME or SGSN.</li> <li>Ratio—Number of successful bearer modify initiated by MME or SGSN for every 100 initiation attempts.</li> </ul>
		Bearer Modifications Failure	<ul style="list-style-type: none"> <li>Count—Total number of unsuccessful bearer modify initiated by MME or SGSN.</li> <li>Rate—Rate at which the unsuccessful bearer modify initiated by MME or SGSN.</li> </ul>
		Dedicated Bearer Activations Success	<ul style="list-style-type: none"> <li>Count—Total number of successful dedicated bearer creation initiated by network.</li> <li>Rate—Rate (per second) of successful dedicated bearer creation initiated by network.</li> <li>Ratio—Number of successful dedicated bearer creation for every 100 bearer creation attempts.</li> </ul>
		Dedicated Bearer Activations Failure	<ul style="list-style-type: none"> <li>Count—Total number of unsuccessful dedicated bearer activation procedures received on this APN.</li> <li>Rate—Rate (per second) of unsuccessful dedicated bearer activation procedures received on this APN.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Successful Dedicated Bearer QOS Modifications/Successful Dedicated Bearer NonQOS Modifications	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## APN Aggregate PDP/Bearer Extended Statistics Daily Reports

MWTM displays the APN Aggregate PDP/Bearer Extended Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



### Note

The 15-minute and hourly reports for APN Aggregate PDP/Bearer Extended Statistics and APN Instance PDP/Bearer Extended Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the APN Aggregate PDP/Bearer Extended Statistics reports or in the APN Instance PDP/Bearer Extended Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose APN Aggregate PDP/Bearer Extended Statistics Daily (or APN Instance PDP/Bearer Extended Statistics Daily) from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
APN	The name of the Access Point Name (APN).
Successful Dynamic PDP/Bearer Activations by MS Ratio	<ul style="list-style-type: none"> <li>Average—Average number of successful dynamic activations for every 100 dynamic activation attempts.</li> <li>Maximum—Maximum number of successful dynamic activations for every 100 dynamic activation attempts.</li> <li>Maximum Date (<i>time zone</i>)—Time the maximum value occurred.</li> </ul>
Successful PDP/Bearer Activations By Network Ratio	<ul style="list-style-type: none"> <li>Average—Average number of successful activations for every 100 dynamic activation attempts.</li> <li>Maximum—Maximum number of successful activations for every 100 dynamic activation attempts.</li> <li>Maximum Date (<i>time zone</i>)—Time the maximum value occurred.</li> </ul>
Successful Dedicated Bearer Activations Ratio	<ul style="list-style-type: none"> <li>Average—Average number of successful dedicated activations for every 100 dynamic activation attempts.</li> <li>Maximum—Maximum number of successful dedicated activations for every 100 dynamic activation attempts.</li> <li>Maximum Date (<i>time zone</i>)—Time the maximum value occurred.</li> </ul>

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:



Report Type	Output	Field	Description
APN Aggregate PDP/Bearer Extended Statistics Daily	Table, CSV	APN Name	The name of the Access Point Name (APN).
		APN Index	A unique numerical identifier for the APN.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Dynamic PDP/Bearer Activations By MS Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed dynamic PDP/Bearer context activation procedures initiated by MS on this APN.</li> <li>Rate—Rate (per second) of successfully completed dynamic PDP/Bearer context activation procedures initiated by MS on this APN.</li> <li>Ratio—Number of successful dynamic activations for every 100 dynamic activation attempts.</li> </ul>
		Dynamic PDP/Bearer Activations By MS Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed dynamic PDP/Bearer context activation procedures initiated by MS on this APN.</li> <li>Rate—Rate (per second) of failed dynamic PDP/Bearer context activation procedures initiated by MS on this APN.</li> </ul>
		PDP/Bearer Activations By Network Success	<ul style="list-style-type: none"> <li>Count—Total number of successfully completed network initiated PDP/Bearer context activation procedures.</li> <li>Rate—Rate (per second) of successfully completed network initiated PDP/Bearer context activation procedures.</li> <li>Ratio—Number of successful network initiated activations for every 100 activation attempts.</li> </ul>
		PDP/Bearer Activations By Network Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed network initiated PDP/Bearer context activation procedures.</li> <li>Rate—Rate (per second) of failed network initiated PDP/Bearer context activation procedures.</li> </ul>

Report Type	Output	Field	Description
		PDP/Bearer Updates By Network Success	<ul style="list-style-type: none"> <li>Count—Total number of successful update responses received from the SGSN for SPGW initiated update requests on this APN.</li> <li>Rate—Rate (per second) of successful update responses received from the SGSN for SPGW initiated update requests on this APN.</li> <li>Ratio—Number of successful update responses received for every 100 update attempts.</li> </ul>
		PDP/Bearer Updates By Network Failure	<ul style="list-style-type: none"> <li>Count—Total number of failed update responses received from the SGSN for SPGW initiated update requests on this APN.</li> <li>Rate—Rate (per second) of failed update responses received from the SGSN for SPGW initiated update requests on this APN.</li> </ul>
		Dedicated Bearer Activations Success	<ul style="list-style-type: none"> <li>Count—Total number of successful dedicated bearer activation procedures received on this APN.</li> <li>Rate—Rate (per second) of successful dedicated bearer activation procedures received on this APN.</li> <li>Ratio—Number of successful dedicated bearer activation procedures for every 100 activation attempts.</li> </ul>
		Dedicated Bearer Activations Failure	<ul style="list-style-type: none"> <li>Count—Total number of unsuccessful dedicated bearer activation procedures received on this APN.</li> <li>Rate—Rate (per second) of unsuccessful dedicated bearer activation procedures received on this APN.</li> </ul>
	Graph	Successful Dynamic PDP/Bearer Activations by MS Ratio	Number of successful dynamic activations for every 100 dynamic activation attempts.
		Successful PDP/Bearer Activations By Network Ratio	Number of successful activations for every 100 dynamic activation attempts.
		Successful Dedicated Bearer Activations Ratio	Number of successful dedicated activations for every 100 dynamic activation attempts.

### APN Aggregate Throughput Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Throughput Statistics Daily report of GGSN Reports. See [APN Aggregate Throughput Statistics Daily Reports, page 13-139](#).

### APN Instance Miscellaneous Statistics Daily Reports

The GUI displays the same fields as that of APN Instance Miscellaneous Statistics Daily report of GGSN Reports. See [APN Instance Miscellaneous Statistics Daily Reports, page 13-143](#).

### APN Instance PDP/Bearer Statistics Daily Reports

The GUI displays the same fields as that of APN Instance PDP/Bearer Statistics Daily report of GGSN Reports. See [APN Instance PDP/Bearer Statistics Daily Reports, page 13-143](#).

### APN Instance PDP/Bearer Extended Statistics Daily Reports

The GUI displays the same fields as that of APN Instance PDP/Bearer Extended Statistics Daily report of GGSN Reports. See [APN Instance PDP/Bearer Extended Statistics Daily Reports, page 13-143](#).

### APN Instance Bearer Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate Bearer Statistics Daily report of SPGW reports. See [APN Aggregate Bearer Statistics Daily Reports, page 13-204](#).

### APN Instance Bearer QOS Statistics Daily Reports

The GUI displays the same fields as that of APN Aggregate BearerQOS Statistics Daily report of SPGW reports. See [APN Aggregate Bearer QOS Statistics Daily Reports, page 13-228](#).

### APN Instance Throughput Statistics Daily Reports

The GUI displays the same fields as that of APN Instance Throughput Statistics Daily report of GGSN Reports. See [APN Instance Throughput Statistics Daily Reports, page 13-143](#).

### APN Instance DHCP V6 Proxy Server Statistics Daily Reports

The GUI displays the same fields as that of APN Instance DHCP V6 Proxy Server Statistics Daily report of GGSN Reports. See [APN Instance DHCP V6 Proxy Server Statistics Daily Reports, page 13-143](#).

### Charging Group Statistics Daily Reports

The GUI displays the same fields as that of Charging Group Statistics Daily report of GGSN Reports. See [Charging Group Statistics Daily Reports, page 13-156](#).

### Charging Gateway Group Statistics Daily Reports

The GUI displays the same fields as that of Charging Gateway Group Statistics Daily report of GGSN Reports. See [Charging Gateway Group Statistics Daily, page 13-157](#).

### EPC Gateway Protection Statistics Daily Reports

MWTM displays the EPC Gateway Protection Statistics Daily report obtained during the specified period. See [EPC Gateway Protection Statistics Daily Reports, page 13-162](#).

## EPC Gateway Session Statistics Daily Reports

MWTM displays the EPC Gateway Session Statistics Daily report obtained during the specified period.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



**Note** The 15-minute and hourly EPC Gateway Session Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the EPC Gateway Session Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose EPC Gateway Session Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Active Bearers	Number of active bearer contexts that are currently established on the SPGW devices.
Active Dedicated Bearers	Total number of dedicated bearers currently active.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
EPC Gateway Session Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Active Bearers	Number of active bearer contexts that are currently established on the SPGW devices.
		Active SGW Sessions	Number of active SGW sessions.
		Active PGW Sessions	Number of active PGW sessions.
		Active SPGW Sessions	Number of active SPGW sessions.
		Default Active Dedicated Bearers	Total number of default and dedicated bearers currently active.
		Active Dedicated Bearers	Total number of dedicated bearers currently active.
		Active IPv4 Dedicated Bearers	Total number of IPv4 dedicated bearers currently active.
		Active IPv6 Dedicated Bearers	Total number of IPv6 dedicated bearers currently active.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Active Bearers/Active Dedicated Bearers	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## EPC Gateway Buffering Statistics Daily Reports

MWTM displays the EPC Gateway Buffering Statistics Daily report obtained during the specified period. See [EPC Gateway Buffering Statistics Daily Reports, page 13-164](#).

## GTP Active Statistics Daily Reports

MWTM displays the GTP Active Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



### Note

The 15-minute and hourly GTP Active Statistics (SPGW) reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Active Statistics (SPGW) reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTP Active Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Average Active Sessions	Average sessions which are in active state.
Maximum Active Sessions	Maximum sessions which are in active state.
Maximum Date (time zone)	Timestamp when the maximum value occurred.
Average Active Users	Average users that are active.
Maximum Active Users	Maximum users that are active.
Maximum Date (time zone)	Timestamp when the maximum value occurred.

### Step 3

Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTP Active Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Active Bearers	Total number of active bearers on this GTP.
		Active Sessions	Total number of sessions currently established with the system.
		Direct Tunnel PDP Contexts	Direct tunnels enabled for the PDP contexts in the GGSN.
		GTP v0 PDP Contexts	PDP contexts (GTP version 0) that are active.
		GTP v1 PDP Contexts	PDP contexts (GTP version 1) that are active.
		PPP Regen PDPs	Device-specific interfaces created for association with PDP contexts regenerated to a Point-to-Point (PPP) session.
		PPP PDPs	Total number of point to point PDP contexts.
		Active Users	Number of active users.
		Idle Users	Total number of users currently in Idle state in the gateway.
		Suspended Users	Total number of users suspended by the gateway.
		Total Direct Tunnel	<ul style="list-style-type: none"> <li>Enabled—Total number of enabled direct tunnels.</li> <li>PDP Error Indications—Total number of PDP error indicated direct tunnels.</li> <li>PDP Deleted—Number of deleted tunnels.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Active Sessions/ Active Users	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTP Charging Statistics Daily Reports

The GUI displays the same fields as that of GTP Charging Statistics Daily report of GGSN Reports. See [GTP Charging Statistics Daily Reports, page 13-149](#).

## GTP Error Statistics Daily Reports

MWTM displays the GTP Error Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



### Note

The 15-minute and hourly GTP Error Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Error Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTP Error Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Average Unexpected Signaling Messages	The average unexpected GTP signaling messages sent or received
Maximum Unexpected Signaling Messages	The maximum unexpected GTP signaling messages sent or received
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.
Average Dropped Signaling Messages	The average dropped GTP signaling messages sent or received
Maximum Dropped Signaling Messages	The maximum dropped GTP signaling messages sent or received
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

### Step 3

Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:



Report Type	Output	Field	Description
GTP Error Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		PDP Context Activations	<ul style="list-style-type: none"> <li>Insufficient Resources Rejection—Number of PDP context requests rejected due to insufficient resources.</li> </ul>
		PDP Context Requests	<ul style="list-style-type: none"> <li>PPP Regeneration Insufficient Resources Rejection—PDP context requests rejected due to insufficient resources for PPP regeneration.</li> <li>PPP Regeneration Threshold Limit Drops—Number of PDP context requests dropped due to the PPP regeneration threshold limit.</li> </ul>
		PDP Context Messages	<ul style="list-style-type: none"> <li>TFT Semantic Errors—Total number of received PDP context messages that had Traffic Flow Templates (TFT) with semantic errors.</li> <li>TFT Syntax Errors—Total number of received PDP context messages that had TFTs with syntax errors.</li> <li>Packet Filter Semantic Errors—Total number of received PDP context messages that had packet filters with semantic errors.</li> <li>Packet Filter Syntax Errors—Total number of received PDP context messages that had packet filters with syntax errors.</li> </ul>
		Signaling Messages	<ul style="list-style-type: none"> <li>Unexpected—Number of unexpected GTP signaling messages sent or received.</li> <li>Dropped—Number of GTP messages received with wrong value.</li> </ul>
		GTP Message Parsers Errors	<ul style="list-style-type: none"> <li>Unexpected—Number of unexpected GTP parser error messages sent or received.</li> <li>Dropped—Number of GTP parser error messages received with wrong value.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Average Unexpected Signaling Messages/ Maximum Unexpected Signaling Messages/ Average Dropped Signaling Messages/ Maximum Dropped Signaling Messages	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTP Path Data PDU Statistics Daily Reports

MWTM displays the GTP Path Data PDU Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



#### Note

The 15-minute and hourly GTP Path Data PDU Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path Data PDU Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose GTP Path Data PDU Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Report Type	Field	Description
GTP Path Data PDU Statistics Daily	Node	Name of the node.
	GTP Path	Path of the GTP.
	Timestamp (time zone)	Timestamp of the report.
	IPv6 PDU Messages Sent	<ul style="list-style-type: none"> <li>Count—Number of IPv6 PDU messages sent on SGSN path.</li> <li>Rate—Rate (per second) of IPv6 PDU messages sent on SGSN path.</li> </ul>
	IPv6 PDU Messages Received	<ul style="list-style-type: none"> <li>Count—Number of IPv6 PDU messages received on SGSN path.</li> <li>Rate—Rate (per second) of IPv6 PDU messages received on SGSN path.</li> </ul>
	IPv6 PDU Bits Sent	<ul style="list-style-type: none"> <li>Count—Number of bytes sent in IPv6 PDU message on SGSN path.</li> <li>Rate—Rate (per second) of IPv6 PDU bits sent on SGSN path.</li> </ul>
	IPv6 PDU Bits Received	<ul style="list-style-type: none"> <li>Count—Number of bytes received in IPv6 PDU message on SGSN path.</li> <li>Rate—Rate (per second) of IPv6 PDU bits received on SGSN path.</li> </ul>

### GTP Path Signaling Statistics Daily Reports

MWTM displays the GTP Path Signaling Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



#### Note

The 15-minute and hourly GTP Path Signaling Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path Signaling Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTP Path Signaling Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Report Type	Field	Description
GTP Path Signaling Statistics Daily	Node	Name of the node.
	GTP Path	Path of the GTP.
	Timestamp (time zone)	Timestamp of the report.
	Signaling Messages Sent	<ul style="list-style-type: none"> <li>Count—Number of signalling messages sent on SGSN path.</li> <li>Rate—Rate (per second) of signaling messages sent on SGSN path.</li> </ul>
	Signaling Messages Received	<ul style="list-style-type: none"> <li>Count—Number of signalling messages received on SGSN path.</li> <li>Rate—Rate (per second) of signaling messages received received on SGSN path.</li> </ul>

### GTP Path PDP Roaming Statistics Daily Reports

MWTM displays the GTP Path PDP Roaming Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



#### Note

The 15-minute and hourly GTP Path PDP Roaming Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path PDP Roaming Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTP Path PDP Roaming Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Report Type	Field	Description
GTP Path PDP Roaming Statistics Daily	Node	Name of the node.
	GTP Path	Path of the GTP.
	Timestamp (time zone)	Timestamp of the report.
	PDP Contexts Trusted Roaming	<ul style="list-style-type: none"> <li>Count—Number of roaming PDP contexts in a trusted PLMN.</li> <li>Rate—Rate (per second) of PDP contexts trusted roamings in PLMN.</li> </ul>
	PDP Contexts Non Trusted Roaming	<ul style="list-style-type: none"> <li>Count—Number of roaming PDP contexts that are not in a trusted PLMN.</li> <li>Rate—Rate (per second) of PDP contexts that are not in a trusted PLMN.</li> </ul>
	PDP Contexts Non Roaming	<ul style="list-style-type: none"> <li>Count—Number of non-roaming PDPs on a SGSN path.</li> <li>Rate—Rate (per second) of PDP contexts non roamings on a SGSN path.</li> </ul>

### GTP Path PDP Statistics Daily Reports

MWTM displays the GTP Path PDP Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



#### Note

The 15-minute and hourly GTP Path PDP Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path PDP Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose GTP Path PDP Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Report Type	Field	Description
GTP Path PDP Statistics Daily	Node	Name of the node.
	GTP Path	Path of the GTP.
	Timestamp (time zone)	Timestamp of the report.
	PDPs Created	<ul style="list-style-type: none"> <li>Count—Number of created PDPs since system is up.</li> <li>Rate—Rate (per second) of PDPs created since system is up.</li> </ul>
	PDPs Deleted	<ul style="list-style-type: none"> <li>Count—Number of PDPs deleted since system is up.</li> <li>Rate—Rate (per second) of PDPs Deleted since system is up.</li> </ul>
	PPP PDPs Created	<ul style="list-style-type: none"> <li>Count—Number of PPP PDPs created since the system is up.</li> <li>Rate—Rate (per second) of PPP PDPs created since the system is up.</li> </ul>
	PPP PDPs Deleted	<ul style="list-style-type: none"> <li>Count—Number of PPP PDPs deleted since the system is up.</li> <li>Rate—Rate (per second) of PPP PDPs deleted since the system is up.</li> </ul>
	IPv6 PDPs Created	<ul style="list-style-type: none"> <li>Count—Number of IPv6 PDPs successfully created on SGSN path.</li> <li>Rate—Rate (per second) of IPv6 PDPs created on SGSN path.</li> </ul>
	IPv6 PDPs Deleted	<ul style="list-style-type: none"> <li>Count—Number of IPv6 PDPs deleted on SGSN path.</li> <li>Rate—Rate (per second) of IPv6 PDPs deleted on SGSN path.</li> </ul>
	IPv4v6 PDPs Created	<ul style="list-style-type: none"> <li>Count—Number of IPv4v6 PDPs successfully created on SGSN path.</li> <li>Rate—Rate (per second) of IPv4v6 PDPs created on SGSN path.</li> </ul>
	IPv4v6 PDPs Deleted	<ul style="list-style-type: none"> <li>Count—Number of IPv4v6 PDPs deleted on SGSN path.</li> <li>Rate—Rate (per second) of IPv4v6 PDPs deleted on SGSN path.</li> </ul>

### GTP Path PDP Update Statistics Daily Reports

MWTM displays the GTP Path PDP Update Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



**Note** The 15-minute and hourly GTP Path PDP Update Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path PDP Update Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose SGSN Throughput Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Report Type	Field	Description
GTP Path PDP Update Statistics Daily	Node	Name of the node.
	GTP Path	Path of the GTP.
	Timestamp (time zone)	Timestamp of the report.
	Update Create Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create requests received, which are treated as update request on GGSN.</li> <li>Rate—Rate (per second) of update create requests received, which are treated as update request on GGSN.</li> </ul>
	Update PDP Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of GGSN initiated update PDP requests sent on a SGSN path.</li> <li>Rate—Rate (per second) of GGSN initiated update PDP requests sent on SGSN path.</li> </ul>
	Update PDP Responses Received	<ul style="list-style-type: none"> <li>Count—Number of update PDP responses received from the SGSN for the GGSN initiated update PDP requests.</li> <li>Rate—Rate (per second) of update PDP responses received from the SGSN for the GGSN initiated update PDP requests.</li> </ul>

### GTP Path PDP Version Statistics Daily Reports

MWTM displays the GTP Path PDP Version Statistics Daily report obtained during the specified period.



**Note** If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.

**Note**

The 15-minute and hourly GTP Path PDP Version Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path PDP Version Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTP Path PDP Version Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Report Type	Field	Description
GTP Path PDP Version Statistics Daily	Node	Name of the node.
	GTP Path	Path of the GTP.
	Timestamp (time zone)	Timestamp of the report.
	GTP Version Changes	<ul style="list-style-type: none"> <li>Count—Number of GTP version changes occurred on a SGSN path.</li> <li>Rate—Rate (per second) of GTP version changes occurred on a SGSN path.</li> </ul>
	Locally Deleted PDPs Version Upgrade	<ul style="list-style-type: none"> <li>Count—Number of PDPs, which are deleted locally, due to version upgrade.</li> <li>Rate—Rate (per second) of locally deleted PDPs due to version upgrade.</li> </ul>
	Locally Deleted PDPs Version Fallback	<ul style="list-style-type: none"> <li>Count—Number of PDPs, which are deleted locally, due to fallback in GTP version.</li> <li>Rate—Rate (per second) of locally deleted PDPs due to fallback in GTP version.</li> </ul>

### GTP Path PDP Miscellaneous Statistics Daily Reports

MWTM displays the GTP Path PDP Miscellaneous Statistics Daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.

**Note**

The 15-minute and hourly GTP Path PDP Miscellaneous Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path PDP Miscellaneous Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.



- Step 2** Choose GTP Path PDP Miscellaneous Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Report Type	Field	Description
GTP Path PDP Miscellaneous Statistics Daily	Node	Name of the node.
	GTP Path	Path of the GTP.
	Timestamp ( <i>time zone</i> )	Timestamp of the report.
	Single PDP Contexts Cleared	<ul style="list-style-type: none"> <li>Count—Number of hanging single PDP contexts cleared on the GGSN.</li> <li>Rate—Rate (per second) of single PDP contexts cleared on the GGSN.</li> </ul>
	Path Fail Locally Deleted PDPs	<ul style="list-style-type: none"> <li>Count—Number of PDPs deleted locally because of path failure.</li> <li>Rate—Rate (per second) of PDPs deleted locally because of path failure.</li> </ul>
	PDP Create Delete Collisions	<ul style="list-style-type: none"> <li>Count—Number of collisions happened when a PDP is locally deleted and recreated.</li> <li>Rate—Rate (per second) of collisions happened when a PDP is locally deleted and recreated.</li> </ul>
	Retransmitted Create PDP Requests	<ul style="list-style-type: none"> <li>Count—Number of retransmitted create PDP requests received.</li> <li>Rate—Rate (per second) of retransmitted create PDP requests received.</li> </ul>
	IPv6 PDP Activation Rejected	<ul style="list-style-type: none"> <li>Count—Number of IPv6 PDP activation rejected by the GGSN.</li> <li>Rate—Rate (per second) of IPv6 PDP activation rejected by the GGSN.</li> </ul>
	Direct Tunnel Enabled	<ul style="list-style-type: none"> <li>Count—Number of times Direct tunnel is enabled for the PDP contexts in GGSN.</li> <li>Rate—Rate (per second) of times Direct tunnel is enabled for the PDP contexts in GGSN.</li> </ul>

## GTP Path Errors Daily Reports

MWTM displays the GTP Path Errors Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > PDNGW, SPGW**.



**Note** The 15-minute and hourly GTP Path Error (PDNGW) reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTP Path Error (PDNGW) reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose GTP Path Errors Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Dropped Signaling Messages	The signaling messages are dropped.
Unexpected Signaling Messages	The unexpected GTP signaling messages are sent or received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Field	Description
Node	Name of the node.
GTP Path	Path of the GTP.
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Signaling Messages	<p><b>Unexpected</b></p> <ul style="list-style-type: none"> <li>Count—Number of unexpected GTP signaling messages sent or received.</li> <li>Rate—Rate at which the unexpected GTP signaling messages are sent or received.</li> </ul> <p><b>Dropped</b></p> <ul style="list-style-type: none"> <li>Count—Number of signaling messages that are dropped.</li> <li>Rate—Rate at which the signaling messages are dropped.</li> </ul>

## GTP PDP/Bearer Statistics Daily Reports

The GUI displays the same fields as that of GTP PDP Statistics Daily report of PDNGW Reports. See [GTP PDP/Bearer Statistics Daily Reports, page 13-173](#).

## GTP Throughput Statistics Daily Reports

The GUI displays the same fields as that of GTP Throughput Statistics Daily report of GGSN Reports. See [GTP Throughput Statistics Daily Reports, page 13-153](#).

## GTPv2 Bearer Statistics Daily Reports

MWTM displays the GTPv2 Bearer Statistics Daily report obtained during the specified period. See [GTPv2 Bearer Statistics Daily Reports, page 13-175](#).

## GTPv2 Session Statistics Daily Reports

MWTM displays the GTPv2 Session Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**



### Note

The 15-minute and hourly GTPv2 Session Daily reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Session Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTPv2 Session Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Session Requests Sent	The create session request messages are sent.
Create Session Requests Received	The create session request messages are received.
Delete Session Responses Sent	The delete session response messages are sent.
Delete Session Responses Received	The delete session response messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

### Step 3

Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Session Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Create Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create session request messages received.</li> <li>Rate—Rate at which the create session request messages are received.</li> </ul>
		Create Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session request messages rejected.</li> <li>Rate—Rate at which the create session request messages are rejected.</li> </ul>
		Delete Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages received.</li> <li>Rate—Rate at which the delete session request messages are received.</li> </ul>
		Delete Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages rejected.</li> <li>Rate—Rate at which the delete session request messages are rejected.</li> </ul>
		Create Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of create session response messages sent.</li> <li>Rate—Rate at which the create session response messages are sent.</li> </ul>
		Delete Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages sent.</li> <li>Rate—Rate at which the delete session response messages are sent.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Session Requests Sent/Create Session Requests Received/Delete Session Responses Sent/Delete Session Responses Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTPv2 Path Bearer Requests Statistics Daily Reports

MWTM displays the GTPv2 Path Bearer Requests Statistics Daily report obtained during the specified period. See [GTPv2 Path Bearer Requests Statistics Daily Reports, page 13-218](#).

### GTPv2 Path Bearer Responses Statistics Daily Reports

MWTM displays the GTPv2 Path Bearer Responses Statistics Daily report obtained during the specified period. See [GTPv2 Path Bearer Responses Statistics Daily Reports, page 13-221](#).

### GTPv2 Path Session Statistics Daily Reports

MWTM displays the GTPv2 Path Session Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.

**Note**

The 15-minute and hourly GTPv2 Path Session Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the GTPv2 Path Session Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTPv2 Path Session Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Session Requests Sent	The create session request messages are sent.
Create Session Requests Received	The create session request messages are received.
Delete Session Responses Sent	The delete session response messages are sent.
Delete Session Responses Received	The delete session response messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Path Session Statistics Daily	Table, CSV	Node	Name of the node.
		GTP Path	Path of GTP.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Create Session Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create session request messages sent.</li> <li>Rate—Rate at which the create session request messages are sent.</li> </ul>
		Create Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create session request messages received.</li> <li>Rate—Rate at which the create session request messages are received.</li> </ul>
		Create Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session request messages rejected.</li> <li>Rate—Rate at which the create session request messages are rejected.</li> </ul>
		Delete Session Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages sent.</li> <li>Rate—Rate at which the delete session request messages are sent.</li> </ul>
		Delete Session Requests Received	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages received.</li> <li>Rate—Rate at which the delete session request messages are received.</li> </ul>
		Delete Session Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session request messages rejected.</li> <li>Rate—Rate at which the delete session request messages are rejected.</li> </ul>
		Create Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of create session response messages sent.</li> <li>Rate—Rate at which the create session response messages are sent.</li> </ul>
		Create Session Responses Received	<ul style="list-style-type: none"> <li>Count—Number of create session response messages received.</li> <li>Rate—Rate at which the create session response messages are received.</li> </ul>
		Create Session Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of create session response messages rejected.</li> <li>Rate—Rate at which the create session response messages are rejected.</li> </ul>

Report Type	Output	Field	Description
		Delete Session Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages sent.</li> <li>Rate—Rate at which the delete session response messages are sent.</li> </ul>
		Delete Session Responses Received	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages received.</li> <li>Rate—Rate at which the delete session response messages are received.</li> </ul>
		Delete Session Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of delete session response messages rejected.</li> <li>Rate—Rate at which the delete session response messages are rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Session Requests Sent/Create Session Requests Received/Delete Session Responses Sent/Delete Session Responses Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTPv2 Downlink Statistics Daily Reports

MWTM displays the GTPv2 Downlink Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



**Note**

The 15-minute and hourly GTPv2 Downlink Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SPGW GTPv2 Downlink Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTPv2 Downlink Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Downlink Data Notification Sent	The downlink data notification messages are sent.
Downlink Data Notification Received	The downlink data notification messages are received.
Downlink Data Notification Rejected	The downlink data notification messages are rejected.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

A summary table displays the information described in the following table:

Report Type	Output	Field	Description
GTPv2 Downlink Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp (time zone)	Timestamp shows the time bits-per second value occurred.
		Downlink Data Notification Sent	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification messages sent.</li> <li>Rate—Rate at which the downlink data notification messages are sent.</li> </ul>
		Downlink Data Notification Received	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification messages received.</li> <li>Rate—Rate at which the downlink data notification messages are received.</li> </ul>
		Downlink Data Notification Rejected	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification messages rejected.</li> <li>Rate—Rate at which the downlink data notification messages are rejected.</li> </ul>
		Downlink Data Notification Failure Indication Sent	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification failure indication messages sent.</li> <li>Rate—Rate at which the downlink data notification failure indication messages sent.</li> </ul>
		Downlink Data Notification Failure Indication Received	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification failure indication messages received.</li> <li>Rate—Rate at which the downlink data notification failure indication messages received.</li> </ul>
		Downlink Data Notification Failure Indication Rejected	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification failure indication messages rejected.</li> <li>Rate—Rate at which the downlink data notification failure indication messages rejected.</li> </ul>
		Downlink Data Notification Acknowledgements Sent	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification acknowledgements sent.</li> <li>Rate—Rate at which the downlink data notification acknowledgements sent.</li> </ul>

Report Type	Output	Field	Description
		Downlink Data Notification Acknowledgements Received	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification acknowledgements received.</li> <li>Rate—Rate at which the downlink data notification acknowledgements received.</li> </ul>
		Downlink Data Notification Acknowledgements Rejected	<ul style="list-style-type: none"> <li>Count—Number of downlink data notification acknowledgements rejected.</li> <li>Rate—Rate at which the downlink data notification acknowledgements rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Downlink Data Notification Sent/Downlink Data Notification Received/Downlink Data Notification Rejected	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTPv2 Tunnel Statistics Daily Reports

MWTM displays the GTPv2 Tunnel Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.

**Note**

The 15-minute and hourly GTPv2 Tunnel Statistics Daily reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SPGW GTPv2 Tunnel Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTPv2 Tunnel Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Create Indirect Tunnel Requests Sent	The indirect tunnel request messages are sent.
Create Indirect Tunnel Requests Received	The indirect tunnel request messages are received.
Create Indirect Tunnel Responses Sent	The indirect tunnel response messages are sent.
Create Indirect Tunnel Responses Received	The indirect tunnel response messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Tunnel Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Create Indirect Tunnel Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel create request messages sent.</li> <li>Rate—Rate at which the indirect tunnel create request messages are sent.</li> </ul>
		Create Indirect Tunnel Requests Received	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel create request messages received.</li> <li>Rate—Rate at which the indirect tunnel create request messages are received.</li> </ul>
		Create Indirect Tunnel Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel create request messages rejected.</li> <li>Rate—Rate at which the indirect tunnel create request messages are rejected.</li> </ul>
		Delete Indirect Tunnel Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel delete request messages sent.</li> <li>Rate—Rate at which the indirect tunnel delete request messages are sent.</li> </ul>
		Delete Indirect Tunnel Requests Received	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel delete request messages received.</li> <li>Rate—Rate at which the indirect tunnel delete request messages are received.</li> </ul>
		Delete Indirect Tunnel Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel delete request messages rejected.</li> <li>Rate—Rate at which the indirect tunnel delete request messages are rejected.</li> </ul>
		Create Indirect Tunnel Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel create response messages sent.</li> <li>Rate—Rate at which the indirect tunnel create response messages are sent.</li> </ul>
		Create Indirect Tunnel Responses Received	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel create response messages received.</li> <li>Rate—Rate at which the indirect tunnel create response messages are received.</li> </ul>

Report Type	Output	Field	Description
		Create Indirect Tunnel Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel create response messages rejected.</li> <li>Rate—Rate at which the indirect tunnel create response messages are rejected.</li> </ul>
		Delete Indirect Tunnel Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel delete response messages sent.</li> <li>Rate—Rate at which the indirect tunnel delete response messages are sent.</li> </ul>
		Delete Indirect Tunnel Responses Received	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel delete response messages received.</li> <li>Rate—Rate at which the indirect tunnel delete response messages are received.</li> </ul>
		Delete Indirect Tunnel Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of indirect tunnel delete response messages rejected.</li> <li>Rate—Rate at which the indirect tunnel delete response messages are rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Create Indirect Tunnel Requests Sent/Create Indirect Tunnel Requests Received/Create Indirect Tunnel Responses Sent/Create Indirect Tunnel Responses Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTPv2 Notification Statistics Daily Reports

MWTM displays the GTPv2 Notification Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



### Note

The 15-minute and hourly GTPv2 Notification Statistics Daily reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SPGW GTPv2 Notification Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTPv2 Notification Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Suspend Notification Sent	The suspend notification messages are sent.
Suspend Notification Received	The suspend notification messages are received.
Resume Notification Sent	The resume notification messages are sent.
Resume Notification Received	The resume notification messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

### Step 3

Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

A summary table displays the information described in the following table:

Report Type	Output	Field	Description
GTPv2 Notification Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp (time zone)	Timestamp shows the time bits-per second value occurred.
		Suspend Notification Sent	<ul style="list-style-type: none"> <li>Count—Number of suspend notification messages sent.</li> <li>Rate—Rate at which the suspend notification messages are sent.</li> </ul>
		Suspend Notification Received	<ul style="list-style-type: none"> <li>Count—Number of suspend notification messages received.</li> <li>Rate—Rate at which the suspend notification messages are received.</li> </ul>
		Suspend Notification Rejected	<ul style="list-style-type: none"> <li>Count—Number of suspend notification messages rejected.</li> <li>Rate—Rate at which the suspend notification messages are rejected.</li> </ul>
		Suspend Notification Acknowledgements Sent	<ul style="list-style-type: none"> <li>Count—Number of suspend notification acknowledgement messages sent.</li> <li>Rate—Rate at which the suspend notification acknowledgement messages are sent.</li> </ul>
		Suspend Notification Acknowledgements Received	<ul style="list-style-type: none"> <li>Count—Number of suspend notification acknowledgement messages received.</li> <li>Rate—Rate at which the suspend notification acknowledgement messages are received.</li> </ul>
		Suspend Notification Acknowledgements Rejected	<ul style="list-style-type: none"> <li>Count—Number of suspend notification acknowledgement messages rejected.</li> <li>Rate—Rate at which the suspend notification acknowledgement messages are rejected.</li> </ul>
		Resume Notification Sent	<ul style="list-style-type: none"> <li>Count—Number of resume notification messages sent.</li> <li>Rate—Rate at which the resume notification messages are sent.</li> </ul>
		Resume Notification Received	<ul style="list-style-type: none"> <li>Count—Number of resume notification messages received.</li> <li>Rate—Rate at which the resume notification messages are received.</li> </ul>
		Resume Notification Rejected	<ul style="list-style-type: none"> <li>Count—Number of resume notification messages rejected.</li> <li>Rate—Rate at which the resume notification messages are rejected.</li> </ul>
		Resume Notification Acknowledgements Sent	<ul style="list-style-type: none"> <li>Count—Number of resume notification acknowledgement messages sent.</li> <li>Rate—Rate at which the resume notification acknowledgement messages are sent.</li> </ul>



Report Type	Output	Field	Description
		Resume Notification Acknowledgements Received	<ul style="list-style-type: none"> <li>Count—Number of resume notification acknowledgement messages received.</li> <li>Rate—Rate at which the resume notification acknowledgement messages are received.</li> </ul>
		Resume Notification Acknowledgements Rejected	<ul style="list-style-type: none"> <li>Count—Number of resume notification acknowledgement messages rejected.</li> <li>Rate—Rate at which the resume notification acknowledgement messages are rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Suspend Notification Sent/Suspend Notification Received/Resume Notification Sent/Resume Notification Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTPv2 Echo Statistics Daily Reports

MWTM displays the GTPv2 Echo Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



### Note

The 15-minute and hourly GTPv2 Echo Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SPGW GTPv2 Echo Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose GTPv2 Echo Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Echo Requests Sent	The echo request messages are sent.
Echo Requests Received	The echo request messages are received.
Echo Responses Sent	The echo response messages are sent.
Echo Responses Received	The echo response messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Echo Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Echo Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of echo request messages sent.</li> <li>Rate—Rate at which the echo request messages are sent.</li> </ul>
		Echo Requests Received	<ul style="list-style-type: none"> <li>Count—Number of echo request messages received.</li> <li>Rate—Rate at which the echo request messages are received.</li> </ul>
		Echo Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of echo request messages rejected.</li> <li>Rate—Rate at which the echo request messages are rejected.</li> </ul>
		Echo Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of echo response messages sent.</li> <li>Rate—Rate at which the echo response messages are sent.</li> </ul>
		Echo Responses Received	<ul style="list-style-type: none"> <li>Count—Number of echo response messages received.</li> <li>Rate—Rate at which the echo response messages are received.</li> </ul>
		Echo Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of echo response messages rejected.</li> <li>Rate—Rate at which the echo response messages are rejected.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Echo Requests Sent/Echo Requests Received/E cho Responses Sent/Echo Responses Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

## GTPv2 Miscellaneous Statistics Daily Reports

MWTM displays the GTPv2 Miscellaneous Statistics Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



### Note

The 15-minute and hourly GTPv2 Miscellaneous Statistics daily reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SPGW GTPv2 Miscellaneous Statistics daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

### Step 2

Choose GTPv2 Miscellaneous Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Delete PDN Connection Set Requests Sent	The create bearer request messages are sent.
Delete PDN Connection Set Requests Received	The create bearer request messages are received.
Release Access Bearer Requests Sent	The create bearer request messages are sent.
Release Access Bearer Requests Received	The create bearer request messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

### Step 3

Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Miscellaneous Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Delete PDN Connection Set Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Delete PDN Connection Set Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Delete PDN Connection Set Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>
		Delete PDN Connection Set Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
		Delete PDN Connection Set Responses Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
		Delete PDN Connection Set Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>

Report Type	Output	Field	Description
		Release Access Bearer Requests Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Release Access Bearer Requests Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Release Access Bearer Requests Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>
		Release Access Bearer Responses Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
		Release Access Bearer Responses Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
		Release Access Bearer Responses Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Delete PDN Connection Set Requests Sent/Delete PDN Connection Set Requests Received/Release Access Bearer Requests Sent/Release Access Bearer Requests Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTPv2 Bearer Commands Statistics Daily Reports

MWTM displays the GTPv2 Bearer Commands Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



#### Note

The 15-minute and hourly GTPv2 Bearer Commands Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SPGW GTPv2 Bearer Commands Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose GTPv2 Bearer Commands Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Modify Bearer Commands Sent	The create bearer request messages are sent.
Modify Bearer Commands Received	The create bearer request messages are received.
Delete Bearer Commands Sent	The create bearer request messages are sent.
Delete Bearer Commands Received	The create bearer request messages are received.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:



Report Type	Output	Field	Description
GTPv2 Bearer Commands Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Modify Bearer Commands Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Modify Bearer Commands Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Modify Bearer Commands Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>
		Modify Bearer Failure Indication Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
		Modify Bearer Failure Indication Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
		Modify Bearer Failure Indication Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>
		Delete Bearer Commands Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Delete Bearer Commands Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Delete Bearer Commands Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>

Report Type	Output	Field	Description
		Delete Bearer Failure Indication Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
		Delete Bearer Failure Indication Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
		Delete Bearer Failure Indication Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Modify Bearer Commands Sent/Modify Bearer Commands Received/Delete Bearer Commands Sent/Delete Bearer Commands Received	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### GTPv2 Bearer Resource Commands Statistics Daily Reports

MWTM displays the GTPv2 Bearer Resource Commands Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



**Note** The 15-minute and hourly GTPv2 Bearer Resource Commands Statistics Daily reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SPGW GTPv2 Bearer Resource Commands Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose GTPv2 Bearer Resource Commands Statistics Daily from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field	Description
Node	The name of the node.
Bearer Resource Commands Sent	The create bearer request messages are sent.
Bearer Resource Commands Received	The create bearer request messages are received.
Bearer Resource Commands Rejected	The create bearer request messages are rejected.
Maximum Date ( <i>time zone</i> )	Time the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
GTPv2 Bearer Resource Commands Statistics Daily	Table, CSV	Node	Name of the node.
		Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
		Bearer Resource Command s Sent	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Bearer Resource Command s Received	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages received.</li> <li>Rate—Rate at which the create bearer request messages are received.</li> </ul>
		Bearer Resource Command s Rejected	<ul style="list-style-type: none"> <li>Count—Number of create bearer request messages rejected.</li> <li>Rate—Rate at which the create bearer request messages are rejected.</li> </ul>
		Bearer Resource Failure Indication Sent	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages received.</li> <li>Rate—Rate at which the modify bearer request messages are received.</li> </ul>
		Bearer Resource Failure Indication Received	<ul style="list-style-type: none"> <li>Count—Number of modify bearer request messages rejected.</li> <li>Rate—Rate at which the modify bearer request messages are rejected.</li> </ul>
		Bearer Resource Failure Indication Rejected	<ul style="list-style-type: none"> <li>Count—Number of update bearer request messages received.</li> <li>Rate—Rate at which the update bearer request messages are received.</li> </ul>

Report Type	Output	Field	Description
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing.
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Bearer Resource Commands Sent/Bearer Resource Commands Received/Bearer Resource Commands Rejected	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.

### SGSN Throughput Statistics Daily Reports

MWTM displays the SGSN Throughput Statistics Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

#### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Statistics > SPGW**.



#### Note

The 15-minute and hourly SGSN Throughput Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the SGSN Throughput Statistics Daily reports to navigate to a specific node to view hourly and 15 minute reports for that node.

#### Step 2

Choose SGSN Throughput Statistics Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Report Type	Field	Description
SGSN Throughput Statistics Daily	Node	Name of the node.
	GTP Path	Path of the GTP.
	Timestamp (time zone)	Timestamp of the report.
	Upstream Packets	<ul style="list-style-type: none"> <li>Count—Number of upstream packets sent on this SGSN data path.</li> <li>Rate—Rate (per second) of upstream packets sent on this SGSN.</li> </ul>
	Upstream Bits	<ul style="list-style-type: none"> <li>Count—Number of upstream bytes sent on this SGSN data path.</li> <li>Rate—Rate (per second) of upstream bytes sent on this SGSN data path.</li> </ul>
	Downstream Packets	<ul style="list-style-type: none"> <li>Count—Number of downstream packets sent on this SGSN data path.</li> <li>Rate—Rate (per second) of downstream packets sent on this SGSN data path.</li> </ul>
	Downstream Bits	<ul style="list-style-type: none"> <li>Count—Number of downstream bytes sent on this SGSN data path.</li> <li>Rate—Rate (per second) of downstream bytes sent on this SGSN data path.</li> </ul>

## Viewing RAN Statistics Reports

RAN Statistics Reports are located within **Reports > RAN Reports** in the MWTM web interface. You can also find the RAN statistics reports in the `/opt/CSCOsgm/reports` directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All reports are saved as export files in .csv format.


You can view any of the following RAN statistics reports:

- [PWE3 Reports, page 13-278](#)
- [QOS Reports, page 13-284](#)
- [RAN-Optimized Reports, page 13-290](#)

### PWE3 Reports


The MWTM web interface provides network-wide and node level reports that summarize PWE3 over a specified time period. The information is available in graphical, tabular, and CSV formats. Administrators use these reports for analysis of network-wide performance and errors for RAN backhauls and shorthauls. For example, you can generate a report to show which backhaul links were the most heavily utilized in the last 24 hours.

To generate a network-wide PWE3 report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > PWE3**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu (see [Table 13-1](#) for a list of report types and their contents).
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu (see [Table 13-1](#) for contents of each output type).
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.



**Note** The Graph output displays up to twelve RAN data streams based on traffic and/or number of errors. To view all RAN data streams, choose Table or CSV.

- Step 6** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [PWE3 Peak Performance Daily Reports, page 13-279](#)
- [PWE3 Average Performance Daily Reports, page 13-282](#)

## PWE3 Peak Performance Daily Reports

MWTM displays the PWE3 Peak Performance Daily report obtained during the specified period.



**Note** If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > PWE3**.



**Note** The 15-minute and hourly PWE3 Peak Performance reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PWE3 Peak Performance reports to navigate to a specific node to view hourly and 15 minute reports for that node.

- Step 2** Choose PWE3 Peak Performance Daily from Type drop-down menu.
- A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Virtual Circuit	Name of the Virtual Circuit

Field	Description
Send Bits/Sec	<ul style="list-style-type: none"><li>• Average—Average bits/second sent.</li><li>• Maximum—Maximum bits/second sent.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>
Recv Bits/Sec	<ul style="list-style-type: none"><li>• Average—Average bits/second received.</li><li>• Maximum—Maximum bits/second received.</li><li>• Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>



**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PWE3 Peak Performance Daily	Table, CSV	Node	Name of the node for the virtual circuit.
		ID	Virtual circuit ID.
		Timestamp (time zone)	Timestamp of the report.
		Peer Address	IP address of the peer node.
		Received	<ul style="list-style-type: none"> <li>• Packet Count—Number of packets received.</li> <li>• Packet Max Rate—Maximum packet rate for traffic received.</li> <li>• Packet Avg Rate—Average packet rate for traffic received.</li> <li>• Packet Min Rate—Minimum packet rate for traffic received.</li> <li>• Total—Total bits received.</li> <li>• Max Rate—Maximum bits received.</li> <li>• Avg Rate—Average bits received.</li> <li>• Min Rate—Minimum bits received.</li> </ul>
		Sent	<ul style="list-style-type: none"> <li>• Packet Count—Number of packets sent.</li> <li>• Packet Max Rate—Maximum packet rate for traffic sent.</li> <li>• Packet Avg Rate—Average packet rate for traffic sent.</li> <li>• Packet Min Rate—Minimum packet rate for traffic sent.</li> <li>• Total—Total bits sent.</li> <li>• Max Rate—Maximum bits sent.</li> <li>• Avg Rate—Average bits sent.</li> <li>• Min Rate—Minimum bits sent.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Maximum Bits/Sec	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		Legend	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## PWE3 Average Performance Daily Reports

MWTM displays the PWE3 Average Performance Daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1**

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > PWE3**.

**Note**

The 15-minute and hourly PWE3 Average Performance reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the PWE3 Average Performance reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2**

Choose PWE3 Average Performance Daily from Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Virtual Circuit	Name of the Virtual Circuit
Send Bits/Sec	<ul style="list-style-type: none"><li>Average—Average bits/second sent.</li><li>Maximum—Maximum bits/second sent.</li><li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>
Recv Bits/Sec	<ul style="list-style-type: none"><li>Average—Average bits/second received.</li><li>Maximum—Maximum bits/second received.</li><li>Maximum Date (<i>time zone</i>)—Timestamp when the maximum value occurred.</li></ul>



**Step 3**

Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PWE3 Average Performance Daily	Table, CSV	Node	Name of the node for the virtual circuit.
		ID	Virtual circuit ID.
		Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Peer Address	IP address of the peer node.
		Received	<ul style="list-style-type: none"> <li>• Packet Count—Number of packets received.</li> <li>• Packet Max Rate—Maximum packet rate for traffic received.</li> <li>• Packet Avg Rate—Average packet rate for traffic received.</li> <li>• Packet Min Rate—Minimum packet rate for traffic received.</li> <li>• Total—Total bits received.</li> <li>• Max Rate—Maximum bits received.</li> <li>• Avg Rate—Average bits received.</li> <li>• Min Rate—Minimum bits received.</li> </ul>
		Sent	<ul style="list-style-type: none"> <li>• Packet Count—Number of packets sent.</li> <li>• Packet Max Rate—Maximum packet rate for traffic sent.</li> <li>• Packet Avg Rate—Average packet rate for traffic sent.</li> <li>• Packet Min Rate—Minimum packet rate for traffic sent.</li> <li>• Total—Total bits sent.</li> <li>• Max Rate—Maximum bits sent.</li> <li>• Avg Rate—Average bits sent.</li> <li>• Min Rate—Minimum bits sent.</li> </ul>
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Average Bits/Sec	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## QOS Reports

The MWTM web interface provides node-level QOS reports. To generate a network-wide QOS report:

- 
- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > QOS**
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Table or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [QOS Class Map Daily Reports, page 13-284](#)
  - [QOS Match Statement Daily Reports, page 13-285](#)
  - [QOS Packet Marking Daily Reports, page 13-286](#)
  - [QOS Policing Daily Reports, page 13-287](#)
  - [QOS Queuing Daily Reports, page 13-288](#)
  - [QOS Traffic Shaping Daily Reports, page 13-289](#)
- 

### QOS Class Map Daily Reports

MWTM displays the QOS Class Map Daily report obtained during the specified period.



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

---

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > QOS**.



#### Note

The 15-minute and hourly QOS Class Map reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the QOS Class Map Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

---

- Step 2** Choose QOS Class Map Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Class Map	User-defined traffic class that contains one or many match statements used to classify packets into different categories.
Service Policy Direction	The direction of traffic for which the service policy is applied.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Pre-Policy	<ul style="list-style-type: none"> <li>• Packets—The number of inbound packets prior to executing any QoS policies.</li> <li>• Bits—The number of inbound octets prior to executing any QoS policies.</li> <li>• Bits Rate—The rate of the traffic prior to executing any QoS policies.</li> </ul>
Post-Policy	<ul style="list-style-type: none"> <li>• Bits—The number of outbound octets after executing QoS policies.</li> <li>• Bits Rate—The rate of the traffic after executing QoS policies</li> </ul>
Dropped	<ul style="list-style-type: none"> <li>• Packets—The number of outbound packets after executing QoS policies.</li> <li>• SRAM Buffer Packets—The number of drop packet count which occurred due to a lack of SRAM buffers during output processing on an interface.</li> <li>• Bits—The number of drop octet count which occurred due to a lack of SRAM buffers during output processing on an interface.</li> <li>• Bits Rate—The rate of the traffic due to a lack of SRAM buffers during output processing on an interface.</li> </ul>

## QoS Match Statement Daily Reports

MWTM displays the QoS Match Statement Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

### Step 1

In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > QoS**.



### Note

The 15-minute and hourly QoS Match Statement Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the QoS Match Statement Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose QOS Match Statement Daily from Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Class Map	User-defined traffic class that contains one or many match statements used to classify packets into different categories.
Service Policy Direction	The direction of traffic for which the service policy is applied.
Match Statement	The specific match criteria to identify packets for classification purposes.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Pre-Policy	<ul style="list-style-type: none"> <li>• Packets—The number of inbound packets prior to executing any QoS policies.</li> <li>• Bits—The number of inbound octets prior to executing any QoS policies.</li> <li>• Bits Rate—The rate of the traffic prior to executing any QoS policies.</li> </ul>

## QOS Packet Marking Daily Reports

MWTM displays the QOS Packet Marking Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > QOS**.



### Note

The 15-minute and hourly QOS Packet Marking Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the QOS Packet Marking Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose QOS Packet Marking Daily from Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Class Map	User-defined traffic class that contains one or many match statements used to classify packets into different categories.
Service Policy Direction	The direction of traffic for which the service policy is applied.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
QOS Group Packets	The number of packets whose QoS Group field is marked by Set feature.
ATM CLP Packets	The number of packets whose ATM CLP Bit is marked by Set feature.
Layer 2 COS Packets	The Layer 2 CoS value to use when mapping this DSCP to layer 2 CoS.
Discard Class Packets	The number of packets whose Discard Class field is marked by Set feature.
SRP Priority Packets	The number of packets whose SRP Priority field is marked by Set feature.
Precedence	<ul style="list-style-type: none"> <li>Packets—The number of packets whose Precedence field is marked by Set feature.</li> <li>Tunnel Packets—The number of packets whose Precedence Tunnel field is marked by Set feature.</li> </ul>
Frame Relay	<ul style="list-style-type: none"> <li>DE Packets—The number of packets whose Frame Relay DE Bit is marked by Set feature.</li> <li>FECN—The number of packets whose Frame Relay FECN BECN field is marked by Set feature.</li> </ul>
MPLS Experimental	<ul style="list-style-type: none"> <li>Imposition Packets—The number of packets whose MPLS Experimental Imposition field is marked by Set feature.</li> <li>Topmost Packets—The number of packets whose MPLS Experimental Top Most field is marked by Set feature.</li> </ul>
DSCP	<ul style="list-style-type: none"> <li>Packets—The number of packets whose DSCP field is marked by Set feature.</li> <li>Tunnel Packets—The number of packets whose Precedence Tunnel field is marked by Set feature.</li> </ul>

## QOS Policing Daily Reports

MWTM displays the QOS Policing Daily report obtained during the specified period.



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > QOS**.

**Note**

The 15-minute and hourly QOS Policing Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the QOS Policing Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose QOS Policing Daily from Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Class Map	User-defined traffic class that contains one or many match statements used to classify packets into different categories.
Service Policy Direction	The direction of traffic for which the service policy is applied.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Conformed	<ul style="list-style-type: none"> <li>Packets—The number of packets treated as conforming by the policing feature.</li> <li>Bits—The number of octets treated as conforming by the policing feature.</li> <li>Bits Rate—The rate of conforming traffic.</li> </ul>
Exceeded	<ul style="list-style-type: none"> <li>Packets—The number of packets treated as non-conforming by the policing feature.</li> <li>Bits—The number of octets treated as non-conforming by the policing feature.</li> <li>Bits Rate—The rate of non-conforming traffic.</li> </ul>
Violated	<ul style="list-style-type: none"> <li>Packets—The number of packets treated as violated by the policing feature.</li> <li>Bits—The number of octets treated as violated by the policing feature.</li> <li>Bits Rate—The rate of the violating traffic.</li> </ul>

## QOS Queuing Daily Reports

MWTM displays the QOS Queuing Daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > QOS**.



**Note**

The 15-minute and hourly QOS Queuing Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the QOS Queuing Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose QOS Queuing Daily from Type drop-down menu.

A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Class Map	User-defined traffic class that contains one or many match statements used to classify packets into different categories.
Service Policy Direction	The direction of traffic for which the service policy is applied.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Queue Depth	The current depth of the queue.
Max Queue Depth	The maximum depth of the queue.
Queue Discarded	<ul style="list-style-type: none"> <li>Bits—The number of octets, associated with this class, that were dropped by queueing.</li> <li>Packets—The number of packets, associated with this class, that were dropped by queueing.</li> </ul>

## QOS Traffic Shaping Daily Reports

MWTM displays the QOS Traffic Shaping Daily report obtained during the specified period.

**Note**

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > QOS**.

**Note**

The 15-minute and hourly QOS Traffic Shaping Statistics reports are available from the node level only; they are not available from the top level or the network level. Click on a node name in the QOS Traffic Shaping Statistics reports to navigate to a specific node to view hourly and 15 minute reports for that node.

**Step 2** Choose QOS Traffic Shaping Daily from Type drop-down menu.


A summary table displays the information described in the following table:

Field	Description
Node	Name of the node.
Class Map	User-defined traffic class that contains one or many match statements used to classify packets into different categories.
Service Policy Direction	The direction of traffic for which the service policy is applied.
Timestamp ( <i>time zone</i> )	Timestamp shows the time bits-per second value occurred.
Active	The current traffic-shaping state. When traffic-shaping is enabled and the traffic rate exceeds the shape rate, traffic-shaping is considered to be active. Otherwise, it is considered inactive.
Queue Size	The current traffic-shaping queue depth in packets.
Delayed	<ul style="list-style-type: none"> <li>Bits—The number of octets that have been delayed.</li> <li>Packets—The number of packets that have been delayed.</li> </ul>
Dropped	<ul style="list-style-type: none"> <li>Bits—The number of octets that have been dropped during shaping.</li> <li>Packets—The number of packets that have been dropped during shaping.</li> </ul>

## RAN-Optimized Reports


The MWTM web interface provides network-wide reports that summarize IP-RAN over a specified time period. The information is available in graphical, tabular, and CSV formats. Administrators use these reports for analysis of network-wide performance and errors for RAN backhauls and shorthauls. For example, you can generate a report to show which backhaul links were the most heavily utilized in the last 24 hours.

To generate a network-wide RAN report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > RAN Statistics > RAN-Optimized**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu (see [Table 13-1](#) for a list of report types and their contents).
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu (see [Table 13-1](#) for contents of each output type).
- Step 5** Choose a sort parameter from the Sort Parameter drop-down menu.



**Note** The Graph output displays up to twelve RAN data streams based on traffic and/or number of errors. To view all RAN data streams, choose Table or CSV.

- Step 6** To generate the report, click the Run icon (green arrow ).
- Step 7** To understand the report, click the report type listed in [Table 13-1](#) for a detailed description of the report fields.

Report Type	Output	Contents
<a href="#">Backhaul Performance Daily Report</a>	Graph	Minimum, maximum, and average performance data for all the RAN backhauls in the network: <ul style="list-style-type: none"> <li>• Send Summary—Table summary of backhaul send data.</li> <li>• Receive Summary—Table summary of backhaul receive data.</li> <li>• Send Backhaul Performance Daily—Graph of backhaul send data.</li> <li>• Receive Backhaul Performance Daily—Graph of backhaul receive data.</li> </ul>
	Table or CSV	Send and receive data, node, and backhaul in tabular format.
<a href="#">Backhaul Errors Daily Report</a>	Graph	For all the RAN backhauls in the network: <ul style="list-style-type: none"> <li>• Table—Average error rate, total errors, and total GSM-Abis and UMTS-Iub errors in tabular format.</li> <li>• Backhaul Errors Daily—Graph that shows total errors, GSM errors, and UMTS errors.</li> </ul>
	Table or CSV	Tabular information that shows total errors, total GSM-Abis errors, total UMTS-Iub errors, node, and backhaul.
<a href="#">Shorthaul Performance Daily Report</a>	Graph	Minimum, maximum, and average performance data for all the RAN shorthauls in the network: <p>Send Summary—Table summary of shorthaul send data.</p> <p>Receive Summary —Table summary of shorthaul receive data.</p> <p>Send Shorthaul Performance Daily—Graph of shorthaul send data.</p> <p>Receive Shorthaul Performance Daily—Graph of shorthaul receive data.</p>
	Table or CSV	Tabular information that shows send and receive data, protocol type, node, and shorthaul.
<a href="#">GSM Errors Daily Reports</a>	Graph	Table—Tabular data that shows total GSM error counts and average error rate over the chosen time period. <p>GSM Errors Daily—Graph of GSM errors over the chosen time period.</p>
	Table or CSV	Tabular information that shows total errors, total missed packets, total protocol errors, total miscellaneous errors, node, backhaul, and shorthaul.

Report Type	Output	Contents
<a href="#">UMTS Errors Daily Reports</a>	Graph	Table—Tabular data that shows total UMTS error counts and average error rate over the chosen time period.  UMTS Errors Daily—Graph of UMTS errors over the chosen time period.
	Table or CSV	Tabular information that shows total errors, total protocol errors, total miscellaneous errors, node, backhaul, and shorthaul.

## Backhaul Performance Daily Report

Output	GUI Element	Description
Graph	Node	Table column that lists nodes that contain RAN backhauls. To access details for a specific node, click a node in this column.
	Backhaul	Table column that lists the visible backhauls. To access details for a specific backhaul, click a backhaul in this column.  <b>Note</b> The column shows a maximum of 12 backhauls by default. To change the number of visible backhauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	Average Utilization %	Table column that shows the average of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.
	Average	Table column that shows average bits per second for the backhaul.
	Minimum Utilization %	Table column that shows the minimum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.
	Minimum	Table column that shows minimum number of bits per second for the backhaul.
	Minimum Date ( <i>time zone</i> )	Table column that shows time when the minimum bits-per-second value occurred.
	Maximum Utilization %	Table column that shows the maximum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.
	Maximum	Table column that shows maximum number of bits per second for the backhaul.
	Maximum Date ( <i>time zone</i> )	Table column that shows time when the maximum bits-per-second value occurred.
	Expand to Full Screen	Click this link to open the graph in a full-screen window for better viewing.
	Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
	Minimum Bits/Sec	Y-axis labels for graphs that show minimum, average, and maximum bits per second for the visible backhauls.  <b>Note</b> The graph shows a maximum of 12 backhauls by default. To change the number of visible backhauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	Average Bits/Sec	
	Maximum Bits/Sec	
	<i>Legend</i>	Appearing below each graph, a legend of color-coded labels for each backhaul that appears in the graph.

Output	GUI Element	Description
Table, CSV	Node	Table column that lists all network nodes that contain backhauls. If Output is Table, to access performance details for a specific node, click a node in this column.
	Backhaul	Table column that lists all the backhauls in the network. If Output is Table, to access performance details for a specific backhaul, click a backhaul in this column.
	Errors	Table column that shows total error counts for each backhaul.
	Send Bits/Sec	<ul style="list-style-type: none"> <li>Minimum Date (<i>time zone</i>)—Table column that shows time when the minimum bits-per-second value occurred.</li> <li>Minimum Utilization %—Table column that shows the minimum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Minimum—Table column that shows minimum number of bits per second for the backhaul.</li> <li>Average Date (<i>time zone</i>)—Table column that shows time when the Average bits-per-second value occurred.</li> <li>Average Utilization %—Table column that shows the average of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Average—Table column that shows average of bits per second for the backhaul.</li> <li>Maximum Date (<i>time zone</i>)—Table column that shows time when the maximum bits-per-second value occurred.</li> <li>Maximum Utilization %—Table column that shows the maximum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Maximum—Table column that shows maximum number of bits per second for the backhaul.</li> </ul>

Output	GUI Element	Description
	Receive Bits/Sec	<ul style="list-style-type: none"> <li>Minimum Date (<i>time zone</i>)—Table column that shows time when the minimum bits-per-second value occurred.</li> <li>Minimum Utilization %—Table column that shows the minimum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Minimum—Table column that shows minimum number of bits per second for the backhaul.</li> <li>Average Date (<i>time zone</i>)—Table column that shows time when the Average bits-per-second value occurred.</li> <li>Average Utilization %—Table column that shows the average of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Average—Table column that shows average of bits per second for the backhaul.</li> <li>Maximum Date (<i>time zone</i>)—Table column that shows time when the maximum bits-per-second value occurred.</li> <li>Maximum Utilization %—Table column that shows the maximum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Maximum—Table column that shows maximum number of bits per second for the backhaul.</li> </ul>

## Backhaul Errors Daily Report

Output	GUI Element	Description
Graph	Node	Table column that lists nodes that contain RAN backhauls. To access details for a specific node, click a node in this column.
	Backhaul	Table column that lists the visible backhauls. To access details for a specific backhaul, click a backhaul in this column.  <b>Note</b> The graph shows a maximum of 12 backhauls by default. To change the number of visible backhauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	Avg. Error Rate (Per Sec)	Table column that lists the average error rate each second for the visible backhauls.
	Total Errors	Table column that lists the total number of errors (GSM and UMTS) for each visible backhaul.
	Total Errors GSM-Abis	Table column that lists the total number of GSM-Abis errors for each visible backhaul.
	Total Errors UMTS-Iub	Table column that lists the total number of UMTS-Iub errors for each visible backhaul.
	Expand to Full Screen	Click this link to open the graph in a full-screen window for better viewing.
	Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
	UMTS Errors	Y-axis labels for graphs that show total UMTS errors, total GSM errors, and a combined total of UMTS and GSM errors for the visible backhauls.  <b>Note</b> The graph shows a maximum of 12 backhauls by default. To change the number of visible backhauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	GSM Errors	
	Total Errors	
	<i>Legend</i>	Positioned below the graph, a legend of color-coded labels for each backhaul that appears in the graph.
Table, CSV	Lists the same information as the graph output type, but in tabular format; also includes one unique field:  Timestamp—identifies the time that each error value occurred for each visible backhaul.	



## Shorthaul Performance Daily Report

Output	GUI Element	Description
Graph	Node	Table column that lists nodes that contain RAN shorthauls. To access details for a specific node, click a node in this column.
	Backhaul	Table column that lists the visible backhauls. To access details for a specific backhaul, click a backhaul in this column.
	Shorthaul	Table column that lists the visible shorthauls. To access details for a specific shorthaul, click a shorthaul in this column.  <b>Note</b> The graph shows a maximum of 12 shorthauls by default. To change the number of visible shorthauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	Average	Table column that shows the average bits per second for the shorthaul.
	Minimum	Table column that shows the minimum number of bits per second for the shorthaul.
	Minimum Date ( <i>time zone</i> )	Table column that shows time when the minimum bits-per-second value occurred.
	Maximum	Table column that shows maximum number of bits per second for the shorthaul.
	Maximum Date ( <i>time zone</i> )	Table column that shows time when the maximum bits-per-second value occurred.
	Expand to Full Screen	Click this link to open the graph in a full-screen window for better viewing.
	Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
	Minimum Bits/Sec	Y-axis labels for graphs that show minimum, average, and maximum bits per second for the visible shorthauls.
	Average Bits/Sec	<b>Note</b> The graph shows a maximum of 12 shorthauls by default. To change the number of visible shorthauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	Maximum Bits/Sec	
	Legend	Positioned below each graph, a legend of color-coded labels for each shorthaul that appears in the graph.

Output	GUI Element	Description
Table, CSV	Node	Table column that lists all the nodes that contain RAN backhauls. If Output is Table, to access details for a specific node, click a node in this column.
	Backhaul	Table column that lists all the RAN backhauls in the network. If Output is Table, to access details for a specific backhaul, click a backhaul in this column.
	Shorthaul	Table column that lists all the RAN shorthauls in the network. If Output is Table, to access details for a specific shorthaul, click a shorthaul in this column.
	Protocol	Table column that shows whether the shorthaul protocol is GSM or UMTS.
	Send Bits/Sec	<ul style="list-style-type: none"> <li>Minimum Date (<i>time zone</i>)—Table column that shows time when the minimum bits-per-second value occurred.</li> <li>Minimum Utilization %—Table column that shows the minimum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Minimum—Table column that shows minimum number of bits per second for the backhaul.</li> <li>Average Date (<i>time zone</i>)—Table column that shows time when the Average bits-per-second value occurred.</li> <li>Average Utilization %—Table column that shows the average of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Average—Table column that shows average of bits per second for the backhaul.</li> <li>Maximum Date (<i>time zone</i>)—Table column that shows time when the maximum bits-per-second value occurred.</li> <li>Maximum Utilization %—Table column that shows the maximum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>Maximum—Table column that shows maximum number of bits per second for the backhaul.</li> </ul>

Output	GUI Element	Description
	Receive Bits	<ul style="list-style-type: none"> <li>• Minimum Date (<i>time zone</i>)—Table column that shows time when the minimum bits-per-second value occurred.</li> <li>• Minimum Utilization %—Table column that shows the minimum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>• Minimum—Table column that shows minimum number of bits per second for the backhaul.</li> <li>• Average Date (<i>time zone</i>)—Table column that shows time when the Average bits-per-second value occurred.</li> <li>• Average Utilization %—Table column that shows the average of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>• Average—Table column that shows average of bits per second for the backhaul.</li> <li>• Maximum Date (<i>time zone</i>)—Table column that shows time when the maximum bits-per-second value occurred.</li> <li>• Maximum Utilization %—Table column that shows the maximum of the backhaul. A value greater than 100% indicates that the backhaul is oversubscribed.</li> <li>• Maximum—Table column that shows maximum number of bits per second for the backhaul.</li> </ul>

## GSM Errors Daily Reports

Output	GUI Element	Description
Graph	Node	Table column that lists nodes that contain GSM shorthauls. To access details for a specific node, click a node in this column.
	Backhaul	Table column that lists backhauls that contain GSM shorthauls. To access details for a specific backhaul, click a backhaul in this column.
	Shorthaul	Table column that lists the visible GSM shorthauls. To access details for a specific shorthaul, click a shorthaul in this column.  <b>Note</b> The table shows a maximum of 12 shorthauls by default. To change the number of visible shorthauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	Total Counts	Table column that lists the total number of GSM errors for the visible shorthauls during the chosen duration.
	Avg. Error Rate (Per Sec)	Table column that lists the average error rate each second for the visible shorthauls.
	Expand to Full Screen	Click this link to open the graph in a full-screen window for better viewing.
	Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
	Error Counts	Y-axis label for graph that shows total GSM errors for the visible GSM shorthauls.  <b>Note</b> The graph shows a maximum of 12 shorthauls by default. To change the number of visible shorthauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	<i>Legend</i>	Positioned below the graph, a legend of color-coded labels for each shorthaul that appears in the graph.

Output	GUI Element	Description
Table, CSV	Node	Table column that lists all the nodes that contain GSM shorthauls. If Output is Table, to access details for a specific node, click a node in this column.
	Backhaul	Table column that lists all the backhauls that contain GSM shorthauls. If Output is Table, to access details for a specific backhaul, click a backhaul in this column.
	Shorthaul	Table column that lists all the GSM shorthauls in the network. If Output is Table, to access details for a specific shorthaul, click a shorthaul in this column.
	Timestamp ( <i>time zone</i> )	Timestamp of the report.
	Total Errors	Table column that lists the total number of GSM errors for the visible shorthauls during the chosen duration.
	Total Missed Packets	Total number of missed packets on the GSM shorthaul.
	Total Protocol Errors	Total number of protocol errors on the GSM shorthaul.
	Total Miscellaneous Errors	Total number of miscellaneous errors on the GSM shorthaul.

## UMTS Errors Daily Reports

Output	GUI Element	Description
Graph	Node	Table column that lists nodes that contain UMTS shorthauls. To access details for a specific node, click a node in this column.
	Backhaul	Table column that lists backhauls that contain UMTS shorthauls. To access details for a specific backhaul, click a backhaul in this column.
	Shorthaul	Table column that lists the visible UMTS shorthauls. To access details for a specific shorthaul, click a shorthaul in this column.  <b>Note</b> The table shows only 12 shorthauls by default. To change the number of visible shorthauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	Total Counts	Table column that lists the total number of UMTS errors that occurred for the visible shorthauls during the chosen duration.
	Avg. Error Rate (Per Sec)	Table column that lists the average error rate each second for the visible shorthauls during the chosen duration.
	Expand to Full Screen	Click this link to open the graph in a full-screen window for better viewing.
	Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
	Error Counts	Y-axis label for the graph that shows the total number of UMTS errors for the visible UMTS shorthauls.  <b>Note</b> The graph shows only 12 shorthauls by default. To change the number of visible shorthauls, use the Graph Series Editor. See <a href="#">Using the Toolbar, page 11-6</a> , for more information.
	<i>Legend</i>	Positioned below the graph, a legend of color-coded labels for each UMTS shorthaul that appears in the graph.

Output	GUI Element	Description
Table, CSV	Node	Table column that lists nodes that contain UMTS shorthauls. If Output is Table, to access details for a specific node, click a node in this column.
	Backhaul	Table column that lists all the backhauls that contain UMTS shorthauls. If Output is Table, to access details for a specific backhaul, click a backhaul in this column.
	Shorthaul	Table column that lists all the UMTS shorthauls in the network. If Output is Table, to access details for a specific shorthaul, click a shorthaul in this column.
	Timestamp (time zone)	Time that the error values occurred for the visible shorthauls.
	Total Errors	Table column that lists the total number of UMTS errors for the visible shorthauls during the chosen duration.
	Total Protocol Errors	Table column that lists the total number of protocol errors on the UMTS shorthaul.
	Total Miscellaneous Errors	Table column that lists the total number of miscellaneous errors on the UMTS shorthaul.

## Generating Node-Level CPU/Memory Reports

In addition to generating network-wide CPU/Memory reports as explained in [CPU Reports, page 13-13](#), you can also generate node-level CPU/Memory reports as explained in the following steps.

- 
- Step 1** From the MWTM web interface, click on a node name.
- Step 2** Click the Performance tab.
- Step 3** From the View pulldown menu, select **Historical CPU Utilization** or **Historical Memory Utilization**.  
If the device you selected has multiple CPUs, in addition to the Summary tab, there are also separate Slot tabs. Each Slot tab contains CPU statistics for the CPUs in that slot.
- Step 4** From the Type menu, select which CPU or Memory report to view:
- CPU Peak Utilization 15 Minutes
  - CPU Average Utilization 15 Minutes
  - CPU Peak Utilization Hourly
  - CPU Average Utilization Hourly
  - CPU Peak Utilization Daily
  - CPU Average Utilization Daily
  - Memory Peak Utilization 15 Minutes
  - Memory Average Utilization 15 Minutes
  - Memory Peak Utilization Hourly

- Memory Average Utilization Hourly
- Memory Peak Utilization Daily
- Memory Average Utilization Daily

## Viewing ITP Accounting Reports

You can view any of the following statistics reports:

- [AS Accounting Reports, page 13-304](#)
- [GTT Accounting Reports, page 13-305](#)
- [MTP3 Accounting Reports, page 13-306](#)



### Note

All accounting reports are supported on ITP platforms only.

## AS Accounting Reports

You can view daily reports for application server (AS) accounting statistics by using the MWTM. You can also export the report. AS accounting describes MTP3 layer traffic in support of application servers.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the linkset.
Network Name	Name of the network for the linkset.
Signaling Point	Name of the signaling point for the linkset.
AS	Name of the application server.
OPC	Originating point code of the traffic, which is a unique identifier for each set of statistics.  To see only statistics that match a specific OPC for a given linkset, find the linkset and click the point code.
DPC	Destination point code of the traffic.  To see only statistics that match a specific DPC for a given linkset, find the linkset and click the point code.



Field or Column	Description
SI	<p>Service indicator, which indicates the type of Signaling System 7 (SS7) traffic. Valid values include:</p> <ul style="list-style-type: none"> <li>• <b>0</b>—Signaling Network Management Message (SNM)</li> <li>• <b>1</b>—Maintenance Regular Message (MTN)</li> <li>• <b>2</b>—Maintenance Special Message (MTNS)</li> <li>• <b>3</b>—Signaling Connection Control Part (SCCP)</li> <li>• <b>4</b>—Telephone User Part (TUP)</li> <li>• <b>5</b>—ISDN User Part (ISUP)</li> <li>• <b>6</b>—Data User Part (call and circuit-related messages)</li> <li>• <b>7</b>—Data User Part (facility registration/cancellation messages)</li> </ul> <p>To see only more information for a specific type of SI, click the SI type.</p>
Send MSUs	Total number of MTP3 MSUs sent on the specified date.
Receive MSUs	Total number of MTP3 MSUs received on the specified date.
Send Bytes	Total number of bytes sent on the specified date.
Receive Bytes	Total number of bytes received on the specified date.

## GTT Accounting Reports

You can view summary reports of daily GTT accounting statistics. You can also export the reports.

### GTT Accounting Daily Reports

You can view a daily summary of GTT accounting reports for all nodes that the MWTM detected on a specified date. The GTT Accounting Daily Report page shows all MWTM daily GTT accounting reports by date. Each file contains a daily summary of GTT accounting statistics for all nodes that the MWTM detected on a specified date.

The GTT Accounting Daily Report table is sorted based on the information in the Packets column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns](#), page 4-24).



#### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node associated with the <b>From Network Name</b> for which data is visible.
From Network Name	Name of the network from which GTT traffic originated, and for which data is visible.
Signaling Point	Name of the signaling point associated with the <b>From Network Name</b> instance for which data is visible.

Field or Column	Description
Linkset	Name of the linkset associated with the <b>From Network Name</b> instance for which data is visible.
Selector	Name of the selector.
GTA	Global Title Address (GTA) associated with the selector.
To Network Name	Name of the network in which the translated point code resides.
Point Code	Destination point code for the GTA.
Packets	Total number of packets requiring translation by GTT on the specified date.
Octets	Total number of octets requiring translation by GTT on the specified date.

## MTP3 Accounting Reports

MTP3 accounting describes MTP3 layer traffic in support of linksets. You can also export the MTP3 accounting reports.



### Note

Every five minutes (by default), the ITP moves data records from a quick-access table to a database that stores long term accounting records. This database contains accumulated accounting data since the last clearing or from the time accounting was originally enabled. The MWTM shows only the data from this database, not from the quick-access table.

## MTP3 Accounting Daily Reports

You can view a daily summary of MTP3 accounting statistics for the MWTM on a specified date. The MTP3 Accounting Daily Report page shows detail reports of all MWTM daily MTP3 accounting statistics by date. Each file contains a daily summary of MTP3 accounting statistics for the MWTM on a specified date.

The MTP3 Accounting Daily Report table is sorted based on the information in the Send MSUs column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns](#), page 4-24).



### Note

If a statistics calculation results in an undefined value, such as a number divided by zero (0), or an undefined number, based on the configuration, then `MathError` appears in the field.

Field or Column	Description
Date	Date of the report.
Node	Name of the node for the linkset.
Network Name	Name of the network for the linkset.
Signaling Point	Name of the signaling point for the linkset.
Linkset	Name of the linkset.

Field or Column	Description
Gateway Screening	Indicates whether the traffic passed or failed the Gateway Screening test at the ITP.  To see only statistics that passed or failed for a specific linkset, select a linkset and click <b>Pass</b> , <b>Fail</b> , or <b>Unroutable</b> .
OPC	Originating point code of the traffic, which is a unique identifier for each set of statistics.  To see only statistics that match a specific OPC for a given linkset, find the linkset and click the point code.
DPC	Destination point code of the traffic.  To see only statistics that match a specific DPC for a given linkset, find the linkset and click the point code.
SI	Service indicator, which indicates the type of SS7 traffic. Valid values include: <ul style="list-style-type: none"> <li>• <b>0</b>—Signaling Network Management Message (SNM)</li> <li>• <b>1</b>—Maintenance Regular Message (MTN)</li> <li>• <b>2</b>—Maintenance Special Message (MTNS)</li> <li>• <b>3</b>—Signaling Connection Control Part (SCCP)</li> <li>• <b>4</b>—Telephone User Part (TUP)</li> <li>• <b>5</b>—ISDN User Part (ISUP)</li> <li>• <b>6</b>—Data User Part (call and circuit-related messages)</li> <li>• <b>7</b>—Data User Part (facility registration/cancellation messages)</li> </ul> To see only more information for a specific type of SI, click the SI type.
Send MSUs	Total number of MTP3 MSUs sent on the specified date.
Receive MSUs	Total number of MTP3 MSUs received on the specified date.
Send Bytes	Total number of bytes sent on the specified date.
Receive Bytes	Total number of bytes received on the specified date.

## Viewing Mobile Subscribers Reports

You can view any of the following subscriber count reports:

- [BWG Subscribers Reports, page 13-308](#)
- [CSG Subscribers Reports, page 13-309](#)
- [GGSN Subscribers Reports, page 13-315](#)
- [HA Subscribers Reports, page 13-317](#)
- [PDNGW Subscribers Reports, page 13-318](#)
- [PDSN Subscribers Reports, page 13-324](#)
- [SGW Subscribers Reports, page 13-326](#)
- [SPGW Subscribers Reports, page 13-332](#)

## Node Instance Counts in BWG and GGSN Subscriber Reports

When viewing BWG and GGSN subscriber reports, you might notice a discrepancy in the Node Instance column between the most recent record and older records. This occurs when the most recent record is not complete due to the differences in polling intervals of BWG and GGSN devices. Up to 6 BWG and GGSN IOS instances can run on a single SAMI card. MWTM sees each instance as a separate device and is not aware at the management level that different devices might run on the same physical card. As a result, the devices are polled and data is collected at different times during the regular polling interval.

For example, *GGSN A* on *SAMI 1* is polled at 12:01 p.m. and *GGSN B* on *SAMI 1* is polled at 12:14 p.m. during a regular 15-minute polling interval. When you view the latest report data for reports that aggregate data at the SAMI card level, such as subscriber reports, there are discrepancies. The subscriber report is a card-level report that aggregates the results of each device instance that runs on a SAMI card by adding the subscriber count of all devices with the same serial number. Using the times given in the above example, if you view the GGSN subscriber report for the last 6 hours at 12:10 p.m., you see the results from *GGSN A* only, and only *GGSN A* contributes to those results. If you view the same report at 12:15 p.m., you will see the sum of *GGSN A* and *GGSN B* subscriber counts, and both devices contribute to the results.

## BWG Subscribers Reports

You can view any of the following BWG Subscriber Count Reports

- [BWG Subscribers 15 Minute Reports, page 13-308](#)
- [BWG Subscribers Hourly Reports, page 13-308](#)
- [BWG Subscribers Daily Reports, page 13-309](#)
- [BWG Subscribers Monthly Reports, page 13-309](#)

### Related Topic

- [Node Instance Counts in BWG and GGSN Subscriber Reports, page 13-308](#)

## BWG Subscribers 15 Minute Reports

The BWG Subscribers 15 Minute Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers per node.
Node Instances	Number of node instances per SAMI.

## BWG Subscribers Hourly Reports

The BWG Subscribers Hourly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers per node.
Node Instances	Number of node instances per SAMI.

### BWG Subscribers Daily Reports

The BWG Subscribers Daily Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers per node.
Node Instances	Number of node instances per SAMI.


### BWG Subscribers Monthly Reports


The BWG Subscribers Monthly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers per node.
Node Instances	Number of node instances per SAMI.

### CSG Subscribers Reports

The MWTM web interface provides network level CSG Subscribers reports. To generate a network-wide CSG Subscribers report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > CSG**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.

- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** To generate the report, click the Run icon (green arrow ).
- The Type drop-down menu contains the following reports:
- [CSG Subscribers 15 Minute Reports, page 13-310](#)
  - [CSG Subscribers Hourly Reports, page 13-311](#)
  - [CSG Subscribers Daily Reports, page 13-312](#)
  - [CSG Subscribers Monthly Reports, page 13-313](#)

### CSG Subscribers 15 Minute Reports

MWTM displays the CSG Subscribers 15 Minute report obtained during the specified period.

The CSG Subscribers 15 Minute Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > CSG**.
- Step 2** Choose CSG Subscribers 15 Minute from the Type drop-down menu.
- A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
CSG Subscribers 15 Minute	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

### CSG Subscribers Hourly Reports

MWTM displays the CSG Subscribers Hourly report obtained during the specified period.

The CSG Subscribers Hourly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > CSG**.
- Step 2** Choose CSG Subscribers Hourly from the Type drop-down menu.
- A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
CSG Subscribers Hourly	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## CSG Subscribers Daily Reports

MWTM displays the CSG Subscribers Daily report obtained during the specified period.

The CSG Subscribers Daily Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > CSG**.

- Step 2** Choose CSG Subscribers Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.



Field or Column	Description
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
CSG Subscribers Daily	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## CSG Subscribers Monthly Reports

MWTM displays the CSG Subscribers Monthly report obtained during the specified period.

The CSG Subscribers Monthly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > CSG**.

**Step 2** Choose CSG Subscribers Monthly from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
CSG Subscribers Monthly	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## GGSN Subscribers Reports

You can view any of the following GGSN Subscribers Reports:

- [GGSN Subscribers 15 Minute Reports, page 13-315](#)
- [GGSN Subscribers Hourly Reports, page 13-316](#)
- [GGSN Subscribers Daily Reports, page 13-316](#)
- [GGSN Subscribers Monthly Reports, page 13-316](#)

### Related Topic

- [Node Instance Counts in BWG and GGSN Subscriber Reports, page 13-308](#)

## GGSN Subscribers 15 Minute Reports

The GGSN Subscribers 15 Minute Report tables are sorted based on the information in the **Subscriber Count** column. However, you can sort each table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.
Node Instances	Number of node instances per SAMI.

### GGSN Subscribers Hourly Reports

The GGSN Subscribers Hourly Report tables are sorted based on the information in the **Subscriber Count** column. However, you can sort each table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.
Node Instances	Number of node instances per SAMI.

### GGSN Subscribers Daily Reports

The GGSN Subscribers Daily Report tables are sorted based on the information in the **Subscriber Count** column. However, you can sort the tables based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.
Node Instances	Number of node instances per SAMI.

### GGSN Subscribers Monthly Reports

The GGSN Subscribers Monthly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.
Node Instances	Number of node instances per SAMI.

## HA Subscribers Reports

You can view any of the following HA Subscribers Reports:

- [HA Subscribers 15 Minute Reports, page 13-317](#)
- [HA Subscribers Hourly Reports, page 13-317](#)
- [HA Subscribers Daily Reports, page 13-317](#)
- [HA Subscribers Monthly Reports, page 13-318](#)

### HA Subscribers 15 Minute Reports

The HA Subscribers 15 Minute Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Node	Name of the node.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.

### HA Subscribers Hourly Reports

The HA Subscribers Hourly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Node	Name of the node.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.

### HA Subscribers Daily Reports

The HA Subscribers Daily Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Node	Name of the node.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.



## HA Subscribers Monthly Reports

The HA Subscribers Monthly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Node	Name of the node.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.

## PDNGW Subscribers Reports

The MWTM web interface provides network level PDNGW Subscribers reports. To generate a network-wide PDNGW Subscribers report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > PDNGW**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [PDNGW Subscribers 15 Minute Reports, page 13-318](#)
- [PDNGW Subscribers Hourly Reports, page 13-320](#)
- [PDNGW Subscribers Daily Reports, page 13-322](#)
- [PDNGW Subscribers Monthly Reports, page 13-323](#)

## PDNGW Subscribers 15 Minute Reports

MWTM displays the PDNGW Subscribers 15 Minute report obtained during the specified period.

The PDNGW Subscribers 15 Minute Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > PDNGW**.
- Step 2** Choose PDNGW Subscribers 15 Minute from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PDNGW Subscribers 15 Minute	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## PDNGW Subscribers Hourly Reports

MWTM displays the PDNGW Subscribers Hourly report obtained during the specified period.

The PDNGW Subscribers Hourly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > PDNGW**.

- Step 2** Choose PDNGW Subscribers Hourly from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.



Field or Column	Description
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PDNGW Subscribers Hourly	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## PDNGW Subscribers Daily Reports

MWTM displays the PDNGW Subscribers Daily report obtained during the specified period.

The PDNGW Subscribers Daily Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > PDNGW**.

- Step 2** Choose PDNGW Subscribers Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.

Field or Column	Description
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PDNGW Subscribers Daily	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## PDNGW Subscribers Monthly Reports

MWTM displays the PDNGW Subscribers Monthly report obtained during the specified period.

The PDNGW Subscribers Monthly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

**Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > PDNGW**.

**Step 2** Choose PDNGW Subscribers Monthly from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
PDNGW Subscribers Monthly	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## PDSN Subscribers Reports

You can view any of the following PDSN Subscribers Reports:

- [PDSN Subscribers 15 Minute Reports, page 13-325](#)
- [PDSN Subscribers Hourly Reports, page 13-325](#)
- [PDSN Subscribers Daily Reports, page 13-325](#)
- [PDSN Subscribers Monthly Reports, page 13-325](#)

### PDSN Subscribers 15 Minute Reports

The PDSN Subscribers 15 Minute Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Node	Name of the node.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.

### PDSN Subscribers Hourly Reports

The PDSN Subscribers Hourly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Node	Name of the node.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.

### PDSN Subscribers Daily Reports

The PDSN Subscribers Daily Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Node	Name of the node.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.



### PDSN Subscribers Monthly Reports

The PDSN Subscribers Monthly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

Field or Column	Description
Timestamp ( <i>time zone</i> )	Timestamp of the report.
Node	Name of the node.
Serial Number	Serial number of the chassis.
Subscriber Count	Number of subscribers.

## SGW Subscribers Reports

The MWTM web interface provides network level SGW Subscribers reports. To generate a network-wide SGW Subscribers report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SGW**.
- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [SGW Subscribers 15 Minute Reports, page 13-326](#)
- [SGW Subscribers Hourly Reports, page 13-328](#)
- [SGW Subscribers Daily Reports, page 13-330](#)
- [SGW Subscribers Monthly Reports, page 13-331](#)

### SGW Subscribers 15 Minute Reports

MWTM displays the SGW Subscribers 15 Minute report obtained during the specified period.

The SGW Subscribers 15 Minute Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SGW**.
- Step 2** Choose SGW Subscribers 15 Minute from the Type drop-down menu.  
A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
SGW Subscribers 15 Minute	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## SGW Subscribers Hourly Reports

MWTM displays the SGW Subscribers Hourly report obtained during the specified period.

The SGW Subscribers Hourly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SGW**.

- Step 2** Choose SGW Subscribers Hourly from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.



Field or Column	Description
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
SGW Subscribers Hourly	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## SGW Subscribers Daily Reports

MWTM displays the SGW Subscribers Daily report obtained during the specified period.

The SGW Subscribers Daily Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SGW**.

- Step 2** Choose SGW Subscribers Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.

Field or Column	Description
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
SGW Subscribers Daily	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## SGW Subscribers Monthly Reports

MWTM displays the SGW Subscribers Monthly report obtained during the specified period.

The SGW Subscribers Monthly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SGW**.
- Step 2** Choose SGW Subscribers Monthly from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.



- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
SGW Subscribers Monthly	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## SPGW Subscribers Reports

The MWTM web interface provides network level SPGW Subscribers reports. To generate a network-wide SPGW Subscribers report:

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SPGW**.

- Step 2** In the tool bar of the right pane, choose a report type from the Type drop-down menu for a list of report types and their contents.
- Step 3** Choose a time range from the Duration drop-down menu or customize your own time range by clicking the Customize the date and time range icon . Note that these dates are the dates with server time zone.
- Step 4** Choose an output format (Graph, Table, or CSV) from the Output drop-down menu for contents of each output type.
- Step 5** To generate the report, click the Run icon (green arrow .

The Type drop-down menu contains the following reports:

- [SPGW Subscribers 15 Minute Reports, page 13-333](#)
- [SPGW Subscribers Hourly Reports, page 13-334](#)
- [SPGW Subscribers Daily Reports, page 13-336](#)
- [SPGW Subscribers Monthly Reports, page 13-337](#)

### SPGW Subscribers 15 Minute Reports

MWTM displays the SPGW Subscribers 15 Minute report obtained during the specified period.

The SPGW Subscribers 15 Minute Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SPGW**.
- Step 2** Choose SPGW Subscribers 15 Minute from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
SPGW Subscribers 15 Minute	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## SPGW Subscribers Hourly Reports

MWTM displays the SPGW Subscribers Hourly report obtained during the specified period.

The SPGW Subscribers Hourly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SPGW**.

- Step 2** Choose SPGW Subscribers Hourly from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.

Field or Column	Description
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

- Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
SPGW Subscribers Hourly	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## SPGW Subscribers Daily Reports

MWTM displays the SPGW Subscribers Daily report obtained during the specified period.

The SPGW Subscribers Daily Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SPGW**.

- Step 2** Choose SPGW Subscribers Daily from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.



Field or Column	Description
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
SPGW Subscribers Daily	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

### SPGW Subscribers Monthly Reports

MWTM displays the SPGW Subscribers Monthly report obtained during the specified period.

The SPGW Subscribers Monthly Report table is sorted based on the information in the **Subscriber Count** column. However, you can sort the table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

- Step 1** In the left pane (navigation tree) of the MWTM web interface, choose **Reports > Mobile Subscribers > SPGW**.
- Step 2** Choose SPGW Subscribers Monthly from the Type drop-down menu.

A summary table displays the information described in the following table:

Field or Column	Description
Node	Name of the node.
Average	Average statistics for the specified duration.
Maximum	Maximum statistics for the specified duration.
Maximum Date ( <i>time zone</i> )	Timestamp that shows time when the maximum value occurred.

**Step 3** Select the duration and output (see [Using the Toolbar, page 11-6](#)), and the following information is displayed:

Report Type	Output	Field	Description
SPGW Subscribers Monthly	Table, CSV	Timestamp ( <i>time zone</i> )	Timestamp of the report.
		Node	Name of the node.
		Serial Number	Serial number of the chassis.
		Subscriber Count	Number of subscribers per node.
	Graph	Expand to Full Screen	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing
		Hide Summary Table	If Output Type is Graph, this text link hides the summary table at the top of the report and only shows the graph.
		Subscriber Count	If Output Type is Graph, the Y-axis label shows Daily statistics over time.
		Server Time	If Output Type is Graph, the X-axis label shows a historical time scale and the server time zone.
		<i>Legend</i>	If Output Type is Graph, this text link displays the graph in a new, full-screen window for easier viewing

## Viewing File Archive Inventory Reports

Inventory Reports that have been archived are located within **File Archive > Inventory** in the MWTM web interface. You can also find archived reports in the `/opt/CSCOs/gm/reports` directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in .csv format.

You can view full descriptions of all fields in export file archive reports by clicking **Administrative** from the MWTM web interface, then clicking **Export Reports README** under System Information.

You can view any of the following Inventory archived reports:

- [Chassis Inventory Archived Reports, page 13-339](#)
- [Element Inventory Archived Reports, page 13-339](#)

## Chassis Inventory Archived Reports

You can access these following Chassis Inventory Archived Reports:

- [Chassis Inventory Daily Archived Reports, page 13-339](#)

### Chassis Inventory Daily Archived Reports

The Daily Chassis Inventory Archived Reports page shows summary reports for all archived MWTM daily chassis inventory statistics reports for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *servername\_version\_ChassisInventory.2010-06-17.csv.zip* file contains the summary report for daily chassis inventory statistics for June 17, 2010.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily chassis inventory statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Element Inventory Archived Reports

You can access these following Element Inventory Archived Reports:

- [Element Inventory Daily Archived Reports, page 13-339](#)

### Element Inventory Daily Archived Reports

The Daily Element Inventory Archived Reports page shows summary reports for all archived MWTM daily element inventory statistics reports for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *servername\_version\_ElementInventory.2010-06-17.xml.zip* file contains the summary report for daily element inventory statistics for June 17, 2010.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily element inventory statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Viewing File Archive Common Statistics Reports

Common Reports that have been archived are located within **File Archive > Common Statistics** in the MWTM web interface. You can also find archived reports in the */opt/CSCOs/gm/reports* directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in .csv format.

You can view full descriptions of all fields in export file archive reports by clicking **Administrative** from the MWTM web interface, then clicking **Export Reports README** under System Information.

You can view any of the following Common archived reports:

- [AAA Archived Reports, page 13-340](#)
- [CPU Archived Reports, page 13-342](#)
- [IP Local Pool Archived Reports, page 13-343](#)
- [Interface Archived Reports, page 13-344](#)
- [Memory Archived Reports, page 13-345](#)

### AAA Archived Reports

You can access these following AAA Archived Reports:

- [AAA Accounting Statistics 15 Minute Archived Reports, page 13-340](#)
- [AAA Accounting Statistics Hourly Archived Reports, page 13-340](#)
- [AAA Accounting Statistics Daily Archived Reports, page 13-341](#)
- [AAA Authentication Statistics 15 Minute Archived Reports, page 13-341](#)
- [AAA Authentication Statistics Hourly Archived Reports, page 13-341](#)
- [AAA Authentication Statistics Daily Archived Reports, page 13-342](#)

#### AAA Accounting Statistics 15 Minute Archived Reports

The 15 minute AAA Accounting Statistics Archived Reports page shows summary reports for all archived MWTM 15 minute AAA accounting statistics reports for the server to which you connect, stored as downloadable .zip files.

The .zip files are archived by type, date, hour, and minute; for example, the *AAAAccounting.2009-06-22-16-00.csv.zip* file contains the summary report of archived 15 minute AAA accounting statistics for June 22, 2009.

Each archived .zip file contains a comma-separated value (CSV) text file with a summary report of 15 minute AAA accounting statistics on that date, hour, and minute. You can download the .zip files and extract them.

To download a .zip file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

#### AAA Accounting Statistics Hourly Archived Reports

The Hourly AAA Accounting Statistics Archived Reports page shows all summary reports for archived MWTM hourly AAA accounting statistics for the server to which you connect, stored as downloadable .zip files.

The *.zip* files are archived by type, date, and hour; for example, the *AAAAccounting2009-06-22-11.csv.zip* file contains the summary report for hourly AAA accounting statistics for the 11th hour on June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly AAA accounting statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### AAA Accounting Statistics Daily Archived Reports

The Daily AAA Accounting Statistics Archived Reports page shows all summary reports for archived MWTM daily AAA accounting statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the daily *AAAAccounting.2009-06-22-16-00.csv.zip* file contains the summary report of archived daily AAA accounting statistics for June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily AAA accounting statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### AAA Authentication Statistics 15 Minute Archived Reports

The 15 minute AAA Authentication Statistics Archived Reports page shows summary reports for all archived MWTM 15 minute AAA authentication statistics reports for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, hour, and minute; for example, the *AAAAuthentication.2009-06-22-16-00.csv.zip* file contains the summary report of archived 15 minute AAA authentication statistics for June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute AAA authentication statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### AAA Authentication Statistics Hourly Archived Reports

The Hourly AAA Authentication Statistics Archived Reports page shows all summary reports for archived MWTM hourly AAA authentication statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *AAAAuthentication.2009-06-22-11.csv.zip* file contains the summary report for hourly AAA authentication statistics for the 11th hour on June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly AAA authentication statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## AAA Authentication Statistics Daily Archived Reports

The Daily AAA Authentication Statistics Archived Reports page shows all summary reports for archived MWTM daily AAA authentication statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the daily *AAAAuthentication.2009-06-22.csv.zip* file contains the summary report of archived daily AAA authentication statistics for June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily AAA authentication statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## CPU Archived Reports

You can access these following CPU Archived Reports:

- [CPU Utilization 15 Minute Archived Reports, page 13-342](#)
- [CPU Utilization Hourly Archived Reports, page 13-342](#)
- [CPU Utilization Daily Archived Reports, page 13-342](#)

### CPU Utilization 15 Minute Archived Reports

The CPU Utilization 15 Minute Archived Reports page shows all summary reports for archived MWTM 15 minute CPU statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, hour, and minute; for example, the *CPUStats.2009-06-22-11-20.csv.zip* file contains the summary report of archived 15 minute CPU statistics for June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute CPU statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### CPU Utilization Hourly Archived Reports

The CPU Utilization Hourly Archived Reports page shows all summary reports for archived MWTM hourly CPU statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *CPUStats.2009-06-22-11.csv.zip* file contains the summary report for hourly CPU statistics for the 11th hour on June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly CPU statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### CPU Utilization Daily Archived Reports

The CPU Utilization Daily Archived Reports page shows summary reports for all archived MWTM daily CPU statistics reports for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *CPUStats.2009-06-22.csv.zip* file contains the summary report for daily CPU statistics for June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily CPU statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## IP Local Pool Archived Reports

You can access the following IP Local Pool Archived Reports. These reports are supported on mSEF platforms only:

- [IP Local Pool Statistics 15 Minute Archived Reports, page 13-343](#)
- [IP Local Pool Statistics Hourly Archived Reports, page 13-343](#)
- [IP Local Pool Statistics Daily Archived Reports, page 13-343](#)

### IP Local Pool Statistics 15 Minute Archived Reports

The IP Local Pool 15 Minute Archived Reports page shows summary reports of 15-minute statistical details of the IP Local Pool. The 15 Minute IP Local Pool Statistics Archived Report has the file name *IpLocalPoolStats.year-month-day-hour-minute.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15-minute IP local pool statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### IP Local Pool Statistics Hourly Archived Reports

The IP Local Pool Hourly Archived Reports page shows summary reports of hourly statistical details of the IP Local Pool. The Hourly IP Local Pool Statistics Archived Report has the filename *IpLocalPoolStats.year-month-day-hour.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly IP local pool statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### IP Local Pool Statistics Daily Archived Reports

The IP Local Pool Daily Archived Reports page shows summary reports of daily statistical details of the IP Local Pool. The Daily IP Local Pool Statistics Archived Report has the filename *IpLocalPoolStats.year-month-day.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily IP local pool statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## Interface Archived Reports

You can access the following Interface Archived Reports. These reports are supported on mSEF platforms only:

- [Interface Statistics 15 Minute Archived Reports, page 13-344](#)
- [Interface Statistics Hourly Archived Reports, page 13-344](#)
- [Interface Statistics Daily Archived Reports, page 13-344](#)
- [Extended Interface Statistics 15 Minute, page 13-345](#)
- [Extended Interface Statistics Hourly, page 13-345](#)
- [Extended Interface Statistics Daily, page 13-345](#)

### Interface Statistics 15 Minute Archived Reports

The Interface Statistics 15 Minute Archived Reports page shows all summary reports for archived MWTM 15 minute interface statistics for the server to which you connect, stored as downloadable .zip files.

The .zip files are archived by type, date, hour, and minute; for example, the *InterfaceStats.2009-06-22-16-00.csv.zip* file contains the summary report of archived 15 minute interface statistics for June 22, 2009.

Each archived .zip file contains a comma-separated value (CSV) text file with a summary report of 15 minutes Interface statistics on that date, hour, and minute. You can download the .zip files and extract them.

To download a .zip file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### Interface Statistics Hourly Archived Reports

The Interface Statistics Hourly Archived Reports page shows all summary reports for archived MWTM hourly interface statistics for the server to which you connect, stored as downloadable .zip files.

The .zip files are archived by type, date, and hour; for example, the *InterfaceStats.2009-06-22-11.csv.zip* file contains the summary report for hourly interface statistics for the 11th hour on June 22, 2009.

Each archived .zip file contains a comma-separated value (CSV) text file with a summary report of hourly Interface statistics on that date and hour. You can download the .zip files and extract them.

To download a .zip file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### Interface Statistics Daily Archived Reports

The Interface Statistics Daily Archived Reports page shows summary reports for all archived MWTM daily interface statistics reports for the server to which you connect, stored as downloadable .zip files.

The .zip files are archived by type and date; for example, the *InterfaceStats.2009-06-22.csv.zip* file contains the summary report for daily interface statistics for June 22, 2009.

Each archived .zip file contains a comma-separated value (CSV) text file with a summary report of daily Interface statistics on that date. You can download the .zip files and extract them.

To download a .zip file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.



### Extended Interface Statistics 15 Minute

The Extended Interface Statistics 15 Minute Reports page shows summary reports for all archived MWTM 15 minute extended interface statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, hour, and minute; for example, the *InterfaceExtStats.2011-01-05-15-00.csv.zip* file contains the summary report of archived 15 minute extended interface statistics for January 05, 2011.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minutes extended interface statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### Extended Interface Statistics Hourly

The Extended Interface Statistics Hourly Reports page shows summary reports for all archived MWTM hourly extended interface statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *InterfaceExtStats.2011-01-05-11.csv.zip* file contains the summary report for hourly extended interface statistics for the 11th hour on January 05, 2011.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly extended interface statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### Extended Interface Statistics Daily

The Extended Interface Statistics Daily Reports page shows summary reports for all archived MWTM dailyextended interface statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *InterfaceExtStats.2011-01-05.csv.zip* file contains the summary report for daily extended interface statistics for January 05, 2011.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily extended interface statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## Memory Archived Reports

You can access the following Memory Archived reports:

- [Memory Utilization 15 Minute Archived Reports, page 13-346](#)
- [Memory Utilization Hourly Archived Reports, page 13-346](#)
- [Memory Utilization Daily Archived Reports, page 13-346](#)
- [Memory Buffer Utilization 15 Minute Archived Reports, page 13-346](#)
- [Memory Buffer Utilization Hourly Archived Reports, page 13-347](#)
- [Memory Buffer Utilization Daily Archived Reports, page 13-347](#)

## Memory Utilization 15 Minute Archived Reports

The Memory Utilization 15 Minute Archived Reports page shows summary reports for all archived MWTM 15 minute memory statistics for the server to which you connect, stored as downloadable .zip files.

The .zip files are archived by type, date, hour, and minute; for example, the *MemStats.2009-06-22-16-00.csv.zip* file contains the summary report for 15 minute memory statistics for June 22, 2009.

Each archived .zip file contains a comma-separated value (CSV) text file with a summary report of 15 minute memory statistics on that date, hour, and minute. You can download the .zip files and extract them.

To download a .zip file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Memory Utilization Hourly Archived Reports

The Memory Utilization Hourly Archived Reports page shows all summary reports for archived MWTM hourly memory statistics for the server to which you connect, stored as downloadable .zip files.

The .zip files are archived by type, date, and hour; for example, the *MemStats.2009-06-22-08.csv.zip* file contains the summary report for hourly memory statistics for the 8th hour on June 22, 2009.

Each archived .zip file contains a comma-separated value (CSV) text file with a summary report of hourly memory statistics on that date and hour. You can download the .zip files and extract them.

To download a .zip file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Memory Utilization Daily Archived Reports

The Memory Utilization Daily Archived Reports page shows summary reports for all archived MWTM daily memory statistics for the server to which you connect, stored as downloadable .zip files.

The .zip files are archived by type and date; for example, the *MemStats.2009-06-22.csv.zip* file contains the summary report for daily memory statistics for June 22, 2009.

Each archived .zip file contains a comma-separated value (CSV) text file with a summary report of daily memory statistics on that date and hour. You can download the .zip files and extract them.

To download a .zip file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Memory Buffer Utilization 15 Minute Archived Reports

The Memory Buffer Utilization 15 Minute Archived Reports page shows summary reports for all archived MWTM 15 minute memory buffer statistics for the server to which you connect, stored as downloadable .zip files.

The .zip files are archived by type, date, hour, and minute; for example, the *MemStats.2009-06-22-16-00.csv.zip* file contains the summary report for 15 minute memory statistics for June 22, 2009.

Each archived .zip file contains a comma-separated value (CSV) text file with a summary report of 15 minute memory statistics on that date, hour, and minute. You can download the .zip files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### Memory Buffer Utilization Hourly Archived Reports

The Memory Buffer Utilization Hourly Archived Reports page shows all summary reports for archived MWTM hourly memory buffer statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *MemStats.2009-06-22-08.csv.zip* file contains the summary report for hourly memory statistics for the 8th hour on June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly memory statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### Memory Buffer Utilization Daily Archived Reports

The Memory Buffer Utilization Daily Archived Reports page shows summary reports for all archived MWTM daily memory buffer statistics for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *MemStats.2009-06-22.csv.zip* file contains the summary report for daily memory statistics for June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily memory statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Viewing File Archive ITP Statistics Reports

ITP Reports that have been archived are located within **File Archive > ITP Statistics** in the MWTM web interface. You can also find archived reports in the */opt/CSCOsgm/reports* directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in *.csv* format.

You can view full descriptions of all fields in export file archive reports by clicking **Administrative** from the MWTM web interface, then clicking **Export Reports README** under System Information.

You can view any of the following ITP archived reports:

- [Custom Archived Reports](#), page 13-348
- [Rolling Archived Reports](#), page 13-350
- [Application Server Archived Reports](#), page 13-351
- [Application Server Process Archived Reports](#), page 13-352
- [GTT Rates Archived Reports](#), page 13-353
- [Link Archived Reports](#), page 13-353
- [Linkset Archived Reports](#), page 13-354
- [MLR Archived Reports](#), page 13-355
- [MSU Archived Reports](#), page 13-356

- [MTP3/AS Events Archived Reports, page 13-357](#)
- [Point Code Archived Reports, page 13-358](#)
- [Q752 Archived Reports, page 13-359](#)
- [SCTP Archived Reports, page 13-360](#)

## Custom Archived Reports

The Custom Archived Report pages show all archived MWTM custom network and accounting statistics reports for the server to which you connect. These reports can be viewed on the web, or downloaded as .zip files. These .zip files are also stored in the default directory (*/opt/CSCOsgm* by default) in the */reports/custom* directory.

**Note**

Custom archive reports are supported on ITP platforms only.

**Note**

Custom reports are *custom* because you can specify that they run at custom time intervals. The content of custom reports is the same as regularly scheduled reports.

Custom archived reports are those that you enable by using these commands:

Command	Generates these custom statistics:
mwtm accstats	MTP3/AS accounting
mwtm gttstats	GTT
mwtm linkstats	Link and linkset
mwtm mlrstats	MLR
mwtm msustats	MSU rates
mwtm mtpevents	MTP3/AS events
mwtm q752stats	Q.752
mwtm xuastats	Application server and application server process

**Note**

For detailed descriptions of these commands, see [Appendix B, “Command Reference.”](#)

**Note**

Custom ITP reports can be run manually from the command line or setup to run at custom intervals by creating crontab entries. See [Generating Custom ITP Statistics Reports Using the CLI, page 13-400](#) and [Including or Excluding Specified Objects in ITP Reports, page 13-402](#) for more information.

The Custom Report tables are sorted based on the information in the Export File column. However, you can sort a table based on the information in one of the other columns (see [Navigating Table Columns, page 4-24](#)).

The Custom Report tables contain:

Column	Description
Export File	<p>Name of the custom statistics export <i>.zip</i> file, archived by type, date, and hour; for example, the <i>sgmLinksetStats.custom.20867.2009-06-24-16:15.csv.zip</i> file contains the summary report of custom linkset statistics with the ID tag 20867 for the 15th minute of the 16th hour on June 24, 2009.</p> <p>Each archived <i>.zip</i> file contains a comma-separated value (CSV) text file with a daily statistics report for that date. You can download the <i>.zip</i> files and extract them.</p> <p>To download a <i>.zip</i> file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.</p>
Report Date ( <i>time zone</i> )	Date the custom report began.
Report Hour	Time the custom report began.
Last Modified Date ( <i>time zone</i> )	Date and time the custom report was last modified.
View	Shows the detail report for the object. Not available for Q.752 reports.

To show details in HTML for custom archived reports, click on a link in the View column of the Custom Archived Report page:

Link	Description
Application Servers	<a href="#">AS Statistics Custom Archived Reports, page 13-352</a>
Application Server Processes	<a href="#">ASP Statistics Custom Archived Reports, page 13-353</a>
Links	<a href="#">Link Statistics Custom Archived Reports, page 13-354</a>
Linksets	<a href="#">Linkset Statistics Custom Archived Reports, page 13-355</a>
Aborts and Continues	<a href="#">•MLR Aborts &amp; Continuous Statistics Custom Archived Reports, page 13-356</a>
Processed	<a href="#">•MLR Processed Statistics Custom Archived Reports, page 13-356</a>
ResultInvokes	<a href="#">•MLR ResultInvokes Statistics Custom Archived Reports, page 13-356</a>
RuleMatches	<a href="#">•MLR RuleMatches Statistics Custom Archived Reports, page 13-356</a>
SubTriggers	<a href="#">•MLR Sub Triggers Statistics Custom Archived Reports, page 13-356</a>
Triggers	<a href="#">•MLR Triggers Statistics Custom Archived Reports, page 13-356</a>
MTP3/AS Events	<a href="#">MTP3/AS Events Custom Archived Reports, page 13-358</a>
Q752	<a href="#">Q752 Statistics Custom Archived Reports, page 13-359</a>

All custom detail reports contain these headings and general menu options:

Heading/ Menu Option	Description
Date and Hour (in heading)	Date and hour of the report.
Offset (in heading)	Shows the number of rows in the table, prior to the first visible row; for example, if the first visible row is 501, the <b>Offset</b> is 500.
Number and Sort Order (in heading)	Shows the number of records (rows) in the table, the column by which the table is sorted, and whether the sort is in ascending or descending order.
10/Page	Shows 10 rows in the table.
20/Page	Shows 20 rows in the table.
50/Page	Shows 50 rows in the table.
100/Page	Shows 100 rows in the table.
300/Page	Shows 300 rows in the table.
500/Page	Shows 500 rows in the table.
Max/Page	Shows up to 15,000 rows in the table.  <b>Note</b> Depending on the number of rows, this could take up to 15 minutes.
DefPrefs	Resets the <b>/Page</b> preferences for this web page to the default settings for the MWTM server.
First (at bottom of table)	Shows the first page of entries for the table.  For example, if the table is sorted by <b>Total Aborted</b> in descending order, clicking this field shows the entries with the highest number of MSUs aborted by MLR.  You cannot click this field if the first page of entries is already visible.
Previous (Rows) (at bottom of table)	Shows the previous page of entries for the table.  You cannot click this field if the first page of entries is already visible.
Next (Rows) (at bottom of table)	Shows the next page of entries for the table.  You cannot click this field if the last page of entries is already visible.
Last (at bottom of table)	Shows the last page of entries for the table.  For example, if the table is sorted by <b>Total Aborted</b> in descending order, clicking this field shows the entries with the lowest number of MSUs aborted by MLR.  You cannot click this field if the last page of entries is already visible.
Total (at bottom of table)	Shows the total number of entries in the table.

## Rolling Archived Reports

The All Rolling Reports page shows summary reports of concatenated MWTM hourly and daily network statistics for all of the following objects detected by the MWTM for the server you are connected to:

- Application servers

- Application server processes
- Links
- Linksets

These statistics are stored as downloadable *.zip* files. The *.zip* files are archived by type and number of days (7 or 30). For example:

- *sgmLinkStats.RollingSevenDayAllHours.csv.zip*
- *sgmLinkStats.Rolling30DayAllDays.csv.zip*
- *sgmASEStats.Rolling30DayAllDays.csv.zip*
- *sgmASEStats.RollingSevenDayAllHours.csv.zip*
- *sgmASPStats.Rolling30DayAllDays.csv.zip*
- *sgmASPStats.RollingSevenDayAllHours.csv.zip*



**Note** To limit the maximum number of rows in export CSV files (for example, Excel can only handle 65,535 rows.) See [mwtm statreps, page B-81](#).



**Note**

Rolling Archived Reports are supported for ITP platforms only.

The MWTM creates a new set of files every hour.

You can download the *.zip* files and extract them. To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Application Server Archived Reports

You can access the following Application Server Archived Reports. These reports are supported on ITP platforms only:

- [AS Statistics Hourly Archived Reports, page 13-351](#)
- [AS Statistics Daily Archived Reports, page 13-352](#)
- [AS Statistics Custom Archived Reports, page 13-352](#)

### AS Statistics Hourly Archived Reports

The AS Statistics Hourly Archived Reports page shows all summary reports for archived MWTM hourly network statistics for all application servers that the MWTM detects for the server to which you connect. The information is stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *sgmASEStats.2009-06-22-08.csv.zip* file contains the summary report for hourly application server statistics for the 8th hour on June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly network statistics for all application servers that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## AS Statistics Daily Archived Reports

The AS Statistics Daily Archived Reports page shows summary reports for all archived MWTM daily network statistics for all application servers that the MWTM detects for the server to which you connect. The information is stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *sgmASEStats.DailySum.2009-06-22.csv.zip* file contains the summary report for daily application server statistics for June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily network statistics for all application servers that the MWTM detects on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## AS Statistics Custom Archived Reports

The Application Server Statistics Custom Archived Report pages show all archived MWTM custom network and accounting statistics reports for all application servers that the MWTM detects for the server to which you connect. These reports can be viewed on the web, or downloaded as *.zip* files. These *.zip* files are also stored in the default directory (*/opt/CSCOsgm* by default) in the */reports/custom* directory.

The detailed information about custom archived reports is available in [Custom Archived Reports](#).

## Application Server Process Archived Reports

You can access the following Application Server Process Archived Reports. These reports are supported on ITP platforms only:

- [ASP Statistics Hourly Archived Reports, page 13-352](#)
- [ASP Statistics Daily Archived Reports, page 13-352](#)
- [ASP Statistics Custom Archived Reports, page 13-353](#)

## ASP Statistics Hourly Archived Reports

The ASP Hourly Statistics Archived Reports page shows the summary reports of all archived MWTM hourly network statistics for all application server processes that the MWTM detects for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *sgmASPStats.2009-06-22-11.csv.zip* file contains the summary report of hourly application server process statistics for the 11th hour on June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with the summary report for hourly network statistics for all application server processes that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## ASP Statistics Daily Archived Reports

The ASP Daily Statistics Archived Reports page shows summary reports of all archived MWTM daily network statistics for all application server processes that the MWTM detects for the server to which you connect, stored as downloadable *.zip* files.



The *.zip* files are archived by type and date; for example, the *sgmASPStats.DailySum.2009-06-22.csv.zip* file contains the summary report of daily application server process statistics for June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily network statistics for all application server processes that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### ASP Statistics Custom Archived Reports

The ASP Statistics Custom Archived Report pages show all archived MWTM custom network and accounting statistics reports for all application server processes that the MWTM detects for the server to which you connect. These reports can be viewed on the web, or downloaded as *.zip* files. These *.zip* files are also stored in the default directory (*/opt/CSCOSgm* by default) in the */reports/custom* directory.

The detailed information about custom archived reports is available in [Custom Archived Reports](#).

## GTT Rates Archived Reports

You can access the following GTT Rates Archived Report. This report is supported on ITP platforms only:

- [GTT Rates Statistics Hourly Archived Reports, page 13-353](#).

### GTT Rates Statistics Hourly Archived Reports

The GTT Rates Statistics Hourly Archived Reports page shows all archived MWTM hourly GTT rates statistics reports for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *sgmGTTRates.2009-06-22-11.csv.zip* file contains the hourly GTT rates statistics report for the 11th hour on June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with an hourly GTT rates statistics report for that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Link Archived Reports

You can access the following Link Archived Reports. These reports are supported on ITP platforms only:

- [Link Statistics Hourly Archived Reports, page 13-353](#)
- [Link Statistics Daily Archived Reports, page 13-354](#)
- [Link Statistics Custom Archived Reports, page 13-354](#)

### Link Statistics Hourly Archived Reports

The Link Statistics Hourly Archived Reports page shows summary reports for all archived MWTM hourly network statistics for all links that the MWTM detected for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *sgmLinkStats.2009-06-24-09.csv.zip* file contains the summary reports for hourly link statistics for June 24, 2009 at 9:00 a.m.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of an hourly network statistics for all links that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### Link Statistics Daily Archived Reports

The Link Statistics Daily Archived Reports page shows summary reports for all archived MWTM daily network statistics for all links that the MWTM detected for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *sgmLinkStats.DailySum.2009-06-24.csv.zip* file contains the summary report of daily link statistics for June 24, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily network statistics for all links that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### Link Statistics Custom Archived Reports

The Link Statistics Custom Archived Report pages show all archived MWTM custom network and accounting statistics reports for all Link statistics servers that the MWTM detects for the server to which you connect. These reports can be viewed on the web, or downloaded as *.zip* files. These *.zip* files are also stored in the default directory (*/opt/CSCOsgm* by default) in the */reports/custom* directory.

The detailed information about custom archived reports is available in [Custom Archived Reports](#).

## Linkset Archived Reports

You can access the following Linkset Archived Reports. These reports are supported on ITP platforms only:

- [Linkset Statistics Hourly Archived Reports, page 13-354](#)
- [Linkset Statistics Daily Archived Reports, page 13-355](#)
- [Linkset Statistics Custom Archived Reports, page 13-355](#)

### Linkset Statistics Hourly Archived Reports

The Linkset Statistics Hourly Archived Reports page shows summary reports of all archived MWTM hourly network statistics for all linksets that the MWTM detects for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *sgmLinksetStats.2009-06-24-09.csv.zip* file contains the summary report for the hourly linkset statistics for June 24, 2009 at 9:00 a.m.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly network statistics for all linksets that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Linkset Statistics Daily Archived Reports

The Linkset Statistics Daily Archived Reports page shows the summary report of all archived MWTM daily network statistics for all linksets that the MWTM detected for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *sgmLinksetStats.DailySum.2009-06-24.csv.zip* file contains the summary reports of daily linkset statistics for June 24, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily network statistics for all linksets that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Linkset Statistics Custom Archived Reports

The Link Statistics Custom Archived Report pages show all archived MWTM custom network and accounting statistics reports for all Linkset statistics servers that the MWTM detects for the server to which you connect. These reports can be viewed on the web, or downloaded as *.zip* files. These *.zip* files are also stored in the default directory (*/opt/CSCOsgm* by default) in the */reports/custom* directory.

The detailed information about custom archived reports is available in [Custom Archived Reports](#).

## MLR Archived Reports

You can access the following MLR Archived Reports. These reports are supported on ITP platforms only:

- [MLR Daily Archived Reports, page 13-355](#)
- [MLR Custom Archived Reports, page 13-356](#)

## MLR Daily Archived Reports

The MLR Daily Archived Reports pages show all archived MWTM daily MLR statistics for the server to which you connect, stored as downloadable *.zip* files. MWTM creates the following MLR archived report files:

- MLR Abort & Continues Statistics Daily Archived Reports
- MLR Processed Statistics Daily Archived Reports
- MLR ResultInvokes Statistics Daily Archived Reports
- MLR RuleMatches Statistics Daily Archived Reports
- MLR SubTriggers Statistics Daily Archived Reports
- MLR Triggers Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a daily MLR statistics report for that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## MLR Custom Archived Reports

The MLR Custom Archived Report pages show all archived MWTM custom network and accounting statistics reports for all MLR servers that the MWTM detects for the server to which you connect. These reports can be viewed on the web, or downloaded as *.zip* files. These *.zip* files are also stored in the default directory (*/opt/CSCOsgm* by default) in the */reports/custom* directory.

MWTM displays the following MLR Custom archived reports:

- MLR Aborts & Continuous Statistics Custom Archived Reports
- MLR Processed Statistics Custom Archived Reports
- MLR ResultInvokes Statistics Custom Archived Reports
- MLR RuleMatches Statistics Custom Archived Reports
- MLR Sub Triggers Statistics Custom Archived Reports
- MLR Triggers Statistics Custom Archived Reports

The detailed information about custom archived reports is available in [Custom Archived Reports](#).

## MSU Archived Reports

You can access the following MSU Archived Reports. These reports are supported on ITP platforms only:

- [MSU Statistics 15 Minutes Archived Reports, page 13-356](#)
- [MSU Statistics Hourly Archived Reports, page 13-356](#)
- [MSU Statistics Daily Archived Reports, page 13-357](#)

**Note**

While upgrading MWTM from an earlier version to 6.1.7, remove the cron entry **45 \* \* \* \*** */opt/CSCOsgm/bin/mwtmCron.sh msustats* manually using **crontab -e** command.

## MSU Statistics 15 Minutes Archived Reports

The MSU Statistics 15 Minutes Archived Reports page shows summary reports of all archived MWTM hourly MSU rates that the MWTM detects for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *itp15MinutesMsuLoad.2009-06-24-09-15.csv.zip* file contains the summary report for the hourly MSU rates for June 24, 2009 at 9:15 a.m.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute MSU rates that the MWTM detected on that date, hour and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## MSU Statistics Hourly Archived Reports

The MSU Statistics Hourly Archived Reports page shows summary reports of all archived MWTM hourly MSU rates that the MWTM detects for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type, date, and hour; for example, the *itpHourlyMsuLoad.2009-06-24-09.csv.zip* file contains the summary report for the hourly MSU rates for June 24, 2009 at 9:00 a.m.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly MSU rates that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### MSU Statistics Daily Archived Reports

The MSU Daily Archived Reports page shows the summary report of all archived MWTM daily MSU rates that the MWTM detected for the server to which you connect, stored as downloadable *.zip* files.

The *.zip* files are archived by type and date; for example, the *itpDailyMsuLoad.2009-06-24.csv.zip* file contains the summary reports of daily MSU rates for June 24, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily MSU rates that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### MTP3/AS Events Archived Reports

You can access the following MTP3/AS Events Reports. These reports are supported on ITP platforms only:

- [MTP3/AS Events Hourly Archived Reports, page 13-357](#)
- [MTP3/AS Events Custom Archived Reports, page 13-358](#)

### MTP3/AS Events Hourly Archived Reports

To create hourly MTP3/AS event reports for the MWTM:

---

**Step 1** Log in as the root user, as described in [Starting the MWTM Client, page 3-3](#), or as a superuser, as described in [Specifying a Super User \(Server Only\), page 2-21](#).

**Step 2** Enter these commands:

```
# cd /opt/CSC0sgm/bin
# ./mwtm evreps enable
# ./mwtm evreps mtp
```

For more details on the **mwtm evreps** commands, see [Appendix B, “Command Reference.”](#)

Field or Column	Description
Export File	<p>Name of the network events export <i>.zip</i> file, archived by type, date, and hour; for example, the <i>sgmMTP3Events.custom.20867.2009-06-24-16-15.csv.zip</i> file contains the summary report of custom network events with ID tag 20867 for the 15th minute of the 16th hour on June 24, 2009.</p> <p>Each archived <i>.zip</i> file contains a comma-separated value (CSV) text file with a daily statistics report for that date. You can download the <i>.zip</i> files and extract them.</p> <p>To download a <i>.zip</i> file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.</p>
Report Start Date ( <i>time zone</i> )	Date and time the custom report began.
Report Finish Date ( <i>time zone</i> )	Date and time the custom report ended.
Last Modified Date ( <i>time zone</i> )	Date and time the custom report was last modified.
View	Shows the custom detail report for the object.

## MTP3/AS Events Custom Archived Reports

The MTP3/AS Custom Archived Report pages show all archived MWTM custom network and accounting statistics reports for all MTP3/AS servers that the MWTM detects for the server to which you connect. These reports can be viewed on the web, or downloaded as *.zip* files. These *.zip* files are also stored in the default directory (*/opt/CSCOsgm* by default) in the */reports/custom* directory.

The detailed information about custom archived reports is available in [Custom Archived Reports](#).

## Point Code Archived Reports

You can access the following Point Code Archived Report. This report is supported on ITP platforms only:

- [Point Codes Daily Archived Reports, page 13-358](#)

### Point Codes Daily Archived Reports

The Point Codes Daily Archived Reports page shows all archived MWTM daily point code inventory reports for the server to which you connect, stored as downloadable *.zip* files.

On the Point Codes Daily Archived Reports page, the *.zip* files are archived by date; for example, the *sgmPointCodes.DailyInv.2009-06-24.csv.zip* file contains the daily point code inventory report for June 24, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a list of all point codes that were being used by all nodes that the MWTM detected on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Q752 Archived Reports

You can access the following Q752 Archived Reports:

- [Q752 Statistics Hourly Archived Reports, page 13-359](#)
- [Q752 Statistics Daily Archived Reports, page 13-359](#)
- [Q752 Statistics Custom Archived Reports, page 13-359](#)

### Q752 Statistics Hourly Archived Reports

The Q752 Statistics Archived Reports page shows all archived MWTM hourly Q752 reports for the server to which you connect, stored as downloadable *.zip* files. The MWTM creates the following Q752 hourly archived report files each hour:

- Q752 Statistics Hourly
- Q752 Table 4 Statistics Hourly
- Q752 Table 5 Destination Congestion Statistics Hourly
- Q752 Table 5 Routing Drops Statistics Hourly
- Q752 Table 5 User Part Unavailable Statistics Hourly

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of all Q752 links that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### Q752 Statistics Daily Archived Reports

The Q752 Statistics Archived Reports page shows all archived MWTM daily Q752 reports for the server to which you connect, stored as downloadable *.zip* files. The MWTM creates the following Q752 daily archived report files each day:

- Q752 Statistics Daily
- Q752 Table 4 Statistics Daily
- Q752 Table 5 Destination Congestion Statistics Daily
- Q752 Table 5 Routing Drops Statistics Daily
- Q752 Table 5 User Part Unavailable Statistics Daily

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of all Q752 links that the MWTM detected on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### Q752 Statistics Custom Archived Reports

The Q752 Statistics Custom Archived Reports page shows all archived MWTM hourly Q752 reports for the server to which you connect, stored as downloadable *.zip* files.

On the Q752 Custom Archived Reports page, the *.zip* files are archived by date; for example, the *sgmQ752Stats.2009-06-24.csv.zip* file contains the Custom Q752 report for June 24, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of all Q752 links that the MWTM detected on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## SCTP Archived Reports

You can access the following SCTP Archived Report:

- [SCTP Statistics 15 Minute Archived Reports, page 13-360](#)
- [SCTP Statistics Hourly Archived Reports, page 13-360](#)
- [SCTP Statistics Daily Archived Reports, page 13-360](#)

### SCTP Statistics 15 Minute Archived Reports

The SCTP Statistics 15 Minute Archived Reports page shows all archived MWTM SCTP 15 minute reports for the server to which you connect, stored as downloadable *.zip* files.

On the SCTP Statistics 15 Minute Archived Reports page, the *.zip* files are archived by date; for example, the *sgmSCTPStats.2009-06-22-11-30.csv.zip* file contains the SCTP 15-minute report for the 11th hour, 30 minutes on June 22, 2009.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of all SCTP links that the MWTM detected on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### SCTP Statistics Hourly Archived Reports

The SCTP Statistics Hourly Archived Reports page shows all archived MWTM SCTP hourly reports for the server to which you connect, stored as downloadable *.zip* files.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of all SCTP links that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### SCTP Statistics Daily Archived Reports

The SCTP Statistics Daily Archived Reports page shows all archived MWTM SCTP daily reports for the server to which you connect, stored as downloadable *.zip* files.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of all SCTP links that the MWTM detected on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.



## Viewing File Archive Mobile Statistics Reports

Mobile Reports that have been archived are located within **File Archive > Mobile Statistics** in the MWTM web interface. You can also find archived reports in the `/opt/CSCOs/gm/reports` directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in .csv format.

You can view full descriptions of all fields in export file archive reports by clicking **Administrative** from the MWTM web interface, then clicking **Export Reports README** under System Information.

You can view any of the following Mobile archived reports:

- [CSG Archived Reports, page 13-361](#)
- [GGSN Archived Reports, page 13-363](#)
- [HA Archived Reports, page 13-365](#)
- [PDNGW Archived Reports, page 13-366](#)
- [PDSN Archived Reports, page 13-369](#)
- [SGW Archived Reports, page 13-370](#)
- [SLB Archived Reports, page 13-372](#)
- [SPGW Archived Reports, page 13-373](#)

### CSG Archived Reports

You can access the following CSG Archived Reports:

- [CSG 15 Minute Archived Reports, page 13-361](#)
- [CSG Hourly Archived Reports, page 13-362](#)
- [CSG Daily Archived Reports, page 13-363](#)

#### CSG 15 Minute Archived Reports

The 15 minute CSG Archived Reports page shows summary reports of all archived MWTM 15 minute CSG statistics. MWTM creates the following CSG 15 Minute archived report files for every 15 Minutes:

- CSG BMA Statistics 15 Minute Archived Reports
- CSG Global Peak Rates 15 Minute Archived Reports
- CSG Protocol Rates 15 Minute Archived Reports
- CSG Load Session Rates 15 Minute Archived Reports
- CSG Load Radius Rates 15 Minute Archived Reports
- CSG Load BMA Rates 15 Minute Archived Reports
- CSG Load User DB Rates 15 Minute Archived Reports
- CSG Load Quota Manager Rates 15 Minute Archived Reports
- CSG Load Gx Event Statistics 15 Minute Archived Reports
- CSG Quota Manager Statistics 15 Minute Archived Reports
- CSG Billing Plan Statistics 15 Minute Archived Reports
- CSG Gx Global Message Statistics 15 Minute Archived Reports

- CSG Gx Global Message Errors 15 Minute Archived Reports
- CSG Gx PCRF Method List Message Statistics 15 Minute Archived Reports
- CSG Gx PCRF Method List Message Errors 15 Minute Archived Reports
- CSG Gx Policy Preload Statistics 15 Minute Archived Reports
- CSG Gx Policy Preload Errors 15 Minute Archived Reports
- CSG Gx Policy Preload Accounting Policy Statistics 15 Minute Archived Reports
- CSG Gx Policy Preload Billing Plan Statistics 15 Minute Archived Reports
- CSG Gx Policy Preload Billing Services Statistics 15 Minute Archived Reports
- CSG Gx Policy Preload Content Policy Statistics 15 Minute Archived Reports
- CSG Gx Policy Preload Service Content Statistics 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute CSG statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### CSG Hourly Archived Reports

The CSG Hourly Archived Reports page shows the summary reports of all archived MWTM hourly CSG statistics. MWTM creates the following CSG hourly archived report files each hour:

- CSG BMA Statistics Hourly Archived Reports
- CSG Global Peak Rates Hourly Archived Reports
- CSG Protocol Rates Hourly Archived Reports
- CSG Load Session Rates Hourly Archived Reports
- CSG Load Radius Rates Hourly Archived Reports
- CSG Load BMA Rates Hourly Archived Reports
- CSG Load User DB Rates Hourly Archived Reports
- CSG Load Quota Manager Rates Hourly Archived Reports
- CSG Load Gx Event Statistics Hourly Archived Reports
- CSG Quota Manager Statistics Hourly Archived Reports
- CSG Billing Plan Statistics Hourly Archived Reports
- CSG Gx Global Message Statistics Hourly Archived Reports
- CSG Gx Global Message Errors Hourly Archived Reports
- CSG Gx PCRF Method List Message Statistics Hourly Archived Reports
- CSG Gx PCRF Method List Message Errors Hourly Archived Reports
- CSG Gx Policy Preload Statistics Hourly Archived Reports
- CSG Gx Policy Preload Errors Hourly Archived Reports
- CSG Gx Policy Preload Accounting Policy Statistics Hourly Archived Reports
- CSG Gx Policy Preload Billing Plan Statistics Hourly Archived Reports
- CSG Gx Policy Preload Billing Services Statistics Hourly Archived Reports
- CSG Gx Policy Preload Content Policy Statistics Hourly Archived Reports

- CSG Gx Policy Preload Service Content Statistics Hourly Archived Reports

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## CSG Daily Archived Reports

The Daily CSG Archived Reports page shows summary reports of all archived MWTM daily CSG statistics. MWTM creates the following CSG daily archived report files each day:

- CSG BMA Statistics Daily Archived Reports
- CSG Global Peak Rates Daily Archived Reports
- CSG Protocol Rates Daily Archived Reports
- CSG Load Session Rates Daily Archived Reports
- CSG Load Radius Rates Daily Archived Reports
- CSG Load BMA Rates Daily Archived Reports
- CSG Load User DB Rates Daily Archived Reports
- CSG Load Quota Manager Rates Daily Archived Reports
- CSG Load Gx Event Statistics Daily Archived Reports
- CSG Quota Manager Statistics Daily Archived Reports
- CSG Billing Plan Statistics Daily Archived Reports
- CSG Gx Global Message Statistics Daily Archived Reports
- CSG Gx Global Message Errors Daily Archived Reports
- CSG Gx PCRF Method List Message Statistics Daily Archived Reports
- CSG Gx PCRF Method List Message Errors Daily Archived Reports
- CSG Gx Policy Preload Statistics Daily Archived Reports
- CSG Gx Policy Preload Errors Daily Archived Reports
- CSG Gx Policy Preload Accounting Policy Statistics Daily Archived Reports
- CSG Gx Policy Preload Billing Plan Statistics Daily Archived Reports
- CSG Gx Policy Preload Billing Services Statistics Daily Archived Reports
- CSG Gx Policy Preload Content Policy Statistics Daily Archived Reports
- CSG Gx Policy Preload Service Content Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily CSG statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## GGSN Archived Reports

You can access these reports:

- [GGSN 15 Minute Archived Reports, page 13-364](#)
- [GGSN Hourly Archived Reports, page 13-364](#)
- [GGSN Daily Archived Reports, page 13-365](#)

## GGSN 15 Minute Archived Reports

The 15 minute GGSN Archived Reports page shows summary reports of all archived MWTM 15 minute GGSN statistics. MWTM creates the following GGSN 15 Minute archived report files for every 15 Minutes:

- APN Aggregate Miscellaneous Statistics 15 Minute Archived Reports
- APN Aggregate PDP/Bearer Statistics 15 Minute Archived Reports
- APN Aggregate PDP/Bearer Extended Statistics 15 Minute Archived Reports
- APN Aggregate Throughput Statistics 15 Minute Archived Reports
- APN Instance Miscellaneous Statistics 15 Minute Archived Reports
- APN Instance PDP/Bearer Statistics 15 Minute Archived Reports
- APN Instance PDP/Bearer Extended Statistics 15 Minute Archived Reports
- APN Instance Throughput Statistics 15 Minute Archived Reports
- GTP Active Statistics 15 Minute Archived Reports
- GTP Error Statistics 15 Minute Archived Reports
- GTP PDP Statistics 15 Minute Archived Reports
- GTP Throughput Statistics 15 Minute Archived Reports
- GTP Path Throughput Statistics 15 Minute Archived Reports
- GTP Charging Statistics 15 Minute Archived Reports
- Gateway Charging Group Statistics 15 Minute Archived Reports
- APN Instance DHCP V6 Proxy Server Statistics 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute network statistics for all application servers that the MWTM detects on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## GGSN Hourly Archived Reports

The Hourly GGSN Archived Reports page shows all summary reports for archived MWTM hourly statistics. MWTM creates the following GGSN hourly archived report files for each hour:

- APN Aggregate Miscellaneous Statistics Hourly Archived Reports
- APN Aggregate PDP/Bearer Statistics Hourly Archived Reports
- APN Aggregate PDP/Bearer Extended Statistics Hourly Archived Reports
- APN Aggregate Throughput Statistics Hourly Archived Reports
- APN Instance Miscellaneous Statistics Hourly Archived Reports
- APN Instance PDP/Bearer Statistics Hourly Archived Reports
- APN Instance PDP/Bearer Extended Statistics Hourly Archived Reports
- APN Instance Throughput Statistics Hourly Archived Reports
- GTP Active Statistics Hourly Archived Reports
- GTP Error Statistics Hourly Archived Reports

- GTP PDP Statistics Hourly Archived Reports
- GTP Throughput Statistics Hourly Archived Reports
- GTP Path Throughput Statistics Hourly Archived Reports
- GTP Charging Statistics Hourly Archived Reports
- Gateway Charging Group Statistics Hourly Archived Reports
- APN Instance DHCP V6 Proxy Server Statistics Hourly Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly network statistics for all application servers that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### GSGN Daily Archived Reports

The GSGN Daily Archived Reports page shows summary reports for all archived MWTM daily statistics. MWTM creates the following GSGN daily archived report files for each day:

- APN Aggregate Miscellaneous Statistics Daily Archived Reports
- APN Aggregate PDP/Bearer Statistics Daily Archived Reports
- APN Aggregate PDP/Bearer Extended Statistics Daily Archived Reports
- APN Aggregate Throughput Statistics Daily Archived Reports
- APN Instance Miscellaneous Statistics Daily Archived Reports
- APN Instance PDP/Bearer Statistics Daily Archived Reports
- APN Instance PDP/Bearer Extended Statistics Daily Archived Reports
- APN Instance Throughput Statistics Daily Archived Reports
- GTP Active Statistics Daily Archived Reports
- GTP Error Statistics Daily Archived Reports
- GTP PDP Statistics Daily Archived Reports
- GTP Throughput Statistics Daily Archived Reports
- GTP Path Throughput Statistics Daily Archived Reports
- GTP Charging Statistics Daily Archived Reports
- Gateway Charging Group Statistics Daily Archived Reports
- APN Instance DHCP V6 Proxy Server Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily network statistics for all application servers that the MWTM detects on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### HA Archived Reports

You can access these HA Archived Reports:

- [HA Registration Statistics 15 Minute Archived Reports, page 13-366](#)

- [HA Registration Statistics Hourly Archived Reports, page 13-366](#)
- [HA Registration Statistics Daily Archived Reports, page 13-366](#)

### HA Registration Statistics 15 Minute Archived Reports

The HA Registration Statistics 15 Minute Archived Reports page shows summary reports of 15-minute statistical details on Home Agent registration and binding updates. The HA 15 Minute Archived Report has the file name `HomeAgentRegistrationStatsEntry.year-month-day-hour-minute.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of 15-minute registration statistics on that date, hour, and minute. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### HA Registration Statistics Hourly Archived Reports

The HA Registration Statistics Hourly Archived Reports page shows summary reports of hourly statistical details on Home Agent registration and binding updates. The HA Hourly Archived Report has the file name `HomeAgentRegistrationStatsEntry.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly registration statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### HA Registration Statistics Daily Archived Reports

The HA Registration Statistics Daily Archived Reports page shows summary reports of daily statistical details on Home Agent registration and binding updates. The HA Daily Archived Report has the file name `HomeAgentRegistrationStatsEntry.year-month-day.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of daily registration statistics on that date. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## PDNGW Archived Reports

You can access these reports

- [PDNGW 15 Minute Archived Reports, page 13-366](#)
- [PDNGW Hourly Archived Reports, page 13-367](#)
- [PDNGW Daily Archived Reports, page 13-368](#)

### PDNGW 15 Minute Archived Reports

The 15 minute PDNGW Archived Reports page shows summary reports of all archived MWTM 15 minute PDNGW statistics. MWTM creates the following PDNGW 15 Minute archived report files for every 15 Minutes:

- APN Aggregate Miscellaneous Statistics 15 Minute Archived Reports
- APN Aggregate PDP/Bearer Statistics 15 Minute Archived Reports

- APN Aggregate PDP/Bearer Extended Statistics 15 Minute Archived Reports
- APN Aggregate Throughput Statistics 15 Minute Archived Reports
- APN Instance Miscellaneous Statistics 15 Minute Archived Reports
- APN Instance PDP/Bearer Statistics 15 Minute Archived Reports
- APN Instance PDP/Bearer Extended Statistics 15 Minute Archived Reports
- APN Instance Throughput Statistics 15 Minute Archived Reports
- EPC Gateway Protection Statistics 15 Minute Archived Reports
- EPC Gateway Buffering Statistics 15 Minute Archived Reports
- GTP Active Statistics 15 Minute Archived Reports
- GTP Error Statistics 15 Minute Archived Reports
- GTP Path Errors 15 Minute Archived Reports
- GTP PDP/Bearer Statistics 15 Minute Archived Reports
- GTP Throughput Statistics 15 Minute Archived Reports
- GTP Path Throughput Statistics 15 Minute Archived Reports
- GTP Path PDP Miscellaneous Statistics 15 Minute Archived Reports
- GTP Charging Statistics 15 Minute Archived Reports
- GTPv2 Bearer Statistics 15 Minute Archived Reports
- GTPv2 Session Statistics 15 Minute Archived Reports
- GTPv2 Path Bearer Requests Statistics 15 Minute Archived Reports
- GTPv2 Path Bearer Responses Statistics 15 Minute Archived Reports
- GTPv2 Path Session Statistics 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute network statistics for all application servers that the MWTM detects on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PDNGW Hourly Archived Reports

The Hourly PDNGW Archived Reports page shows all summary reports for archived MWTM hourly statistics. MWTM creates the following PDNGW hourly archived report files for each hour:

- APN Aggregate Miscellaneous Statistics Hourly Archived Reports
- APN Aggregate PDP/Bearer Statistics Hourly Archived Reports
- APN Aggregate PDP/Bearer Extended Statistics Hourly Archived Reports
- APN Aggregate Throughput Statistics Hourly Archived Reports
- APN Instance Miscellaneous Statistics Hourly Archived Reports
- APN Instance PDP/Bearer Statistics Hourly Archived Reports
- APN Instance PDP/Bearer Extended Statistics Hourly Archived Reports
- APN Instance Throughput Statistics Hourly Archived Reports
- EPC Gateway Protection Statistics Hourly Archived Reports

- EPC Gateway Buffering Statistics Hourly Archived Reports
- GTP Active Statistics Hourly Archived Reports
- GTP Error Statistics Hourly Archived Reports
- GTP Path Errors Hourly Archived Reports
- GTP PDP/Bearer Statistics Hourly Archived Reports
- GTP Throughput Statistics Hourly Archived Reports
- GTP Path Throughput Statistics Hourly Archived Reports
- GTP Path PDP Miscellaneous Statistics Hourly Archived Reports
- GTP Charging Statistics Hourly Archived Reports
- GTPv2 Bearer Statistics Hourly Archived Reports
- GTPv2 Session Statistics Hourly Archived Reports
- GTPv2 Path Bearer Requests Statistics Hourly Archived Reports
- GTPv2 Path Bearer Responses Statistics Hourly Archived Reports
- GTPv2 Path Session Statistics Hourly Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly network statistics for all application servers that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### PDNGW Daily Archived Reports

The PDNGW Daily Archived Reports page shows summary reports for all archived MWTM daily statistics. MWTM creates the following PDNGW daily archived report files for each day:

- APN Aggregate Miscellaneous Statistics Daily Archived Reports
- APN Aggregate PDP/Bearer Statistics Daily Archived Reports
- APN Aggregate PDP/Bearer Extended Statistics Daily Archived Reports
- APN Aggregate Throughput Statistics Daily Archived Reports
- APN Instance Miscellaneous Statistics Daily Archived Reports
- APN Instance PDP/Bearer Statistics Daily Archived Reports
- APN Instance PDP/Bearer Extended Statistics Daily Archived Reports
- APN Instance Throughput Statistics Daily Archived Reports
- EPC Gateway Protection Statistics Daily Archived Reports
- EPC Gateway Buffering Statistics Daily Archived Reports
- GTP Active Statistics Daily Archived Reports
- GTP Error Statistics Daily Archived Reports
- GTP Path Errors Daily Archived Reports
- GTP PDP/Bearer Statistics Daily Archived Reports
- GTP Throughput Statistics Daily Archived Reports
- GTP Path Throughput Statistics Daily Archived Reports



- GTP Path PDP Miscellaneous Statistics Daily Archived Reports
- GTP Charging Statistics Daily Archived Reports
- GTPv2 Bearer Statistics Daily Archived Reports
- GTPv2 Session Statistics Daily Archived Reports
- GTPv2 Path Bearer Requests Statistics Daily Archived Reports
- GTPv2 Path Bearer Responses Statistics Daily Archived Reports
- GTPv2 Path Session Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily network statistics for all application servers that the MWTM detects on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## PDSN Archived Reports

You can access the following PDSN Archived Reports:

- [PDSN 15 Minute Archived Reports, page 13-369](#)
- [PDSN Hourly Archived Reports, page 13-369](#)
- [PDSN Daily Archived Reports, page 13-370](#)

### PDSN 15 Minute Archived Reports

The PDSN 15 Minute Archived Reports page shows summary reports of 15-minute statistical details of the PDSN. The MWTM creates the following PDSN 15 minute archived report files for every 15 minutes:

- PDSN Session Statistics 15 Minute Archived Reports
- PDSN Session Bandwidth Statistics 15 Minute Archived Reports
- PDSN Flow Statistics 15 Minute Archived Reports
- PDSN Flow Extended Statistics 15 Minute Archived Reports
- PDSN Packet Control Function Statistics 15 Minute Archived Reports
- PDSN Traffic Statistics 15 Minute Archived Reports
- PDSN Traffic Extended Statistics 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15-minute PDSN statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PDSN Hourly Archived Reports

The PDSN Hourly Archived Reports page shows summary reports of hourly statistical details of the PDSN. MWTM creates the following PDSN hourly archived reports every hour:

- PDSN Session Statistics Hourly Archived Reports

- PDSN Session Bandwidth Statistics Hourly Archived Reports
- PDSN Flow Statistics Hourly Archived Reports
- PDSN Flow Extended Statistics Hourly Archived Reports
- PDSN Packet Control Function Statistics Hourly Archived Reports
- PDSN Traffic Statistics Hourly Archived Reports
- PDSN Traffic Extended Statistics Hourly Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly PDSN statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PDSN Daily Archived Reports

The PDSN Daily Archived Reports page shows summary reports of daily statistical details of the PDSN. MWTM creates the following PDSN daily archived reports each day:

- PDSN Session Statistics Daily Archived Reports
- PDSN Session Bandwidth Statistics Daily Archived Reports
- PDSN Flow Statistics Daily Archived Reports
- PDSN Flow Extended Statistics Daily Archived Reports
- PDSN Packet Control Function Statistics Daily Archived Reports
- PDSN Traffic Statistics Daily Archived Reports
- PDSN Traffic Extended Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily PDSN statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### SGW Archived Reports

You can access these reports

- [SGW 15 Minute Archived Reports, page 13-370](#)
- [SGW Hourly Archived Reports, page 13-371](#)
- [SGW Daily Archived Reports, page 13-372](#)

### SGW 15 Minute Archived Reports

The 15 minute SGW Archived Reports page shows summary reports of all archived MWTM 15 minute SGW statistics. MWTM creates the following SGW 15 Minute archived report files for every 15 Minutes:

- APN Aggregate Bearer Statistics 15 Minute Archived Reports
- APN Aggregate Throughput Statistics 15 Minute Archived Reports
- APN Instance Bearer Statistics 15 Minute Archived Reports
- APN Instance Throughput Statistics 15 Minute Archived Reports

- EPC Gateway Protection Statistics 15 Minute Archived Reports
- EPC Gateway Buffering Statistics 15 Minute Archived Reports
- GTP Active Statistics 15 Minute Archived Reports
- GTP Error Statistics 15 Minute Archived Reports
- GTP Path Errors 15 Minute Archived Reports
- GTP Bearer Statistics 15 Minute Archived Reports
- GTP Throughput Statistics 15 Minute Archived Reports
- GTP Path Throughput Statistics 15 Minute Archived Reports
- GTP Path PDP Miscellaneous Statistics 15 Minute Archived Reports
- GTP Charging Statistics 15 Minute Archived Reports
- GTPv2 Bearer Statistics 15 Minute Archived Reports
- GTPv2 Session Statistics 15 Minute Archived Reports
- GTPv2 Path Bearer Requests Statistics 15 Minute Archived Reports
- GTPv2 Path Bearer Responses Statistics 15 Minute Archived Reports
- GTPv2 Path Session Statistics 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute network statistics for all application servers that the MWTM detects on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### SGW Hourly Archived Reports

The Hourly SGW Archived Reports page shows all summary reports for archived MWTM hourly statistics. MWTM creates the following SGW hourly archived report files for each hour:

- APN Aggregate Bearer Statistics Hourly Archived Reports
- APN Aggregate Throughput Statistics Hourly Archived Reports
- APN Instance Bearer Statistics Hourly Archived Reports
- APN Instance Throughput Statistics Hourly Archived Reports
- EPC Gateway Protection Statistics Hourly Archived Reports
- EPC Gateway Buffering Statistics Hourly Archived Reports
- GTP Active Statistics Hourly Archived Reports
- GTP Error Statistics Hourly Archived Reports
- GTP Path Errors Hourly Archived Reports
- GTP Bearer Statistics Hourly Archived Reports
- GTP Throughput Statistics Hourly Archived Reports
- GTP Path Throughput Statistics Hourly Archived Reports
- GTP Path PDP Miscellaneous Statistics Hourly Archived Reports
- GTP Charging Statistics Hourly Archived Reports
- GTPv2 Bearer Statistics Hourly Archived Reports

- GTPv2 Session Statistics Hourly Archived Reports
- GTPv2 Path Bearer Requests Statistics Hourly Archived Reports
- GTPv2 Path Bearer Responses Statistics Hourly Archived Reports
- GTPv2 Path Session Statistics Hourly Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly network statistics for all application servers that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## SGW Daily Archived Reports

The SGW Daily Archived Reports page shows summary reports for all archived MWTM daily statistics. MWTM creates the following SGW daily archived report files for each day:

- APN Aggregate Bearer Statistics Daily Archived Reports
- APN Aggregate Throughput Statistics Daily Archived Reports
- APN Instance Bearer Statistics Daily Archived Reports
- APN Instance Throughput Statistics Daily Archived Reports
- EPC Gateway Protection Statistics Daily Archived Reports
- EPC Gateway Buffering Statistics Daily Archived Reports
- GTP Active Statistics Daily Archived Reports
- GTP Error Statistics Daily Archived Reports
- GTP Path Errors Daily Archived Reports
- GTP Bearer Statistics Daily Archived Reports
- GTP Throughput Statistics Daily Archived Reports
- GTP Path Throughput Statistics Daily Archived Reports
- GTP Path PDP Miscellaneous Statistics Daily Archived Reports
- GTP Charging Statistics Daily Archived Reports
- GTPv2 Bearer Statistics Daily Archived Reports
- GTPv2 Session Statistics Daily Archived Reports
- GTPv2 Path Bearer Requests Statistics Daily Archived Reports
- GTPv2 Path Bearer Responses Statistics Daily Archived Reports
- GTPv2 Path Session Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily network statistics for all application servers that the MWTM detects on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## SLB Archived Reports

The SLB archived reports shows all the archived MWTM reports for the server to which you connected.

You can access these reports:

- [SLB 15 Minute Archived Reports, page 13-373](#)
- [SLB Hourly Archived Reports, page 13-373](#)
- [SLB Daily Archived Reports, page 13-373](#)

### SLB 15 Minute Archived Reports

The 15 Minute SLB Archived Reports page shows all archived MWTM SLB 15 minute reports for the server to which you connect, stored as downloadable *.zip* files. MWTM creates the following SLB15 Minute archived report files for every 15 minutes:

- SLB Global Statistics 15 Minute Archived Reports
- SLB Real Server Statistics 15 Minute Archived Reports
- SLB Virtual Server Statistics 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly SLB statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### SLB Hourly Archived Reports

The SLB Hourly Archived Reports page shows the summary reports of all archived MWTM hourly SLB statistic. MWTM creates the following SLB hourly archived report files for each hour:

- SLB Global Statistics Hourly Archived Reports
- SLB Real Server Statistics Hourly Archived Reports
- SLB Virtual Server Statistics Hourly Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly SLB statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### SLB Daily Archived Reports

The SLB Daily Archived Reports page shows summary reports of all archived MWTM daily SLB statistics. MWTM creates the following SLB daily archived report files each day:

- SLB Global Statistics Daily Archived Reports
- SLB Real Server Statistics Daily Archived Reports
- SLB Virtual Server Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly SLB statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## SPGW Archived Reports

You can access these reports

- [SPGW 15 Minute Archived Reports, page 13-374](#)
- [SPGW Hourly Archived Reports, page 13-375](#)
- [SPGW Daily Archived Reports, page 13-376](#)

**Note**

GTP Path PDP Miscellaneous Statistics is splitted into following SPGW GUI reports:

- GTP Path PDP Roaming Statistics
- GTP Path PDP Statistics
- GTP Path PDP Update Statistics
- GTP Path PDP Version Statistics
- GTP Path PDP Miscellaneous Statistics

## SPGW 15 Minute Archived Reports

The 15 minute SPGW Archived Reports page shows summary reports of all archived MWTM 15 minute SPGW statistics. MWTM creates the following SPGW 15 Minute archived report files for every 15 Minutes:

- APN Aggregate Miscellaneous Statistics 15 Minute Archived Reports
- APN Aggregate PDP/Bearer Statistics 15 Minute Archived Reports
- APN Aggregate PDP/Bearer Extended Statistics 15 Minute Archived Reports
- APN Instance Miscellaneous Statistics 15 Minute Archived Reports
- APN Instance PDP/Bearer Statistics 15 Minute Archived Reports
- APN Instance PDP/Bearer Extended Statistics 15 Minute Archived Reports
- APN Aggregate Bearer Statistics 15 Minute Archived Reports
- APN Aggregate Throughput Statistics 15 Minute Archived Reports
- APN Instance Bearer Statistics 15 Minute Archived Reports
- APN Instance Throughput Statistics 15 Minute Archived Reports
- EPC Gateway Protection Statistics 15 Minute Archived Reports
- EPC Gateway Session Statistics 15 Minute Archived Reports
- EPC Gateway Buffering Statistics 15 Minute Archived Reports
- GTP Active Statistics 15 Minute Archived Reports
- GTP Error Statistics 15 Minute Archived Reports
- GTP Path Errors 15 Minute Archived Reports
- GTP PDP/Bearer Statistics 15 Minute Archived Reports
- GTP Throughput Statistics 15 Minute Archived Reports
- GTP Path Throughput Statistics 15 Minute Archived Reports
- GTP Path PDP Miscellaneous Statistics 15 Minute Archived Reports
- GTP Path Data PDU Statistics 15 Minute Archived Reports
- GTP Charging Statistics 15 Minute Archived Reports
- GTPv2 Bearer Statistics 15 Minute Archived Reports
- GTPv2 Bearer Command Statistics 15 Minute Archived Reports

- GTPv2 Session Statistics 15 Minute Archived Reports
- GTPv2 Path Bearer Requests Statistics 15 Minute Archived Reports
- GTPv2 Path Bearer Responses Statistics 15 Minute Archived Reports
- GTPv2 Path Session Statistics 15 Minute Archived Reports
- GTPv2 Downlink Statistics 15 Minute Archived Reports
- GTPv2 Tunnel Statistics 15 Minute Archived Reports
- GTPv2 Notification Statistics 15 Minute Archived Reports
- GTPv2 Echo Statistics 15 Minute Archived Reports
- GTPv2 Miscellaneous Statistics 15 Minute Archived Reports
- Gateway Charging Group Statistics 15 Minute Archived Reports
- APN Instance DHCP V6 Proxy Server Statistics 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute network statistics for all application servers that the MWTM detects on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### SPGW Hourly Archived Reports

The Hourly SPGW Archived Reports page shows all summary reports for archived MWTM hourly statistics. MWTM creates the following SPGW hourly archived report files for each hour:

- APN Aggregate Miscellaneous Statistics Hourly Archived Reports
- APN Aggregate PDP/Bearer Statistics Hourly Archived Reports
- APN Aggregate PDP/Bearer Extended Statistics Hourly Archived Reports
- APN Instance Miscellaneous Statistics Hourly Archived Reports
- APN Instance PDP/Bearer Statistics Hourly Archived Reports
- APN Instance PDP/Bearer Extended Statistics Hourly Archived Reports
- APN Aggregate Bearer Statistics Hourly Archived Reports
- APN Aggregate Throughput Statistics Hourly Archived Reports
- APN Instance Bearer Statistics Hourly Archived Reports
- APN Instance Throughput Statistics Hourly Archived Reports
- EPC Gateway Protection Statistics Hourly Archived Reports
- EPC Gateway Session Statistics Hourly Archived Reports
- EPC Gateway Buffering Statistics Hourly Archived Reports
- GTP Active Statistics Hourly Archived Reports
- GTP Error Statistics Hourly Archived Reports
- GTP Path Errors Hourly Archived Reports
- GTP PDP/Bearer Statistics Hourly Archived Reports
- GTP Throughput Statistics Hourly Archived Reports
- GTP Path Throughput Statistics Hourly Archived Reports

- GTP Path PDP Miscellaneous Statistics Hourly Archived Reports
- GTP Path Data PDU Statistics Hourly Archived Reports
- GTP Charging Statistics Hourly Archived Reports
- GTPv2 Bearer Statistics Hourly Archived Reports
- GTPv2 Bearer Command Statistics Hourly Archived Reports
- GTPv2 Session Statistics Hourly Archived Reports
- GTPv2 Path Bearer Requests Statistics Hourly Archived Reports
- GTPv2 Path Bearer Responses Statistics Hourly Archived Reports
- GTPv2 Path Session Statistics Hourly Archived Reports
- GTPv2 Downlink Statistics Hourly Archived Reports
- GTPv2 Tunnel Statistics Hourly Archived Reports
- GTPv2 Notification Statistics Hourly Archived Reports
- GTPv2 Echo Statistics Hourly Archived Reports
- GTPv2 Miscellaneous Statistics Hourly Archived Reports
- Gateway Charging Group Statistics Hourly Archived Reports
- APN Instance DHCP V6 Proxy Server Statistics Hourly Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly network statistics for all application servers that the MWTM detected on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### SPGW Daily Archived Reports

The SPGW Daily Archived Reports page shows summary reports for all archived MWTM daily statistics. MWTM creates the following SPGW daily archived report files for each day:

- APN Aggregate Miscellaneous Statistics Daily Archived Reports
- APN Aggregate PDP/Bearer Statistics Daily Archived Reports
- APN Aggregate PDP/Bearer Extended Statistics Daily Archived Reports
- APN Instance Miscellaneous Statistics Daily Archived Reports
- APN Instance PDP/Bearer Statistics Daily Archived Reports
- APN Instance PDP/Bearer Extended Statistics Daily Archived Reports
- APN Aggregate Bearer Statistics Daily Archived Reports
- APN Aggregate Throughput Statistics Daily Archived Reports
- APN Instance Bearer Statistics Daily Archived Reports
- APN Instance Throughput Statistics Daily Archived Reports
- EPC Gateway Protection Statistics Daily Archived Reports
- EPC Gateway Session Statistics Daily Archived Reports
- EPC Gateway Buffering Statistics Daily Archived Reports
- GTP Active Statistics Daily Archived Reports



- GTP Error Statistics Daily Archived Reports
- GTP Path Errors Daily Archived Reports
- GTP PDP/Bearer Statistics Daily Archived Reports
- GTP Throughput Statistics Daily Archived Reports
- GTP Path Throughput Statistics Daily Archived Reports
- GTP Path PDP Miscellaneous Statistics Daily Archived Reports
- GTP Path Data PDU Statistics Daily Archived Reports
- GTP Charging Statistics Daily Archived Reports
- GTPv2 Bearer Statistics Daily Archived Reports
- GTPv2 Bearer Command Statistics Daily Archived Reports
- GTPv2 Session Statistics Daily Archived Reports
- GTPv2 Path Bearer Requests Statistics Daily Archived Reports
- GTPv2 Path Bearer Responses Statistics Daily Archived Reports
- GTPv2 Path Session Statistics Daily Archived Reports
- GTPv2 Downlink Statistics Daily Archived Reports
- GTPv2 Tunnel Statistics Daily Archived Reports
- GTPv2 Notification Statistics Daily Archived Reports
- GTPv2 Echo Statistics Daily Archived Reports
- GTPv2 Miscellaneous Statistics Daily Archived Reports
- Gateway Charging Group Statistics Daily Archived Reports
- APN Instance DHCP V6 Proxy Server Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily network statistics for all application servers that the MWTM detects on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Viewing File Archive RAN Statistics Reports

RAN Reports that have been archived are located within **File Archive > RAN Statistics** in the MWTM web interface. You can also find archived reports in the */opt/CSCOsgm/reports* directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in *.csv* format.

You can view full descriptions of all fields in export file archive reports by clicking **Administrative** from the MWTM web interface, then clicking **Export Reports README** under System Information.

You can view any of the following RAN archived reports:

- [Ethernet Archived Reports, page 13-378](#)
- [PWE3 Archived Reports, page 13-378](#)
- [QOS Archived Reports, page 13-379](#)
- [RAN-Optimized Archived Reports, page 13-380](#)

## Ethernet Archived Reports

The Ethernet archived reports shows all the archived MWTM reports for the server to which you connected.

You can access these reports:

- [Ethernet Statistics 15 Minute Archived Reports, page 13-378](#)
- [Ethernet Statistics Hourly Archived Reports, page 13-378](#)
- [Ethernet Statistics Daily Archived Reports, page 13-378](#)

### Ethernet Statistics 15 Minute Archived Reports

The Ethernet Statistics 15 Minute Archived Reports page shows summary reports of 15-minute statistical details of the Ethernet.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15-minute Ethernet statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### Ethernet Statistics Hourly Archived Reports

The Ethernet Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the Ethernet.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly Ethernet statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### Ethernet Statistics Daily Archived Reports

The Ethernet Statistics Daily Archived Reports page shows summary reports of daily statistical details of the Ethernet.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily Ethernet statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## PWE3 Archived Reports

The PWE3 archived reports shows all the archived MWTM reports for the server to which you connected.



---

**Note** PWE3 reports are available for IPRAN platforms with PWE3 data tunnels configured only. All other RAN reports are available for RAN-O platforms only.

---

You can access these reports:

- [PWE3 Performance 15 Minute Archived Reports, page 13-379](#)

- [PWE3 Performance Hourly Archived Reports, page 13-379](#)
- [PWE3 Performance Daily Archived Reports, page 13-379](#)

### PWE3 Performance 15 Minute Archived Reports

The PWE3 Performance 15 Minute Archived Reports page shows summary reports of 15-minute statistical details of the PWE3 performance.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15-minute PWE3 Performance statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PWE3 Performance Hourly Archived Reports

The PWE3 Performance Hourly Archived Reports page shows summary reports of hourly statistical details of the PWE3 Performance.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly PWE3 Performance statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PWE3 Performance Daily Archived Reports

The PWE3 Performance Daily Archived Reports page shows summary reports of daily statistical details of the PWE3 performance.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily PWE3 Performance statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## QOS Archived Reports

The QOS archived reports shows all the archived MWTM reports for the server to which you connected.

You can access these reports:

- [QOS 15 Minute Archived Reports, page 13-379](#)
- [QOS Hourly Archived Reports, page 13-380](#)
- [QOS Daily Archived Reports, page 13-380](#)

### QOS 15 Minute Archived Reports

The 15 Minute QOS Archived Reports page shows all archived MWTM QOS 15 minute reports for the server to which you connect, stored as downloadable *.zip* files. MWTM creates the following QOS 15 Minute archived report files for every 15 minutes:

- QOS Class Map Statistics 15 Minute Archived Reports
- QOS Match Statement Statistics 15 Minute Archived Reports

- QOS Packet Marking Statistics 15 Minute Archived Reports
- QOS Policing Statistics 15 Minute Archived Reports
- QOS Queuing Statistics 15 Minute Archived Reports
- QOS Traffic Shaping Statistics 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute QOS statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### QOS Hourly Archived Reports

The Hourly QOS Archived Reports page shows all archived MWTM QOS hourly reports for the server to which you connect, stored as downloadable *.zip* files. MWTM creates the following QOS hourly archived report files for every hour:

- QOS Class Map Statistics Hourly Archived Reports
- QOS Match Statement Statistics Hourly Archived Reports
- QOS Packet Marking Statistics Hourly Archived Reports
- QOS Policing Statistics Hourly Archived Reports
- QOS Queuing Statistics Hourly Archived Reports
- QOS Traffic Shaping Statistics Hourly Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly QOS statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### QOS Daily Archived Reports

The daily QOS Archived Reports page shows all archived MWTM QOS daily reports for the server to which you connect, stored as downloadable *.zip* files. MWTM creates the following QOS daily archived report files each day:

- QOS Class Map Statistics Daily Archived Reports
- QOS Match Statement Statistics Daily Archived Reports
- QOS Packet Marking Statistics Daily Archived Reports
- QOS Policing Statistics Daily Archived Reports
- QOS Queuing Statistics Daily Archived Reports
- QOS Traffic Shaping Statistics Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily QOS statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

### RAN-Optimized Archived Reports

The QOS archived reports shows all the archived MWTM reports for the server to which you connected.

You can access these reports:

- [RAN-Optimized 15 Minute Archived Reports, page 13-381](#)
- [RAN-Optimized Hourly Archived Reports, page 13-381](#)
- [RAN-Optimized Daily Archived Reports, page 13-381](#)

### RAN-Optimized 15 Minute Archived Reports

The 15 Minute RAN-Optimized Archived Reports page shows all archived MWTM RAN-Optimized 15 minute reports for the server to which you connect, stored as downloadable *.zip* files. MWTM creates the following RAN-Optimized 15 Minute archived report files for every 15 minutes:

- RAN-O Backhaul Statistics 15 Minute Archived Reports
- RAN-O Congestion Statistics 15 Minute Archived Reports
- RAN-O GSM Errors 15 Minute Archived Reports
- RAN-O Shorthaul Performance 15 Minute Archived Reports
- RAN-O UMTS Errors 15 Minute Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15 minute RAN-Optimized statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### RAN-Optimized Hourly Archived Reports

The Hourly RAN-Optimized Archived Reports page shows all archived MWTM RAN-Optimized hourly reports for the server to which you connect, stored as downloadable *.zip* files. MWTM creates the following RAN-Optimized hourly archived report files for every hour:

- RAN-O Backhaul Statistics Hourly Archived Reports
- RAN-O Congestion Statistics Hourly Archived Reports
- RAN-OGSM Errors Hourly Archived Reports
- RAN-O Shorthaul Performance Hourly Archived Reports
- RAN-O UMTS Errors Hourly Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly RAN-Optimized statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### RAN-Optimized Daily Archived Reports

The daily RAN-Optimized Archived Reports page shows all archived MWTM RAN-Optimized daily reports for the server to which you connect, stored as downloadable *.zip* files. MWTM creates the following RAN-Optimized daily archived report files each day:

- RAN-O Backhaul Statistics Daily Archived Reports
- RAN-O Congestion Statistics Daily Archived Reports
- RAN-OGSM Errors Daily Archived Reports

- RAN-O Shorthaul Daily Archived Reports
- RAN-O UMTS Errors Daily Archived Reports

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily RAN-Optimized statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, click a filename, then save the file to a location of your choice. You can also import the file directly into Microsoft Excel.

## Viewing File Archive ITP Accounting Reports

ITP Accounting Reports that have been archived are located within **File Archive > ITP Accounting** in the MWTM web interface. You can also find archived reports in the */opt/CSCOs/gm/reports* directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in *.csv* format.

You can view full descriptions of all fields in export file archive reports by clicking **Administrative** from the MWTM web interface, then clicking **Export Reports README** under System Information.

You can view any of the following ITP Accounting archived reports:

- [GTT Accounting Archived Reports, page 13-382](#)
- [MTP3/AS Accounting Archived Reports, page 13-383](#)

## GTT Accounting Archived Reports

The GTT accounting archived reports shows all the archived MWTM reports for the server to which you connected. You can access these reports:

- [GTT Accounting Daily Archived Reports, page 13-382](#)
- [GTT Accounting Custom Archived Reports, page 13-382](#)

### GTT Accounting Daily Archived Reports

The GTT Accounting Daily Archived Reports page shows summary reports of daily statistical details of the GTT Accounting Daily Reports.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily GTT accounting statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### GTT Accounting Custom Archived Reports

The GTT Accounting Custom Archived Reports page shows summary reports of daily statistical details of the GTT accounting custom reports.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily GTT accounting custom statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## MTP3/AS Accounting Archived Reports

The MTP3/AS Accounting archived reports shows all the archived MWTM reports for the server to which you connected. You can access these reports:

- [MTP3/AS Accounting Daily Archived Reports, page 13-383](#)
- [MTP3/AS Accounting Custom Archived Reports, page 13-383](#)

### MTP3/AS Accounting Daily Archived Reports

The MTP3/AS Accounting Daily Archived Reports page shows summary reports of daily statistical details of the MTP3/AS Accounting Daily Reports.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily MTP3/AS accounting statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### MTP3/AS Accounting Custom Archived Reports

The MTP3/AS Accounting Custom Archived Reports page shows summary reports of daily statistical details of the GTT accounting custom reports.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily MTP3/AS accounting custom statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## Viewing File Archive Mobile Subscribers Reports

Mobile Subscribers Reports that have been archived are located within **File Archive > Mobile Subscribers** in the MWTM web interface. You can also find archived reports in the */opt/CSCOsgm/reports* directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in *.csv* format.

You can view full descriptions of all fields in export file archive reports by clicking **Administrative** from the MWTM web interface, then clicking **Export Reports README** under System Information.

You can view the following Mobile Subscribers archived reports:

- [BWG Subscriber Statistics Archived Reports, page 13-384](#)
- [CSG Subscriber Statistics Archived Reports, page 13-385](#)
- [GGSN Subscriber Statistics Archived Reports, page 13-386](#)
- [HA Subscriber Statistics Archived Reports, page 13-387](#)
- [PDNGW Subscriber Statistics Archived Reports, page 13-388](#)
- [PDSN Subscriber Statistics Archived Reports, page 13-389](#)
- [SGW Subscriber Statistics Archived Reports, page 13-390](#)
- [SPGW Subscriber Statistics Archived Reports, page 13-391](#)

## BWG Subscriber Statistics Archived Reports

You can access the following BWG Subscribers Archived Reports:

- [BWG Subscriber Statistics 15 Minute Archived Reports, page 13-384](#)
- [BWG Subscriber Statistics Hourly Archived Reports, page 13-384](#)
- [BWG Subscriber Statistics Daily Archived Reports, page 13-384](#)
- [BWG Subscriber Statistics Monthly Archived Reports, page 13-384](#)

### BWG Subscriber Statistics 15 Minute Archived Reports

The BWG Subscriber Statistics 15 Minute Archived Reports page shows summary reports of 15 minutes statistical details of the BWG. The 15 Minute BWG Subscriber Statistics Archived Report has the filename `BWGSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly BWG Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### BWG Subscriber Statistics Hourly Archived Reports

The BWG Subscriber Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the BWG. The Hourly BWG Subscriber Statistics Archived Report has the filename `BWGSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly BWG Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### BWG Subscriber Statistics Daily Archived Reports

The BWG Subscriber Statistics Daily Archived Reports page shows summary reports of daily statistical details of the BWG. The Daily BWG Subscriber Statistics Archived Report has the filename `BWGSubsStats.year-month-day.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of daily BWG Subscriber statistics on that date. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### BWG Subscriber Statistics Monthly Archived Reports

The BWG Subscriber Statistics Monthly Archived Reports page shows summary reports of monthly statistical details of the BWG. The monthly BWG Subscriber Statistics Archived Report has the filename `BWGSubsStats.year-month.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of monthly BWG Subscriber statistics on that month. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.



## CSG Subscriber Statistics Archived Reports

You can access the following CSG Subscribers Archived Reports:

- [CSG Subscriber Statistics 15 Minute Archived Reports, page 13-385](#)
- [CSG Subscriber Statistics Hourly Archived Reports, page 13-385](#)
- [CSG Subscriber Statistics Daily Archived Reports, page 13-385](#)
- [CSG Subscriber Statistics Monthly Archived Reports, page 13-385](#)

### CSG Subscriber Statistics 15 Minute Archived Reports

The CSG Subscriber Statistics 15 Minute Archived Reports page shows summary reports of 15 Minute statistical details of the CSG. The 15 Minute CSG Subscriber Statistics Archived Report has the filename `CSGSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly CSG Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### CSG Subscriber Statistics Hourly Archived Reports

The CSG Subscriber Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the CSG. The Hourly CSG Subscriber Statistics Archived Report has the filename `CSGSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly CSG Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### CSG Subscriber Statistics Daily Archived Reports

The CSG Subscriber Statistics Daily Archived Reports page shows summary reports of daily statistical details of the CSG. The Daily CSG Subscriber Statistics Archived Report has the filename `CSGSubsStats.year-month-day.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of daily CSG Subscriber statistics on that date. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### CSG Subscriber Statistics Monthly Archived Reports

The CSG Subscriber Statistics Monthly Archived Reports page shows summary reports of monthly statistical details of the CSG. The monthly CSG Subscriber Statistics Archived Report has the filename `CSGSubsStats.year-month.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of monthly CSG Subscriber statistics on that month. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## GGSN Subscriber Statistics Archived Reports

You can access the following GGSN Subscribers Archived Reports:

- [GGSN Subscriber Statistics 15 Minute Archived Reports, page 13-386](#)
- [GGSN Subscriber Statistics Hourly Archived Reports, page 13-386](#)
- [GGSN Subscriber Statistics Daily Archived Reports, page 13-386](#)
- [GGSN Subscriber Statistics Monthly Archived Reports, page 13-386](#)

### GGSN Subscriber Statistics 15 Minute Archived Reports

The GGSN Subscriber Statistics 15 Minute Archived Reports page shows summary reports of 15 Minute statistical details of the GGSN. The 15 Minute GGSN Subscriber Statistics Archived Report has the filename `GGSNSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly GGSN Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### GGSN Subscriber Statistics Hourly Archived Reports

The GGSN Subscriber Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the GGSN. The Hourly GGSN Subscriber Statistics Archived Report has the filename `GGSNSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly GGSN Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### GGSN Subscriber Statistics Daily Archived Reports

The GGSN Subscriber Statistics Daily Archived Reports page shows summary reports of daily statistical details of the GGSN. The Daily GGSN Subscriber Statistics Archived Report has the filename `GGSNSubsStats.year-month-day.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of daily GGSN Subscriber statistics on that date. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### GGSN Subscriber Statistics Monthly Archived Reports

The GGSN Subscriber Statistics Monthly Archived Reports page shows summary reports of monthly statistical details of the GGSN. The monthly GGSN Subscriber Statistics Archived Report has the filename `GGSNSubsStats.year-month.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of monthly GGSN Subscriber statistics on that month. You can download the `.zip` files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## HA Subscriber Statistics Archived Reports

You can access the following HA Subscribers Archived Reports:

- [HA Subscriber Statistics 15 Minute Archived Reports, page 13-387](#)
- [HA Subscriber Statistics Hourly Archived Reports, page 13-387](#)
- [HA Subscriber Statistics Daily Archived Reports, page 13-387](#)
- [HA Subscriber Statistics Monthly Archived Reports, page 13-387](#)

### HA Subscriber Statistics 15 Minute Archived Reports

The HA Subscriber Statistics 15 Minute Archived Reports page shows summary reports of 15 Minute statistical details of the HA. The 15 Minute HA Subscriber Statistics Archived Report has the filename *HASubsStats.year-month-day-hour.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly HA Subscriber statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### HA Subscriber Statistics Hourly Archived Reports

The HA Subscriber Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the HA. The Hourly HA Subscriber Statistics Archived Report has the filename *HASubsStats.year-month-day-hour.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly HA Subscriber statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### HA Subscriber Statistics Daily Archived Reports

The HA Subscriber Statistics Daily Archived Reports page shows summary reports of daily statistical details of the HA. The Daily HA Subscriber Statistics Archived Report has the filename *HASubsStats.year-month-day.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily HA Subscriber statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### HA Subscriber Statistics Monthly Archived Reports

The HA Subscriber Statistics Monthly Archived Reports page shows summary reports of monthly statistical details of the HA. The monthly HA Subscriber Statistics Archived Report has the filename *HASubsStats.year-month.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of monthly HA Subscriber statistics on that month. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## PDNGW Subscriber Statistics Archived Reports

You can access the following PDNGW Subscribers Archived Reports:

- [PDNGW Subscriber Statistics 15 Minute Archived Reports, page 13-388](#)
- [PDNGW Subscriber Statistics Hourly Archived Reports, page 13-388](#)
- [PDNGW Subscriber Statistics Daily Archived Reports, page 13-388](#)
- [PDNGW Subscriber Statistics Monthly Archived Reports, page 13-388](#)

### PDNGW Subscriber Statistics 15 Minute Archived Reports

The PDNGW Subscriber Statistics 15 Minute Archived Reports page shows summary reports of 15 Minute statistical details of the PDNGW. The 15 Minute PDNGW Subscriber Statistics Archived Report has the filename *PDNGWSubsStats.year-month-day-hour.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly PDNGW Subscriber statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PDNGW Subscriber Statistics Hourly Archived Reports

The PDNGW Subscriber Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the PDNGW. The Hourly PDNGW Subscriber Statistics Archived Report has the filename *PDNGWSubsStats.year-month-day-hour.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly PDNGW Subscriber statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PDNGW Subscriber Statistics Daily Archived Reports

The PDNGW Subscriber Statistics Daily Archived Reports page shows summary reports of daily statistical details of the PDNGW. The Daily PDNGW Subscriber Statistics Archived Report has the filename *PDNGWSubsStats.year-month-day.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily PDNGW Subscriber statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PDNGW Subscriber Statistics Monthly Archived Reports

The PDNGW Subscriber Statistics Monthly Archived Reports page shows summary reports of monthly statistical details of the PDNGW. The monthly PDNGW Subscriber Statistics Archived Report has the filename *PDNGWSubsStats.year-month.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of monthly PDNGW Subscriber statistics on that month. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## PDSN Subscriber Statistics Archived Reports

You can access the following PDSN Subscribers Archived Reports:

- [PDSN Subscriber Statistics 15 Minute Archived Reports, page 13-389](#)
- [PDSN Subscriber Statistics Hourly Archived Reports, page 13-389](#)
- [PDSN Subscriber Statistics Daily Archived Reports, page 13-389](#)
- [PDSN Subscriber Statistics Monthly Archived Reports, page 13-390](#)

### PDSN Subscriber Statistics 15 Minute Archived Reports

The PDSN Subscriber Statistics 15 Minute Archived Reports page shows summary reports of 15 Minute statistical details of the PDSN. The 15 Minute PDSN Subscriber Statistics Archived Report has the filename *PDSNSubsStats.year-month-day-hour.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly PDSN Subscriber statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PDSN Subscriber Statistics Hourly Archived Reports

The PDSN Subscriber Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the PDSN. The Hourly PDSN Subscriber Statistics Archived Report has the filename *PDSNSubsStats.year-month-day-hour.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly PDSN Subscriber statistics on that date and hour. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### PDSN Subscriber Statistics Daily Archived Reports

The PDSN Subscriber Statistics Daily Archived Reports page shows summary reports of daily statistical details of the PDSN. The Daily PDSN Subscriber Statistics Archived Report has the filename *PDSNSubsStats.year-month-day.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily PDSN Subscriber statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## PDSN Subscriber Statistics Monthly Archived Reports

The PDSN Subscriber Statistics Monthly Archived Reports page shows summary reports of monthly statistical details of the PDSN. The monthly PDSN Subscriber Statistics Archived Report has the filename `PDSNSubsStats.year-month.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of monthly PDSN Subscriber statistics on that month. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## SGW Subscriber Statistics Archived Reports

You can access the following SGW Subscribers Archived Reports:

- [SGW Subscriber Statistics 15 Minute Archived Reports, page 13-390](#)
- [SGW Subscriber Statistics Hourly Archived Reports, page 13-390](#)
- [SGW Subscriber Statistics Daily Archived Reports, page 13-390](#)
- [SGW Subscriber Statistics Monthly Archived Reports, page 13-391](#)

### SGW Subscriber Statistics 15 Minute Archived Reports

The SGW Subscriber Statistics 15 Minute Archived Reports page shows summary reports of 15 Minute statistical details of the SGW. The 15 Minute SGW Subscriber Statistics Archived Report has the filename `SGWSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly SGW Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### SGW Subscriber Statistics Hourly Archived Reports

The SGW Subscriber Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the SGW. The Hourly SGW Subscriber Statistics Archived Report has the filename `SGWSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly SGW Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### SGW Subscriber Statistics Daily Archived Reports

The SGW Subscriber Statistics Daily Archived Reports page shows summary reports of daily statistical details of the SGW. The Daily SGW Subscriber Statistics Archived Report has the filename `SGWSubsStats.year-month-day.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of daily SGW Subscriber statistics on that date. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## SGW Subscriber Statistics Monthly Archived Reports

The SGW Subscriber Statistics Monthly Archived Reports page shows summary reports of monthly statistical details of the SGW. The monthly SGW Subscriber Statistics Archived Report has the filename `SGWSubsStats.year-month.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of monthly SGW Subscriber statistics on that month. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## SPGW Subscriber Statistics Archived Reports

You can access the following SPGW Subscribers Archived Reports:

- [SPGW Subscriber Statistics 15 Minute Archived Reports, page 13-391](#)
- [SPGW Subscriber Statistics Hourly Archived Reports, page 13-391](#)
- [SPGW Subscriber Statistics Daily Archived Reports, page 13-391](#)
- [SPGW Subscriber Statistics Monthly Archived Reports, page 13-392](#)

## SPGW Subscriber Statistics 15 Minute Archived Reports

The SPGW Subscriber Statistics 15 Minute Archived Reports page shows summary reports of 15 Minute statistical details of the SPGW. The 15 Minute SPGW Subscriber Statistics Archived Report has the filename `SPGWSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly SPGW Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## SPGW Subscriber Statistics Hourly Archived Reports

The SPGW Subscriber Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the SPGW. The Hourly SPGW Subscriber Statistics Archived Report has the filename `SPGWSubsStats.year-month-day-hour.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of hourly SPGW Subscriber statistics on that date and hour. You can download the `.zip` files and extract them.

To download a `.zip` file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## SPGW Subscriber Statistics Daily Archived Reports

The SPGW Subscriber Statistics Daily Archived Reports page shows summary reports of daily statistical details of the SPGW. The Daily SPGW Subscriber Statistics Archived Report has the filename `SPGWSubsStats.year-month-day.csv.zip`.

Each archived `.zip` file contains a comma-separated value (CSV) text file with a summary report of daily SPGW Subscriber statistics on that date. You can download the `.zip` files and extract them.



To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### SPGW Subscriber Statistics Monthly Archived Reports

The SPGW Subscriber Statistics Monthly Archived Reports page shows summary reports of monthly statistical details of the SPGW. The monthly SPGW Subscriber Statistics Archived Report has the filename *SPGWSubsStats.year-month.csv.zip*.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of monthly SPGW Subscriber statistics on that month. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## Viewing File Archive PCRF Reports

PCRF Reports that have been archived are located within **File Archive > PCRF** in the MWTM web interface. You can also find archived reports in the */opt/CSCOsgm/reports* directory on the MWTM server or an alternate location as configured by the MWTM system administrator. All archived reports are saved as export files in *.csv* format.

You can view full descriptions of all fields in export file archive reports by clicking **Administrative** from the MWTM web interface, then clicking **Export Reports README** under System Information.

You can view the following PCRF archived report:

- [Host Resources Statistics Reports, page 13-392](#)

### Host Resources Statistics Reports

You can access the following PCRF Archived Reports:

- [Host Resources Statistics 15 Minute Archived Reports, page 13-392](#)
- [Host Resources Statistics Hourly Archived Reports, page 13-392](#)
- [Host Resources Statistics Daily Archived Reports, page 13-393](#)

### Host Resources Statistics 15 Minute Archived Reports

The Host Resources Statistics 15 Minute Archived Reports page shows summary reports of 15-minute statistical details of the Host Resources.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of 15-minute Host Resources statistics on that date, hour, and minute. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### Host Resources Statistics Hourly Archived Reports

The Host Resources Statistics Hourly Archived Reports page shows summary reports of hourly statistical details of the Host Resources.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of hourly Host Resources statistics on that date and hour. You can download the *.zip* files and extract them.



To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

### Host Resources Statistics Daily Archived Reports

The Host Resources Statistics Daily Archived Reports page shows summary reports of daily statistical details of the Host Resources.

Each archived *.zip* file contains a comma-separated value (CSV) text file with a summary report of daily Host Resources statistics on that date. You can download the *.zip* files and extract them.

To download a *.zip* file, right-click a filename, then save the file to a location of your choice. You can also import the file into Microsoft Excel.

## Viewing the MWTM Statistics Reports Logs

You can view a log that contains all messages pertaining to MWTM reports, and a display of the current values of MWTM report parameters and timers.

This section contains this information:

- [Viewing the MWTM Report Log, page 13-393](#)
- [Viewing the MWTM Report Parameters and Timers, page 13-393](#)

### Viewing the MWTM Report Log

For details on viewing the MWTM report log, see [Viewing the Report Log, page 12-13](#).

### Viewing the MWTM Report Parameters and Timers

The Report Parameters and Timers page shows the current values of report parameters and timers for the server to which you connect, and which is currently running the MWTM server.

To access the Report Parameters and Timers page, you must run the **mwtm statrep** CLI command on the server. You can also see this information from the Administrative page of the MWTM web interface (**Administrative > General > Properties > Reports**).

Column	Description
AAAREports	Indicates whether the MWTM should generate AAA statistics reports. For more information, see the description of the <b>mwtm statreps [aaa   noaaa]</b> command in <a href="#">mwtm statreps, page B-81</a>
APNReports	Indicates whether the MWTM should APN reports. For more information, see the description of the <b>mwtm statreps [apn   noapn]</b> command in <a href="#">mwtm statreps, page B-81</a> .
AcctReports	Indicates whether the MWTM should generate MTP3 accounting statistics reports. For more information, see the description of the <b>mwtm statreps [acct   noacct]</b> command in <a href="#">mwtm statreps, page B-81</a> .
ChassisInventory	Indicates whether the MWTM should generate chassis inventory reports. For more information, see the description of the <b>mwtm statreps [chassisinventory   nochassisinventory]</b> command in <a href="#">mwtm statreps, page B-81</a> .

Column	Description
CPUReports	Indicates whether the MWTM should generate CPU statistics reports. For more information, see the description of the <b>mwtm statreps [ggsn   noggsn]</b> command in <a href="#">mwtm statreps, page B-81</a> .
CSGReports	Indicates whether the MWTM should generate CSG statistics reports. For more information, see the description of the <b>mwtm statreps [ggsn   noggsn]</b> command in <a href="#">mwtm statreps, page B-81</a> .
Custom Age	Indicates the maximum number of days the MWTM should archive custom network statistics reports. For more information, see the description of the <b>mwtm statreps custage</b> and <b>mwtm repcustage</b> commands in <a href="#">mwtm statreps, page B-81</a> .
Daily Age	Indicates the maximum number of days the MWTM should archive daily network statistics reports. For more information, see the description of the <b>mwtm statreps dailyage</b> command in <a href="#">mwtm statreps, page B-81</a> .
Daily CSV Age	Indicates the maximum number of days the MWTM should archive daily CSV reports. For more information, see the description of the <b>mwtm statreps dailycsvage</b> command in <a href="#">mwtm statreps, page B-81</a> .
DiskCheck	Indicates whether the MWTM should verify that a disk has at least 10 MB of space remaining before enabling network statistics reports. For more information, see the description of the <b>mwtm statreps [diskcheck   nodiskcheck]</b> command in <a href="#">mwtm statreps, page B-81</a> .
EPCReports	Indicates whether the MWTM should generate EPC reports. For more information, see the description of the <b>mwtm statreps [epc   noepc]</b> command in <a href="#">mwtm statreps, page B-81</a> .
ExportReports	Indicates whether the MWTM should generate network statistics reports in export format. For more information, see the description of the <b>mwtm statreps [export   noexport]</b> command in <a href="#">mwtm statreps, page B-81</a> .
GTPReports	Indicates whether the MWTM should generate GTP reports. For more information, see the description of the <b>mwtm statreps [gtp   nogtp]</b> command in <a href="#">mwtm statreps, page B-81</a> .
GTTRatesReports	Indicates whether the MWTM should generate GTT Rates statistics reports. For more information, see the description of the <b>mwtm statreps [gttrates   nogttrates]</b> command in <a href="#">mwtm statreps, page B-81</a> .
GTTReports	Indicates whether the MWTM should generate GTT accounting statistics reports. For more information, see the description of the <b>mwtm statreps [gtt   nogtt]</b> command in <a href="#">mwtm statreps, page B-81</a> .
HAReports	Indicates whether the MWTM should generate HA statistics reports. For more information, see the description of the <b>mwtm statreps [ha   noha]</b> command in <a href="#">mwtm statreps, page B-81</a> .
Hourly Age	Indicates the maximum number of days the MWTM should archive hourly network statistics reports. For more information, see the description of the <b>mwtm statreps hourlyage</b> command in <a href="#">mwtm statreps, page B-81</a> .
Hourly CSV Age	Indicates the maximum number of days the MWTM should archive hourly CSV reports. For more information, see the description of the <b>mwtm statreps hourlycsvage</b> command in <a href="#">mwtm statreps, page B-81</a> .

Column	Description
InterfaceReports	Indicates whether the MWTM should generate interface reports. For more information, see the description of the <b>mwtm statreps [interface   nointerface]</b> command in <a href="#">mwtm statreps, page B-81</a> .
Inventory Age	Indicates the maximum number of days the MWTM should archive inventory statistics reports. For more information, see the description of the <b>mwtm statreps invage</b> command in <a href="#">mwtm statreps, page B-81</a> .
IPLinks	<i>For ITP link and linkset reports only.</i> Indicates whether the MWTM should include links that use the Stream Control Transmission Protocol (SCTP) IP transport protocol in network statistics reports. For more information, see the description of the <b>mwtm statreps [iplinks   noiplinks]</b> command in <a href="#">mwtm statreps, page B-81</a> .
IpLocalPoolReports	Indicates whether the MWTM should generate IP Local Pool statistics reports. For more information, see the description of the <b>mwtm statreps [iplocalpool   noiplocalpool]</b> command in <a href="#">mwtm statreps, page B-81</a> .
LinkReports	Reports of ITP link and linkset statistics.
Max CSV Rows	Indicates the maximum number of rows the MWTM should include in export CSV files. For more information, see the description of the <b>mwtm statreps maxcsvrows</b> command in <a href="#">mwtm statreps, page B-81</a> .
MEMReports	Indicates whether the MWTM should generate Memory statistics reports. For more information, see the description of the <b>mwtm statreps [mem   nomem]</b> command in <a href="#">mwtm statreps, page B-81</a> .
MLRReports	Indicates whether the MWTM should generate MLR statistics reports. For more information, see the description of the <b>mwtm statreps [mlr   nomlr]</b> command in <a href="#">mwtm statreps, page B-81</a> .
Monthly Age	Indicates the maximum number of days the MWTM should archive monthly network statistics reports. For more information, see the description of the <b>mwtm statreps monthlyage</b> command in <a href="#">mwtm statreps, page B-81</a> .
Monthly CSV Age	Indicates the maximum number of days the MWTM should archive monthly CSV reports. For more information, see the description of the <b>mwtm statreps monthlycsvage</b> command in <a href="#">mwtm statreps, page B-81</a> .
MSUReports	Indicates whether the MWTM should generate MSU rates reports. For more information, see the description of the <b>mwtm statreps [msu   nomsu]</b> command in <a href="#">mwtm statreps, page B-81</a> .
NullCaps	Indicates whether the MWTM should include SCTP links that do not have planned send and receive capacities in network statistics reports. For more information, see the description of the <b>mwtm statreps [nullcaps   nonullcaps]</b> command in <a href="#">mwtm statreps, page B-81</a> .
Node Name Type	Indicates the name type for the Node column of the CSV reports.  The valid values are: <ul style="list-style-type: none"> <li>• DNS Name</li> <li>• Custom Name</li> <li>• Sys Name</li> </ul>



Column	Description
PDSNReports	Indicates whether the MWTM should generate PDSN statistics reports. For more information, see the description of the <b>mwtm statreps [pdsn   nopdsn]</b> command in <a href="#">mwtm statreps, page B-81</a> .
PWE3Reports	Indicates whether the MWTM should generate PWE3 statistics reports. For more information, see the description of the <b>mwtm statreps [pwe3   nopwe3]</b> command in <a href="#">mwtm statreps, page B-81</a> .
QOSReports	Indicates whether the MWTM should generate QOS statistics reports. For more information, see the description of the <b>mwtm statreps [qos   noqos]</b> command in <a href="#">mwtm statreps, page B-81</a> .
Q752Reports	Indicates whether the MWTM should generate Q752 reports. For more information, see the description of the <b>mwtm statreps [q752   noq752]</b> command in <a href="#">mwtm statreps, page B-81</a> .
RANOReports	Indicates whether the MWTM should generate RANO statistics reports. For more information, see the description of the <b>mwtm statreps [rano   norano]</b> command in <a href="#">mwtm statreps, page B-81</a> .
SCTPReports	Indicates whether the MWTM should generate SCTP statistics reports. For more information, see the description of the <b>mwtm statreps [sctp   nosctp]</b> command in <a href="#">mwtm statreps, page B-81</a> .
ServRatio	<p><i>For ITP link and linkset reports only.</i> In-Service values that are outside a normal range are indicated with a red status ball icon in the In-Service cell. An In-Service value is outside the normal range if the following condition is met:</p> <p style="text-align: center;"><b>Current In-Service &lt; factor * Long-Term In-Service</b></p> <p>This inequality is used to recognize drops in the In-Service value. Assuming the default factor of 0.95, the Current In-Service value must be greater than or equal to 95% of the Long-Term In-Service value to be in the normal range.</p> <p>For more information, see the description of the <b>mwtm statreps servratio</b> command in <a href="#">mwtm statreps, page B-81</a>.</p>
SLBReports	Indicates whether the MWTM should generate SLB statistics reports. For more information, see the description of the <b>mwtm statreps [slb   noslb]</b> command in <a href="#">mwtm statreps, page B-81</a> .
Status	Indicates whether the MWTM should generate network statistics reports. For more information, see the description of the <b>mwtm statreps [disable   enable]</b> command in <a href="#">mwtm statreps, page B-81</a> .
TimeMode	Indicates the time mode for dates in network statistics reports. For more information, see the description of the <b>mwtm statreps timemode [12   24]</b> command in <a href="#">mwtm statreps, page B-81</a> .
Timer files	Indicates timer activities during the last report run by the MWTM. The timer file is useful for identifying how much time the MWTM spends gathering report data and generating reports.

Column	Description
UtilRatio	<p><i>For ITP link and linkset reports only.</i> Values that are outside a normal range are indicated with a red status ball icon in the Send or Receive cell. A value is outside the normal range if the following condition is met:</p> <p style="text-align: center;"><b>Current &gt; factor * Long-Term</b></p> <p>This inequality is used to recognize increases in the value. Assuming the default factor of 1.5, the Current value must be less than or equal to 150% of the Long-Term value to be in the normal range.</p> <p>The default value for <i>factor</i> is <b>1.5</b>.</p> <p>For more information, see the description of the <b>mwtm statreps utilratio</b> command in <a href="#">mwtm statreps, page B-81</a>.</p>
Web Names	<p>Indicates whether the MWTM should show real node names or display names in web pages. For more information, see the description of the <b>mwtm webnames [display   real]</b> command in the <a href="#">mwtm webnames, page B-101</a>.</p>
Web Util	<p><i>For ITP link and linkset reports only.</i> Indicates whether the MWTM should display send and receive for linksets and links as percentages or in Erlangs (E), in web pages. For more information, see the description of the <b>mwtm webutil [percent   erlangs]</b> command in <a href="#">mwtm who, page B-103</a>.</p>
XUARports	<p>Indicates whether the MWTM should generate accounting statistics reports for application servers and application server processes. For more information, see the description of the <b>mwtm statreps [xua   noxua]</b> command in <a href="#">mwtm statreps, page B-81</a>.</p>
15 Min Age	<p>Indicates the maximum number of days the MWTM should archive 15 minute statistics reports. For more information, see the description of the <b>mwtm statreps 15minage</b> command in <a href="#">mwtm statreps, page B-81</a>.</p>
15 Min CSV Age	<p>Indicates the maximum number of days the MWTM should archive 15 minute CSV statistics reports. For more information, see the description of the <b>mwtm statreps 15mincsvage</b> command in <a href="#">mwtm statreps, page B-81</a>.</p>

## Viewing Graph Series Editor Details

The Graph Series Editor window allows you to select data series to show or hide. This window box is available when you select the report output as *Graph*. Most network-level reports contain more than 12 series.

The Graph Series Editor window contains:

Column or Buttons	Description
<b>Selected Series</b>	Displays the FQDN IDs for the data that is used to create the report.
<b>Available Series</b>	<p>Displays the list of available objects for this report.</p> <p><b>Note</b> If there are many objects in the report, the objects in the Available Series column span multiple pages and not all objects are shown on one page. See <a href="#">Using the Toolbar, page 11-6</a> for more information on using the paging features. To view all selected objects, sort the table by the Display column.</p>
<p>Display</p> <p><b>Note</b> Depending on the report type you select, other columns displayed will differ.</p>	<p>Column of check boxes that allow you to display (by checking) or hide (by unchecking) the data series associated with the chosen backhaul.</p> <p>The MWTM displays no more than 12 series by default. You can change this setting for the <a href="#">MWTM Client Display</a> or the <a href="#">MWTM Web Display</a>:</p> <p><b>MWTM Client Display</b></p> <p>To change the maximum number of data series that the MWTM client interface displays by default, edit the MAX_CHART_SERIES parameter in the client-side <i>System.properties</i> file:</p> <ul style="list-style-type: none"> <li>For the Windows client: <i>C:\Program Files\Cisco Systems\MWTM Client\properties\System.properties</i></li> <li>For Solaris or Linux client: <i>/opt/CSCOSgmClient/System.properties</i></li> </ul> <p></p> <p><b>Caution</b> Depending on the processing power and memory of your client system, setting the MAX_CHART_SERIES parameter too high can cause the client display to become unresponsive. If the client becomes unresponsive, set the MAX_CHART_SERIES to a lower value.</p> <p>Remember to restart the client to activate the new MAX_CHART_SERIES value.</p> <p><b>MWTM Web Display</b></p> <p>To change the maximum number of data series that the MWTM web interface displays by default, edit the MAX_CHART_SERIES parameter in the server-side <i>System.properties</i> file: <i>/opt/CSCOSgm/properties/System.properties</i>.</p> <p></p> <p><b>Caution</b> Depending on the number of shorthauls that you display, setting the MAX_CHART_SERIES parameter too high can cause the web display to become unresponsive. If the web become unresponsive, set the MAX_CHART_SERIES to a lower value.</p> <p>Remember to restart the client to activate the new MAX_CHART_SERIES value.</p>
Clear Selection	Deselects the selected list of series and then the <b>OK</b> button is grayed out. This is a simple way to deselect all the display check boxes.
OK	Applies the selections you made. If you deselect all items in the dialog box, the <b>OK</b> and <b>Clear Selection</b> buttons are grayed out.
Cancel	Cancels your selections and closes the Graph Series Editor window.
Help	Opens the help system for the Graph Series Editor window.

# Locating Stored Reports

The MWTM stores all reports in the report files directory on the */reports* directory. If you installed the MWTM in:

- The default directory, */opt*, then the default report files directory is */opt/CSCOs/gm/reports*.
- A different directory or used the **mwtm repdir** command to specify a new directory in which the MWTM should store report files, then the default report files directory resides in that directory.



## Note

For details on changing the default reports directory by using the **mwtm repdir** command, see [Changing the MWTM Reports Directory, page 13-399](#).

The */reports* directory contains these subdirectories:

Subdirectory	Description
<i>/custom</i>	Contains all custom report files. These are the report files that you generate using these commands: <b>mwtm accstats</b> , <b>mwtm gttstats</b> , <b>mwtm linkstats</b> , <b>mwtm mlrstats</b> , <b>mwtm mtpevents</b> , <b>mwtm q752stats</b> , and <b>mwtm xuastats</b>  <b>Note</b> A unique ID tag, specified when you enter the command, identifies each file. If the user does not specify an ID tag, the MWTM uses the process ID of the command.
<i>/etc</i>	Contains additional files that the MWTM reporting scripts and web pages use, including the <i>nodes.include</i> , <i>linksets.include</i> , <i>nodes.exclude</i> , <i>linksets.exclude</i> and <i>filter.include</i> files, if they exist.
<i>/export15min</i>	Contains all 15 minute report files exported in <i>csv.zip</i> format.
<i>/exportdaily</i>	Contains all daily report files exported in <i>csv.zip</i> format.
<i>/exporthourly</i>	Contains all hourly report files exported in <i>csv.zip</i> format.
<i>/exportmonthly</i>	Contains all monthly report files exported in <i>csv.zip</i> format.
<i>/exportrolling</i>	Contains all rolling report files for these statistics: <ul style="list-style-type: none"> <li>• Application server</li> <li>• Application server process</li> <li>• Link</li> <li>• Linkset</li> </ul> Files are edited and formatted for export and stored as <i>.zip</i> files in CSV format. The MWTM rebuilds the files in this subdirectory every hour.

## Changing the MWTM Reports Directory

On the server, you can change the directory in which the MWTM stores reports.

To change the MWTM report files directory, log in as the root user, as described in [Starting the MWTM Client, page 3-3](#); or, as a superuser, as described in [Specifying a Super User \(Server Only\), page 2-21](#), and enter:

```
# cd /opt/CSCOs/gm/bin
```

```
# ./mwtm repdir directory
```

where *directory* is the new directory.

**Note**

This command copies all files in the current directory to the new directory. If you log in as the superuser and you do not own the new directory, you might not be able to copy the files. In that case, you must specify a directory that you own or log in as the root user.

## Customizing ITP Reports

The following sections include information about generating and modifying ITP reports:

- [Generating Custom ITP Statistics Reports Using the CLI, page 13-400](#)
- [Including or Excluding Specified Objects in ITP Reports, page 13-402](#)

## Generating Custom ITP Statistics Reports Using the CLI

In the MWTM, you can use custom ITP CLI commands to create summary reports of custom ITP statistics and open them as an export file. To create a custom report:

- Step 1** Log in as the root user, as described in [Starting the MWTM Client, page 3-3](#), or as a superuser, as described in [Specifying a Super User \(Server Only\), page 2-21](#).
- Step 2** Enter:
- ```
# cd /opt/CSC0sgm/bin
```
- Step 3** Based on the type of custom report you want to generate, enter one of these commands to enable the report:

**Note**

For complete information about these commands, see [Appendix B, “Command Reference.”](#)

**Table 13-1 Custom Report Commands**

| Custom Report                                                         | Command        |
|-----------------------------------------------------------------------|----------------|
| Application server and application server processes custom statistics | mwtm xuastats  |
| GTT accounting statistics                                             | mwtm gttstats  |
| Link and linkset summary                                              | mwtm linkstats |
| MLR statistics                                                        | mwtm mlrstats  |
| MTP3 accounting statistics                                            | mwtm acstats   |
| MTP3 event summary                                                    | mwtm mtpevents |
| Q.752 statistics                                                      | mwtm q752stats |

For example, if you entered the command:



```
# ./mwtm accstats mwtm-2600a.cisco.com test1
```

where *test1* is name tag added to the file name to make it easier to find the report.

The MWTM generates these reports:

```
mwtmAccStats.custom.test1.2004-02-13:15.csv.zip
mwtmAccStats.custom.test1.2004-02-13:15.csv.zip
```

To generate a report for all nodes, do not specify a node name as shown in the following example:

```
# ./mwtm accstats
```

**Step 4** (Optional) To include or exclude specific nodes, signaling points or linksets in the report, see [NoteThe MWTM processes the include files first, then the exclude files.](#), page 13-402.

**Step 5** (First-time users only) If this is your first time using the **mwtm accstats**, **mwtm gttstats**, **mwtm mlrstats**, **mwtm mtpevents**, **mwtm q752stats**, or **mwtm xuastats** command to generate a custom ITP report, you must enter the command one more time. The:

- First entry gets the first set of raw data.
- Second entry begins calculating useful accounting statistics and, if the data being collected appears valid, begins generating the report.

or

If this is your first time using the **mwtm linkstats** command to generate a custom ITP report, you must enter the command two more times. The:

- First entry gets the first set of raw data.
- Second entry begins calculating useful link and linkset statistics.
- Third entry continues to calculate statistics, calculates long-term averages, and, if the data being collected appears to be valid, begins generating the report.

Thereafter, you need only enter these commands once to generate the ITP custom report.

**Step 6** (Optional) You can automate custom ITP report generation using crontab. For example, to run custom MTP3 accounting statistics every 30 minutes, enter:

```
00, 30 * * * * /opt/CSC0sgm/bin/mwtm accstats quiet
```

or, to run custom link statistics every 15 minutes, enter:

```
00,15,30,45 * * * * /opt/CSC0sgm/bin/mwtm linkstats quiet
```

**Step 7** You can view custom ITP reports on the MWTM Web interface under **File Archive > Reports > Custom**. Click on the respective link in the View column to see the data in HTML, or click on a *.zip* file to see the data in *.csv* format.



**Note** You can only view Q752 reports in *.csv* format.

The MWTM also stores custom reports in the */custom* directory (for details, see [Locating Stored Reports](#), page 13-399.)

## Including or Excluding Specified Objects in ITP Reports

You can include or exclude specific nodes, signaling points, or linksets in ITP reports by creating user-defined files. The nodes, signaling points, and/or linksets that you specify in these files will be included or excluded from enabled MWTM statistics reports and in custom reports enabled with the **default** keyword (or no *node-list* keyword at all), which include:

| Command        | Filename <sup>1</sup>                                  |
|----------------|--------------------------------------------------------|
| mwtm linkstats | nodes.include.linkstats or nodes.include               |
|                | nodes.exclude.linkstats or nodes.exclude               |
|                | linksets.include.linkstats or linkstats.include        |
|                | linksets.exclude.linkstats or linkstats.exclude        |
| mwtm q752stats | nodes.include.q752stats or nodes.include               |
|                | nodes.exclude.q752stats or nodes.exclude               |
|                | linksets.include.q752stats or linkstats.include        |
|                | linksets.exclude.q752stats or linkstats.exclude        |
| mwtm accstats  | nodes.include.accstats or nodes.include                |
|                | nodes.exclude.accstats or nodes.exclude                |
|                | linksets.include.accstats or linkstats.include         |
|                | linksets.exclude.accstats or linkstats.exclude         |
|                | filter.include.accstats or filter.include <sup>2</sup> |
| mwtm gttstats  | nodes.include.gttstats or nodes.include                |
|                | nodes.exclude.gttstats or nodes.exclude                |
|                | linksets.include.gttstats or linkstats.include         |
|                | linksets.exclude.gttstats or linkstats.exclude         |
|                | filter.include.gttstats or filter.include <sup>3</sup> |
| mwtm mtpevents | nodes.include.mtpevents or nodes.include               |
|                | nodes.exclude.mtpevents or nodes.exclude               |
| mwtm mlrstats  | nodes.include.mlrstats or nodes.include                |
|                | nodes.exclude.mlrstats or nodes.exclude                |
| mwtm xuastats  | nodes.include.xuastats or nodes.include                |
|                | nodes.exclude.xuastats or nodes.exclude                |

1. Files on the command line override system files. For example, nodes.include.accstats overrides nodes.include.

2. Format is opc:dpc (originating point code and destination point code).

3. Format is gta:sel (global title address and selector).



### Note

The MWTM processes the include files first, then the exclude files.

When creating user-defined files, remember that if you installed the MWTM in:

- The default directory, */opt*, then the user-defined file resides in */opt/CSCOSgm/reports/etc/<user-defined file>*.

A different directory, or if you moved the report files directory using the **mwtm repdir** command, then the */reports/etc/<user-defined file>* resides in that directory.

- Wildcard matching is not supported.
- If a node, signaling point, or linkset appears in both the *include* file and the *exclude* file, it is excluded. That is, excluding an object overrides including the same object.
- If you specify a special *include* file on the **mwtm accstats**, **mwtm gttstats**, **mwtm linkstats**, **mwtm mlrstats**, **mwtm mtpevents**, **mwtm q752stats**, or **mwtm xuastats** command, the MWTM ignores the *include* or *exclude* file.

When creating a *nodes.include* or *nodes.exclude* file:

Each line in the file must contain a single node name, or node name and signaling point name, separated by a colon (:) that matches exactly the real, fully qualified name of the node; for example:

```
mwtm-75-59a.cisco.com
mwtm-26-51a.cisco.com
```

To include a specific signaling point, specify the node name and signaling point:

```
mwtm-75-59a.cisco.com;net0
mwtm-26-51a.cisco.com;net0
```

When creating a *linksets.include* or *linksets.exclude* file:

Each line in the file must contain a single linkset name that matches exactly the real, fully qualified linkset name of the linkset, including the node name and signaling point name; for example:

```
mwtm-75-59a.cisco.com;net0:linkset2
mwtm-26-51a.cisco.com;net0:linkset1
```

When creating a *filter.include* file:

Each line in the file must contain a single originating point code and destination point code (for accounting statistics) that matches the current point code format; or a single phone number and selector name (for GTT statistics); for example:

```
1.2.3:5.6.7
8882214040:Selector_1
```

