



## CHAPTER 20

# Using Cisco Carrier Grade NAT Commands

---

Carrier Grade NAT is a large-scale Network Address Translation (NAT) that provides translation of millions of private IPv4 addresses to public IPv4 addresses. These translations support subscribers and content providers with a bandwidth throughput of at least 10 Gbps full-duplex.

Carrier Grade NAT addresses the IPv4 address completion problem. It employs Network Address and Port Translation (NAPT) to aggregate many private IPv4 addresses into fewer public IPv4 addresses. For example, a single public IPv4 address with a pool of 32,000 port numbers supports 320 individual private IP subscribers, assuming that each subscriber requires 100 ports. Carrier Grade NAT also offers a way to implement a graceful transition to IPv6 addresses.

Carrier Grade NAT attributes and instances are configured as a CRS-ADVSVC-PLIM card on Cisco CRS-1 routers. To route internal public addresses to external public addresses, a VPN Routing and Forwarding (VRF) instance is created. Interfaces are created for the VRF at the subscriber-side (private) and the Internet-side (public). The VRF enables static or dynamic routing of protocols on the interfaces.

Cisco Prime Network displays the following attributes in the logical inventory of the Cisco Prime Network Vision application:

- Carrier Grade NAT Instance Name — The Carrier Grade NAT instance name identifies the Carrier Grade NAT instance. Cisco Prime Network supports the following instances for Carrier Grade NAT:
  - Stateful Address Translation- NAT44 Stateful
  - Stateless Address Translation- NAT 64 Stateless (X-LAT)
  - IPv6 rapid deployment (6rd)

Each Carrier Grade NAT instance has several attributes listed under them. The attributes are grouped under related categories. The categories and attributes are listed below:

- Preferred Location
  - Preferred Location—Hyperlink to the card in physical inventory
  - Preferred Location—Alternate name for card location
  - Location Type—Configured type of location
  - Redundancy Status
  - Service Infra Interface—Hyperlink to routing entity in logical inventory
- Address Pools
  - Inside VRF—Hyperlink to inside VRF in logical inventory
  - Outside VRF—Hyperlink to outside VRF in logical inventory
  - Address Pool—Range of IP Addresses for the instance

- Address Family—Type of IP Address in this pool
- Associated Interfaces
  - Interface—SVI service-related hyperlink entry to logical inventory
- Statistics
  - Statistics Name
  - Statistics Value

## Supported Network Elements

You can run the Carrier Grade NAT commands on the following network element:

- Cisco CRS Series Routers

Cisco CRS series includes both the CRS-1 and CRS-3 Series Routers.

See Part 1—Cisco VNEs for details on the software versions Prime Network supports for these network elements. To run the Carrier Grade NAT commands, the software on the network element must support the Carrier Grade NAT technology.

The following commands facilitate the configuration of Carrier Grade NAT components:

- [Configuring Carrier Grade NAT Instance, page 20-2](#)
- [Removing a Carrier Grade NAT instance, page 20-3](#)
- [Displaying Pool Utilization, page 20-3](#)
- [Adding 6rd Forwarding, page 20-4](#)
- [Adding Carrier Grade Nat 64 Forwarding, page 20-5](#)

## Configuring Carrier Grade NAT Instance

Use the **Add Static Port Forwarding** command to add a Carrier Grade NAT instance to the device.

- 
- Step 1** In the inventory window, expand the Logical Inventory tree and Carrier Grade NAT node.
- Step 2** Right-click any Carrier Grade NAT instance and choose **Commands > Configure > Static Port Forwarding**.
- The Static Port Forwarding dialog box opens.
- Step 3** By default, the General tab is selected. Enter values for the following parameters.

Input Parameter	Description
Carrier Grade NAT Instance Name	Name of the Carrier Grade NAT instance.
Inside VRF Name	Name of the inside VPN routing and forwarding (VRF).
CGN Instance Name	Name of the CGN instance added under each Carrier Grade NAT Instance Name.
Address Family	Name of the IP address family. The default and only value is IPv4.

Input Parameter	Description
Protocol	Name of the protocol session. The values are TCP, UDP, or ICMP. The default value is TCP.
Address	Address of the inside VRF.
Port Number	Port number for the inside VRF. The range is from 1 to 65535.

- Step 4** To see the commands that will be applied on the device, click **Preview**.  
You can view the commands in the Result tab. You can go back and make any required changes to the input parameters.
- Step 5** To schedule the command, click the Scheduling tab. For more details on scheduling, see [Scheduling a Command](#).
- Step 6** To run the commands, click **Execute Now**.  
The newly added Carrier Grade NAT instance appears in the Carrier Grade NAT tree. Any errors are displayed in the Result tab.
- Step 7** To close the dialog box, click **Close**.

## Removing a Carrier Grade NAT instance

Use the **Static Port Forwarding** command to remove a Carrier Grade NAT instance from the device.

- Step 1** In the inventory window, expand the Logical Inventory tree and Carrier Grade NAT node.
- Step 2** Right-click the Carrier Grade NAT instance that you want to remove and choose **Commands > Delete > Static Port Forwarding**.
- Step 3** The Static Port Forwarding dialog box opens. By default, the General tab is selected.
- Step 4** To see the commands that will be applied on the device, click **Preview**.  
You can view the commands in the Result tab.
- Step 5** To schedule the command, click the Scheduling tab. For more details on scheduling, see [Scheduling a Command](#).
- Step 6** To run the commands, click **Execute Now**.  
The Carrier Grade NAT instance is no longer visible under the Carrier Grade NAT tree. Any errors are displayed in the Result tab.
- Step 7** To close the dialog box, click **Close**.

## Displaying Pool Utilization

Use the **Pool Utilization** command to view the ports that the Carrier Grade NAT instances use in the given address range.

- Step 1** In the inventory window, expand the Logical Inventory tree and Carrier Grade NAT node.
- Step 2** Right-click the Carrier Grade NAT instance and choose **Commands > Show > Pool Utilization**.  
The Pool Utilization dialog box opens.
- Step 3** By default, the General tab is selected. Enter values for the following parameters.

Input Parameter	Description
CGN Instance Name	Name of the CGN instance.
Inside VRF Name	Name of the inside VRF.
Start Address	Starting IPv4 address in the range.
End Address	Ending IPv4 address in the range.

- Step 4** To see the commands that will be applied on the device, click **Preview**.  
You can view the commands in the Result tab. You can go back and make any required changes to the input parameters.
- Step 5** To schedule the command, click the Scheduling tab. For more details on scheduling, see [Scheduling a Command](#).
- Step 6** To run the commands, click **Execute Now**.  
Any errors are displayed in the Result tab.
- Step 7** To close the dialog box, click **Close**.

## Adding 6rd Forwarding

Use the **Add 6rd Forwarding** command to add a 6rd forwarding.

- Step 1** In the inventory window, expand the Logical Inventory tree and Carrier Grade NAT node.
- Step 2** Right-click the Carrier Grade NAT instance and choose **Commands > Configure > Static Port Forwarding**.  
The Add 6rd Forwarding dialog box opens.
- Step 3** By default, the General tab is selected. Enter values for the following parameters.

Input Parameter	Description
CGN Instance Name	Name of the CGN instance.
6rd Name	Name of the 6rd instance.
ServiceAppipv4	Name of serviceApp Ipv4 interface.
ServiceAppipv6	Name of serviceApp Ipv6 interface.

- Step 4** To see the commands that will be applied on the device, click **Preview**.

You can view the commands in the Result tab. You can go back and make any required changes to the input parameters.

- Step 5** To schedule the command, click the Scheduling tab. For more details on scheduling, see [Scheduling a Command](#).
- Step 6** To run the commands, click **Execute Now**.  
Any errors are displayed in the Result tab.
- Step 7** To close the dialog box, click **Close**.
- 

## Adding Carrier Grade Nat 64 Forwarding

Use the **Add Nat 64 Forwarding** command to add a 6rd forwarding.

---

- Step 1** In the inventory window, expand the Logical Inventory tree and Carrier Grade NAT node.
- Step 2** Right-click the Carrier Grade NAT instance and choose **Commands > Configure > Static Port Forwarding**.  
The Add 6rd Forwarding dialog box opens.
- Step 3** By default, the General tab is selected. Enter values for the following parameters.

Input Parameter	Description
CGN Instance Name	Name of the CGN instance.
Nat 64 Name	Name of the Nat 64 instance.
ServiceAppipv4	Name of serviceApp Ipv4 interface.
ServiceAppipv6	Name of serviceApp Ipv6 interface.

- Step 4** To see the commands that will be applied on the device, click **Preview**.  
You can view the commands in the Result tab. You can go back and make any required changes to the input parameters.
- Step 5** To schedule the command, click the Scheduling tab. For more details on scheduling, see [Scheduling a Command](#).
- Step 6** To run the commands, click **Execute Now**.  
Any errors are displayed in the Result tab.
- Step 7** To close the dialog box, click **Close**.
-

