

# **Repository Views**

A view is a stored query accessible as a virtual table composed of the result set of a query. Unlike ordinary tables (base tables) in a relational database, a view does not form part of the physical schema; it is a dynamic and virtual table computed or collated from data in the database. Changing the data in a table alters the data shown in subsequent invocations of the view.

The advantages of repository views are as follows:

- Data security: Provides an additional level of table security by restricting access to a pre-determined set of rows and/or columns of a table.
- Provides an easy way to query data from different data sources like a single table.
- Useful when developing complex reports based on multiple tables.

This appendix contains the following sections:

- Creating Repository Views, page D-1
- Using Views in Prime Provisioning, page D-2

## **Creating Repository Views**

This section describes how to create views in Sybase repository and Oracle repository.

- Creating Views Sybase Repository, page D-1
- Creating Views in Oracle Repository, page D-2

## **Creating Views Sybase Repository**

#### **New and Upgrade Installation**

All the views available in Prime Provisioning (see the Using Views in Prime Provisioning, page D-2) are created as part of the new and upgrade installation of Prime Provisioning 6.5.

## **Creating Views in Oracle Repository**

#### **New and Upgrade Installation**

To create repository views (see the Using Views in Prime Provisioning, page D-2) in new and upgrade installation of Prime Provisioning 6.5, follow these steps:

Step 1

Copy the **schema.tar** file to the Oracle server and then extract all files into a directory.



The schema information is held in the schema.tar file in the software package. Obtain the correct package (schemas can change between packages) and extract the **schema.tar** file from the package.

- **Step 2** Navigate to the directory containing the expanded schema, then go to the **ddl/6.0** sub-directory.
- **Step 3** Run the command **sqlplus**.
- Step 4 Log in as sysdba and provide the DBA privileges to the Prime Provisioning user using the command: GRANT DBA, CONNECT, RESOURCE TO <isc\_user>;
- **Step 5** Log in with the username and password previously created.
- Step 6 Enter the SQL command start DBViews.sql;

This will create all the views in Oracle repository.

# **Using Views in Prime Provisioning**

The different views available in Prime Provisioning are as follows:

- Summary View, page D-2
- Site View, page D-4
- Customer View, page D-5
- Region View, page D-5

## **Summary View**

You can query using the column name for summary view. Table D-1 describes the column name and its type name.

Column Name	Type Name
SR_Number	Integer
SR_STATE	Integer
SR_Last_Modified_Time	Varchar

Table D-1 Summary View Column Names

Column Name	Type Name	
PE_Name	Varchar	
PE_Interface	Varchar	
PE_Interface_IPAddress	Varchar	
CE_Name	Varchar	
CE_Interface	Varchar	
CE_Interface_IPAddress	Varchar	
CE_Type	Integer	
CE_Site_ID	Integer	
CE_Site_Name	Varchar	
VPN_Name	Varchar	
VRF_Name	Varchar	
Customer_ID	Integer	
Customer_Name	Varchar	
JOB_DESCRIPTION	Varchar	

#### Table D-1 Summary View Column Names (continued)

The description of the column name is as follows:

- SR\_Number—Service Request Number, represents the service request JOB ID that is available on the Service Request page in the Prime Provisioning GUI
- SR\_STATE—State of the Service Request and the following table maps the value in the database and its associated state:

Database Value	Associated State	
-1	UNKNOWN	
0	All States	
1	Requested	-
2	Pending	
3	Failed Deploy	
4	InValid	
5	Deployed	
6	Broken	
7	Functional	
8	Lost	
9	Closed	
10	Failed Audit	
11	Wait Deploy	-
12	In Progress	-

- SR\_Last\_Modified\_Time—last modified time of SR based on the current state of the SR
- PE\_Name—PE Host Name
- PE\_Interface—PE Interface Name associated with SR.
- PE\_Interface\_IPAddress—IP address of the PE interface
- CE\_Name—CE Host Name
- CE\_Interface—CE interface name associated with SR
- CE\_Interface\_IPAddress—IP address of the CE interface
- CE\_Type—Management type of the CE Device, the following table maps the value in the database and the CE Management Type:

Database Value	CE Management Type
-1	UNKNOWN
0	Managed
1	UnManaged
2	Managed - Management LAN
3	UnManaged - Management LAN
4	Directly Connected
5	Directly Connected Management Host
6	Multi-VRF
7	Un Managed Multi-VRF

- CE\_Site\_ID—Site ID of the CE
- CE\_Site\_Name—Site name of the CE
- VPN\_Name—VPN name associated with SR
- VRF\_Name—VRF name associated with SR
- Customer\_ID—Customer ID
- Customer\_Name—Customer Name
- JOB\_DESCRIPTION—Job description of MPLS SR

An example for the summary view query is as follows:

select SR\_Number, PE\_Name, CE\_Name, VPN\_Name from Summary\_View;

## **Site View**

You can query using the column name for site veiw. Table D-2 describes the column name and its type name.

Column Name	Type Name
SITE_ID	Integer
SITE_NAME	Varchar
CPE_Name	Varchar
LINK_ID	Integer

Table D-2Site View Column Names

The description of the column name is as follows:

- SITE\_ID—Site ID
- SITE\_NAME—Site Name
- CPE\_Name—CPE name associated with the site
- LINK\_ID—Link ID of the CPE associated to a SR

An example for the site view query is as follows:

select Site\_Id, Site\_Name, CPE\_Name, Link\_ID from Site\_View;

## **Customer View**

You can query using the column name for customer view. Table D-3 describes the column name and its type name.

Table D-3 Customer View Column Names

Column Name	Type Name
CUSTOMER_ID	Integer
CUSTOMER_CONTACT	Varchar

The description of the column name is as follows:

- CUSTOMER\_ID—Customer ID
- CUSTOMER\_CONTACT—Information about the customer

An example for the customer view query is as follows:

select \* from Customer\_View;

## **Region View**

You can query using the column name that is available for region view. Table D-4 describes the column name and its type name.

Column Name	Type Name
PROVIDER_ID	Integer
REGION_ID	Integer
PE_NAME	Varchar

The description of the column name is as follows:

- PROVIDER\_ID—Provider ID
- REGION\_ID—Region ID of the provider
- PE\_NAME—PE Host Name associated to this Region

An example for the region view query is as follows:

select Region\_Id, PE\_Name from Region\_View;