

# **S** Commands

This chapter describes the Cisco NX-OS Enhanced Interior Gateway Routing Protocol (EIGRP) commands that begin with S.

### **Review Draft -- Cisco Confidential**

## shutdown (EIGRP)

To shut down an instance of Enhanced Interior Gateway Routing Protocol (EIGRP), use the **shutdown** command. To disable this function, use the **no** form of this command.

shutdown

no shutdown

Syntax Description	This command has no	arguments or keywords.
--------------------	---------------------	------------------------

Command Default Enabled

**Command Modes** Address family configuration mode Router configuration mode Router VRF configuration mode

Command History	Release	Modification
	6.0(2)N1(1)	This command was introduced.

#### Use the shutdown command to disable an instance of EIGRP without removing the configuration. This command requires the LAN Base Services license.

**Examples** This example shows how to disable eigrp 209:

switch(config)# router eigrp 209
switch(config-router)# shutdown
switch(config-router)#

<b>Related Commands</b>	Command	Description
	copy running-config startup-config	Saves the configuration in the startup configuration file.
	show ip eigrp interfaces	Displays information about EIGRP interfaces.

### **Review Draft -- Cisco Confidential**

## stub

To configure a router as a stub using the Enhanced Interior Gateway Routing Protocol (EIGRP), use the **stub** command. To disable the EIGRP stub routing feature, use the **no** form of this command.

stub [direct | leak-map map-name| receive-only | redistributed]

no stub [direct | leak-map map-name| receive-only | redistributed]]

Syntax Description	direct	(Optional) Advertises directly connected routes.	
Cyntax Desonption	leak-map map-name	(Optional) Allows dynamic prefixes based on the leak map.	
	receive-only	(Optional) Sets the router as a receive-only neighbor.	
	redistributed	(Optional) Advertises redistributed routes from other protocols and autonomous systems.	
Command Default	Disabled		
Command Modes	Address-family configu Router configuration mo Router VRF configurati	ode	
Command History	Release	Modification	
	6.0(2)N1(1)	This command was introduced.	
Usage Guidelines	Use the <b>stub</b> command to configure a router as a stub where the router directs all IP traffic to a distribution router. The <b>direct</b> keyword permits EIGRP stub routing to advertise connected routes. This option is enabled by default.		
	The <b>receive-only</b> keyword restricts the router from sharing any of its routes with any other router in that EIGRP autonomous system, and the <b>receive-only</b> keyword does not permit any other option to be specified because it prevents any type of route from being sent.		
	The <b>redistributed</b> keyword permits EIGRP stub routing to send other routing protocols and autonomous systems. Without the configuration of this option, EIGRP does not advertise redistributed routes.		
	If you use any of these four keywords ( <b>direct</b> , <b>leak-map</b> , <b>receive-only</b> , <b>redistributed</b> ) with the <b>stub</b> command, only the route types specified by the particular keyword(s) are advertised.		
	This command requires	the LAN Base Services license.	
Examples	This example shows how	w to configure the router as a receive-only neighbor:	
	<pre>switch(config)# route switch(config-router)</pre>		

### **Review Draft -- Cisco Confidential**

switch(config-router)#

#### **Related Commands**

Command	Description
copy running-config startup-config	Saves the configuration changes to the startup configuration file.
show ip eigrp	Displays EIGRP information.
show ip eigrp neighbors	Displays EIGRP neighbor information.