



Configuring an Email Account to Access Cisco Unity Connection Voice Messages

Cisco Unity Connection allows licensed users to use a third-party IMAP client to access voice messages from their desktop machines. You can also forward voice messages with text and reply to voice messages with text; the text portion of the message is accessible through the Unity Connection text-to-speech feature.

See the following sections:

- [Considerations When Configuring IMAP Email Clients in Cisco Unity Connection](#), page 3-2
- [Creating and Configuring an Account to Access Cisco Unity Connection in Apple Mail](#), page 3-2
- [Creating and Configuring an Account to Access Cisco Unity Connection in Eudora](#), page 3-4
- [Creating and Configuring an Account to Access Cisco Unity Connection in IBM Lotus Notes](#), page 3-5
- [Creating and Configuring an Account to Access Cisco Unity Connection in Microsoft Outlook](#), page 3-7
- [Creating and Configuring an Account to Access Cisco Unity Connection in Microsoft Outlook Express](#), page 3-9
- [Creating and Configuring an Account to Access Cisco Unity Connection in Novell GroupWise](#), page 3-10
- [Creating and Configuring an Account to Access Cisco Unity Connection in Opera](#), page 3-12
- [Creating and Configuring an Account to Access Cisco Unity Connection in Thunderbird](#), page 3-13
- [Creating and Configuring an Account to Access Cisco Unity Connection in Novell GroupWise](#), page 3-10
- [Setting Up ViewMail for Outlook in Cisco Unity Connection](#), page 3-16
- [Configuring Cisco Unity Connection for HTML-based Message Notification](#), page 3-18
- [Configuring Cisco Unity Connection for Cisco Unity Connection Mini Web Inbox](#), page 3-23
- [Troubleshooting IMAP Client Sign-In Problems in Cisco Unity Connection](#), page 3-24



Note

When users change their Cisco Personal Communications Assistant (PCA) password (also known as the web-application password) in the Unity Connection Messaging Assistant, they also must update the password in their IMAP client application. Passwords are not synchronized between IMAP clients and

the Cisco PCA. If users have trouble receiving voice messages in an IMAP client even after updating their Cisco PCA password in both applications, see the [“To create the registry entries for Microsoft Outlook, do the following:” section on page 3-21](#).

Considerations When Configuring IMAP Email Clients in Cisco Unity Connection

Note the following considerations when configuring IMAP email clients to access Cisco Unity Connection voice messages:

- In Cisco Unity Connection Administration, configure the following settings on the System Settings > SMTP Configuration > Server page to match the SSL settings in the IMAP email clients:
 - Allow Connections From Untrusted IP Addresses
 - Require Authentication From Untrusted IP Addresses
 - Transport Layer Security From Untrusted IP Addresses Is (Disabled, Required, Optional)
- IMAP email clients all include two fields in which you can enter either the IP address or the fully qualified domain name of the Unity Connection server. When a Unity Connection cluster is configured, enter the fully qualified domain name of a DNS A record that includes the Unity Connection publisher and subscriber servers. If your DNS server allows you to specify the order in which DNS tries to contact Unity Connection servers, specify that the server that is available most often is the first server contacted. This usually is the publisher server.

Some IMAP email clients do not respect DNS A records. For those clients, if the first Unity Connection server is not available, the client does not try to access the other Unity Connection server.
- When a user forwards or replies to a voice message from an IMAP email client, the message will be sent to recipients on the Unity Connection server unless the user specifically configures the message to be sent through another account.

Creating and Configuring an Account to Access Cisco Unity Connection in Apple Mail

To use Apple Mail to access Cisco Unity Connection voice messages, create and configure a new Apple Mail account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

To Create and Configure a New Account in Apple Mail

- Step 1** Start Apple Mail.
- Step 2** In Apple Mail, on the Mail menu, select **Preferences**.
- Step 3** At the top of the Preferences dialog box, select **Accounts**.
- Step 4** In the lower left corner, select **+**.
- Step 5** In the Account Type list, select **IMAP**.
- Step 6** In the Description field, enter a name for the account. This name appears only in Apple Mail.
- Step 7** In the E-Mail Address field, enter the Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The E-Mail Address typically follows this format:
<alias>@<fully qualified domain name of the Unity Connection server>
- Step 8** In the Full Name field, enter the username.
- Step 9** In the Incoming Mail Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.

**Caution**

Do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

- Step 10** In the User Name field, enter the Unity Connection username.
- Step 11** In the Password field, enter the Cisco PCA password.
- Step 12** In the Outgoing Mail Server (SMTP) field, select the IP address or the fully qualified domain name of the Unity Connection server.
- Step 13** Select **Server Settings**.
- Step 14** Optionally, in the SMTP Server Options dialog box, check the **Use Secure Sockets Layer (SSL)** check box.

**Caution**

If you do not configure Apple Mail to use SSL, the Unity Connection username and password that are sent to Unity Connection over the network and the voice messages sent back from Unity Connection are not encrypted.

- Step 15** In the Authentication list, select **Password**.
- Step 16** Select **OK** to close the SMTP Options dialog box.
- Step 17** Select the **Advanced** tab.
- Step 18** In the Keep Copies of Messages for Offline Viewing list, select the applicable option.
- Step 19** Close the Preferences dialog box.
- Step 20** In the Save Changes dialog box, select **Save**.
-

Creating and Configuring an Account to Access Cisco Unity Connection in Eudora

To use Eudora to access Cisco Unity Connection voice messages, create and configure a new Eudora account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

To Create and Configure a New Account in Eudora

- Step 1** Start Eudora.
- Step 2** On the Eudora Tools menu, select **Personalities**.
- Step 3** Right-click anywhere in the Personalities tab, and select **New**.
- Step 4** In the New Account wizard, on the Account Settings page, select **Next** to accept the default value, Create a Brand New E-Mail Account.
- Step 5** On the Personality Name page, enter a display name for the account. The value that you enter here is visible only in Eudora.
- Step 6** Select **Next**.
- Step 7** On the Personal Information page, enter the username.
- Step 8** Select **Next**.
- Step 9** On the E-Mail Address page, enter the Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The E-Mail Address typically follows this format:
`<alias>@<fully qualified domain name of the Unity Connection server>`
- Step 10** Select **Next**.
- Step 11** On the User Name page, enter the Unity Connection username.
- Step 12** Select **Next**.
- Step 13** On the Incoming E-Mail Server page, enter the IP address or the fully qualified domain name of the Unity Connection server.



Caution Do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

- Step 14** For the type of server, select **IMAP**.
- Step 15** Select **Next**.
- Step 16** On the IMAP Location Prefix page, do not enter a value.
- Step 17** Select **Next**.

- Step 18** On the Outgoing E-Mail Server page, enter the IP address or the fully qualified domain name of the Unity Connection server.
- Step 19** Select **Next**.
- Step 20** On the Success page, select **Finish** to create the account and close the wizard.
- Step 21** In the Enter Password dialog box, enter the Cisco PCA password of the user.
- Step 22** Select **OK**.
- Step 23** Optionally, configure the new account to use SSL. For more information, see Eudora Help.

**Caution**

If you do not configure Eudora to use SSL, the Unity Connection username and password that are sent to Unity Connection over the network and the voice messages sent back from Unity Connection are not encrypted.

Creating and Configuring an Account to Access Cisco Unity Connection in IBM Lotus Notes

**Caution**

If you plan to configure user accounts to use Cisco Unity Connection ViewMail for IBM Lotus Notes, do not follow the instructions in this section. Instead, follow the configuration instructions in the *Release Notes for Cisco Unity Connection ViewMail for IBM Lotus Notes*, available at http://www.cisco.com/en/US/products/ps6509/prod_release_notes_list.html.

To use Notes to access Cisco Unity Connection voice messages, create and configure a new Notes account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

**Caution**

When using Lotus Notes version 7.x to access Unity Connection voice messages, you must first configure Notes to connect to a Domino account before configuring the Unity Connection account.

To Create and Configure a New Account in IBM Lotus Notes

- Step 1** Start IBM Lotus Notes.
- Step 2** On the Notes File menu, select **Preferences > Client Reconfiguration Wizard**.
- Step 3** In the Lotus Notes Client Configuration wizard, on the Additional Services page, check the **Internet Mail Servers (POP or IMAP, SMTP)** check box.
- Step 4** Select **Next**.

- Step 5** On the Set Up Internet Mail page, in the Select the Type of Server Used for Retrieving Incoming Mail list, select **IMAP**.
- Step 6** In the Enter a New Account Name list, select **Incoming Internet Mail**.
- Step 7** In the Incoming Mail Server field, enter the IP address or the fully qualified domain name of the Cisco Unity Connection server.



Caution Do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

- Step 8** Select **Next**.
- Step 9** On the Set Up Internet Mail page, in the Account Name field, enter the Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The Account Name typically follows this format:
- <alias>@<fully qualified domain name of the Unity Connection server>
- Step 10** In the Password fields, enter and confirm the Cisco PCA password of the user.
- Step 11** If you want to encrypt voice messages and other data that are sent between Notes and Unity Connection, check the **Log On Using SSL** check box. If not, skip to [Step 12](#).



Caution If you do not configure Notes to use SSL, the Unity Connection username and password that are sent to Unity Connection over the network and the voice messages that are sent back from Unity Connection are not encrypted.

- Step 12** Select **Next**.
- Step 13** On the second Set Up Internet Mail page, in the Enter a New Account Name list, select **Outgoing Internet Mail**.
- Step 14** In the Outgoing SMTP Mail Server list, enter the IP address or the fully qualified domain name of the Unity Connection server.
- Step 15** Select **Next**.
- Step 16** On the third Set Up Internet Mail page, in the E-Mail Address field, enter the Unity Connection alias of the user and the name of the Unity Connection server. Use the following format:
- <alias>@<fully qualified domain name of the Unity Connection server>
- Step 17** In the Internet Domain field, enter the Internet domain name of the Domino mail server.
- Step 18** Select **Next**.
- Step 19** Select **OK**.

Creating and Configuring an Account to Access Cisco Unity Connection in Microsoft Outlook

**Caution**

If you plan to configure user accounts to use Cisco ViewMail for Microsoft Outlook, do not follow the instructions in this section. Instead, follow the configuration instructions in the applicable *Release Notes for Cisco ViewMail for Microsoft Outlook*, available at http://www.cisco.com/en/US/products/ps6509/prod_release_notes_list.html.

To use Microsoft Outlook to access Cisco Unity Connection voice messages, create and configure a new Microsoft Outlook account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

In addition to configuring Microsoft Outlook to access Unity Connection voice messages, you can also install the optional ViewMail for Outlook plug-in. See the “[Creating and Configuring an Account to Access Cisco Unity Connection in Microsoft Outlook Express](#)” section on page 3-9.

To Create and Configure a New Account in Outlook

-
- Step 1** Start Microsoft Outlook.
- Step 2** On the Microsoft Outlook Tools menu, select **E-Mail Accounts**.
- Step 3** In the E-Mail Accounts wizard, select **Add a New E-Mail Account**.
- Step 4** Select **Next**.
- Step 5** On the Server Type page, select **IMAP**.
- Step 6** Select **Next**.
- Step 7** Enter values in the User Information section:
- a. In the Your Name field, enter a display name for the account. The value that you enter here is visible only in Microsoft Outlook.
 - b. In the E-Mail Address field, enter one of the following:
 - The Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The E-Mail Address typically follows this format:
`<alias>@<SMTP domain name of the Unity Connection server or cluster>`
 - The proxy address for the user.
- Step 8** Enter values in the Server Information Section:
- a. In the Incoming Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.

**Caution**

Do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

- b. In the Outgoing Server field, select the IP address or the fully qualified domain name of the Unity Connection server.

Step 9 Enter values in the Logon Information section:

- a. In the User Name field, enter the Unity Connection username.
- b. In the Password field, enter the Cisco PCA password of the user.
- c. Verify that the Remember Password check box is not checked. If this option is checked, and the Unity Connection password of the user expires, changes, or is locked, Microsoft Outlook does not prompt the user to enter the Unity Connection password. The result is that users do not receive voice messages from Unity Connection.

Step 10 If you do not want to encrypt voice messages and other data that are sent over the network between Microsoft Outlook and Unity Connection, skip to [Step 15](#).

**Caution**

If you do not configure Microsoft Outlook to use SSL, the Unity Connection username and password that are sent to Unity Connection over the network and the voice messages sent back from Unity Connection are not encrypted.

If you want to encrypt voice messages and other data that are sent between Microsoft Outlook and Unity Connection, continue with [Step 11](#).

Step 11 Select **More Settings**.

Step 12 In the Internet E-Mail Settings dialog box, select the **Advanced** tab.

Step 13 Under Incoming Server (IMAP), check the **This Server Requires an Encrypted Unity Connection (SSL)** check box.

Step 14 Select **OK** to close the Internet E-Mail Settings dialog box.

Step 15 If the Unity Connection SMTP server is configured to allow connections from untrusted IP addresses, skip to [Step 21](#).

If the Unity Connection SMTP server is configured to require authentication from untrusted IP addresses, continue with [Step 16](#).

Step 16 Select **More Settings**.

Step 17 In the Internet E-Mail Settings dialog box, select the **Outgoing Server** tab.

Step 18 Verify that the My Outgoing Server (SMTP) Requires Authentication check box is checked.

Step 19 Verify that Use Same Settings as My Incoming Mail is selected.

Step 20 Select **OK** to close the Internet E-Mail Settings dialog box.

Step 21 Select **Next**.

Step 22 Select **Finish**.

Step 23 In the left pane of Microsoft Outlook, select the **Inbox** folder for the new account.

Step 24 On the Microsoft Outlook Tools menu, select **Send/Receive > This Folder**.

Step 25 If prompted, enter the Unity Connection username and Cisco PCA password.

Creating and Configuring an Account to Access Cisco Unity Connection in Microsoft Outlook Express

To use Microsoft Outlook Express to access Cisco Unity Connection voice messages, create and configure a new Microsoft Outlook Express account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

To Create and Configure a New Account in Microsoft Outlook Express

-
- Step 1** Start Microsoft Outlook Express.
- Step 2** On the Microsoft Outlook Express Tools menu, select **Accounts**.
- Step 3** In the Internet Accounts dialog box, select the **Mail** tab.
- Step 4** Select **Add > Mail**, and the Internet Unity Connection wizard appears.
- Step 5** On the Your Name page, in the **Display Name** field, enter the username.
- Step 6** Select **Next**.
- Step 7** On the Internet E-Mail Address page, select **I Already Have an E-Mail Address That I'd Like to Use**.
- Step 8** In the **E-Mail Address** field, enter the Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The E-Mail Address typically follows this format:
 <alias>@<fully qualified domain name of the Unity Connection server>
- Step 9** Select **Next**.
- Step 10** On the E-Mail Server Names page, in the My Incoming Mail Server Is a <protocol> Server list, select **IMAP**.
- Step 11** In the Incoming Mail (POP3, IMAP, or HTTP) Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.



Caution Do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

- Step 12** In the Outgoing Mail (SMTP) Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.
- Step 13** Select **Next**.
- Step 14** On the Internet Mail Logon page, in the Account Name and Password fields, enter the Unity Connection username and Cisco PCA password.
- Step 15** Verify that the **Remember Password** check box is not checked.

If this option is checked, and the Unity Connection password of the user expires, changes, or is locked, Microsoft Outlook Express does not prompt the user to enter the Unity Connection password. The result is that users do not receive voice messages from Unity Connection.

- Step 16** Select **Next**.
- Step 17** On the Congratulations page, select **Finish**.
- Step 18** In the Internet Accounts dialog box, select the account that you created in [Step 4](#), and select **Properties**.
- Step 19** In the <account name> Properties dialog box, select the **IMAP** tab.
- Step 20** Uncheck the **Store Special Folders** check box.
- Step 21** In the Root Folder Path field, enter **INBOX** (all upper-case letters).
- Step 22** If you do not want to encrypt voice messages and other data that are sent over the network between Microsoft Outlook Express and Unity Connection, skip to [Step 25](#).

**Caution**

If you do not configure Microsoft Outlook Express to use SSL, the Unity Connection username and password that are sent to Unity Connection over the network and the voice messages sent back from Unity Connection are not encrypted.

If you want to encrypt voice messages and other data that are sent between Microsoft Outlook Express and Unity Connection, continue with [Step 23](#).

- Step 23** Select the **Advanced** tab.
- Step 24** Under Incoming Mail, check the **This Server Requires a Secure Unity Connection (SSL)** check box.
- Step 25** Select **OK** to close the <account name> Properties dialog box.
- Step 26** Select **Close** to close the Internet Accounts dialog box.

Creating and Configuring an Account to Access Cisco Unity Connection in Novell GroupWise

To use GroupWise to access Cisco Unity Connection voice messages, create and configure a new GroupWise account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

To Create and Configure a New Account in GroupWise

- Step 1** Start GroupWise.
- Step 2** On the GroupWise Tools menu, select **Accounts > Account Options**.
- Step 3** In the Accounts dialog box, select **Add**.
- Step 4** In the Create Account dialog box, in the Account Name field, enter a name for the account. This name appears only in GroupWise.
- Step 5** In the Account Type list, select **IMAP4**.
- Step 6** Select **Next**.

- Step 7** In the Create Internet Account dialog box, in the **Incoming Mail Server (IMAP4)** field, enter the IP address or the fully qualified domain name of the Unity Connection server.



Caution Do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

- Step 8** In the Login Name field, enter the Unity Connection username.
- Step 9** In the Outgoing Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.
- Step 10** In the E-Mail Address field, enter the Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The E-Mail Address typically follows this format:
<alias>@<fully qualified domain name of the Unity Connection server>
- Step 11** In the From Name field, enter the username.
- Step 12** Select **Next**.
- Step 13** Follow the on-screen prompts to complete the configuration.
- Step 14** If you do not want to encrypt voice messages and other data that are sent over the network between GroupWise and Unity Connection, skip to [Step 20](#).



Caution If you do not configure GroupWise to use SSL, the Unity Connection username and password that are sent to Unity Connection over the network and the voice messages sent back from Unity Connection are not encrypted.

If you want to encrypt voice messages and other data that are sent between GroupWise and Unity Connection, continue with [Step 15](#).

- Step 15** In the Accounts dialog box, select the name of the account that you just created.
- Step 16** Select **Properties**.
- Step 17** Select the **Advanced** tab.
- Step 18** Under Incoming Mail Server (IMAP4), check the **Use SSL** check box.
- Step 19** Select **OK** to close the <Account Name> Properties dialog box.
- Step 20** Select **Close** to close the Accounts dialog box.
- Step 21** Create the inbox for the new account, and download Unity Connection voice messages:
- In the left pane of GroupWise, select the name of the new account.
 - In the Logon to <AccountName> dialog box, enter the Cisco PCA password for the user.
 - Verify that the **Remember Password** check box is not checked.

If this option is checked, and the Unity Connection password of the user expires, changes, or is locked, GroupWise does not prompt the user to enter the Unity Connection password. The result is that users do not receive voice messages from Unity Connection.
 - Select **OK** to close the Logon to <AccountName> dialog box.
 - With the name of the new account still selected in the left pane, on the GroupWise Tools menu, select **Send/Receive > This Folder**.

Creating and Configuring an Account to Access Cisco Unity Connection in Opera

To use Opera to access Cisco Unity Connection voice messages, create and configure a new Opera account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

To Create and Configure a New Account in Opera

-
- Step 1** Start Opera.
- Step 2** On the Opera Tools menu, select **Mail and Chat Accounts**.
- Step 3** In the Manage Accounts dialog box, select **New**.
- Step 4** In the New Account wizard, select **IMAP**.
- Step 5** Select **Next**.
- Step 6** In the Real Name field, enter the account name.
- Step 7** In the E-Mail Address field, enter the Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The E-Mail Address typically follows this format:
 <alias>@<fully qualified domain name of the Unity Connection server>
- Step 8** In the Organization field, enter the applicable value.
- Step 9** Select **Next**.
- Step 10** In the Login Name field, enter the Unity Connection username.
- Step 11** In the Password field, enter the Cisco PCA password.
- Step 12** Select **Next**.
- Step 13** In the Incoming Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.



Caution Do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

- Step 14** If you want to encrypt voice messages and other data that are sent between Opera and Unity Connection, check the Use Secure Unity Connection (TLS) check box. (TLS is an updated version of SSL.)



Caution If you do not configure Opera to use SSL, the Unity Connection username and password that are sent to Unity Connection over the network and the voice messages sent back from Unity Connection are not encrypted.

- Step 15** In the Outgoing Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.
- Step 16** Select **Finish**.
- Step 17** Select **OK** to close the Subscribe IMAP Folders dialog box.
- Step 18** Select **OK** to close the Manage Accounts dialog box.
-

Creating and Configuring an Account to Access Cisco Unity Connection in Thunderbird

To use Thunderbird to access Cisco Unity Connection voice messages, create and configure a new Thunderbird account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

To Create and Configure a New Account in Thunderbird

- Step 1** Start Thunderbird.
- Step 2** On the Thunderbird File menu, select **New > Account**.
- Step 3** In the Account wizard, on the New Account Setup page, select **E-Mail Account**.
- Step 4** Select **Next**.
- Step 5** On the Identity page, in the Your Name field, enter the username.
- Step 6** In the E-Mail Address field, enter the Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The E-Mail Address typically follows this format:
<alias>@<fully qualified domain name of the Unity Connection server>
- Step 7** Select **Next**.
- Step 8** On the Server Information page, under Select the Type of Incoming Server You Are Using, select **IMAP**.
- Step 9** In the Incoming Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.

**Caution**

Do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

- Step 10** Select **Next**.
- Step 11** On the User Names page, enter the Unity Connection username.
- Step 12** Select **Next**.
- Step 13** On the Account Name page, enter a name for the account. This name appears only in Thunderbird.

- Step 14** Select **Next**.
- Step 15** On the Congratulations page, confirm that the settings are correct, then select **Finish**.
- Step 16** If you do not want to encrypt voice messages and other data that are sent over the network between Thunderbird and Unity Connection, you are finished creating and configuring a new account.
If you want to encrypt voice messages and other data that are sent between Thunderbird and Unity Connection, continue with [Step 17](#).
- Step 17** In the left pane of Thunderbird, select the name of the account that you just created.
- Step 18** In the right pane of Thunderbird, under Accounts, select **View Settings for This Account**.
- Step 19** In the Account Settings dialog box, under the account that you just created, select **Server Settings**.
- Step 20** Under Server Settings, select the **Use Secure Unity Connection (SSL)** check box.

**Caution**

If you do not configure Thunderbird to use SSL, the Unity Connection username and password that are sent to Unity Connection over the network and the voice messages sent back from Unity Connection are not encrypted.

- Step 21** Select **OK** to close the Account Settings dialog box.

Creating and Configuring an Account to Access Cisco Unity Connection in Windows Mail for Windows Vista

To use Windows Mail for Windows Vista to access Cisco Unity Connection voice messages, create and configure a new Windows Mail account for the user. You need the following information:

- Unity Connection username (alias).
- Cisco Personal Communications Assistant (PCA) password. (This is the web application password that is set on the User pages in Cisco Unity Connection Administration.)
- The IP address, or if DNS is configured, the fully qualified domain name of the Unity Connection server.

To Create and Configure a New Account in Windows Mail

- Step 1** Start Windows Mail.
- Step 2** On the Tools menu, select **Accounts**.
- Step 3** In the Internet Accounts dialog box, select **Add**.
- Step 4** On the Select Account Type page, select **E-Mail Account**.
- Step 5** Select **Next**.
- Step 6** On the Your Name page, in the Display Name field, enter the username.
- Step 7** Select **Next**.

Step 8 On the Internet E-Mail Address page, in the E-Mail Address field, enter the Unity Connection SMTP Address of the user and the name of the Unity Connection server. You can find this information in the SMTP Address field on the User Basics page in Cisco Unity Connection Administration. The E-Mail Address typically follows this format:

<alias>@<fully qualified domain name of the Unity Connection server>

Step 9 Unity ConnectionSelect **Next**.

Step 10 On the Set Up E-Mail Servers page, under Incoming E-Mail Server Type, select **IMAP**.

Step 11 In the Incoming Mail (POP3 or IMAP) Server field, enter the IP address or the fully qualified domain name of the Unity Connection server.

**Caution**

In [Step 11](#) and [Step 12](#), do not use the fully qualified domain name of the Unity Connection server unless DNS is configured for the network.

Step 12 In the Outgoing E-Mail Server (SMTP) Name field, enter the IP address or the fully qualified domain name of the Unity Connection server.

Step 13 If the Unity Connection SMTP server is configured to allow connections from untrusted IP addresses, skip to [Step 15](#).

If the Unity Connection SMTP server is configured to require authentication from untrusted IP addresses, continue with [Step 14](#).

Step 14 Check the **Outgoing Server Requires Authentication** check box.

Step 15 Select **Next**.

Step 16 On the Internet Mail Logon page, enter the user Unity Connection alias and Cisco PCA password.

Step 17 Select **Next**.

Step 18 On the Congratulations page, select **Finish**.

Step 19 Select **Close** to close the Internet Accounts dialog box.

Step 20 If you do not want to encrypt voice messages and other data that are sent over the network between Windows Mail and Unity Connection, you are finished creating and configuring a new account.

If you want to encrypt voice messages and other data that are sent between Windows Mail and Unity Connection, continue with [Step 21](#).

Step 21 On the Tools menu, select **Accounts**.

Step 22 In the Internet Accounts dialog box, select the name of the mail account that you just created and select **Properties**.

Step 23 In the Properties dialog box, select the **Advanced** tab.

Step 24 Under both the Outgoing Mail field and the Incoming Mail field, check the **This Server Requires a Secure Unity Connection (SSL)** check box.

Step 25 Select **OK**.

**Caution**

If you do not configure Windows Mail to use SSL, the Unity Connection username (alias) and password that are sent to Unity Connection over the network and the voice messages sent back from Unity Connection are not encrypted.

Step 26 Select **Close** to close the Internet Accounts dialog box.

Setting Up ViewMail for Outlook in Cisco Unity Connection

Cisco ViewMail for Microsoft Outlook 8.5 and Later


To install and set up Cisco ViewMail for Microsoft Outlook, see the applicable *Release Notes for Cisco ViewMail for Microsoft Outlook* at

http://www.cisco.com/en/US/products/ps6509/prod_release_notes_list.html.

Cisco Unity Connection ViewMail for Microsoft Outlook 8.0

By using ViewMail for Outlook 8.0 to access Cisco Unity Connection voice messages, users can play and record voice messages by using the Media Master. See [Figure 3-1](#).

Figure 3-1 Media Master



See the following sections:

- [Task List for Setting Up ViewMail for Outlook 8.0, page 3-16](#)
- [Configuring the IMAP Account for ViewMail for Outlook 8.0, page 3-17](#)
- [Configuring ViewMail for Outlook 8.0 Settings for Secure Messaging and TRAP, page 3-17](#)

Task List for Setting Up ViewMail for Outlook 8.0

ViewMail must be installed on each user workstation. Complete the following tasks to set up ViewMail 8.0 for users:

1. Review the applicable *Release Notes for Cisco Unity Connection ViewMail for Microsoft Outlook*, available at http://www.cisco.com/en/US/products/ps6509/prod_release_notes_list.html. The document specifies the requirements and procedures for installing 8.0.
2. If you have not already done so, install ViewMail 8.0 according to the procedures in the *Release Notes for Cisco Unity Connection ViewMail for Microsoft Outlook*.
3. If you have not already done so, configure an IMAP account in Microsoft Outlook. See the “[Creating and Configuring an Account to Access Cisco Unity Connection in Microsoft Outlook](#)” section on [page 3-7](#).

4. If users have more than one IMAP account configured, you must configure ViewMail 8.0 to use the IMAP account that is used to access Unity Connection. See the [“Configuring the IMAP Account for ViewMail for Outlook 8.0”](#) section on page 3-17.
5. If you use secure messaging or TRAP, you must configure several ViewMail 8.0 settings. See the [“Configuring ViewMail for Outlook 8.0 Settings for Secure Messaging and TRAP”](#) section on page 3-17.

Configuring the IMAP Account for ViewMail for Outlook 8.0

If users have more than one IMAP account configured, you must configure ViewMail 8.0 to use the IMAP account that is used to access Unity Connection. This ensures that messages composed by using ViewMail are sent to the Unity Connection server. If users have only one IMAP account configured, ViewMail automatically uses it to send messages to Unity Connection.

Do the following procedure on each user workstation.

To Configure ViewMail for Outlook 8.0 Settings

-
- | | |
|---------------|---|
| Step 1 | From the Microsoft Outlook Tools menu, select ViewMail Options . |
| Step 2 | Select the Accounts tab. |
| Step 3 | In the Select the Account to Access Cisco Unity Connection With field, select the IMAP account that is used to access Unity Connection. |
| Step 4 | Select Save . |
-

Configuring ViewMail for Outlook 8.0 Settings for Secure Messaging and TRAP

If you have configured Unity Connection for secure messaging or if you want users to be able to record or play messages by phone by using Telephone Record and Playback (TRAP), you must configure several ViewMail 8.0 settings.

After ViewMail 8.0 has been installed, do the following procedure on each user workstation.

To Configure ViewMail for Outlook 8.0 Secure Message and TRAP Settings

-
- | | |
|---------------|---|
| Step 1 | From the Microsoft Outlook Tools menu, select ViewMail Options . |
| Step 2 | Select the Server tab. |
| Step 3 | Enter the following settings: |

Table 3-1 **Server Settings**

Field	Setting
Cisco Unity Connection Server Name	Enter the name of the Unity Connection server. (Required for secure messaging and TRAP.)
Username	Enter the Unity Connection username (alias).

Table 3-1 **Server Settings (continued)**

Field	Setting
Password	(Optional) Enter the Cisco PCA password (also known as the web-application password) of the user. If you do not enter the password, the user is prompted for it each time Microsoft Outlook is restarted. If you do not want the user to be prompted for the password each time Microsoft Outlook is restarted, you must also check the Remember Password check box.
Remember Password	(Optional) Check this check box if you want ViewMail to remember the user password so that the user does not have to re-enter it each time Microsoft Outlook is restarted.
Proxy Server Address	If you have a firewall that blocks HTTPS traffic between user workstations and the Unity Connection server, enter the IP address of the HTTPS proxy server.
Proxy Server Port	If you have a firewall that blocks HTTPS traffic between user workstations and the Unity Connection server, enter the server port to use when connecting to the HTTPS proxy server.
Validate HTTPS Certificate	If you replace the default self-signed certificate with a certificate from a certificate authority, check the Validate HTTPS Certificate check box. If you are using the default certificate installed with Unity Connection, this check box must not be checked.
Extension	Enter the extension of the user. This setting is required only if you want the user to be able to record or play messages by phone.

Step 4 Select **Save**.

Configuring Cisco Unity Connection for HTML-based Message Notification

Cisco Unity Connection can be configured to send message notifications in the form of an HTML template to an email address. All HTML notifications in Unity Connection require an HTML-based notification template. The HTML-based templates can be selected and applied by the administrator to allow HTML notification for a device. The template selected can either be a default or a custom template that the administrator has created.

For more information on how to create a template, refer to To get the HTML notifications exactly as per the template defined by the administrator, the user's email client must support the display of images and icons. For more information on whether your email client support the display of images and icons, refer to documentation of your email service provider.

HTML notifications are supported with the following email clients:

- Microsoft Outlook 2007
- Microsoft Outlook 2010

- IBM Lotus Notes
- Gmail (Web based access only)

The user must ensure to select the authentication or non-authentication mode as desired. In addition, make sure the signed SSL certificates are installed in order to access the notifications via email and the voice message via Unity Connection Mini Web Inbox.

See the following sections:

- [Configuring the Authentication Mode, page 3-19](#)
- [Configuring the Non-Authentication Mode, page 3-19](#)
- [Configuring Microsoft Outlook to Display Images in an HTML Message Notification, page 3-20](#)
- [Configuring Microsoft Outlook for Automatic Image Download, page 3-22](#)
- [Configuring Cisco Unity Connection to Send Voice Message as an Attachment, page 3-22](#)
- [Configuring the Size of Voice Messages Sent as an Attachment with HTML Notification, page 3-23](#)

Configuring the Authentication Mode

If the administrator has created a template that include images, icons, and/or status items, then the authentication mode ensures that the user authenticates with his or her Unity Connection credentials before the images are displayed as an HTML email on an email client.

By default, the system is configured for the authentication mode. The administrator can configure the authentication mode using the Cisco Unity Connection Administration.

To Configure the Authentication Mode

-
- | | |
|---------------|--|
| Step 1 | In Cisco Unity Connection Administration, select System Settings > General Configuration . |
| Step 2 | On the Edit General Configuration page, select the Authenticate Graphics for HTML Notification option to turn on the authentication mode. |
| Step 3 | Click Save . |
-



Note

- The Unity Connection credentials are required only once for each session of Microsoft Outlook.
 - If the user clicks on the **Cancel** button and does not enter Unity Connection credentials when prompted at the first instance then no image will be displayed in the email notification. You must restart the Microsoft Outlook to enter the Unity Connection credentials and view the images.
 - If the user enters wrong password thrice then Unity Connection will not prompt again and the user must restart the Microsoft Outlook.
-

Configuring the Non-Authentication Mode

The non-authentication mode does not prompt user for credentials and the embedded images or icons are displayed without authentication in the email notification.

To Configure the Non-Authentication Mode

-
- Step 1** In Cisco Unity Connection Administration, select **System Settings > General Configuration**.
- Step 2** On the Edit General Configuration page, deselect the **Authenticate Graphics for HTML Notification** option to turn off the authentication mode.
- Step 3** Click **Save**.
-

Configuring Microsoft Outlook to Display Images in an HTML Message Notification

In the authentication mode, to view all the custom graphics or administrative replaceable images as per the HTML-based template, you must make sure that your Microsoft Outlook client has all the required hotfixes and registry entries.

If the non-authentication mode is configured then your Microsoft Outlook client does not require any hotfixes or registry entries.



Caution

The user workstation must have the SSL certificates installed irrespective of the mode selected (authentication or non-authentication).

If you are using Microsoft Internet Explorer version 8, refer to the settings given in the [Configuring Microsoft Internet Explorer 8 for Cisco Unity Connection Mini Web Inbox](#), page 3-24 section.



Note

If due to certain security implications you are not allowed to install the required hotfixes or update registry entries, then you can create the templates without images, MWI status, and message status.

Table 3-2 *Microsoft Outlook Settings Required for Authentication Mode*

Microsoft Outlook Version	Microsoft Outlook 2007	Microsoft Outlook 2010 (32 bit and 64 bit)
Windows XP SP3, Windows 7 (32 and 64 bit), and Windows Vista (32 and 64 bit)	<ul style="list-style-type: none"> Microsoft Outlook 2007 <ul style="list-style-type: none"> Registry entry for AllowImageProxyAuth, where value=1. Either Install 2007 Office suite SP2. To install 2007 Office suite SP2, refer to http://support.microsoft.com/kb/953195. Then, install Microsoft Outlook 2007 hotfix package. To install hotfix, refer to http://support.microsoft.com/kb/2596993. OR Install 2007 Office suite SP3. To install 2007 Office suite SP3, refer to http://support.microsoft.com/kb/2526086. Microsoft Outlook 2007 with SP2 <ul style="list-style-type: none"> Install Microsoft Outlook 2007 hotfix package. To install hotfix, refer to http://support.microsoft.com/kb/2596993. Registry entry for AllowImageProxyAuth, where value=1. Microsoft Outlook 2007 with SP3 <ul style="list-style-type: none"> Registry entry for AllowImageProxyAuth, where value=1. 	<ul style="list-style-type: none"> Install Microsoft Outlook 2010 hotfix package. For more information, refer to http://support.microsoft.com/kb/2459116. Registry entry for AllowImageProxyAuth, where value=1.

To create the registry entries for Microsoft Outlook, do the following:

-
- Step 1** Go to **Start > Run**. Type regedit and press **Enter**.
- Step 2** Browse to the following path for Microsoft Outlook 2007:
HKEY_CURRENT_USER\Software\Microsoft\Office\12.0\Common
- Step 3** Browse to the following path for Microsoft Outlook 2010:
HKEY_CURRENT_USER\Software\Microsoft\Office\14.0\Common
- Step 4** Add “AllowImageProxyAuth = 1” as new DWORD value.
-

Configuring Microsoft Outlook for Automatic Image Download

Even after updating your Microsoft Outlook with required hotfixes and registry entries, you need to right click on the image, if any given in the template, and select **Show images**. You can also right click on the prompt appearing at the above of message window to show the images.

To automatically download images without performing these steps with every session, you must select the required options given under the **Tools > Trust Center > Automatic Download** section in your Microsoft Outlook email client.

Configuring Cisco Unity Connection to Send Voice Message as an Attachment

Starting with Cisco Unity Connection 10.0(1) release, the administrator can now configure Unity Connection to send the voice message as an attachment in the HTML notification to the user. Along with the link to access Unity Connection Mini Web Inbox through the HTML notification email, the user can now access the voice message attachment in the .wav format that can be played on PC or mobile using any player. Prior to Unity Connection 10.0(1) version, the end user received only a link in the HTML notifications to access Unity Connection Mini Web Inbox and listen to voice messages through Mini Web Inbox only.



Note

In case of forwarded messages, the attachment is sent only for the latest voice message.

If a user tries to access the voice message attachment using mobile, the following mobile clients are supported:

- Supported versions of iPhone 4 and above
- Supported versions of Android



Note

The secure and private voice messages cannot be sent as an attachment.

By default, the system is configured for not to send the voice message as an attachment. The administrator can configure to send voice message as an attachment using the Cisco Unity Connection Administration.

To Configure Unity Connection to Send Voice Message as an Attachment

- Step 1** In Cisco Unity Connection Administration, select **Advanced > Messaging**.
- Step 2** On the Messaging Configuration page, select the **Allow voice mail as attachments to HTML notifications** option to send the voice message as an attachment.
- Step 3** Click **Save**.

Configuring the Size of Voice Messages Sent as an Attachment with HTML Notification

The administrator can configure the size of voice messages sent as an attachment with HTML notifications. The user can access the voice message attachment in the .wav format that can be played on PC or mobile using any player.

By default, the system is configured to send the voice message as an attachment upto 2048KB and maximum size can be 12288 KB. The administrator can configure the size of the voice message using the Cisco Unity Connection Administration.

To Configure the Size of Voice Message Sent as an Attachment

-
- | | |
|---------------|--|
| Step 1 | In Cisco Unity Connection Administration, select Advanced > Messaging . |
| Step 2 | On the Messaging Configuration page, enter the size of voice message in the Max size of voice mail as attachment to HTML notifications (KB) text box. |
| Step 3 | Click Save . Make sure to restart the Connection Notifier service in order to changes take effect. |
-

Configuring Cisco Unity Connection for Cisco Unity Connection Mini Web Inbox

See the following sections:

- [Configuring IBM Lotus Notes for Cisco Unity Connection Mini Web Inbox, page 3-23](#)
- [Configuring Microsoft Internet Explorer 8 for Cisco Unity Connection Mini Web Inbox, page 3-24](#)
- [Configuring Windows Vista and Windows 7 \(32 bit and 64 bit\) for Cisco Unity Connection Mini Web Inbox, page 3-24](#)

Configuring IBM Lotus Notes for Cisco Unity Connection Mini Web Inbox

Cisco Unity Connection Mini Web Inbox does not support the default IBM Lotus Notes supported browser. When a user receives a message notification on his IBM Lotus Notes email client and clicks a link in the notification to open Unity Connection Mini Web Inbox, the Unity Connection Mini Web Inbox must open in the default operating system browser.

To Configure the Web Browser as Operating System Default Browser in Lotus Notes Email Client

-
- | | |
|---------------|---|
| Step 1 | In your Lotus Notes client, select File > Preferences > Web Browser . |
| Step 2 | Select the Use the browser I have set as the default for this operating system option. |
| Step 3 | Click Apply and then Ok . |
-

Configuring Microsoft Internet Explorer 8 for Cisco Unity Connection Mini Web Inbox

To Configure Microsoft Internet Explorer 8 for Cisco Unity Connection Mini Web Inbox

-
- Step 1** In your browser window, go to **Tools > Intranet Options** and select the **Security** tab.
- Step 2** Select the **Local intranet** option and click **Sites**.
- Step 3** Uncheck all the check boxes and click **Ok**.
- Step 4** Select the **Trusted sites** option and click **Sites**.
- Step 5** Add the website that you are using for Unity Connection, for example, <https://ucbu-cisco-vmxyz.cisco.com>.
- Step 6** Click **Close** and then **Ok**.
-

Configuring Windows Vista and Windows 7 (32 bit and 64 bit) for Cisco Unity Connection Mini Web Inbox

To Configure Windows Vista and Windows 7 (32 bit and 64 bit) for Cisco Unity Connection Mini Web Inbox

-
- Step 1** Select **Start > Control Panel > Flash Player**.
- Step 2** Select the **Camera and Mic** tab in the Flash Player Settings Manager window.
- Step 3** Click **Camera and Microphone Settings by Site**.
- Step 4** Select the **Ask me when a site wants to use the camera or microphone** option in the **Camera and Microphone Settings by Site** window.
- Step 5** Click **Add**.
- Step 6** Add the website that you are using for Unity Connection, for example, ucbu-cisco-vmxyz.cisco.com.
- Step 7** Click **Allow** and then **Close**.
-

Troubleshooting IMAP Client Sign-In Problems in Cisco Unity Connection

When users change their Cisco PCA password (also known as the web-application password) in the Cisco Unity Connection Messaging Assistant, they also must update the password in their IMAP client application so that the client can continue to access Unity Connection and retrieve voice messages.

If users have trouble receiving voice messages in an IMAP client, consider the following possibilities:

- If the IMAP client application prompts a user for the Cisco PCA password, but does not accept it, the Cisco PCA password may have expired or changed, or is locked. Users can change their password in the Unity Connection Messaging Assistant first and then update it from their IMAP client application.

- If Microsoft Outlook users are not prompted for their Cisco PCA password, verify that the Remember Password check box on the Internet E-mail Settings (IMAP) page is not checked. If this option is checked, and the password of the user has expired, changed, or is locked, Microsoft Outlook does not prompt the user to enter the Cisco PCA password. The result is that the user does not receive voice messages from Unity Connection, and Microsoft Outlook prompts for the username and password.

