



D

Last Updated: November 17, 2010

[description \(backup-schedule\)](#)

[description \(kron schedule\)](#)

[disabled \(backup-schedule\)](#)

[disabled \(kron-schedule\)](#)

[domain](#)

description (backup-schedule)

To configure a description for a scheduled backup job, use the **description** command in Cisco Unity Express scheduled backup configuration mode. Use the **no** form of this command to remove the description for the backup job.

description *"text"*

no description *"text"*

Syntax Description

<i>"text"</i>	Describes the scheduled backup job.
---------------	-------------------------------------

Command Default

None.

Command Modes

Cisco Unity Express scheduled backup configuration (config-sched)

Command History

Cisco UMG Version	Modification
8.0	This command was introduced.

Usage Guidelines

The text of the description must be enclosed in quotes.

The maximum length of the description is 64 characters. If a longer description is entered, it is truncated and a message is displayed indicating that truncation occurred.

Examples

The following example configures a description for a daily scheduled backup:

```
umg-1# config t
umg-1(config)# backup schedule 22
umg-1(backup-schedule)# description "daily midnight backup"
```

Related Commands

Command	Description
backup schedule	Enters commands enters backup-schedule submode.

description (kron schedule)

To configure the description of the kron schedule, use the **description** command in Cisco Unity Express kron schedule configuration mode. Use the **no** form of this command to remove the description for the kron job.

description *“text”*

no description

Syntax Description

<i>“text”</i>	Describes the kron job.
---------------	-------------------------

Defaults

None.

Command Modes

Cisco UMG kron schedule configuration

Command History

Cisco UMG Version	Modification
8.0	This command was introduced.

Usage Guidelines

The text of the description must be enclosed in quotes.

The maximum length of the description is 64 characters. If a longer description is entered, it is truncated and a message is displayed indicating that truncation occurred.

Examples

The following example configures the description of the kron schedule to “monday”:

```
umg-1# config t
umg-1(config)# kron schedule kron1234
umg-1(kron-schedule)# description monday
```

Related Commands

Command	Description
commands (kron schedule)	Enters the interactive mode to create the command block for a kron job.
kron schedule	Creates a new kron schedule and enters kron-schedule configuration mode.
show kron schedules	Displays a list of kron jobs.
show kron schedule detail job	Displays details of a specific kron job.

disabled (backup-schedule)

To configure a period time for the scheduled backup activity to be temporarily disabled, use the **disabled** command in Cisco Unity Express backup-schedule configuration mode. To remove the configured period of time to temporarily disable the backup, use the **no** form of this command.

disabled from *date to date*

no disabled from *date to date*

Syntax Description

from <i>date</i>	Specifies the date from which the backup activity is temporarily disabled. The format is MM/DD/YYYY.
until <i>date</i>	Specifies the date until which the backup activity is temporarily disabled. The format is MM/DD/YYYY.

Defaults

No default.

Command Modes

Cisco UMG backup-schedule configuration

Command History

Cisco UMG Version	Modification
8.0	This command was introduced.

Usage Guidelines

The format for the date is month, day, and then year (for example: 05/30/2010).

Examples

The following example specifies to disable the scheduled backup from October 2, 2010 to October 6, 2010.

```
umg-1# config t
umg-1(config)# backup schedule name 22
umg-1(backup-schedule)# disabled from 10/02/2010 to 10/06/2010
```

Related Commands

Command	Description
backup schedule	Enters backup-schedule configuration mode.

disabled (kron-schedule)

To configure a period time for the scheduled kron job to be temporarily disabled, use the **disabled** command in Cisco Unity Express kron-schedule configuration mode. To remove the configured period of time to temporarily disable the kron job, use the **no** form of this command.

disabled from *date to date*

no disabled from *date to date*

Syntax Description	from <i>date</i>	Specifies the date from which the kron job is temporarily disabled. The format is MM/DD/YYYY.
	until <i>date</i>	Specifies the date until which the kron job is temporarily disabled. The format is MM/DD/YYYY.

Defaults	No default.
----------	-------------

Command Modes	Cisco UMG kron-schedule configuration
---------------	---------------------------------------

Command History	Cisco UMG Version	Modification
	8.0	This command was introduced.

Usage Guidelines	The format for the date is month, day, and then year (for example: 05/302010).
------------------	--

Examples	The following example specifies to disable the scheduled kron job from October 2, 2010 to October 6, 2010:
----------	--

```
umg-1# kron schedule krj1
umg-1(kron-schedule)# disabled from 10/02/2010 to 10/06/2010
```

Related Commands	Command	Description
	kron schedule	Enters kron-schedule configuration mode.

domain

To provision the domain name of an endpoint to Cisco UMG, use the **domain** command in Cisco UMG endpoint configuration mode. To clear this configuration, use the **no** form of this command or precede the command with **default**, as in **default domain**.

domain *domain*

no domain

Syntax Description

<i>domain</i>	Domain name of the endpoint, for example, sj.mycompany.com.
---------------	---

Command Default

The default domain name is none.

Command Modes

Cisco UMG endpoint configuration (config-endpoint)

Command History

Cisco UMG Version	Modification
1.0	This command was introduced.

Usage Guidelines

When you configure a domain for an endpoint, Cisco UMG does an MX lookup on the domain provided and uses those host addresses.

Examples

The following example shows how the domain name is set as part of the process of provisioning an endpoint to Cisco UMG:

```
umg-1> enable
umg-1# config t
umg-1(config)# endpoint 12345 unity
umg-1(config-endpoint)# domain sj.mycompany.com
umg-1(config-endpoint)# prefix 408902
umg-1(config-endpoint)# hostname unity-408
umg-1(config-endpoint)# end
umg-1(config)#
```

Related Commands

Command	Description
endpoint	Enters the endpoint configuration mode to provision endpoints manually.
hostname (endpoint)	Specifies the hostname of an endpoint you are provisioning manually.
prefix	Sets the phone number prefix of an endpoint.