



T

Last Updated: November 17, 2010

[translation-rule](#)

translation-rule

To configure the translation rule for the message or SMTP header for each supported endpoint, use the **translation-rule** command in Cisco UMG configuration mode.

```
translation-rule { smtp | message } { cue | interchange | umg | unity } { from-user umg-user |
from-host { text | umg-host } | to-host { text | umg-host } | to-user umg-user }
```

Syntax Description

smtp	Configures SMTP header translation rules.
message	Configures message header translation rules.
cue	Configures message or SMTP header translation rules for <Abbreviation>Cisco Unity Express.
interchange	Configures message or SMTP header translation rules for Avaya Interchange.
umg	Configures message or SMTP header translation rules for Cisco UMG.
unity	Configures message or SMTP header translation rules for Cisco Unity.
from-user	Configures src-user translation rules for an endpoint.
from-user <i>umg-user</i>	Variable name used for src-user translation.
from-host	Configures src-host translation rules for an endpoint.
from-host <i>text</i>	Sets source email domain value.
from-host <i>umg-host</i>	Variable name used for src-host translation.
to-host	Configures dest-host translation rules for an endpoint.
to-host <i>text</i>	Sets destination e-mail domain value.
to-host <i>umg-host</i>	Variable name used for dest-host translation.
to-user	Configures dest-user translation rules for an endpoint.
to-user <i>umg-user</i>	Variable name used for dest-user translation.

Command Modes

Cisco UMG configuration

Command History

Cisco UMG Version	Modification
1.0	This command was introduced.

Usage Guidelines

Do not use this command unless Cisco Tech Support instructs you to do so.

<Abbreviation>Cisco Unity Express utilizes the “SMTP Envelope To:” data to route voice messages for delivery. Cisco Unity uses the “Message Header To:” line, and Avaya Interchange uses the “SMTP Envelope From:” and the “Message Envelope From:”.

Examples

The following example illustrates the use of the **translation-rule** command.

```
umg-1# config t
umg-1(config)# translation-rule smtp cue from-host mycompany.com
```

Save the change to startup configuration and reload the module for the new configuration to take effect.

```
umg-1(config)# end
umg-1# show translation-rule message
Message Translation Rules -
CUE
From User:          src-user
From Host:          src-host
To User:            dest-user
To Host:            dest-host
UNITY
From User:          src-user
From Host:          to-host
To User:            dest-user
To Host:            dest-host
INTERCHANGE
From User:          src-user
From Host:          umg-host
To User:            dest-user
To Host:            dest-host
UMG
From User:          src-user
From Host:          src-host
To User:            dest-user
To Host:            dest-host

umg-1# show translation-rule smtp
SMTP Translation Rules -
CUE
From User:          src-user
From Host:          mycompany.com
To User:            dest-user
To Host:            dest-host
UNITY
From User:          src-user
From Host:          umg-host
To User:            dest-user
To Host:            dest-host
INTERCHANGE
From User:          src-user
From Host:          umg-host
To User:            dest-user
To Host:            dest-host
UMG
From User:          src-user
From Host:          src-host
To User:            dest-user
To Host:            dest-host

umg-1# write memory
```

Related Commands

Command	Description
show translation-rule	Displays the translation rule for the message or SMTP header for each supported endpoint type.

