

Virtualizing Oracle JD Edwards on Cisco Unified Computing System

Oracle JD Edwards EnterpriseOne on Cisco UCS with Oracle VM 3.1.1 and EMC VNX 5300 Last Updated: January 2, 2014



Building Architectures to Solve Business Problems

· I | I · I | I · CISCO ·



About the Authors



Anil Dhiman

Anil Dhiman, Technical Marketing Engineer, SAVBU, Cisco Systems

Anil Dhiman is a Technical Marketing Engineer with Server Access Virtualization Business Unit (SAVBU) at Cisco. Anil has over 12 years of experience in benchmarking and performance analysis of large multi-tier systems, such as Foreign Exchange products. Anil specializes in optimizing and tuning of applications deployed on J2EE application servers and has delivered world record numbers for SPECjbb2005 and SPECjbb2013 benchmarks on Cisco Unified Computing Systems. Anil has worked as a performance engineer for Oracle IAS team. Prior to joining Cisco, Anil worked as a performance engineering architect with Symphony Services.

Acknowledgment

For their support and contribution to the design, validation, and creation of the Cisco Validated Design, I would like to thank:

- Vadiraja Bhatt- Cisco
- Ramakrishna Nishtala- Cisco
- Niranjan Mohapatra- Cisco
- John McAbel– Cisco
- Sindhu Sudhir– Cisco
- Rini Kuriakose– Cisco
- Anthony Schifano- Oracle
- Kathy Sharp- EMC

About Cisco Validated Design (CVD) Program

The CVD program consists of systems and solutions designed, tested, and documented to facilitate faster, more reliable, and more predictable customer deployments. For more information visit:

http://www.cisco.com/go/designzone

ALL DESIGNS, SPECIFICATIONS, STATEMENTS, INFORMATION, AND RECOMMENDATIONS (COLLEC-TIVELY, "DESIGNS") IN THIS MANUAL ARE PRESENTED "AS IS," WITH ALL FAULTS. CISCO AND ITS SUPPLIERS DISCLAIM ALL WARRANTIES, INCLUDING, WITHOUT LIMITATION, THE WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE. IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THE DESIGNS, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

THE DESIGNS ARE SUBJECT TO CHANGE WITHOUT NOTICE. USERS ARE SOLELY RESPONSIBLE FOR THEIR APPLICATION OF THE DESIGNS. THE DESIGNS DO NOT CONSTITUTE THE TECHNICAL OR OTHER PROFESSIONAL ADVICE OF CISCO, ITS SUPPLIERS OR PARTNERS. USERS SHOULD CONSULT THEIR OWN TECHNICAL ADVISORS BEFORE IMPLEMENTING THE DESIGNS. RESULTS MAY VARY DEPENDING ON FACTORS NOT TESTED BY CISCO.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

Cisco and the Cisco Logo are trademarks of Cisco Systems, Inc. and/or its affiliates in the U.S. and other countries. A listing of Cisco's trademarks can be found at http://www.cisco.com/go/trademarks. Third party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1005R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

© 2013 Cisco Systems, Inc. All rights reserved.

Virtualizing Oracle JD Edwards on Cisco Unified Computing System

Executive Summary

Oracle JD Edwards is a suite of products from Oracle that caters to the Enterprise Resource Planning (ERP) requirement of an Organization. Oracle has three flag ship ERP Applications, Oracle E-Business Suite, PeopleSoft, and JD Edwards. ERP Applications have been thriving and improving the productivity of Organizations for a couple of decades now. But with the increased complexity and extreme performance requirements, customers are constantly looking for better Infrastructure to host and run these Applications.

This document presents a differentiated solution using Oracle Virtualized Environment that validates Oracle JD Edwards EnterpriseOne environment on Cisco Unified Computing System (UCS) with Oracle VM 3.1.1, Oracle Linux 5.8, Oracle 11gR2 RAC Database, Cisco UCS Blade Servers, Cisco Nexus 5548UP Switches, Cisco UCS Management System and EMC VNX5300. Cisco Oracle Competency Center tested, validated, benchmarked and has showcased the Oracle JD Edwards ERP Application using Oracle Day in the Life (DIL) Kit.

Purpose of this Guide

This design guide demonstrates the best practices for deployment of Oracle JD Edwards EnterpriseOne on Oracle Virtualized Environment. It elaborates on step by step procedure to deploy Cisco UCS, Cisco Nexus family of switches, EMC VNX 5300 and Oracle JD Edwards application on Oracle VM.

The design was validated by measuring the performance and scalability of Oracle JD Edwards. This was achieved by executing Oracle JD Edwards Day in the Life (DIL) Kit on Cisco UCS Platform by benchmarking various Application workloads using Load Runner tool. Oracle JDE DIL kit comprises of interactive Application workloads and batch workload, Universal Batch Engine Processes (UBEs). The interactive Application Users were validated and benchmarked by scaling from 1000 to 7,000 concurrent users. Achieving sub second response times for various JDE Application workloads with a large variation of interactive apps and UBEs, clearly demonstrate the suitability of Cisco UCS for small to large Oracle JD Edwards EnterpriseOne and help customers to make an informed decision on choosing Cisco UCS for their virtualized Oracle JD Edwards implementation.



Business Needs

Customers constantly look value for money, when they transition from one platform to another or migrate from proprietary systems to commodity hardware platforms; they endeavor to improve operational efficiency and optimal resource utilization.

Other important aspects are Management and Maintenance; ERP Applications are business critical Applications and need to be up and running without down time. Ease of Maintenance and efficient management with minimal staff and reduced budgets are pushing infrastructure managers to balance uptime and ROI.

Organizations have steadily adopted virtualization technologies in recent years to reduce the size, cost, and complexity of their infrastructure. Virtualization technologies let IT departments run multiple operating systems and applications on the same physical server, thereby allowing them to consolidate server hardware.

Server sprawl, old technologies that consume precious real estate space and power with increase in the cooling requirement have pushed customers to look for innovative technologies that can address some of these challenges.

Audience

The target audience for this guide include sales engineers, field consultants, professional services staff, IT managers, partner engineering staff, and customers who want to deploy Oracle JDE on Cisco UCS with EMC VNX5300 and Oracle VM.

This design guide is intended to assist Solution Architects, JDE Project Manager, Infrastructure Manager, Sales Engineers, Field Engineers and Consultants in planning, designing, and deployment of Oracle JD Edwards hosted on Cisco UCS environment. This document assumes that the reader has an architectural understanding of the Cisco UCS servers, Nexus 5548UP Switch, Oracle JD Edwards, EMC VNX5300, Oracle VM and related software.

Solution Overview

The solution in the design guide demonstrates the deployment of Oracle JD Edwards EnterpriseOne on Cisco UCS. The Oracle JD Edwards solution architecture is designed to run on multiple platforms and multiple databases. In this deployment, the Oracle JD Edwards Enterprise One (JDE E1) Release 9.0.2 was deployed on Oracle VM 3.1.1 with Oracle Linux 5.8 as the OS for Guest VMs. The JDE E1 database was hosted on two-node Oracle 11gR2, and the JDE HTML server ran on Oracle Weblogic Server Release 10.3.6. The design validates the use of Oracle RAC database for mission critical applications such as JDE E1 to provide high availability and scalability.

The deployment and testing was conducted in a Cisco® test and development environment to measure the performance of Oracle's JDE E1 Release 9.0.2 on Oracle VM with Cisco UCS. The JDE E1 DIL kit was deployed as a test workload which is a suite of 17 test scripts that exercise representative transactions of the most popular JDE E1 applications, including SCM, SRM, HCM, CRM, and Financial Management. This complex mix of applications simulate workloads to more closely reflect the customer environments.

The solution describes the following aspects of Oracle JD Edwards deployment on Cisco UCS:

• Sizing and Design guidelines for Oracle JD Edwards E1 using JDE E1 DIL kit for both interactive and batch processes.

- Configuring Cisco UCS for Oracle JD Edwards
 - Configuring Fabric Interconnect
 - Configuring Cisco UCS Blades
- Configuring EMC VNX5300 storage system for Oracle JD Edwards
 - Configuring the storage and creating LUNs
 - Associating LUNs with the hosts
- Configuring Oracle VM environment
 - Installation of Oracle Virtual Server (OVS) and Oracle VM Manager
 - Installation and Configuration of Para-Virtualized Guest (PVMs) with Oracle Linux 5.8
- Installation and Configuration of two-node Oracle RAC 11.2.0.3 on Oracle Virtualized environment
- Installing and configuring JDE E1 release 9.02 with Tool update 8.98.4.6
 - Provisioning the required server resource
 - Installing and Configuring JDE HTML Server, JDE Enterprise Server and Oracle 11gR2 RAC on Oracle Linux 5.8
- Performance characterization of JD Edwards E1 Day in the life Kit (DIL Kit)
 - Performance and Scaling analysis for JDE E1 interactive Apps
 - Performance Analysis of JDE batch processes (UBEs)
- Best Practices and Tuning Recommendations to deploy Oracle JD Edward son Cisco UCS

Figure 1 illustrates the components of JD Edwards E1 using Cisco UCS Servers.

Figure 1 Deployment Overview of JD Edwards EnterpriseOne on Cisco UCS with EMC VNX5300



Technology Overview

Cisco Unified Computing System Overview

Cisco UCS is a set of pre-integrated data center components, including Cisco Blade Servers, Adapters, Fabric Interconnects, and Fabric Extenders, that are integrated within a common embedded management system. This approach results in far fewer system components and much better manageability, operation efficiency, and more flexibility than comparable data center platforms.

Main Differentiating Technologies

The main differentiating technologies described here make Cisco UCS unique and give it advantages over competing offerings. The technologies presented here are high level, and the discussions do not include the technologies (such as Fibre Channel over Ethernet [FCoE]) that support these high-level elements.

Unified Fabric

Unified fabric can dramatically reduce the number of network adapters, Cisco Blade Server Switches, cables, and management touch points by passing all network traffic to parent Cisco Fabric Interconnects, where it can be prioritized, processed, and managed centrally. This approach improves performance, agility, and efficiency and dramatically reduces the number of devices that need to be powered, cooled, secured, and managed.

Embedded Multirole Management

Cisco UCS Manager is a centralized management application that is embedded on the fabric switch. Cisco UCS Manager controls all Cisco UCS elements within a single redundant management domain. These elements include all aspects of system configuration and operation, eliminating the need to use multiple, separate element managers for each system component. Massive reduction in the number of management modules, consoles and in the proliferation of agents resident on all the hardware (which must be separately managed and updated) are important deliverables of Cisco UCS. Cisco UCS Manager, using role-based access and visibility, helps enable cross-function communication efficiency, promoting collaboration between data center roles for increased productivity.

Cisco Data Center VM-FEX Virtualization Support and Virtualization Adapter

With Cisco data center VM-FEX, virtual machines have virtual links that allow them to be managed in the same way as physical links. Virtual links can be centrally configured and managed without the complexity of traditional systems, which interpose multiple switching layers in virtualized environments. I/O configurations and network profiles move along with virtual machines, helping increase security and efficiency while reducing complexity. Cisco data center VM-FEX helps improve performance and reduce Network Interface Card (NIC) infrastructure.

Dynamic Provisioning with Service Profiles

Cisco UCS Manager delivers service profiles, which contain abstracted server-state information, creating an environment in which everything unique about a server is stored in the fabric, and the physical server is simply another resource to be assigned. Cisco UCS Manager implements role-based and policy-based management focused on service profiles and templates. These mechanisms fully provision one or many servers and their network connectivity in minutes, rather than hours or days.

Cisco UCS Manager

Cisco UCS Manager (UCSM) is an embedded, unified manager that provides a single point of management for Cisco UCS. Cisco UCS Manager can be accessed through an intuitive GUI, a command-line interface (CLI), or the comprehensive open XML API. It manages the physical assets of the server and storage - LAN connectivity and it is designed to simplify the management of virtual network connections through integration with several major hypervisor vendors. It provides IT departments with the flexibility to allow people to manage the system as a whole, or to assign specific management functions to individuals based on their roles as managers of server or network hardware assets. It simplifies operations by automatically discovering all the components available on the system and enabling a stateless model for resource use. Every instance of Cisco UCS Manager and all of the components managed by it form a domain. Multiple Domains can be managed through Cisco UCS Central which integrates with Cisco UCS Manager, and utilizes it to provide global configuration capabilities for pools, policies, and firmware. Cisco UCS Central software manages multiple, globally distributed Cisco UCS domains with thousands of servers from a single pane.

The elements managed by Cisco UCS Manager include:

- Cisco UCS Integrated Management Controller (IMC) firmware
- RAID controller firmware and settings
- BIOS firmware and settings, including server Universal User ID (UUID) and boot order
- Converged Network Adapter (CNA) firmware and settings, including MAC addresses and WorldWide Names (WWNs) and SAN boot settings
- Virtual port groups used by virtual machines, using Cisco data center VM-FEX technology
- Interconnect configuration, including uplink and downlink definitions, MAC address and WWN pinning, VLANs, VSANs, Quality of Service (QoS), bandwidth allocations, Cisco Data Center VM-FEX settings, and EtherChannels to upstream LAN switches

I

Cisco Unified Computing System Components

Figure 2 shows the Cisco Unified Computing System (UCS) components.



Figure 2 Cisco UCS Components

Cisco UCS is designed from the start to be programmable and self-integrating. A server's entire hardware stack, ranging from server firmware and settings to network profiles, is configured through model-based management. With Cisco virtual interface cards (VICs), even the number and type of I/O interfaces is programmed dynamically, making every server ready to power any workload at any time.

With model-based management, administrators manipulate a model of a desired system configuration and associate a model's service profile with hardware resources, and the system configures itself to match the model. This automation accelerates provisioning and workload migration with accurate and rapid scalability. The result is increased IT staff productivity, improved compliance, and reduced risk of failures due to inconsistent configurations.

Cisco FEX Technology reduces the number of system components that need to be purchased, configured, managed, and maintained by condensing three network layers into one. It eliminates both blade server and hypervisor-based switches by connecting Cisco UCS Fabric Interconnect ports directly to individual blade servers and virtual machines. Virtual networks are now managed exactly the same way that physical networks are, but enable massive scalability. This approach represents a radical simplification compared to traditional systems, reducing capital expenditures (CapEx) and operating expenses (OpEx) while increasing business agility, simplifying and accelerating deployment, and improving performance.

Cisco UCS Fabric Interconnects

Cisco UCS Fabric Interconnects create a unified network fabric throughout Cisco UCS. They provide uniform access to both networks and storage, eliminating the barriers to deployment of a fully virtualized environment based on a flexible, programmable pool of resources. Cisco Fabric Interconnects comprise a family of line-rate, low-latency, lossless 10 Gigabit Ethernet, IEEE Data Center Bridging (DCB), and FCoE interconnect switches. Based on the same switching technology as the Cisco Nexus® 5000 Series Switches, Cisco UCS 6200 Series Fabric Interconnects provide additional features and management capabilities that make them the central nervous system of Cisco UCS. The Cisco UCS Manager software runs inside the Cisco UCS Fabric Interconnects. The Cisco UCS 6200 Series Fabric Interconnects expand the Cisco UCS networking portfolio and offer higher capacity, higher port density, and lower power consumption. These interconnects provide the management and communication backbone for the Cisco UCS B-Series Blade Servers and Cisco UCS Blade Server Chassis. All chassis and all blades that are attached to interconnects are part of a single, highly available management domain. By supporting unified fabric, the Cisco UCS 6200 Series provides the flexibility to support LAN and SAN connectivity for all blades within its domain at configuration time. Typically deployed in redundant pairs, Cisco UCS Fabric Interconnects provide uniform access to both networks and storage, facilitating a fully virtualized environment.

The Cisco UCS Fabric Interconnect portfolio currently consists of the Cisco UCS 6248UP Fabric Interconnects deployed in redundant pair.

Figure 3 Cisco UCS 6248UP 48-Port Fabric Interconnect



The Cisco UCS 6248UP 48-Port Fabric Interconnect is a one-rack-unit (1RU) 10 Gigabit Ethernet, IEEE DCB, and FCoE interconnect providing more than 1-terabit-per-second (Tbps) throughput with low latency. It has 32 fixed ports of Fibre Channel, 10 Gigabit Ethernet, IEEE DCB, and FCoE Enhanced Small Form-Factor Pluggable (SFP+) ports.

One expansion module slot can provide up to 16 additional Fibre Channel, 10 Gigabit Ethernet, IEEE DCB, and FCoE SFP+ ports.

Cisco UCS Virtual Interface Card 1240

A Cisco innovation, the Cisco UCS VIC 1240 is a four-port 10 Gigabit Ethernet, FCoE-capable modular LAN on motherboard (mLOM) designed exclusively for the M3 generation of Cisco UCS B-Series Blade Servers. When used in combination with an optional port expander, the Cisco UCS VIC 1240 capabilities can be expanded to eight ports of 10 Gigabit Ethernet.

Cisco UCS Virtual Interface Card 1280

A Cisco innovation, the Cisco UCS VIC 1280 is an eight-port 10 Gigabit Ethernet, FCoE-capable mezzanine card designed exclusively for Cisco UCS B-Series Blade Servers.

The Cisco UCS VIC 1240 and 1280 enable a policy-based, stateless, agile server infrastructure that can present up to 256 PCI Express (PCIe) standards-compliant interfaces to the host that can be dynamically configured as either NICs or HBAs. In addition, the Cisco UCS VIC 1280 supports Cisco Data Center VM-FEX technology, which extends the Cisco UCS Fabric Interconnect ports to virtual machines, simplifying server virtualization deployment.



Figure 4

The Cisco UCS 5108 Blade Server Chassis is a 6RU blade chassis that accepts up to eight half-width Cisco UCS B-Series Blade Servers or up to four full-width Cisco UCS B-Series Blade Servers, or a combination of the two. The Cisco UCS 5108 can accept four redundant power supplies with automatic load sharing and failover and two Cisco UCS 2100 or 2200 Series Fabric Extenders. The chassis is managed by Cisco UCS chassis management controllers, which are mounted in the Cisco UCS Fabric Extenders and work in conjunction with Cisco UCS Manager to control the chassis and its components.

A single Cisco UCS managed domain can theoretically scale to up to 40 individual chassis and 320 blade servers. At this time, Cisco UCS supports up to 20 individual chassis and 160 blade servers.

Basing the I/O infrastructure on a 10-Gbps unified network fabric allows Cisco UCS to have a streamlined chassis with a simple yet comprehensive set of I/O options. The result is a chassis that has only five basic components:

- The physical chassis with passive midplane and active environmental monitoring circuitry
- Four power supply bays with power entry in the rear and hot-swappable power supply units accessible from the front panel
- Eight hot-swappable fan trays, each with two fans
- Two Cisco Fabric Extender slots accessible from the back panel
- Eight half width Cisco Blade Server slots accessible from the front panel

Cisco UCS 5100 Series Blade Server Chassis

Figure 5 Cisco UCS B200 M3 Blade Servers



The Cisco UCS B200 M3 Blade Server delivers performance, versatility, and density without compromise. It addresses the broadest set of workloads, from IT and web infrastructure to distributed databases. Building on the success of the Cisco UCS B200 M2 Blade Server, the enterprise-class Cisco UCS B200 M3 Blade Server further extends the capabilities of the Cisco UCS portfolio in a half-width blade form factor. The Cisco UCS B200 M3 harnesses the power of the latest Intel Xeon processor E5-2600 product family, with up to 384 GB of RAM (using 16-GB DIMMs), two disk drives, and up to dual 4x 10 Gigabit Ethernet throughput. In addition, Cisco UCS has the architectural advantage of not having to power and cool excess switches in each blade chassis. With a larger power budget per blade server, Cisco can design uncompromising expandability and capabilities in its blade servers, as evidenced by the new Cisco UCS B200 M3, with its leading memory slot and drive capacity.

Cisco Nexus 5500 Series Switch

The Cisco Nexus 5500 Series Switch is designed for data center environments with cut-through technology that enables consistent, low-latency Ethernet solutions with front-to-back or back-to-front cooling and data ports in the rear, bringing switching into close proximity with servers and making cable

runs short and simple. The switch series is highly serviceable, with redundant, hot-pluggable power supplies and fan modules. It uses data-center-class Cisco NX-OS Software for high reliability and ease of management.

Cisco Nexus 5500 series switches provide higher density, lower latency, and multilayer services. The Cisco Nexus 5500 series switch is well suited for enterprise-class data center server access layer deployments across a diverse set of physical, virtual, storage-access, and high-performance computing (HPC) data center environments.

Figure 6 Cisco Nexus 5548UP



The Cisco Nexus 5548UP is a 1RU 10 Gigabit Ethernet (10 GE), Fibre Channel (FC), and Fibre Channel over Ethernet (FCoE) switch offering up to 960 Gbps of throughput and up to 48 ports. The switch has 32 unified ports and one expansion slot supporting modules with 10 Gigabit Ethernet and FCoE ports or connectivity to Fibre Channel SANs with 8/4/2/1 Gbps Fibre Channel switch ports, or both.

Cisco UCS Service Profiles

Programmatically Deploying Server Resources

Cisco UCS Manager provides centralized management capabilities, creates a unified management domain, and serves as the central nervous system of the Cisco UCS. Cisco UCS Manager is embedded device management software that manages the system from end-to-end as a single logical entity through an intuitive GUI, CLI, or XML API. Cisco UCS Manager implements role- and policy-based management using service profiles and templates. This construct improves IT productivity and business agility. Now infrastructure can be provisioned in minutes instead of days, shifting IT's focus from maintenance to strategic initiatives.

Dynamic Provisioning with Service Profiles

Cisco UCS resources are abstract in the sense that their identity, I/O configuration, MAC addresses and WWNs, firmware versions, BIOS boot order, and network attributes (including QoS settings, ACLs, pin groups, and threshold policies) all are programmable using a just-in-time deployment model. The manager stores this identity, connectivity, and configuration information in service profiles that reside on the Cisco UCS 6200 Series Fabric Interconnect. A service profile can be applied to any blade server to provision it with the characteristics required to support a specific software stack. A service profile allows server and network definitions to move within the management domain, enabling flexibility in the use of system resources. Service profile templates allow different classes of resources to be defined and applied to a number of resources, each with its own unique identities assigned from predetermined pools.

Service Profiles and Templates

A service profile contains configuration information about the server hardware, interfaces, fabric connectivity, and server and network identity. The Cisco UCS Manager provisions servers utilizing service profiles. The Cisco UCS Manager implements a role-based and policy-based management focused on service profiles and templates. A service profile can be applied to any blade server to provision it with the characteristics required to support a specific software stack. A service profile allows server and network definitions to move within the management domain, enabling flexibility in the use of system resources.

Service profile templates are stored in the Cisco UCS 6200 Series Fabric Interconnects for reuse by server, network, and storage administrators. Service profile templates consist of server requirements and the associated LAN and SAN connectivity. Service profile templates allow different classes of resources to be defined and applied to a number of resources, each with its own unique identities assigned from predetermined pools.

The Cisco UCS Manager can deploy the service profile on any physical server at any time. When a service profile is deployed to a server, the Cisco UCS Manager automatically configures the server, adapters, Fabric Extenders, and Fabric Interconnects to match the configuration specified in the service profile. A service profile template parameterizes the UIDs that differentiate between server instances.

This automation of device configuration reduces the number of manual steps required to configure servers, Network Interface Cards (NICs), Host Bus Adapters (HBAs), and LAN and SAN switches. The Figure 9 shows the Service profile which contains abstracted server state information, creating an environment to store unique information about a server.



Figure 7 Service Profile

UCS Central

Cisco UCS® Manager provides a single point of management for an entire Cisco Unified Computing System[™] (Cisco UCS) domain of up to 160 servers and associated infrastructure. Cisco UCS Manager uses a policy-based approach to provision servers by applying a desired configuration to physical infrastructure. Using Cisco UCS service profiles, administrators can reproduce existing physical

environments, including the I/O configuration, firmware, and settings. The configuration is applied quickly, accurately, and automatically, improving business agility. A role-based access control (RBAC) model helps ensure security of the system configurations.

Cisco UCS Central Software extends the simplicity and agility of managing a single Cisco UCS domain across multiple Cisco UCS domains. Cisco UCS Central Software allows companies to easily work on a global scale, putting computing capacity close to users while managing infrastructure with centrally defined policies. Cisco UCS Central Software makes it easy to help ensure global policy compliance, with subject-matter experts choosing the resource pools and policies that need to be enforced globally or managed locally. With a simple drag-and-drop operation, Cisco UCS service profiles can be moved between geographies to enable fast deployment of infrastructure, when and where it is needed, to support business workloads. Cisco UCS Central Software does not replace Cisco UCS Manager, which is the basic engine for managing a Cisco UCS domain. It builds on the capabilities provided by Cisco UCS Manager and requires it to be in place to effect changes in individual domains.



Figure 8 Cisco UCS Central Software Architecture

Features and Benefits of Cisco UCS Central

Cisco UCS Central Software enables global management of many Cisco UCS domains, making staff more efficient and effective. It gives Cisco UCS administrators a high-level view and management of all, or groups of, Cisco UCS domains with:

- Centralized Inventory of all Cisco UCS components for a definitive view of the entire infrastructure and simplified integration with current Information Technology Infrastructure Library (ITIL) processes
- Centralized, policy-based firmware upgrades that can be applied globally or selectively through automated schedules or as business workloads demand
- Global ID pooling to eliminate identifier conflicts
- Global administrative policies that enable both global and local management of the Cisco UCS domains
- An XML API, building on the Cisco UCS Manager XML API for easy integration into higher-level data center management frameworks

EMC VNX Storage Family

The EMC VNX family of storage systems represents EMC's next generation of unified storage, optimized for virtual environments, while offering a cost effective choice for deploying mission-critical enterprise applications such as Oracle JD EDwards. The massive virtualization and consolidation trends with servers demand a new storage technology that is dynamic and scalable. The EMC VNX series meets these requirements and offers several software and hardware features for optimally deploying enterprise applications such. The EMC VNX family is shown in Figure 9.



Figure 9 The EMC VNX Family of Unified Storage Platforms

A key distinction of the VNX Series is support for both block and file-based external storage access over a variety of access protocols, including Fibre Channel (FC), iSCSI, FCoE, NFS, and CIFS network shared file access. Furthermore, data stored in one of these systems, whether accessed as block or file-based storage objects, is managed uniformly via Unisphere[®], a web-based interface window. For more information on Unisphere see the White Paper titled, Introducing EMC Unisphere: A Common Midrange Element Manager.

EMC VNX Storage Platforms

The EMC VNX Series continues the EMC tradition of providing some of the highest data reliability and availability in the industry. Apart from this they also include in their design a boost in performance and bandwidth to address the sustained data access bandwidth rates. The new system design has also placed heavy emphasis on storage efficiencies and density, as well as crucial green storage factors, such as a smaller data center footprint, lower power consumption, and improvements in power reporting.

The VNX has many features that help improve availability. Data protection is heightened by the lack of any single point of failure from the network to the actual disk drive in which the data is stored. The data resides on the VNX for block storage system, which delivers data availability, protection, and performance. The VNX uses RAID technology to protect the data at the drive level. All data paths to and from the network are redundant.

The basic design principle for the VNX Series storage platform includes the VNX for file front end and the VNX for block hardware for the storage processors on the back end. The control flow is handled by the storage processors in block-only systems and the control station in the file-enabled systems. The VNX OE for block software has been designed to ensure the I/O is well balanced between the two SPs. At the time of provisioning, the odd number LUNs are owned by one SP and even number LUNs are owned by the other. This results in LUNs being evenly distributed between the two SPs. If a failover occurs, LUNs would trespass over to the alternate path/SP. EMC PowerPath[®] restores the "default": path once the error condition is recovered. This brings the LUNs back to a balanced state between the SPs. For more information on EMC VNX Series, see:

http://www.emc.com/collateral/hardware/data-sheets/h8520-vnx-family-ds.pdf

Key efficiency features available with the EMC VNX Series include FAST Cache and FAST VP.

FAST Cache Technology

FAST Cache is a storage performance optimization feature that provides immediate access to frequently accessed data. In traditional storage arrays, the DRAM caches are too small to maintain the hot data for a long period of time. Very few storage arrays give an option to non-disruptively expand DRAM cache, even if they support DRAM cache expansion. FAST Cache extends the available cache to customers by up to 2 TB using enterprise Flash drives. FAST Cache tracks the data temperature at 64 KB granularity and copies hot data to the Flash drives once its temperature reaches a certain threshold. After a data chunk gets copied to FAST Cache, the subsequent accesses to that chunk of data will be served at Flash latencies. Eventually, when the data temperature cools down, the data chunks get evicted from FAST Cache and will be replaced by newer hot data. FAST Cache uses a simple Least Recently Used (LRU) mechanism to evict the data chunks.

FAST Cache is built on the premise that the overall applications' latencies can improve when most frequently accessed data is maintained on a relatively smaller sized, but faster storage medium, like Flash drives. FAST Cache identifies the most frequently accessed data which is temporary and copies it to the flash drives automatically and non-disruptively. The data movement is completely transparent to applications, thereby making this technology application-agnostic and management-free. For example, FAST Cache can be enabled or disabled on any storage pool simply by selecting/clearing the "FAST Cache" storage pool property in advanced settings.

FAST Cache can be selectively enabled on a few or all storage pools within a storage array, depending on application performance requirements and SLAs.

There are several distinctions to EMC FAST Cache:

- It can be configured in read /write mode, which allows the data to be maintained on a faster medium for longer periods, irrespective of application read-to-write mix and data re-write rate.
- FAST Cache is created on a persistent medium like Flash drives, which can be accessed by both the storage processors. In the event of a storage processor failure, the surviving storage processor can simply reload the cache rather than repopulating it from scratch. This can be done by observing the data access patterns again, which is a differentiator.
- Enabling FAST Cache is completely non-disruptive. It is as simple as selecting the Flash drives that are part of FAST Cache and does not require any array disruption or downtime.
- Since FAST Cache is created on external Flash drives, adding FAST Cache will not consume any extra PCI-E slots inside the storage processor.



Additional information on EMC Fast Cache is documented in the white paper titled EMC FAST Cache – A Detailed Review which is available at:

http://www.emc.com/collateral/software/white-papers/h8046-clariion-celerra-unified-fast-cache-wp.pd f

FAST VP

VNX FAST VP is a policy-based auto-tiering solution for enterprise applications. FAST VP operates at a granularity of 1 GB, referred to as a "slice." The goal of FAST VP is to efficiently utilize storage tiers to lower customers' TCO by tiering colder slices of data to high-capacity drives, such as NL-SAS, and to increase performance by keeping hotter slices of data on performance drives, such as Flash drives. This occurs automatically and transparently to the host environment. High locality of data is important to realize the benefits of FAST VP. When FAST VP relocates data, it will move the entire slice to the new storage tier. To successfully identify and move the correct slices, FAST VP automatically collects and analyzes statistics prior to relocating data. Customers can initiate the relocation of slices manually or automatically by using a configurable, automated scheduler that can be accessed from the Unisphere management tool. The multi-tiered storage pool allows FAST VP to fully utilize all the storage tiers: Flash, SAS, and NL-SAS. The creation of a storage pool allows for the aggregation of multiple RAID groups, using different storage tiers, into one object. The LUNs created out of the storage pool can be either thickly or thinly provisioned. These "pool LUNs" are no longer bound to a single storage tier. Instead, they can be spread across different storage tiers within the same storage pool. If you create a storage pool with one tier (Flash, SAS, or NL-SAS), then FAST VP has no impact on the performance of the system. To operate FAST VP, you need at least two tiers.

Additional information on EMC FAST VP for Unified Storage is documented in the white paper titled EMC FAST VP for Unified Storage System – A Detailed Review, see:

http://www.emc.com/collateral/software/white-papers/h8058-fast-vp-unified-storage-wp.pdf

FAST Cache and FAST VP are offered in a FAST Suite package as part of the VNX Total Efficiency Pack. This pack includes the FAST Suite which automatically optimizes for the highest system performance and lowest storage cost simultaneously. In addition, this pack includes the Security and Compliance Suite which keeps data safe from changes, deletions, and malicious activity. For additional information on this Total Efficiency Pack as well as other offerings such as the Total Protection Pack, see:

http://www.emc.com/collateral/software/data-sheet/h8509-vnx-software-suites-ds.pdf

EMC PowerPath

EMC PowerPath is host-based software that provides automated data path management and load-balancing capabilities for heterogeneous server, network, and storage deployed in physical and virtual environments. A critical IT challenge is being able to provide predictable, consistent application availability and performance across a diverse collection of platforms. PowerPath is designed to address those challenges, helping IT meet service-level agreements and scale-out mission-critical applications.

This software supports up to 32 paths from multiple HBAs (iSCSI TCI/IP Offload Engines [TOEs] or FCoE CNAs) to multiple storage ports when the multipathing license is applied. Without the multipathing license, PowerPath will use only a single port of one adapter (PowerPath SE). In this mode, the single active port can be zoned to a maximum of two storage ports. This configuration provides storage port failover only, not host-based load balancing or host-based failover. It is supported, but not recommended, if the customer wants true I/O load balancing at the host and also HBA failover.

PowerPath balances the I/O load on a host-by-host basis. It maintains statistics on all I/O for all paths. For each I/O request, PowerPath intelligently chooses the most under utilized path available. The available under utilized path is chosen based on statistics and heuristics, and the load-balancing and failover policy in effect.

In addition to the load balancing capability, PowerPath also automates path failover and recovery for high availability. If a path fails, I/O is redirected to another viable path within the path set. This redirection is transparent to the application, which is not aware of the error on the initial path. This avoids sending I/O errors to the application. Important features of PowerPath include standardized path management, optimized load balancing, and automated I/O path failover and recovery.

For more information on Powerpath, see:

http://www.emc.com/collateral/software/data-sheet/1751-powerpath-ve-multipathing-ds.pdf

Oracle VM

Oracle VM is a platform that provides a fully equipped environment with all the latest benefits of virtualization technology. Oracle VM enables you to deploy operating systems and application software within a supported virtualization environment. Oracle VM is a Xen-based hypervisor that runs at nearly bare-metal speeds.

Oracle VM Architecture

Figure 11 elaborates on the Oracle VM architecture. The Oracle VM architecture has three important components:



Figure 11 Oracle VM Architecture

- **Oracle VM Manager**—Provides the user interface, which is a standard ADF (Application Development Framework) web application, to manage Oracle VM Servers. Manages virtual machine lifecycle, including creating virtual machines from installation media or from a virtual machine template, deleting, powering off, uploading, deployment and live migration of virtual machines. Manages resources, including ISO files, virtual machine templates and sharable hard disks.
- Oracle VM Server—A self-contained virtualization environment designed to provide a lightweight, secure, server-based platform for running virtual machines. Oracle VM Server is based upon an updated version of the underlying Xen hypervisor technology, and includes Oracle VM Agent.
- **Oracle VM Agent**—Installed with Oracle VM Server. It communicates with Oracle VM Manager for management of virtual machines.

Advantage of using Oracle VM for Oracle JD Edwards EnterpriseOne with Oracle RAC Database

Oracle's virtualization technologies are an excellent delivery vehicle for Independent Software Vendors (ISV's) looking for a simple, easy-to-install and easy-to-support application delivery solution.

Oracle now offers a highly available, grid-ready virtualization solution for your data center, combining all the benefits of a fully virtualized environment.

The combination of Oracle VM and Oracle JD Edwards EnterpriseOne enables a better server consolidation (bare-metal deployments with under utilized CPU resources can often benefit from consolidation with other workloads using server virtualization) sub-capacity licensing, and rapid provisioning.

Oracle RAC on Oracle VM also supports the creation of non-production virtual clusters on a single physical server for production demos and test/dev environments. This deployment combination permits dynamic changes to pre-configured database resources for agile responses to changing service level requirements common in consolidated environments.

Moreover, Oracle VM is the only software based virtualization solution that is fully supported and certified for both Oracle JD Edwards and Oracle real Application Clusters.

There are several reasons why customers may want to run Oracle JD Edwards EnterpriseOne in an Oracle VM environment. Some of the more common ones are:

- Server Consolidation: Oracle JD Edwards EnterpriseOne under utilized CPU resources or variable CPU utilization can often benefit from consolidation with other workloads using server virtualization. A typical use case for this scenario would be the consolidation of several Oracle JD Edwards EnterpriseOne components, such as multiple Batch & interactive Servers running on individual hardware into virtualized environment through multiple VMs hosted on less number of servers.
- **Sub-capacity licensing**: The current Oracle licensing model requires the Oracle RAC database to be licensed for all CPUs on each server in the cluster. Several times customers wish to use only a subset of the CPUs on the server for a particular Oracle RAC database. Oracle VM can be configured in such way that it is recognized as a hard partition. Hard partitions allow customers to only license those CPUs used by the partition instead of licensing all CPUs on the physical server. More information on sub-capacity licensing using hard partitioning can be found in the Oracle partitioning paper. For more information on using hard partitioning with Oracle VM refer to the "Hard Partitioning with Oracle VM" white paper.
- **Create a virtual cluster**: Oracle VM enables the creation of a virtual cluster on a single physical server. This use case is particularly interesting for product demos, educational settings, and test environments. This configuration should never be used to run production Oracle JD Edwards environment. The following are valid deployments for this use case:
 - Test/ development cluster
 - Demo cluster
 - Education cluster
- **Rapid Provisioning:** The provisioning time of a new application consists of the server (physical or virtual) deployment time, and the software install and configuration time. Oracle VM can help reduce the deployment time for both of these components. Oracle VM supports the ability to create deployment templates. These templates can then be used to rapidly provision new systems.

Oracle VM Templates for JD Edwards EnterpriseOne enable rapid implementation of your JD Edwards EnterpriseOne system. With these pre configured, pretested templates of the JD Edwards EnterpriseOne enterprise, database, and HTML servers, you can have your system up and running in just a few days. Oracle VM Templates contain the complete technology stack necessary to run the server: operating system, database, web server, and JD Edwards EnterpriseOne tools and applications.

Paravirtualized VM (PVM)

Guest virtual machines running on Oracle VM server can be configured in para-virtualized mode. In this mode the kernel of the guest operating system is modified to distinguish that it is running on a hypervisor instead of on the bare metal hardware. As a result, I/O actions and system clock timers in particular are handled more efficiently, as compared with non-paravirtualized systems where I/O hardware and timers have to be emulated in the operating system. Oracle VM supports PV kernels for Oracle Linux and Red Hat Enterprise Linux, offering better performance and scalability.

Oracle JD Edwards EnterpriseOne

Oracle JD Edwards is the ERP solution of choice for many small and medium-sized businesses (SMB). JDE E1 offers an attractive combination of a large number of easy-to-deploy and easy-to-use ERP applications across multiple industries. These applications include Supply Chain Management (SCM),

Human Capital Management (HCM), Supplier Relationship Management (SRM), Financials, and Customer Relationship Management (CRM). The various components of Oracle JD Edwards EnterpriseOne are shown in Figure 12.



Figure 12 JD Edwards EnterpriseOne Components

HTML Server

HTML Server is the interface of the JDE to the outside world. It allows the JDE ERP users to connect to their Applications using their Browsers via the Web server. It is one of the Tiers of the standard three-tier JDE Architecture. HTML Server is just not an interface, it has logic and runs Web Services which processes some of the data and only the result set is sent through the WAN to the end users.

Enterprise Server

Enterprise Server hosts the JDE Applications that execute all the basic functions of the JDE ERP systems, like running the Transaction processing service, Batch Services, data replication, security and the entire time stamp and distributed processing happens at this layer. Multiple enterprise servers can be added for scalability, especially when we need to apply Electronic Software Updates (ESU) to one server while the other is online.

Database Server

Database Server in a JDE environment is used to host the data. It simply is a data repository and is not used to process JDE logic. The JDE Database server can run many supported databases such as, Oracle, SQL Server, DB2 or Access. Since this server does not run any Applications as mentioned, the only licensing that is required for this server is the database license; hence the server should be sized correctly. If this server has excess capacity the UBE's can be run on this server to improve their performance.

Deployment Server

Deployment server essentially is a centralized software (C Code) repository for deploying software packages to all the servers and workstations that are part of the Cisco JDE solution. Although the Deployment server is not a business critical server, it is very important to note that it is a critical piece of the JDE Architecture, without which the Installation, upgrade, development or modification of packages (codes) or reports would become impossible.

Server Manager

The Server Manager is a key JDE software component that helps customers deploy the latest JDE tools software onto various JDE Servers that are registered with the server manager. The server manager is web based and enables life cycle management of JDE products like the Enterprise server and HTML server via a web based console. It has in-built abilities for configuration management and it maintains an audit history of changes made to the components and configuration of various JDE Server software.

Batch Server

Batch processes (UBE) are background processes requiring no operator intervention or interactivity. One of most important batch process in JDE is MRP Process. Batch Process can be scheduled using a Process Scheduler which runs in the Batch Server. JDE customers running a high volume of reports often split the load on their Enterprise server such that they have one or more Batch servers which handle the high volume reporting (UBE) loads, thereby freeing up their enterprise server to handle interactive user loads more efficiently. This leads to better interactive application and UBE performance due to the expanded scaling provided by the additional hardware.

Design Considerations for Oracle JD Edwards EnterpriseOne Implementation on Cisco UCS with Oracle VM

The design document provides best practices for designing Oracle JD Edwards EnterpriseOne virtualized environment with Cisco UCS, EMC VNX with Oracle VM. There are several factors which need to be considered vis-à-vis JD Edwards HTML Server, JDE E1 application server for interactive and batch (UBE) processes and most importantly the scalability, ease of deployment and maintenance of hardware installed for JD Edwards deployment.

Scalable Architecture Using Cisco UCS Servers

An obvious immediate benefit with Cisco is a single trusted vendor providing all the components needed for a JD Edwards EnterpriseOne deployment with the ability to provide scalable platform, dynamic provisioning, failover with minimal downtimes and reliability.

Some of the capabilities offered by Cisco UCS, which complement the scalable architecture include the following:

• **Dynamic provisioning and service profiles**—Cisco UCS Manager supports service profiles, which contain abstracted server states, creating a stateless environment. It implements role-based and policy-based management focused on service profiles and templates. These mechanisms fully provision one or many servers and their network connectivity in minutes, rather than hours or days.

I

This can be very valuable in a virtualized JD Edwards EnterpriseOne environment, wherein new VMs may need to be provisioned on short notice, or even whole new farm for specific development activities.

- **Cisco Unified Fabric and Fabric Interconnects**—The Cisco Unified Fabric leads to a dramatic reduction in network adapters, blade-server switches, and cabling by passing all network and storage traffic over one cable to the parent Cisco Fabric Interconnects, where it can be processed and managed centrally. This improves performance and reduces the number of devices that need to be powered, cooled, secured, and managed. The Cisco UCS 6200 series Fabric Interconnects offer key features and benefits, including:
 - High performance Unified Fabric with line-rate, low-latency, lossless 10 Gigabit Ethernet, and Fibre Channel over Ethernet (FCoE).
 - Centralized unified management with Cisco UCS Manager Software.
 - Virtual machine optimized services with the support for VN-Link technologies.

Unified Fabric for Oracle JD Edwards deployment helps to use same fabric path for both Ethernet and FC traffic. This provides multiple storage options using either block or file level storage. 10 Gigabit loseless Ethernet connectivity provides high throughput between Oracle Virtual Servers, thus helping to reduce long running UBE execution time such as MRP.

To accurately design JD Edwards EnterpriseOne on any hardware configuration, we need to understand the characteristics of each tier in JDE deployment vis-à-vis CPU, memory and I/O operations. For instance JDE Enterprise Server for Interactive is both CPU and memory intensive, but is low on disk utilization, whereas, the database server is more memory and disk intensive rather than CPU utilization. Some of the important characteristics to design JD Edwards EnterpriseOne on Cisco UCS Server are listed in Table 1:

Server Type	CPU	Memory	Disk I/O	Comments
JDE HTML Server	Medium	Medium	Low	Multiple JVMs run across single HTML Server and due to high GC activity each JVM require intensive CPU processing cycles.Multiple JVMs configured on a single server with optimum heap size reduces the Full GC pause time for each JVM when compared with a single JVM with large heap size. Guest OS for HTML Server can be configured through virtual disk which is carved out of a Storage Repository with a RAID Pool with low disk giving lesser IOPs.
				This is also a reason we chose a storage repository with RAID 5 and 10 SAS disks configured for HTML Server as well as Enterprise Server deployment. The Guest VM for HTML Server is configured with 8 vCPUs and 64 GB of physical memory
JDE Enterprise Server for Interactive apps	High	Medium	Low	JDE Enterprise Server for interactive is CPU intensive and requires very less IOPs throughout.
				We chose a Guest OS with 10 vCPUs and 64 GB of physical memory. The Virtual Disk is carved out of a common repository used both for HTML and Enterprise Server VMs.

1

Table 1 Oracle JD Edwards EnterpriseOne Design Considerations

Server Type	CPU	Memory	Disk I/O	Comments
JDE Enterprise Server for Batch	High	Low	Low	JDE Enterprise server for batch is CPU intensive but is low on memory and Disk utilization. Presently we have chosen to use configuration for batch server VM similar to JDE Enterprise Server for Apps.
Database Server	High	High	High	Database Server has high memory and Disk utilization (esp. for UBE processes)
				The Oracle RAC nodes are configures with 10 vcPUs and 120 GB of memory each. The DATA and LOG files are configured on physical disk attached directly to the Guest VM. This allows lower IO latency for both DATA and LOG drives.
Deployment Server and Server Manager	Low	Low	Low	Deployment Server is utilized to build and deploy packages for JDE deployment. Server Manager is used for Monitoring JDE run time for example, monitoring Daemon process.
				Thus, UCS B200 M3 with two Intel E5-2609 (4 core) processors and just 32 GB of physical memory was deployed.
				The utilization of this server is maximized by deploying both Server Manager and Deployment Server on a single physical server.

Table 1 Oracle JD Edwards EnterpriseOne Design Considerations

Boot from SAN

I

Boot from SAN is a critical feature which helps to maximize the benefits of Cisco UCS stateless computing, which does not require a static binding between a physical server and the OS/ hypervisor hosted on that server. The hypervisor is installed on a SAN LUN and is booted using the service profile.

When the service profile is moved to another server, the server policy and the PWWN of the HBAs also moves along with the service profile. Thereby, the new server takes the identity of the old server and looks identical to the old server.

The following are the benefits of boot from SAN:

- Reduce Server Footprint—Boot from SAN eliminates the need for each server to have its own direct-attached disk (internal disk) which is a potential point of failure. The following are the advantages of diskless servers:
 - Require less physical space
 - Require less power
 - Require fewer hardware components
 - Less expensive
- Disaster Recovery—Boot information and production data stored on a local SAN can be replicated to another SAN at a remote disaster recovery site. When server functionality at the primary site goes down in the event of a disaster, the remote site can take over with a minimal downtime.
- Recovery from server failures—Recovery from server failures is simplified in a SAN environment. Data can be quickly recovered with the help of server snapshots, and mirrors of a failed server in a SAN environment. This greatly reduces the time required for server recovery.
- High Availability—A typical data center is highly redundant in nature with redundant paths, redundant disks and redundant storage controllers. The operating system images are stored on SAN disks which eliminates potential problems caused due to mechanical failure of a local disk.
- Rapid Re-deployment—Businesses that experience temporary high production workloads can take advantage of SAN technologies to clone the boot image and distribute the image to multiple servers for rapid deployment. Such servers may only need to be in production for hours or days and can be readily removed when the production need has been met. Highly efficient deployment of boot images makes temporary server usage highly cost effective.
- Centralized Image Management—When operating system images are stored on SAN disks, all upgrades and fixes can be managed at a centralized location. Servers can readily access changes made to disks in a storage array.

With boot from SAN, the hypervisor image resides on the SAN and the server communicates with the SAN through a Host Bus Adapter (HBA). The HBA BIOS contain instructions that enable the server to find the boot disk. After Power On-Self Test (POST), the server hardware component fetches the designated boot device in the hardware BOIS settings. Once the hardware detects the boot device, it follows the regular boot process.

Sizing Guidelines for Oracle JD Edwards EnterpriseOne

Sizing ERP deployments on a virtualized environment is a complex, and setting it up correctly depends on the input provided by the customers on how they intend to use the ERP system, and what their priorities are in terms of end user as well as corporate expectations.

Some of the common questions related to ERP sizing are: the number of concurrent interactive users using the system, total number of ERP end users, the kind of applications that the end users will access as well as number of reports and type of reports generated during peak activity can help size the system for optimal performance. Analyzing the demands and its characteristics, the JDE system is expected to handle during different time periods in the fiscal year is necessary to do a proper sizing.

The Oracle JD Edwards EnterpriseOne configuration used in the present deployment is geared to handle a very high workload of end users running heavy SRM interactive applications as well as a high number of batch processes. Each of the HTML Server, Enterprise Server and Database nodes are load balanced with an active-active setup. Each Oracle Virtual Server is hosting an instance of HTML Server, Enterprise Server and Oracle RAC node, thus providing failover during maintenance or failure of Oracle Virtual Server nodes.

The following sections briefly describe the sizing aspects of each tier of the three tier Oracle JD Edwards EnterpriseOne deployment architecture.

Oracle JDE HTML Server

The Oracle JDE HTML server, serves end user interactive application requests from JDE users. The JDE HTML server loads the application forms and requests services from the JDE Enterprise server for application processing based on form input. Some very lightweight application logic also runs on the JDE HTML Server. Client requests do result in significant load on the JDE HTML servers since the JDE HTML servers make and manage database as well as network connections. The JDE HTML server's utilization of CPU and memory depends heavily on the number of interactive users using the server. Disk utilization is not a major factor in the sizing of the JDE HTML Server.

Typically, on the Oracle Linux Server, the number of interactive users per JVM when deployed on an Oracle VM should be capped to around 150 to 200 interactive users for optimal performance. This allows minimizing the heap size for each of the JVM thus reduces Full GC pause time. It is recommended to having multiple JVMs load balanced through Oracle HTTP Server, thus allowing reduced GC pause time and high availability of application. Due to high number of JVMs, typically an HTML server is configured with medium memory and medium computing power.

Oracle JDE Enterprise Server

The Oracle JDE Enterprise Server acts as the central point for serving requests for application logic. The Oracle JDE EnterpriseOne clients make requests for application processing. Depending upon the JDE environment used as well as user preferences, the input data is then processed and returned back to the client. The Call Object kernels running on the JDE Enterprise server are delegated the responsibility of processing end user application processing requests and the Security kernel handles the responsibility of ensuring authentication of the end users. The application processing is CPU intensive and the CPU frequency and number of cores available to the Enterprise server plays a large part affecting the performance and throughput of the system. As the number of interactive users requests grow, the memory requirements of the JDE Enterprise server also increases. This is also true for the batch (UBE) reports that the JDE Enterprise server processes.

The typical sizing recommendation for number of users per call object kernel on Oracle VM would be between 8 - 12 users/call object kernels and about 1 security kernel for every 50 interactive users. The in memory cache usage of call object kernels increase with user load so it is typical for the memory usage of individual call objects to increase with increase in user loads.

Oracle JDE Database Server

The JDE Database Server services the data requests made by both the JDE Enterprise and JDE HTML Servers. The JDE Database Server sizing depends on the type of reports being processed as well as the interactive user loads. Some JDE reports can be very Disk I/O intensive and depending on the kind of reports being processed, careful consideration needs to be given to disk layout. If the Oracle Database Server database has ample memory available to it and the memory is utilized to cache data it can benefit application performance by reducing disk I/O operations. The JDE Database server typically benefits

from having faster disk and high memory allocation. The choice of Oracle RAC database for Oracle JD Edwards EnterpriseOne environment helps to provide high availability, increased transaction response time for concurrent UBE processes and enhanced scalability for JD Edwards EnterpriseOne online users. Moreover, the DATA and LOG disk must be configured as a physical disk to Guest OS configured for Oracle RAC nodes. In the present deployment, we have used virtual machines with 10 vCPU and 124 GB of physical memory for each of the Oracle RAC nodes.

Oracle JD Edwards EnterpriseOne Deployment Architecture

The deployment architecture of Oracle JD Edwards EnterpriseOne on is shown in Figure 13.



Figure 13 Deployment Architecture of JD Edwards EnterpriseOne on Oracle VM

The configuration for each of the Oracle JD Edward's Guest OS deployed on Oracle VM is shown in Figure 14.



Figure 14 Guest OS Configuration of Oracle JD Edwards EnterpriseOne on Oracle VM

The configuration presented in this document is based on the following main configuration components.

Oracle VM Servers	• 2x1 Cisco UCS B200M3 Blade Server equipped with two Intel Xeon E5-2690 2.9GHz Processors and 256GB of physical memory.
	• Oracle VM3.1.1 (Build 819)
JDE HTML Server 1 and 2	• Each VM is configured with 8 vCPUs and 64 GB of physical memory
	• Oracle WebLogic 10.3.6 on Oracle Linux 5.8 (uek kernel)
	• JD Edwards HTML server code release 8.98.4.10 was deployed
JDE E1 Enterprise Server (interactive apps)	Guest OS is configured with 10 vCPUs and 64 GB of physical memory
	• JDE E1 Release 9.0, Update 2, with Tools Release 8.98.4.10, deployed on Oracle Linux 5.8 (uek kernel)
JDE E1 Enterprise Server (batch/ UBEs)	Guest OS is configured with 10 vCPUs and 64 GB of physical memory
	• JDE E1 Release 9.0, Update 2, with Tools Release 8.98.4.10, deployed on Oracle Linux 5.8 (uek kernel)
JDE Database Server (node1 and node2)	• Each VM is configured with 10 vCPUs and 120 GB of physical memory
	• Oracle RAC 11.2.0.3

Table 2Configuration Components

ſ

Deployment Server and Server Manager	• Cisco UCS B200 M2 Blade Server equipped with two 4-core Intel Xeon X5620 2.4-GHz processors and configured with 24 GB of physical memory		
	• Microsoft Windows 2008 R2 Enterprise Edition		
Storage	EMC VNX 5300		
Operating System (64 bit)	 Oracle VM 3.1.1 for Oracle VM Host Guest OS are configured with Oracle Linux 5.8 (uek kernel) 		
Test Client	LoadRunner 9.5 on Microsoft Windows 2003 Server		

Table 2 Configuration Components

Infrastructure Setup

This section elaborates the infrastructure setup details used to deploy Oracle JD Edwards EnterpriseOne. The high-level workflow to configure the system is detailed in Figure 15.



Figure 15 Workflow to Setup Infrastructure for Oracle JD Edwards EnterpriseOne

Cisco Nexus Switch Configuration

This section elaborates on the procedure to configure Cisco Nexus 5548UP Switches. Some of the important configurations detailed in the section are:

- First Time Setup of Cisco Nexus 5548UP Switch
- Enabling Features and Global Configuration
- Creating VSAN and Adding FC Interfaces
- VLAN configuration
- Virtual Port Channel (vPC) configuration

First Time Setup of Cisco Nexus 5548 UP Switch

The NX-OS setup should automatically start on initial boot and connection to the serial or console port of the switch. Enter the following commands to configure the Cisco Nexus 5548UP Switch:

- 1. Enter yes to enforce secure password standards: yes
- 2. Enter the password for the administrator (adminuser): <xxxx>
- 3. Enter the password a second time to commit the password; <xxxx>
- 4. Enter yes to enter the basic configuration dialog: yes
- 5. Create another login account (yes/no) [n]: Enter
- 6. Configure read-only SNMP community string (yes/no) [n]: Enter
- 7. Configure read-write SNMP community string (yes/no) [n]: Enter
- 8. Enter the switch name: Nexus5K-A Enter
- 9. Continue with out-of-band (mgmt0) management configuration? (yes/no) [y]: Enter
- 10. Mgmt0 IPv4 address: <Nexus A mgmt0 IP> Enter
- 11. Mgmt0 IPv4 netmask: <Nexus A mgmt0 netmask> Enter
- **12**. Configure the default gateway? (yes/no) [y]: Enter
- 13. IPv4 address of the default gateway: <Nexus A mgmt0 gateway> Enter
- 14. Enable the telnet service? (yes/no) [n]: Enter
- **15**. Enable the ssh service? (yes/no) [y]: Enter
- 16. Type of ssh key you would like to generate (dsa/rsa):rsa
- 17. Number of key bits <768–2048> :1024 Enter
- **18**. Configure the ntp server? (yes/no) [y]: n Enter
- **19.** NTP server IPv4 address: <NTP Server IP> Enter
- 20. Enter basic FC configurations (yes/no) [n]: Enter
- 21. Would you like to edit the configuration? (yes/no) [n]: Enter
- Note

Be sure to review the configuration summary before enabling it.

22. Use this configuration and save it? (yes/no) [y]: Enter

Note Configuration may be continued from the console or by using SSH. To use SSH, connect to the mgmt0 address of Nexus A.

Note Log in as user admin with the password previously entered.

Follow similar to configure the Cisco Nexus 5548 Switch B (Nexus5k-B).

Enabling Features and Global Configuration

To enable appropriate Nexus 5548 switch licensing, follow these steps on Cisco Nexus 5548 A - (Nexus5k-A), and Cisco Nexus 5548 B - (Nexus5k-B) separately:

- **1.** Type "config t" to enter into the global configuration mode.
- 2. Type "feature lacp".
- 3. Type "feature fcoe".
- 4. Type "feature npiv".
- 5. Type "feature vpc".
- 6. Type "feature fport-channel-trunk".



Note FCoE feature needs to be enabled first before enabling npiv.

Verification: The figure given below, lists the enabled features on Cisco Nexus 5548 (show feature | include enabled").

Figure 16	Features	Enabled i	in Cisco	Nexus	5548
-----------	----------	-----------	----------	-------	------

Nexus5k-A# sh feature		include	enabled
fcoe	1		enabled
fex	1		enabled
interface-vlan	1		enabled
lacp	1		enabled
lldp	1		enabled
npiv	1		enabled
sshServer	1		enabled
telnetServer	1		enabled
vpc	1		enabled
Nexus5k-A#			

Creating VSAN and Adding FC Interfaces

To create VSAN and add FC interfaces, follow these steps on Cisco Nexus 5548 A - (Nexus5k-A), and Cisco Nexus 5548 B - (Nexus5k -B) separately:

I

- **1.** Type "config t" to enter into the global configuration mode.
- 2. Type "vsan database".
- 3. Type "vsan 20 name JDE".

- 4. Type "vsan 20 interface fc1/29-32".
- 5. Type "y" on the "Traffic on fc1/29 may be impacted. Do you want to continue? (y/n) [n]".
- **6.** Similarly type "y" for fc1/29 to fc1/32 interfaces.

Verification: The command sh vsan membership should lists ports fc1/29-32 under "vsan 20".

To configure the ports 29-32 as FC ports, follow these steps on Cisco Nexus 5548 A - (Nexus5k-A), and Cisco Nexus 5548 B - (Nexus5k-B) separately:

- **1.** Type "config t" to enter into the global configuration mode.
- **2.** Type "slot 1".
- **3.** Type "interface fc 1/29-32".
- 4. Type "switchport mode F".
- 5. Type "no shut".

Follow the steps in the previous section to configure the Cisco Nexus Switch B.

Verification: The command "show interface brief" should list these interfaces as FC (Admin Mode "F").

VLAN Configuration

A VLAN is a group of end stations in a switched network that is logically segmented by function, project team, or application, irrespective of the physical locations of the users. VLANs have the same attributes as physical LANs, but the end stations can be grouped even if they are not physically located on the same LAN segment.

In this design the VLANs configured are listed in Table 3.

VLAN Information	VLAN Purpose	VLAN ID
VLAN0613	For external traffic	613
VLAN0760	For traffic between HTML Server, E1 Server and DB Server	760
VLAN0191	For Oracle Clusterware Interconnect Traffic	191

Table 3 VLAN Configuration

To configure the VLANs, follow these steps:

- 1. Type "config t" to enter into the global configuration mode.
- 2. From the global configuration mode, type "vlan613" and press "Enter".
- 3. Type <<name>> to enter a descriptive name for the VLAN.
- 4. Type "vlan760".
- **5.** Type <<name>>.
- 6. Type "vlan191".
- 7. Type <<name>>.
- **8.** Type "Interface ethernet1/17-19" (make sure to choose the Ethernet interfaces where Fabric Interconnects are connected).

9. Type "switchport mode trunk".

Nexus5k-A# sh vlan

- **10.** Type "switchport trunk allowed vlan 613,760, 191".
- 11. Type "exit"

Verification: The command **show vlan** should list the vlans and interfaces assigned to it. Or, the command **show run interface <interface name>** should show the configuration for a given interface or port channel. The figure given below, lists the executed command:

VLAN Name Ports Status _____ 1 default active Po1, Eth1/7, Eth1/8, Eth1/9 Eth1/10, Eth1/11, Eth1/14 Eth1/15, Eth1/16, Eth1/17 Eth1/18, Eth1/19, Eth1/20 Eth1/21, Eth1/22, Eth1/23 Eth1/24, Eth1/25, Eth1/26 Eth1/31, Eth1/32 active Eth1/17, Eth1/19 191 Private 613 VLAN0613 active Eth1/17, Eth1/19, Eth1/32 760 Public active Eth1/17, Eth1/19, Eth1/32



Interface Eth1/32 is configured for outside traffic.

Virtual Port Channel (vPC) Configuration

A virtual port channel (vPC) allows links that are physically connected to two different Cisco Nexus 5000 Series devices to appear as a single port channel by a third device.

Cisco Nexus 5548UP vPC configurations with the vPC domains and corresponding vPC names and IDs for the present setup is listed in Table 4 and Table 5. To provide Layer 2 and Layer 3 switching, a pair of Cisco Nexus 5548UP Switches with upstream switching are deployed, providing high availability in the event of failure to Cisco UCS to handle management, application, and Network storage data traffic. In the Cisco Nexus 5548UP switch topology, a single vPC feature is enabled to provide high availability, faster convergence in the event of a failure, and greater throughput.

Table 4	vPC Mapping for Cisco Nexus 5548A
---------	-----------------------------------

vPC Domain	vPC Name	vPC ID	LAN UpLink Ports	Connected Components
100	vPC-Public1	110	FI A – eth1/9 N5KA – eth1/7	FI-A and N5kA provide vPC for all public and storage network traffic
100	vPC-Public2	111	FI B- eth1/9 N5KA – eth1/8	FI-B and N5kA provide vPC for all public network traffic
vPC Domain	vPC Name	vPC ID	LAN UpLink Ports	Connected Components
------------	-------------	--------	---------------------------------	--
100	vPC-Public1	110	FI A – eth1/10 N5KB – eth1/7	FI-A and N5kB provide vPC for all public & Storage network traffic
100	vPC-Public2	111	FI B- eth1/10 N5KB – eth1/8	FI-B and N5kB provide vPC for all public and Storage network traffic

Table 5 vPC Mapping for Cisco Nexus 5548B



Configuration of ports are listed in Table 4 and Table 5 are for demonstration. Customers can configure ports as per their environment and availability. Follow the network diagram (Figure 13)

In the vPC design table, a single vPC domain, Domain 100, is created across Cisco Nexus 5548UP member switches to define vPCs to carry specific network traffic. This topology defines two vPCs. These vPCs are managed within the Cisco Nexus 5548UP, which connects Cisco UCS Fabric Interconnects and the EMC storage system.

To create vPC, follow these steps for both Cisco Nexus 5548 A and Cisco Nexus 5548 B separately with configuration details as per Table 4 and Table 5.

- 1. In the global configuration mode, type "vpc domain 100".
- 2. Type "role priority 1000".
- 3. Type "peer-keepalive destination 10.x.x.x". (This IP is the Nexus 5548 B Management IP)
- 4. Type "int port-channel 100".
- 5. Type "switchport mode trunk".
- 6. Type "switchport trunk allowed vlan all".
- 7. Type "vpc peer-link".
- **8.** Type "int ethernet 1/3" (peer link port).
- 9. Type "switchport mode trunk".
- 10. Type "switchport trunk allowed vlan all".
- **11**. Type "channel-group 100 mode active".
- **12.** Type "Exit".



Note vPC domain creation command from Step 1 to 12 has to be executed only in one Nexus 5548 UP.

- **13.** Type "int port-channel 110". (Public & Storage Network Traffic)
- 14. Type "switchport mode trunk".
- **15.** Type "switchport trunk allowed vlan191, 760, 613".

- **16.** Type "vpc 110".
- **17.** Type "int ethernet 1/7".
- **18.** Type "channel-group 110 mode active".
- 19. Type "switchport mode trunk".
- **20.** Type "int port-channel 111". (Public & Storage Network Traffic)
- 21. Type "switchport mode trunk".
- 22. Type "switchport trunk allowed vlan191, 760, 613".
- 23. Type "vpc 111".
- **24.** Type "int ethernet 1/8".
- 25. Type "channel-group 111 mode active".
- 26. Type "switchport mode trunk".

Verification: When configuring the Cisco Nexus 5548UP with vPCs, make sure that the status for all vPCs is "Up" for connected Ethernet ports by running the commands (show vpc) from the CLI on the Cisco Nexus 5548UP Switch.

Figure 17 vPC Status on Cisco Nexus 5548UP A and Nexus 5548UP B

d	Port	Status	Active	vlans		
	Po1	up	1,191-:	192,613,760		
PC	status					
d	Port		Status	Consistency	Reason	Active vlans
10	Po11	0	up	success	success	1,191-192,6 13,760
11	Po11	1	up	success	success	1,191-192,6 13,760

For more information on vPC configuration for Cisco Nexus 5548UP switches, see:

http://www.cisco.com/en/US/prod/collateral/switches/ps9441/ps9670/configuration_guide_c.07-54356 3.html

Setting Up Jumbo Frames on Cisco Nexus 5500

Jumbo frames with an mtu size 9000 have to be setup on Cisco Nexus 5500. Oracle Interconnect traffic under normal conditions does not go to the northbound switch like the Cisco Nexus 5500, as all the private vNICs are configured in Fabric B. However if there is a partial link or IOM failure, the private interconnect traffic has to go to the immediate northbound switch (Nexus 5500 in our case) to reach Fabric B.

Follow these commands to configure Jumbo Frames on Cisco Nexus 5500 Fabric A Switch:

```
Nexus5k-A# conf terminal
Enter configuration commands, one per line. End with CNTL/Z.
Nexus5k-A(config)# class-map type network-qos class-platinum
Nexus5k-A(config-cmap-nq)# exit
Nexus5k-A(config)# policy-map type network-qos jumbo
Nexus5k-A(config-pmap-nq)# class type network-qos class-default
```

Cisco Unified Computing System Configuration

This section details the Cisco UCS configuration that is performed as part of the infrastructure build for deployment of Oracle JD Edwards EnterpriseOne. The racking, power, and installation steps can be referred from the Installation Guide, as it is beyond the scope of this document. For more details on each step refer:

• Cisco UCS 5108 Server Chassis Installation Guide:

http://www.cisco.com/en/US/docs/unified_computing/ucs/hw/chassis/install/install.html

• Cisco Unified Computing System CLI Configuration Guide:

http://www.cisco.com/en/US/docs/unified_computing/ucs/sw/cli/config/guide/2.1/b_UCSM_CLI_Configuration_Guide_2_1_chapter_010.html

 Cisco UCS Manager GUI Configuration Guide: http://www.cisco.com/en/US/docs/unified_computing/ucs/sw/gui/config/guide/2.1/b_UCSM_GUI _Configuration_Guide_2_1.html

Validate Installed Firmware

To login to Cisco UCS Manager, follow these steps:

- 1. Open the Web browser with the Cisco UCS 6248UP Fabric Interconnect cluster address.
- 2. Click Launch to download the Cisco UCS Manager software.
- 3. You might be prompted to accept security certificates; accept as necessary.
- 4. In the login page, enter "admin" for both username and password text boxes.
- 5. Click Login to access the Cisco UCS Manager software.
- 6. Click Equipment tab and then Installed Firmware tab in the right pane.
- 7. Verify the Firmware installed. The firmware during the deployment was 2.1(1a).

For more information on Firmware Management, see: http://www.cisco.com/en/US/docs/unified_computing/ucs/sw/firmware-mgmt/gui/2.1/b_GUI_Firmwar e_Management_21_chapter_0100.html

Verification: The Installed Firmware should be displayed as 2.1(1a) as shown in Figure 18.

rvers LAN SAN VM Admin	Main Topology View Eabric Intercon					20111111111	
ilter: All	🛨 🖃 🕰 Filter 🖨 Export 🔂 Print 🤇					y Catalog 🛛 🏺 Mana	agement Exte
nt	Name	Model	Running Version	Startup Version	Backup Version	Update Status	Activate
ssis			2.1(1a)	2.1(1a)	N/A	N/A	Ready
c-Mounts	🗄 🗐 Chassis						
EX	🕀 👘 Chassis 1	Cisco UCS 5108					
Servers	E-Sp Chassis 2	Cisco UCS 5108					
Interconnects	i IO Modules						
Interconnect A (subordinate)	IO Module 1	Cisco UCS 2208XP	2.1(1a)	2.1(1a)	2.1(1a)	Ready	Ready
connect B (primary)	IO Module 2	Cisco UCS 2208XP	2.1(1a)	2.1(1a)	2.0(1s)	Ready	Ready
	E Servers						
	🗄 🦏 Server 1	Cisco UCS B200 M3					
	Adapters						
	BIOS	Cisco UCS B200 M3	B200M3.2.0.3.0.0	B200M3.2.0.3.0	B200M3.2.0.3.0.0.	. Ready	Ready
	CIMC Controller	Cisco UCS B200 M3	2.1(1a)	2.1(1a)	2.1(154)	Ready	Ready
	E Server 3	Cisco UCS B200 M3					
	E Server 4	Cisco UCS B200 M3					
	E Server 5	Cisco UCS B200 M3					
	E Server 6	Cisco UCS B200 M2					
	E Server 7	Cisco UCS B200 M2					
	E Server 8	Cisco UCS B200 M2					
	E S Chassis 3	Cisco UCS 5108					
	⊕ - Sp Chassis 4	Cisco UCS 5108					
	Fabric Interconnects						
	Fabric Interconnect A (subor	dCisco UCS 6248UP					
			5.0(3)N2(2.11a)	5.0(3)N2(2.11a)	N/A	N/A	Ready
	System		5.0(3)N2(2.11a)	5.0(3)N2(2.11a)	N/A	N/A	Ready
	E Fabric Interconnect B (primar	yCisco UCS 6248UP					
			5.0(3)N2(2.11a)	5.0(3)N2(2.11a)	N/A	N/A	Ready
	System		5.0(3)N2(2.11a)	5.0(3)N2(2.11a)	N/A	N/A	Ready
	Rack-Mounts						

Figure 18 Verifying the Installed Firmware Version

1

Chassis Discovery Policy

To edit the chassis discovery policy, follow these steps:

- 1. Navigate to the **Equipment** tab in the left pane of the UCS Manager.
- 2. In the right pane, click the Policies tab.
- 3. Under Policies, click Global Policies, change the Chassis Discovery Policy to 4-link.
- 4. Click Save Changes in the bottom right corner.

Verification: The chassis discovery policy configured to 8-link is displayed in Figure 19.

Equipment Servers LAN SAN VM Admin	📑 Main Topolog	y View	BO Fabric Interconnects		ervers
	🧹 Thermal 🛛 🖓	Decommissioned	📥 Firmware Management	Policies	🔀 Faults
Filter: All	Global Policies Autoconfig Polic	ies Server Inheritance Policies	s Blade Server Discovery Policies SE	EL Policy Power Groups	
Chassis Chassis Servers FeX Servers Fabric Interconnects	Chassis/FEX Discovery Po Action: 4 Link Grouping Preference: 0 Rack Server Discovery Po Action: © Immediate Scrub Policy: <not set=""> Rack Management Conne Action: © Auto Acknowled Power Policy Redundancy: © Non Redu MAC Address Table Aging Aging Time: © Never © Global Power Allocation P</not>	Ilicy Unk None Port Channel Ulicy User Admowledged User Admowledged G User Admowledged I G User Admowledged I G Mode Default O other			

Figure 19 Displaying the Chassis Discovery Policy Configuration

Enabling Network Components

To enable Fibre Channel, servers, and uplink ports, follow these steps:

- 1. Select the **Equipment** tab on the top left of the UCS Manager window.
- 2. Select Equipment > Fabric Interconnects > Fabric Interconnect A (primary) > Fixed Module.
- 3. Expand the Unconfigured Ethernet Ports section.
- 4. Select ports 1-8 that are connected to the UCS chassis and right-click on them and select **Configure** as Server Port.
- 5. Click Yes to confirm, and then click OK to continue.
- 6. Select ports 9 and 10. These ports are connected to the Cisco Nexus 5548 switches for NFS traffic. Right-click on them and select **Configure as Uplink Port**
- 7. Click Yes to confirm, and then click OK to continue.
- 8. Select ports 11 and 12. These ports are connected to the Cisco Nexus 5548 switches. Right-click on them and select **Configure as Uplink Port**.
- 9. Click Yes to confirm, and then click OK to continue.
- 10. On the FI Expansion Module configure port 15 and port 16 as Fiber Channel.
- 11. Select Equipment > Fabric Interconnects > Fabric Interconnect A (primary).
- **12.** Right click, and select **Set FC End-Host Mode** to put the Fabric Interconnect in Fiber Channel Switching Mode.
- **13**. Click **Yes** to confirm.

- **14.** A message displays stating that the "Fiber Channel End-Host Mode has been set and the switch will reboot". Click **OK** to continue. Wait until the UCS Manager is available again and log back into the interface.
- **15.** Re-execute Step 2 to 14 for Fabric Interconnect B.

Verification: Check if all configured links show their status as "up" as shown in Figure 20 for Fabric Interconnect A. This can also be verified on the Cisco Nexus switch side by running "show int status" and all the ports connected to the Cisco UCS Fabric Interconnects are shown as "up".

۵. Note

The FC ports are shown as enabled with VSAN default ID "1". Once we create VSAN id for the present deployment (vsan20 as created in Nexus 5548 FC Configuration steps), we would re-enable the FC port, with VAN16.

Figure 20 Enabling the Server Ports on Cisco UCS Fabric Interconnect



Creating MAC Address Pools

To create MAC Address pools, follow these steps:

- 1. Select the LAN tab on the left of the UCS Manager window.
- 2. Under **Pools** > **root**.



Two MAC address pools will be created, one each for Fabric A and Fabric B.

- **3.** Right-click on MAC Pools under the root organization and select **Create MAC Pool** to create the MAC address pool for Fabric A.
- 4. Enter "MAC-JDE-FIA" for the name of the MAC pool for Fabric A.
- 5. Enter a description of the MAC pool in the Description text box (optional).
- 6. Click Next to continue.
- 7. Click Add to add the MAC address pool.
- 8. Specify a starting MAC address for Fabric A.

Note

The default is fine, but it is recommended to change the pool address as per the deployment and also to differentiate between MAC address for Fabric A and Fabric B. Presently we have configured it as (DE:25:B5:0A:00:00).

- **9.** Specify the size as "24" for the MAC address pool for Fabric A. (MAC address Size "24" is just for demonstration and not a hard limit for MAC address Pool)
- **10.** Click **OK**.
- 11. Click Finish.
- 12. A pop-up message box appears, click **OK** to save changes.
- **13.** Right-click on MAC Pools under the root organization and choose **Create MAC Pool** to create the MAC address pool for Fabric B.
- 14. Enter "MAC-JDE-FIB" for the name of the MAC pool for Fabric B.
- **15.** Enter a description of the MAC pool in the Description text box (optional).
- **16.** Click **Next** to continue.
- 17. Click Add to add the MAC address pool.
- 18. Specify a starting MAC address for Fabric B.



- **Note** The default is fine, but it is recommended to change the pool address as per the deployment and also to differentiate between MAC address for Fabric A and Fabric B. Presently we have configure it as (DE:25:B5:0B:00:00)
- **19.** Specify the size as "24" for the MAC address pool for Fabric B.
- **20.** Click **OK**.
- 21. Click Finish.
- 22. A pop-up message box appears; click OK to save changes and exit.

Verification: Select **LAN** tab > **Pools** > **root**. Select MAC Pools and it expands to show the MAC pools created. On the right pane, details of the MAC pools are displayed as shown in Figure 21.



Equipment Servers LAN SAN VM A	MAC Pools	
Filter: Pools	🛨 😑 🍕 Filter 🗢 Export 😸 Print	
	Name	Size
± =	T MAC POOL MAC-JDE-FIA	24
□	MAC POOL MAC-JDE-FIB	24
E- 🙀 root		
IP Pools MAC Pools Sub-Organizations		

Creating WWPN Pools

To create WWPN pools, follow these steps:

- 1. Select the SAN at the top left of the UCS Manager window.
- 2. Select WWPN Pools > root.
- Note

• Two WWPN pools will be created, one each for Fabric A and Fabric B.

3. Right-click on WWPNPools, and select Create WWPN Pool.

- 4. Enter "ovm_wwpn_A" as the name for the WWPN pool for Fabric A.
- 5. Enter a description of the WWPN pool in the Description text box (optional).
- 6. Click Next.
- 7. Click Add to add a block of WWPNs.
- 8. Enter "20:00:ED:25:B5:A0:00:00" as the starting WWPN in the block for Fabric A.



Note It is recommended to change the WWPN prefix as per the deployment. This would help in identifying WWPNs initiated from Fabric A or Fabric B.

- **9.** Set the size of the WWPN block to "24". (WWPN Pool Size "24" is just for demonstration and not a hard limit for WWPN Pool)
- 10. Click OK to continue.
- 11. Click Finish to create the WWPN pool.
- **12.** Click **OK** to save changes.
- 13. Right-click on the WWPN Pools and select Create WWPN Pool.
- 14. Enter "ovm_wwpn_B" as the name for the WWPN pool for Fabric B.
- **15.** Enter a description of the WWPN pool in the description text box. This is optional; you can choose to omit the description.

I

- 16. Click Next.
- 17. Click Add to add a block of WWPNs.
- 18. Enter "20:00:ED:25:B5:B0:00:00" as the starting WWPN in the block for Fabric B.
- **19.** Set the size of the WWPN block to "24".
- 20. Click OK to continue.
- 21. Click Finish to create the WWPN pool.
- 22. Click OK to save changes and exit.

Verification: As displayed in Figure 22, the new name with the 24 block size.

Figure 22 WWPN Pool Details



Creating WWNN Pools

To create WWNN pools, follow these steps:

- 1. Select the SAN tab at the top left of the UCS Manager window.
- 2. Select **Pools** > **root**.
- 3. Right-click on WWNN Pools and click Create WWNN Pool.
- 4. Enter "OVM_JDE_WWNN" as the name of the WWNN pool.
- 5. Enter a description of the WWNN pool in the Description text box (optional).
- 6. Click Next to continue.
- 7. A pop-up window "Add WWN Blocks" appears; click Add button at the bottom of the page.
- 8. A pop-up window "Create WWN Blocks" appears; set the size of the WWNN block to "24".
- 9. Click **OK** to continue.
- 10. Click Finish.
- 11. Click OK to save changes and exit.

Verification: The new name with the 24 block size displays in the right panel when WWNN pools is selected on the left panel, as shown in Figure 23. (WWNN Pool Size "24" is just for demonstration and not a hard limit for WWNN Pool).

Figure 23 WWNN Pool Details



Creating UUID Suffix Pools

To create UUID suffix pools, follow these steps:

- 1. Select the Servers tab on the top left of the UCS Manager window.
- 2. Select **Pools** > **root**.
- 3. Right-click on "UUID Suffix Pools" and select Create UUID Suffix Pool.
- 4. Enter the name the UUID suffix pool as "OVMU_UID".
- 5. Enter a description of the UUID suffix pool in the Description text box (optional).
- 6. Prefix is set to "derived" by default. Do not change the default setting.
- 7. Click Next to continue.
- **8.** A pop-up window "Add UUID Blocks" appears. Click **Add** button at the bottom of the window to add a block of UUID suffixes.
- 9. The "Form" field will be in default setting. Do not change the "From" field.

- **10.** Set the size of the UUID suffix pool to "24".
- 11. Click **OK** to continue.
- 12. Click Finish to create the UUID suffix pool.
- 13. Click OK to save changes and exit.

Verification: Ensure that the UUID suffix pools created are displayed as shown in Figure 24.

Figure 24 UUID Suffix Pool Details

	Equipment Servers AN SAN VM A	UUID Suffix Pools					
ł		Name	Pool Name	UUID Prefix			
	• •	Pool OVMU_UID	OVMU_UID	82AAF622-1C28-11E2			
	E Opols						
	⊖ Å root						
	UUID Suffix Pools						
	⊡						

Creating VLANs

To create VLANs, follow these steps:

1. Select the LAN tab on the left of the UCS Manager window.

٩,

Note Three VLANs will be created –Management Traffic, Data traffic and Oracle RAC database inter-node private traffic as listed in Table 3.

- 2. Right-click on the "VLANs" in the tree, and click Create VLAN(s).
- **3.** Enter <<name>> as the name of the VLAN (for example, 760). This name will be used for traffic management.
- 4. Keep the option "Common/Global" selected for the scope of the VLAN.
- 5. Enter a VLAN ID for the management VLAN. Keep the sharing type as "none".
- **6.** Similarly create other three VLANs.

Verification: Select **LAN** tab > **LAN Cloud** > **VLANs**. Open VLANs and all of the created VLANs are displayed. The right pane gives the details of all individual VLANs as shown in Figure 25.

I

Equipment Servers LAN SAN VM A	VLANs ≪ Filter ⇔ Export ⇔ Print					
	Name 🗸	ID	Type	Transport	Native	VLAN Sharing
• -	VI AN vmotion (761)	761	Lan	Ether	No	None
E-C LAN Cloud	VLAN VLAN613 (613)	613	Lan	Ether	No	None
E Fabric A	VLAN VIan603 (603)	603	Làn	Ether	No	None
E Eabric B	VLAN VLAN602 (602)	602	Lan	Ether	No	None
QoS System Class LAN Pin Groups	VLAN Storage2 (193)	193	Lan	Ether	No	None
LAN Pin Groups	VLAN Storage (192)	192	Lan	Ether	No	None
LAND's Course Drivets Cha	VLAN Public (760)	760	Lan	Ether	No	None
LAN Pin Group Public-Stora	VLAN Private (191)	191	Lan	Ether	No	None
Threshold Policies VLAN Groups ULANS	Details General Org Permissions VL	AN Group Membership	Faults Events			

Figure 25 Details of Created VLANs

Creating Uplink Ports Channels

To create uplink port channels to Cisco Nexus 5548 switches, follow these steps:

- 1. Select the LAN tab on the left of the UCS Manager window.
- 2. Expand the "Fabric A" tree.
- 3. Right-click on the "Port Channels" and click Create Port Channel.
- 4. Enter "110" as the unique ID of the port channel.
- 5. Enter "Public-Private1" as the name of the port channel.
- 6. Click Next.
- 7. Select ports 1/9 and 1/10 to be added to the port channel.
- 8. Click >> to add the ports to the Port Channel.
- 9. Click Finish to create the port channel.
- 10. A pop-up message box appears, click **OK** to continue.
- **11.** In the left pane, choose the newly created port channel.
- 12. In the right pane under "Actions", choose Enable Port Channel option.
- 13. In the pop-up box, click Yes, and then click OK to save changes.
- 14. Expand the "Fabric B" tree.
- **15.** Right-click on the "Port Channels" and click **Create Port Channel**.
- **16**. Enter "111" as the unique ID of the port channel.
- 17. Enter "Public_Private2" as the name of the port channel.
- 18. Click Next.
- **19.** Select ports **1/9** and **1/10** to be added to the Port Channel.
- **20**. Click >> to add the ports to the Port Channel.
- 21. Click Finish to create the port channel.
- 22. A pop-up message box appears, click OK to continue.
- **23.** In the left pane, click the newly created port channel.
- 24. In the right pane under "Actions", choose Enable Port Channel option.

25. In the pop-up box, click Yes, and then click OK to save changes.

Verification: Select **LAN** tab > **LAN Cloud**. On the Right Pane, select the LAN Uplinks and expand the Port channels listed as shown in Figure 26.

In order for the Fabric Interconnect Port Channels to get enabled, we have already configured vPC in "Cisco Nexus Switch Configuration" section on page 33.

Figure 26 Details of Port Channels

Equipment Serves LAN SAN VM A	Port Channels	_				
Filter: LAN Cloud	🛨 🖃 🍕 Filter 👄 Export 🈸 P	rint				
	Name	Fabric ID	IfType	If Role	Tr	ansport
± =	🔲 👄 Port-Channel 9 (Public_Stora		Aggregation	Network	Ether	
E-CLAN Cloud	Eth Interface 1/9 A		Physical	Network	Ether	
E-Babric A	Eth Interface 1/10 A		Physical	Network	Ether	
E-+	E - Port-Channel 33 (vPC-33-NSA	i	Aggregation	Network	Ether	
VLAN Optimization Sets						
VLANS						
E-B Fabric B						
⊟ ⊕ Port Channels						
⊡ + Port-Channel 10 (Priva						
-I Eth Interface 1/9						
Eth Interface 1/10						

Creating VSANs

All the servers under JD Edwards EnterpriseOne deployment on UCS with EMC VNX 5300 are booted from SAN. The following section elaborates on VSAN creation which we configured under Cisco Nexus Switch Configuration configuration

To create VSANs, follow these steps:

- 1. Select the SAN tab at the top left of the UCS Manager window.
- 2. Expand the SAN cloud tree.
- 3. Right-click on the "VSANs" and click Create VSAN.
- 4. Enter "OVM_VSAN" as the VSAN name
- 5. Enter "20" as the VSAN ID.
- 6. Enter "20" as the FCoE VLAN ID.
- 7. Click **OK** to create the VSANs.

Verification: Select **SAN** tab >**SAN Cloud** >**VSANs** on the left panel. The right panel displays the created VSANs as shown in Figure 27.

<u>Note</u>

Equipment Servers LAN SAN M A	General Faults Events
Filter: SAN Cloud	Fault Summary Properties
SAN Cloud San Cloud	Properties Name: OVM_VSAN 0 0 Actions Table 20 Belete Rabin 20 Name: OVM_VSAN ID: 20 Fabric ID: Dual Network Type: San If Type: Virtual Locale: External Transport Type: Fc FCOE VLAN ID: 20 Operational State: Ok
	FC Zoning Settings FC Zoning: O Disabled O Enabled

Figure 27 Details of VSANs

SAN Boot Policy Configuration

In the present deployment, the UCS Servers are booted from SAN (EMC VNX5300). With boot from SAN, the OS image resides on the SAN and the server communicates with the SAN through a host bus adapter (HBA). The HBAs BIOS contain the instructions that enable the server to find the boot disk. After power on self test (POST), the server hardware component fetches the boot device that is designated as the boot device in the hardware BOIS settings. When the hardware detects the boot device, it follows the regular boot process.

Modifying Service Profile for Boot Policy

In this setup, vhba0 and vhba1 are used both for SAN Boot and JD Edwards EnterpriseOne Installation. Storage SAN WWPN ports will be connected in the boot policy as shown:

```
        vhba0
        ---
        Storage Port SP-A0
        Primary Target
        - 50:06:01:60:3e:a0:05:47

        ---
        Storage Port SP-B0
        Secondary Target
        - 50:06:01:68:3e:a0:05:47

        vhba1
        ---
        Storage Port SP-A1
        Primary Target
        - 50:06:01:61:3E:A0:05:47

        vhba1
        ---
        Storage Port SP-A1
        Primary Target
        - 50:06:01:61:3E:A0:05:47

        ---
        Storage Port SP-B1
        Secondary Target
        - 50:06:01:69:3E:A0:05:47
```

To modify the Service Profile for boot policy, follow these steps:

- Login to the UCS Manager. Click Servers tab > Policies > Boot Policies and the click Add. A pop-up window "Create Boot Policy" appears.
- 2. Enter the name as "JDE_OVM_BootPol" in the "Name" text box and in the Description text box enter "for JD Edwards" and ensure that the check box "Reboot on Boot Order Change" is checked.
- **3.** Add the first target as CD-ROM, as this will enable you to install Operating System through KVM Console.
- **4.** Click **Add SAN Boot** on the vHBAs section; in the "Add SAN Boot" pop-up window, type "vHBA0" and select the type as Primary and click **OK**. This will be the SAN Primary Target.

- Click Add SAN Boot Target to add a target to the SAN Boot Primary in the vHBAs window. In the "Add SAN Boot Target" pop-up window, type "0" in the "Boot Target LUN". Enter "50:06:01:60:3e:a0:05:47" in the "Boot Target WWPN" and select the type as "Primary" and then click OK.
- **6.** To add another target to the SAN Boot Primary, click **Add** to add another SAN Boot Target in the vHBAs window; in the "Add SAN Boot Target" pop-up box, type "0" in the Boot Target LUN; type "50:06:01:68:3e:a0:05:47" in the Boot Target WWPN and ensure that the type selected is ""Secondary" is already selected and greyed out.and click **OK**.



These WWPNs are from storage SPB0 / SPA0 ports (please refer Figure 31: San Zoning Configuration).

- 7. Similarly for the SAN Secondary, Click Add SAN Boot in the vHBAs window; in the "Add SAN Boot" pop-up window, type "vHBA1" and select the type as "Secondary" and then click OK.
- 8. Click Add SAN Boot Target to add a target to the SAN Boot Secondary (vHBA1) in the vHBAs window. In the "Add SAN Boot Target" pop-up window, type "0" in the "Boot Target LUN". Enter "50:06:01:61:3E:A0:05:47" in the "Boot Target WWPN" and select the type as "Primary" and then click **OK**.
- **9.** To add another target to the SAN Boot Secondary, click **Add** to add another SAN Boot Target in the vHBAs window; in the "Add SAN Boot Target" pop-up box, type "0" in the Boot Target LUN; type "50:06:01:69:3E:A0:05:47" in the Boot Target WWPN and ensure that the type selected is "Secondary" which would have already been greyed out and click **OK**.
- **10.** Click **Save Changes** to save all the settings. The Boot Policy window in UCS Manager is as shown in Figure 28.



Figure 28 Boot Policy Service Profile

<u>Note</u>

During OVM Installation, we would change the boot policy so that only one path is available during the boot time. Also make sure that only one path is available before the installation process. Once the installation is complete, this may be reverted back to its full paths.

BIOS Policy

I

BIOS policy is one of the features of Cisco UCS Service Profiles which enable users to incorporate similar BIOS settings all across the deployed servers. It helps to create application specific BIOS setting, For instance in a virtualized environment we would enable VT for direct IO wherein in the non-virtualized environment we would leave that as default. This helps a consistent configuration and the Administrators do not need to interrupt the boot process on each server to alter the BIOS setting. This helps faster deployment as users do not have to use the F2 option to change BIOS of hundreds of servers deployed in a Data Center. The BIOS policy configured for JDE deployment is shown in Figure 29.

彗 BIOS Policy	
Main Advanced Boot Options Server Management Events	
Processor Intel Directed IO RAS Memory Serial Port USB PCI Configuration	
Turbo Boost: C disabled C enabled C Platform Default	
Enhanced Intel Speedstep: C disabled C enabled C Platform Default	
Hyper Threading: C disabled C enabled C Platform Default	
Core Multi Processing: all	
Execute Disabled Bit: O disabled O enabled O Platform Default	
Virtualization Technology (VT): C disabled C Platform Default	
Direct Cache Access: C disabled C enabled C Platform Default	
Processor C State: disabled C enabled Platform Default	
Processor C1E: disabled C enabled C Platform Default	
Processor C3 Report: disabled C acpi-c2 C acpi-c3 C Platform Default	
Processor C6 Report: disabled reabled Platform Default	
Processor C7 Report: disabled reabled Platform Default	
CPU Performance: O enterprise O high-throughput O hpc O Platform Default	
Max Variable MTRR Setting: 💽 auto-max 🔘 8 🔘 Platform Default	
	OK Apply Cancel Help

Figure 29 BIOS Setting for CPU Performance

5 BIOS Policy
Main Advanced Boot Options Server Management Events
Processor Intel Directed IO RAS Memory Serial Port USB PCI Configuration
Processor Inter Directed to read Holino y perial Port USB PCL configuration
Memory RAS Config: maximum-performance
NUMA: C disabled C Platform Default
LV DDR Mode: O power-saving-mode O performance-mode O Platform Default
OK Apply Cancel

Fiaure 30 BIOS setting for Physical Memory Performance

Note

Disable I/O MMU Virtualization Settings (VT-d). See: http://docs.oracle.com/cd/E27300_01/E27307/html/vmrns-bugs.html

UCS Service Profile Configuration

An important aspect of configuring a physical server in a Cisco UCS 5108 chassis is to develop a service profile through Cisco UCS Manager. Service profile is an extension of the virtual machine abstraction applied to physical servers. The definition has been expanded to include elements of the environment that span the entire data center, encapsulating the server identity (LAN and SAN addressing, I/O configurations, firmware versions, boot order, network VLAN, physical port, and quality-of-service [QoS] policies) in logical "service profiles" that can be dynamically created and associated with any physical server in the system within minutes rather than hours or days. The association of service profiles with physical servers is performed as a simple, single operation. It enables migration of identities between servers in the environment without requiring any physical configuration changes and facilitates rapid bare metal provisioning of replacements for failed servers.

Service profiles can be created in several ways:

- Manually—Create a new service profile using the Cisco UCS Manager GUI.
- From a Template—Create a service profile from a template.
- **By Cloning**—Cloning a service profile creates a replica of a service profile. Cloning is equivalent to creating a template from the service policy and then creating a service policy from that template to associate with a server.

I

In the present scenario we created a Service profile updating template and thereafter instantiated service profile through the template. A service profile template parameterizes the UIDs that differentiate one instance of an otherwise identical server from another. Templates can be categorized into two types:

- **Initial Template**—The initial template is used to create a new server from a service profile with UIDs, but after the server is deployed, there is no linkage between the server and the template, so changes to the template will not propagate to the server, and all changes to items defined by the template must be made individually to each server deployed with the initial template.
- Updating Template—An updating template maintains a link between the template and the deployed servers, and changes to the template (most likely to be firmware revisions) cascade to the servers deployed with that template on a schedule determined by the administrator.

Service profiles, templates, and other management data is stored in high-speed persistent storage on the Cisco UCS Fabric Interconnects, with mirroring between fault-tolerant pairs of Fabric Interconnects.

Create vNIC Templates

To configure the vNIC template, follow these steps:

- 1. Click the LAN tab.
- 2. Filter on policies and select vNIC templates. Three templates are created; Public Network template, Private Network template and VM Management Network template. The Private network is for the internal Heart Beat and message transfers between Oracle Nodes while Public network for JD Edwards inter-tier communication. The Management Network is used for Oracle VM Management and VM migration.
- 3. Define Name and Description of vNIC template.
- 4. Pin Public and Management vNIC template to FI-A and Private network vNIC template to FI-B.
- 5. Enable Failover for each of the Fabric option.
- **6.** Select VLANs; Public for Public vNIC Template, Private for Private vNIC template and Management VLAN for Oracle VM Management Network.
- 7. Select MAC Pool that was created in the previous steps.
- 8. Define MTU. For Oracle Private Network we would use 9000 as the MTU size whereas MTU size of 1500 is used for Management & Public Network. Figure 31, Figure 32, and Figure 33 show the created vNIC templates.

	Figure 31	vNIC Template	e for Publi
Create vNIC Templat			
	Name: VIIIC_Public_FIA cription: VIIIC template for JDE in abric ID: C Fabric A C Fabric B J		_
	t profile by the same name will be created ame name exists, and updating templating temp		tten
	te Type: C Initial Template C Up		
Select	Name	Native VLAN	₽
	Private	0	
	Public	•	
	Storage		
	Storage2	0	_
Create VLAN	мти: 1500		
M.	AC Pool: MAC-JDE-FIA	J	
Qo	S Policy: <not set=""> 🔹</not>		
Network Contro	ol Policy: <not set=""></not>		
Pir	Group: <not set=""></not>	-	
	d Policy: default		
Dynamic vNIC Connectio			

vNIC Template for Public Network

1



ſ

vNIC Template for Private Network

		Figure 33	vNIC Templa	ate for Mana	gement Network
📥 Create vNIC	Template				
Create v	NIC Temp	late			
		VNIC_Mgmt_FIA			
	<u> </u>	•			
	Fabric ID:	Fabric A C Fabric B E E	nable Failover		
		Target			
		Adapter			
Warning					
		by the same name will be created ae exists, and updating template		written	
	Template Type:	💿 Initial Template 🔘 Updati	ng Template		
	remplate rype.		ig remplate		
VLANs	2-1	Nama	Net in Man		
	Select	Name Storage	Native VLAN		
		Storage2	0		
	6	VLANG02			
	•	VLAN613	0		
	-	h n			
+ Create VLA	(1500			
	MAC Pool:	MAC-JDE-FIA			
	QoS Policy:	0	J		
Natura	ork Control Policy:				
Netwo		<not set=""></not>	-		
State	Threshold Policy:				
Dynamic VNIC C	Connection Policy:	VIIUT SEL2			

Create vHBA Templates

To create a HBA template, follow these steps:

- 1. Click the SAN tab.
- 2. Filter out policies, right-click the vHBA templates and choose Create vHBA Template.
- **3.** Create two Templates, one each for Fabric A and Fabric B.
- 4. Select OVM_VSAN, as created in creating VAN step. (This is configured with VAN ID 20)
- 5. Select WWPN pool as ovm_wwpn_A for Fabric A vHBA template and ovm_wwpn_B for Fabric B template

1

6. The options selected are shown in Figure 34.

Figure 34 vHBA Template 📥 Create vHBA Template X 2 Create vHBA Template Name: vHBA-A Description: vHBA for Fabric A Fabric ID: 💿 A 🔿 B Select VSAN: OVM_VSAN + Create VSAN Template Type: 🔿 Initial Template 💿 Updating Template Max Data Field Size: 2048 WWPN Pool: ovm_wwpn_A -QoS Policy: <not Pin Group: <not set> Stats Threshold Policy: default ОК Cancel

Creating Service Profile Templates

To create service profile templates in UCSM, follow these steps:

- 1. Click the **Servers** tab at the top left of the UCS Manager window.
- Choose Service Profile Templates > root. Choose Create Service Profile Template under the Actions tab.
- 3. The Create Service Profile Template window appears.
- 4. Identify the Service Profile Template section
 - a. Enter the name of the service profile template as "SPTemplate-JDE".
 - **b.** Select the type as "Updating Template". In the event of change in server configuration, updating template helps to update all the service profiles attached to updating template.
 - c. In the UUID section, select "OVMU_UID" as the UUID pool.
 - d. Click Next to continue to the next section.
- 5. Network Section
 - a. Keep default for the Local Storage option.
 - b. Select the option "Expert" for the field "How would you like to configure LAN connectivity".
 - c. In the WWNN Assignment field, select "OVM_JDE_WWNN".
 - d. Select "use vNIC template".
 - e. Define vNIC name as vNIC_Public and select vNIC template as vNIC_Public_FIA
 - f. Click OK.
 - **g.** Similarly create vNIC for Private and Management Network, with appropriate vNIC template as created in previous step.
- 6. Storage Section

- a. Keep default for the Local Storage option.
- **b.** Select the option "Expert" for the field "How would you like to configure SAN connectivity".
- c. In the WWNN Assignment field, select "OVM_JDE_WWNN".
- d. Click Add.
- e. Define vHBA name as vHBA0.
- f. Select "use vHBA template".
- g. Select vHBA template vHBA0.
- h. Select Adaptor Policy as Linux.
- i. Click OK.
- j. Repeat the above steps for vHBA1 with vHBA template as vHBA-B.
- 7. Zoning section
 - a. Leave as default and move the next section
- 8. vNIC/vHBA Placement section
 - a. Restore the default setting as "Let System Perform Placement" in the Select Placement field.
 - b. Ensure that all the vHBAs are created.
 - c. Click Next to continue.
- 9. Server Boot Order section
 - a. Select JDE_Boot_Pol as created in the previous steps.
- 10. Select default settings for Maintenance Policy and click Next.
- **11.** In Server Assignment section, create a Server Pool (JDE_ServerPool) for Oracle JD Edwards deployment and click **Next.**

A server pool contains a set of servers. These servers typically share the same characteristics. Those characteristics can be their location in the chassis, or an attribute such as server type, amount of memory, local storage, type of CPU, or local drive configuration. You can manually assign a server to a server pool, or use server pool policies and server pool policy qualifications to automate the assignment.

If your system implements multi-tenancy through organizations, you can designate one or more server pools to be used by a specific organization. For example, a pool that includes all servers with two CPUs could be assigned to the Marketing organization, while all servers with 64 GB memory could be assigned to the Finance organization.

For Oracle JD Edwards deployment, this feature can help in assigning servers to a Server Pool with specific CPU and memory for batch workload or for interactive workload. With the help of UCS XML API we can easily integrate Oracle Enterprise Manager (OEM) and provide automatic failover during the failure of server assigned to specific Server Pool. For instance, in the event of a batch server failure assigned to a Batch server pool, OEM can initiate a call to UCS XML scripts and a server from Spare Server Pool can move to a Batch Server Pool and can be automatically assigned to the Service Profile of Failed Batch Server.

- 12. Under Operational Policies, select the BIOS Policy (JDE_BIOS) created under BIOS Policy section.
- **13.** Click **Finish** to complete the creation of Service profile template. The Figure 35 shows the created Service Profile Template.



I

Figure 35 Service Profile Template

Creating Service Profile from the Template and Associating it to Cisco UCS Blade Server

To create a service profile from the template and associating it to a blade, follow these steps:

- 1. Select the Servers tab at the top left of the UCS Manager window.
- 2. Select Service Profile Templates > root > Sub-Organizations > Service Template JD Edwards Template.
- 3. Click Create Service Profiles From Template in the Actions tab of the right pane of the window.
- 4. Enter "JDE-OVM-" in the Naming Prefix text box and the number as "2".
- 5. Click **OK** to create service Profile. This would create two service Profiles each named as JDE-OVM-1 & JDE-OVM-2 respectively.
- **6.** Once the Service Profile is created, it automatically associates to the available server in the Server Pool.

Equipment Servers LAN SAN VM Admin	Virtual Machines General	FC Zones Storage	Policies	Server Detai	is FSM VIF Paths iSCSI vNICs	Faults Events Boot Order
Filter Service Profiles	Fault Summary 0 Status Overal Status: 1 Status Details Actions Set Desired P Solt Server Shutdown Ser Reset MC Console	wer State		<u>م</u> ٥	User Label: Description: UUID: 4 UUID Pool: 4 UUID Pool Instance: Associated Server: 6 Service Profile Template: 5	org-root/uuid-pool-OVMU_UII sys/chassis-4/blade-2 5PTemplate-JDE org-root/ls-SPTemplate-JDE Server Pool

Figure 36 Successful Association of the Service Profile

Creation of Zoneset and Zones on Cisco Nexus 5548UP Switch

Once the server association to a Service Profile is done, we can see the published WWPNs of vhab0 and vhba1 on Cisco Nexus 5548 A, and 5548 B respectively for that specific server. This section details the steps to configure zoneset and zones on each of the Nexus 5548 switch for server Oracle VM Similar the same steps need to be followed for second server on the Oracle JD Edwards deployment with Oracle VM on Cisco Nexus 5548 A, and 5548 B.

Follow these steps to configure zoneset and zones on Nexus 5548UP Switches:

1. Identify Storage and Server WWPNs

Nexus5k-A# conf t Enter configuration commands, one per line. End with CNTL/Z. Nexus5k-A(config) # sh flogi database _____ INTERFACE VSAN FCID PORT NAME NODE NAME _____ 0x7801ef 50:06:01:60:3e:a0:05:47 50:06:01:60:be:a0:05:47 fc2/1 20 0x7800ef 50:06:01:68:3e:a0:05:47 50:06:01:60:be:a0:05:47 fc2/2 20 0x780002 20:4d:54:7f:ee:56:ca:00 20:14:54:7f:ee:56:ca:01 20 fc2/3 20 0x780005 20:00:00:25:b5:de:0a:0e 20:00:00:25:b5:de:0e fc2/3 0x780000 20:4e:54:7f:ee:56:ca:00 20:14:54:7f:ee:56:ca:01 fc2/4 20 fc2/5 16 0x6d0000 50:0a:09:83:9d:93:40:7f 50:0a:09:80:8d:93:40:7f fc2/6 16 0x6d0001 50:0a:09:84:8d:93:40:7f 50:0a:09:80:8d:93:40:7f 16 0x6d0002 20:4f:54:7f:ee:56:ca:00 20:10:54:7f:ee:56:ca:01 $f_{c2}/7$ fc2/716 0x6d0003 20:00:00:25:b5:de:aa:0e 20:de:00:25:b5:00:00:0e fc2/7 16 0x6d0005 20:00:00:25:b5:de:aa:0a 20:de:00:25:b5:00:00:0a fc2/8 16 0x6d0004 20:00:00:25:b5:de:aa:0c 20:de:00:25:b5:00:00:0c 20:00:00:25:b5:de:aa:09 20:de:00:25:b5:00:00:09 fc2/8 16 0x6d0006 0x6d000a 20:50:54:7f:ee:56:ca:00 20:10:54:7f:ee:56:ca:01 16 fc2/8fc2/8 16 0x6d000b 20:00:00:25:b5:de:aa:0f 20:de:00:25:b5:00:00:0f Total number of flogi = 14.



The storage and JDE-OVM servers and EMC VNX controller WWPNs and are marked in bold.

2. Create zone and zoneset

```
Nexus5k-A(config) # zone name jde-ovm1-vhba0 vsan 20
Nexus5k-A(config-zone) # member pwwn 50:06:01:60:3e:a0:05:47
Nexus5k-A(config-zone) # member pwwn 50:06:01:68:3e:a0:05:47
Nexus5k-A(config-zone) # member pwwn 20:00:00:25:b5:de:0a:0e
Nexus5k-A(config-zone) # zoneset name jde-ovm-n5kA vsan 20
Nexus5k-A(config-zoneset) # member jde-ovm1-vhba0
Nexus5k-A(config-zoneset)# zoneset activate name jde-ovm-n5kA vsan 20
WARNING: You are trying to activate zoneset jde-ovm-n5kA, which is different from
current active zoneset jdeovm-n5ka. Do you want to continue? (y/n) [n] y
Zoneset activation initiated. check zone status
Nexus5k-A(config) # sh zoneset active vsan 20
zoneset name jde-ovm-n5kA vsan 20
 zone name jde-ovm1-vhba0 vsan 20
  * fcid 0x7801ef [pwwn 50:06:01:60:3e:a0:05:47]
  * fcid 0x7800ef [pwwn 50:06:01:68:3e:a0:05:47]
  * fcid 0x780005 [pwwn 20:00:00:25:b5:de:0a:0e]
Nexus5k-A(config) # copy r s
Copy complete, now saving to disk (please wait)
```

Similar configuration has to be done on Nexus 5548 B for vhba1 of JDE-OVM-1 Service Profile. Once we configure zones and zoneset on Nexus 5548 B we would see following configuration.

```
Nexus5k-B(config)# sh zoneset active vsan 20
zoneset name jde-ovm1-n5kB vsan 20
zone name jde-ovm1-vhba1 vsan 20
 * fcid 0xdf01ef [pwwn 50:06:01:61:3e:a0:05:47]
 * fcid 0xdf00ef [pwwn 50:06:01:69:3e:a0:05:47]
 * fcid 0xdf0005 [pwwn 20:00:00:25:b5:de:b0:0e]
```

Configuring Connectivity for EMC VNX Storage

The present JD Edwards deployment leverages EMC VNX5300 storage, connected to the Cisco UCS system. It leverages the EMC FAST Cache as well as EMC FAST Virtual Pool capability.

As Edwards Enterprise One Server has very frequent and random access to the database; the Oracle RAC data files would require very fast read/write operations. For such access patterns a storage pool with Flash disks also known as Solid State Disks (SSD) are chosen with RAID level 5. SSD disks provide faster response time for random access IO patterns. The Data LUN would be configured as Physical disk to the Oracle RAC Guest VMs Oracle RAC log files) involves sequential write intensive operations, hence SAS drives with RAID level 10 is chosen. The log LUN would be configured as physical disk to the Oracle RAC Guest VMs Oracle RAC ASM luns is configured with RAID level 10 and attached as physical disk to Oracle RAC guest VMs. For boot LUNs, RAID level 5 is chosen for reliability. All the boot luns would be configured as Virtual Disk to each of the Guest VMs. The installation directory for HTML, JDE E1 and Database resides on RAID5, using multiple SAS drives. For Backing up LUNs, NL-SAS drives are chosen for their high capacity and lower cost characteristics that align with the backup model.

Figure 37 illustrates the disk layout configured for Oracle JD Edwards on Cisco UCS with Oracle VM.



LUNs carved from the EMC VNX storage forming the disk layout for the Oracle JD Edwards EnterpriseOne deployment are shown in Table 6.

I

Table 6 LUN Configuration for JD Edwards EnterpriseOne Deploymen
--

Name	RAID Type	User Capacity (GB)	Host Information	Description
Jde-ovm1-os-lun	RAID 5	40	jde-ovm1	Boot LUN for OVM Server1
Jde-ovm2-os	RAID 5	40	jde-ovm2	Boot LUN for OVM Server2
Cluster-lun	RAID 5	30	jde-ovm1/ jde-ovm2	Cluster LUN shared across OVM Servers for OVM Cluster Pool
Ovm1-data	RAID 5	550	jde-ovm1/ jde-ovm2	OVM1 repository to carve out OS and data luns for Guest VMs
Ovm2-data	RAID 5	550	jde-ovm2/ jde-ovm2	OVM1 repository to carve out OS and data luns for Guest VMs
Orcl-asm-lun	RAID 10	100	jde-ovm1/ jde-ovm2	Physical disk to carve out asm for Oracle RAC VMs

Name	RAID Type	User Capacity (GB)	Host Information	Description
Orcl-data-A	RAID 5	400	jde-ovm1/ jde-ovm2	Physical disk for Oracle Data files for Oracle RAC VMs
Orcl-data-B	RAID 5	400	jde-ovm1/ jde-ovm2	Physical disk for Oracle Data files for Oracle RAC VMs
Orcl-log-A	RAID 10	200	jde-ovm1/ jde-ovm2	Physical disk for Oracle log files for Oracle RAC VMs
Orcl-log-B	RAID 10	200	jde-ovm1/ jde-ovm2	Physical disk for Oracle log files for Oracle RAC VMs

Table 6 LUN Configuration for JD Edwards EnterpriseOne Deployment



Luns except for OVM Server boot luns are shared across multiple Host. This is a requirement to successfully share OVM repositories and execute VM migration.

Creation of Storage Pools/ RAID Groups

To create storage pools/RAID groups, follow these steps:

- 1. Login to the EMC Unisphere to create storage pools.
- 2. To create Storage Pool, click Storage >Storage Configuration > storage pools > Pools tab and the click Create. The "create storage pool" pop-up window appears.
 - a. Ensure that the Storage Pool type is "Pool".
 - **b.** Enter an appropriate name for the storage pool name in the text box.
 - c. Select appropriate RAID group from the drop-down list.
 - d. Select the required disks from the disk selection popup window and the click OK.
- **3.** To create LUNs from the storage pool, right-click on the desired storage pool. A pop window "Create LUN" appears. In the **General** tab of Create LUN pop-up box.
- 4. Click **General** tab of the Create LUN window. Enter the required LUN size in the LUN properties text box.
- 5. Enter the name for the LUN in the "LUN Name" text box.
- **6.** Ensure that the Database LUNs (SQL Server data) are selected as "Highest Available Tier" and Application LUNs are selected as "Lowest Available Tier" in the Tiering Policy.
- 7. To associate LUNs to the host, Navigate to Hosts > Storage Group and the click Create, A pop-up window "Create Storage Group" appears.
 - **a.** Enter an appropriate name in the "Storage Group Name" text box; click **OK** and then click **Yes** to confirm. Click **LUNs** tab, a pop-up window "Storage Group properties" appears.

b. Select the LUN from the respective SPA / SPB and click Add in the "Available LUNs" to add the selected LUNs. In the "Show LUN" drop-down list select the option "All" instead of "Not in other storage groups". The host would be attached to Storage Group once we complete the Nexus 5548 zoning configuration.

Note

The Host ID which is typically 0 for the first LUN attached to the storage group and this Host Id should match with UCS Manager Service Profile > Create Boot Policy > LUN ID for SAN boot.

Figure 38 Host ID on Storage Group

EMC Unisphere				Pool LUN	Search	
< >	🔠 Dashboard	System	Storage	Hosts	Data Protection	🛸 Sei
<u>FNM00102200267</u> > <u>Hosts</u> > Storage Gr	oups					
Storage Groups					2 1	7 4 🚯
Y Filter for	FNM0010220	0267 - SG-JDE-OVI	M1: Storage Group	Properties		
Storage Group Name	General	JNs Hosts				
📴 SG-	Show LUNs:	Not in other Sto	rage Groups 🔽			
📴 SG-Ebiz1	Available	LUNs				
SG-Ebiz-db	Name 🛆	ID		Capacity	Drive Type	
SG-JDE-OVM1	Meta					
SG-JDE-OVM2	Snap	shots				
SG-JDE-OVM2	⊕– 🦗 SP A ⊕– 🌺 SP B ⊕– 🤯 Thin					
	🔜 🗄 – 🤯 Thin	LUNs				
SG-JDE-OVM5	_					
Selected Create Delete Proper	ties					A <u>d</u> d
	Selected L	UNs				
	Name	ID	Capacity	Drive Type	Host ID 🛆	
Details	jde-ovm1-o	s-lun 2	40.000 GB	SAS	0	
Hosts LUNs SAN Copy Connections	OVM1-data cluster-lun	3	550.000 G		1	
	orcl-log-A	9	30.000 GB 200.000 G		2 3	
Y Filter for	ord com lu	-	100 000 0			~
Name					R	emove
📱 jde-ovm1	Warning: HI host failove		than 255 may resu	t in application outag	es if not supported l	by the
				OK A	oply <u>Cancel</u>	Help

Since the zones are configured in the Cisco Nexus switches with the Host HBA WWPNs, they will appear in the EMC VNX5300 – "Host connectivity status".

To establish the Host connectivity at the EMC VNX5300 array, follow these steps:

- Login to the EMC Unisphere, click Hosts > Connectivity Status under "Host management" on the right side of the window. A pop-up window "Connectivity Status" appears.
- 2. Under the Host Initiators Tab, the vHBA WWPNs of the associated blade is available.
- **3.** vHBA0 and vHBA1of the blade would appear first time before any OS install on that blade. After successful OS installation.
- 4. When one of the HBA initiator is selected, click **Register**. A pop-up window "Register Initiator Record" appears.

I

- Select the "Initiator Type" as "CLARiiON Open" and Failover mode as "Active-Active mode(ALUA)-failovermode 4". Define the hostname (JDEOVM1) and IP address which would be allocated to the JD Edwards OVM Server 1.
- **6.** Similarly register the other vhba1 WWPN with the same host and IP address. Select same Failover Mode as "Active-Active mode(ALUA)-failovermode 41".

To associate the LUN for this blade, associate LUN to the already created Storage group. For the JD Edwards HTML Server, the storage group created is "html1-install-lun". To do this, click Hosts > Storage Groups (html1-install-lun) > Connect Hosts; this will open Storage group properties pop-up box > Hosts tab. Locate the "JDEOVM1" from the available hosts section and Click OK. Associating host to the Storage Groups (JDEOVM1) is shown in Figure 39.

Figure 39 Storage Group - Host Association

🤿 EMC Unisphere - Google Chrome	
🕸 bttps://10.65.121.96/start.html	
EMC Unisphere	
FNM00102200267 Dashboard System	n 🧊 St
FNM00102200267 > Hosts > Storage Groups	
Storage Groups	FNM00102200267 - SG-JDE-OVM1: Storage Group Properties
T. Filter for	General LUNS Hosts
	Show Hosts: Not connected
0.0	2:2E:95:AF:
	B:00:18:36:(Filter For:
	2:7F:B8:7D: Available Hosts Hosts to be
	Name IP Address OS Type Name
	:57:65:35:7
	4:89:53:63:1
SG-JDE-OVM5	D:0A:BF:DF:
PR an and a start	
1 Selected Create Delete Properties Connect LUNs Conne	ect Hosts
ENM00102200267 57 1DE	OVM1: Storage Group Properties
General LUNS Hosts	
Show Hosts: Not connected	ed 💌
Select Hosts	
Filter For:	
Available Hosts	Hosts to be Connected
Name IP Ad	ddress OS Type Name IP Address OS Type
	🖳 jde-ovm1 172.76.0 Fibre

Oracle Virtual Server (OVS) Configuration

I

It is not within the scope of this document to include the specifics of Oracle Virtual Server (OVS) Installation. You should refer to the Oracle installation documentation for specific installation instructions for your Environment.

Oracle Virtual Server Installation

Some of the important steps during Oracle Virtual Server installation are:

1. Before we install OVS from SAN, we need to edit the Boot Policy of OVM Service Profile, such that only single SAN path is visible during installation.

2. Figure 40 shows the Boot Policy specifically used during OVS Installation.

Figure 40 Single FC Path for OVS Installation

Equipmen: Servers LAN SAN VM Admin	General Events	
Filter: Policies	Actions	Properties
	Delete	Name: JDE_OVIM_INSTALL Description: Boot Policy forOVIM SAN Boot Installation
		Reboot on Boot Order Change: Enforce vNIC/vHBA/SCSI Name:
BIOS Policies Soot Policy Boot-FCoE-OVM-A Boot Policy Boot-FCoE-OVM-A Soot Policy Boot-FCoE-OVM-B	The effective order of boot de) does not indicate a boot order presence. evices within the same device class (LAN/Storage/ISCSI) is determined by PCIe bus scan order.
- S Boot Policy Boot_Local - S Boot Policy Boot_ISCSI - S Boot Policy - S Boot Policy		ST Name is selected and the VNIC/VHBA/ISCSI does not exist, a config error will be reported. s/vHBAs/ISCSI are selected if they exist, otherwise the vNIC/vHBA/ISCSI with the lowest PCIe bus scan
Boot Policy JDE_OVM_ENSTALL Boot Policy JDE_OVM_INSTALL Boot Policy JDE_OVM_Local Soot Policy LD	Local Devices	Boot Order
- S Boot Policy LR-boot - S Boot Policy LR-boot	vNICs	Name Order VNIC/vHBA/iSCSI vNIC Type Lun ID WWN
- S Boot Policy boot jue Soot Policy default Soot Policy diag	vHBAs	OCD-ROM 1 Image 2 Image 2 Image 2
- S Boot Policy ebs-app-bootpol - S Boot Policy iSCSI-Boot - S Boot Policy iSCSI_JDE	iSCSI vNICs	SAN primary vnoau Primary SAN Target primary Primary 0 50:06:01:60:3E:A0:05:47

3. Attach OVS ISO to KVM virtual media, as shown in Figure 41.

Note

Ensure to use OVS build 3.1.1.819 or later. Contact Oracle support to download the same.

File Help					
📣 Boot Server 🛛 🔩 S	Shutdown Server 🧕 Reset				
KVM Console Properti	es				
KVM Virtual Media					
Client View					
Mapped I	Read Only Drive				Exit
	🗖 🚽 🚽 🖓 🗠 🕞				Create Image
	🖉 🔐 Di - CD/DVD				Create Image
	🖉 🛃 🛃 E: \share \OVM3.	1.1\OVS-3.1.1.	iso - ISO Image F	-ile	Add Image
					Remove Image
					Details ±
Details					
Target Drive	Mapped To	Read Bytes	Write Bytes	Duration	
Virtual CD/DVD	E:\share\OVM3.1.1\OV	21.270M	0	00:14:53	USB Reset
Removable Disk	Not mapped				
Floppy	Not mapped				

Γ

Figure 41 OVS ISO Attached as Virtual Media to KVM Console

4. Make sure that a single Storage path is visible during OVS installation. The WWPN of storage login, should be similar to WWPN we defined in JDE_OVM_INSTALL boot policy. Figure 42 displays single storage path.

F

		Figure 42	Single FC Path for C	S Installation	
File	View Macros Tools Help	2			
d ₿	oot Server 🚽 Shutdown Serv	er 🧕 Reset			
KVM (Console Properties				
KVM	Virtual Media				
	Version 4.29.00 Copyright(c) 20				
	HA –0 (Bus 1 De Battery Status:		RAID SAS 2004 ROMB		
	PCI SLOT ID LUN	VENDOR PRO	DDUCT	REVISION	CAPACITY
	255	LSI LS	I MegaRAID SAS 2004 RO	2.120.184-141	0MB
	0 JBOD(s) found 0 JBOD(s) handl		adapter		
	0 Virtual Drive	(s) found on t	the host adapter.		
	Adapter BIOS Di O Virtual Drive Press <ctrl><h></h></ctrl>	(s) handled by		BIOS on HA - O	
	Cisco VIC FC, B (C) 2010 Cisco DGC 5006 Option ROM inst	Systems, Inc. 01603ea00547:(900		

5. Select the EMC LUN configured during Storage Group creation.

1



6. Select Allow Boot from multipath device.

ſ

Fi	gure 44	Boot from Multipath Device	
File View Macros Tools Help	Q Reset		
KVM Console Properties	~~		
KVM Virtual Media			
/de ∕de	Boot Where do you wa v/mapper/mpath@ (*] Allow b Change drive	Loader Configuration Int to install the boot loader? Master Boot Record (MBR) Dp1 First sector of boot partiti boot from a multipath device order UK Back ats ; (Space) selects ; (F12)))))))))))))))

7. Configure the management Ethernet interface with appropriate ip. Make sure to verify the displayed MAC address with the vNIC Mgmt Ethernet interface created on OVM Service Profile.

1

	Figure 45	vNIC Mgmt Configured for Management IP
📥 / JDE-OVM-2 (Chassis - 2 Serve	r - 8) - K¥M Console	
File View Macros Tools Help		
📣 Boot Server 🛛 🔩 Shutdown Server	🥝 Reset	
KVM Console Properties		
KVM Virtual Media		
Welcome to Oracl	e VM Server	
	Choose the for manage eth eth	UM Management Interface network interface to use ment of this machine. 3: DE:25:85:0A:00:02 1: DE:25:85:0A:00:12 2: DE:25:85:0B:00:04 Back Add to VLAN
<tab>/<alt-tab< td=""><td>> between eleme</td><td>nts <space> selects <f12> next screen</f12></space></td></alt-tab<></tab>	> between eleme	nts <space> selects <f12> next screen</f12></space>

L

Γ

8. Configure Host Name and install OVS Server.

F	figure 46	OVS Installation Status
📥 / JDE-OVM-2 (Chassis - 2 Serve	r - 8) - K¥M Console	
File View Macros Tools Help		
📣 Boot Server 🛛 🔩 Shutdown Server	🥺 Reset	
KVM Console Properties		
KVM Virtual Media		
Welcome to Oracl	e VM Server	
		Package Installation
Name Size Summ Tot Com Rem	: ary: Starting take seve	Install Starting install process. This may ral minutes 8%
<tab>∕<alt-tab< td=""><td>> between elem</td><td>ients <space> selects <f12> next screen</f12></space></td></alt-tab<></tab>	> between elem	ients <space> selects <f12> next screen</f12></space>

Similar steps need to be executed to install the second Oracle Virtual Server.

Some of the important steps executed post OVS installation are:

1. Reconfigure the Boot Policy for OVM Service Profile with all the four paths to EMC.

1
Figure 47 Reconfigure Boot Policy

Equipment Servers AN SAN VM Admin	General Storage Network ISCSI vNICs Boot C	Order Virtual Machines FC Zones	Policies Server Details FSM	4 VIF Paths Fau	Its Events
Filter: Service Profiles	Actions				
	Global Boot Policy Name: JDE_OVII_Bc Boot Policy Instance: org-root/boot- Description: Boot Policy fi Reboot on Boot Order Change: No Pofforce vNIC/vHBA/SCSI Name: No WARNINGS: The type (primary/secondary) does not indicate The effective order of boot devices within the sa If Enforce vNIC/vHBA/ISCSI Name is select If it is not selected, the vNICs/vHBA/ISCSI are is Boot Order	policy-JDE_OVM_BootPol or JDE on OVM a boot order presence. me device dass (LAN/Storage/ISCSI) ed and the VMIC/vHBA/SCSI does no	t exist, a config error will be r	eported.	order is used.
	Name	Order vNIC/vHBA/iSC	SI vNIC Type	Lun ID	WWN
VNIC vNICPublic	CD-ROM	1			
DE-OVM-3	E-Storage	2 vhba0	Primary		
⊟¶ vHBAs	SAN Target primary	wibdu	Primary	0	50:06:01:60:3E:A0:05:47
HBA vhba0	SAN Target secondary		Secondary	0	50:06:01:68:3E:A0:05:47
⊕¶ vHBA vhba1 ⊡¶ vNICs	SAN secondary	vhba1	Secondary		
vNIC vNICMgmt	SAN Target primary		Primary	0	50:06:01:61:3E:A0:05:47
	SAN Target secondary		Secondary	0	50:06:01:69:3E:A0:05:47

2. Update fnic driver.

```
[root@jde-ovm1 ~]# modinfo fnic
filename:
/lib/modules/2.6.39-200.37.1.el5uek/kernel/drivers/scsi/fnic/fnic.ko
version:
              1.5.0.1
license:
              GPL v2
author:
              Abhijeet Joglekar <abjoglek@cisco.com>, Joseph R. Eykholt
<jeykholt@cisco.com>
description: Cisco FCoE HBA Driver
srcversion:
             60031A0CDAEE010E0A0B25A
              pci:v00001137d00000045sv*sd*bc*sc*i*
alias:
              libfcoe,libfc,scsi_transport_fc
depends:
              2.6.39-200.37.1.el5uek SMP mod_unload modversions
vermagic:
              fnic_log_level:bit mask of fnic logging levels (int)
parm:
[root@jde-ovm1 ~] # mkdir /test
[root@jde-ovm1 ~]# mount -o loop,ro dd-fnic-1.5.0.18-oracle-ovs-3.1.1.iso /test
[root@jde-ovm1 ~] # cd /test
[root@jde-ovm1 test]# rpm -ivh --nodeps
/test/rpms/x86_64/kmod-fnic-1.5.0.18-el6uek_ovm_3.1.1.x86_64.rpm
Preparing...
                          1:kmod-fnic
                          WARNING: The initrd image will contain multipath boot from san
[root@jde-ovm1 2.6.39-200.37.1.el5uek]# uname -a
Linux jde-ovm1 2.6.39-200.37.1.el5uek #1 SMP Fri Feb 8 03:53:53 PST 2013 x86_64
x86_64 x86_64 GNU/Linux
[root@jde-ovm1 /]# cd lib/modules/2.6.39-200.37.1.el5uek/kernel/drivers/scsi/fnic/
[root@jde-ovm1 fnic]# cp /lib/modules/2.6.39-200.1.1.el5uek/extra/fnic/fnic.ko .
cp: overwrite `./fnic.ko'? y
[root@jde-ovm1 fnic]# modprobe fnic
[root@jde-ovm1 fnic]# modinfo fnic
```

filename:	
/lib/modules/2	.6.39-200.37.1.el5uek/kernel/drivers/scsi/fnic/fnic.ko
version:	1.5.0.18
license:	GPL v2
author:	Abhijeet Joglekar <abjoglek@cisco.com>, Joseph R. Eykholt</abjoglek@cisco.com>
<jeykholt@cisco< td=""><td>D.COM></td></jeykholt@cisco<>	D.COM>
description:	Cisco FCoE HBA Driver
srcversion:	24F8E443F0EEDBDF4802F20
alias:	pci:v00001137d00000045sv*sd*bc*sc*i*
depends:	libfc,libfcoe,scsi_transport_fc
vermagic:	2.6.39-200.1.1.el5uek SMP mod_unload modversions
parm:	<pre>fnic_log_level:bit mask of fnic logging levels (int)</pre>
parm:	<pre>fnic_trace_max_pages:Total allocated memory pages for fnic trace</pre>
buffer (uint)	

3. Edit /etc/multipath.conf for EMC specific multipath device.

device	{	
	vendor	" EMC "
	product	"SYMMETRIX"
	getuid_callout	"/sbin/scsi_id -g -u -ppre-spc3-83 -s
/block/%n"		
	features	" 0 "
	hardware_handler	" 0 "
	path_grouping_policy	multibus
	rr_weight	uniform
	rr_min_io	8
	path_checker	tur
1		

}

4. Verify that all the FC paths are visible on OVS Server

```
[root@jde-ovml ~]# multipath -1
3600601604c3029009a6d5f53d7d4e211 dm-0 DGC,VRAID
size=40G features='1 queue_if_no_path' hwhandler='1 emc' wp=rw
`-+- policy='round-robin 0' prio=1 status=active
|- 0:0:0:0 sda 8:0 active ready running
|- 0:0:1:0 sdo 8:224 active ready running
`- 1:0:0:0 sdac 65:192 active ready running
`- 1:0:1:0 sdaq 66:160 active ready running
3600601604c302900cc4b23b27bd5e211 dm-1 DGC,VRAID
size=550G features='1 queue_if_no_path' hwhandler='1 emc' wp=rw
`-+- policy='round-robin 0' prio=1 status=active
|- 0:0:0:1 sdb 8:16 active ready running
|- 0:0:1:1 sdp 8:240 active ready running
|- 1:0:0:1 sdad 65:208 active ready running
`- 1:0:1:1 sdar 66:176 active ready running
```

5. As power path is not installed, following commands are issued to scan new luns added to OVS Host.

```
# ls /sys/class/fc_host
host0 host1
# echo "1" > /sys/class/fc_host/host0/issue_lip
# echo "- - -" > /sys/class/scsi_host/host0/scan
# echo "1" > /sys/class/fc_host/host1/issue_lip
# echo "- - -" > /sys/class/scsi_host/host1/scan
```

6. Once post-installation steps are executed we would proceed to Oracle VM Manager Installation.

OVM Manager Installation

Oracle VM Manager is installed as a production level; this is the preferred installation type, with options for selecting Oracle SE or EE database as the location for the Oracle VM Manager repository. Prior to installing Oracle VM Manager, ensure that Oracle SE Database is installed. Please follow the steps below to successfully install OVM Manager.

```
[root@ovmmanager ovmmanager]# ./runInstaller.sh
Oracle VM Manager Release 3.1.1 Installer
Oracle VM Manager Installer log file:
/tmp/install-2013-06-10-164951.log
Please select an installation type:
  1: Demo
  2: Production
  3: Uninstall
  4: Help
  Select Number (1-4): 2
Starting production installation ...
Verifying installation prerequisites ...
Oracle Database Repository
------
Use an existing Oracle database
Enter the Oracle Database hostname [localhost]: ovmmanager
Enter the Oracle Database System ID (SID) [XE]: orcl
Enter the Oracle Database SYSTEM password:
Enter the Oracle Database listener port [1521]: 1521
Enter the Oracle VM Manager database schema [ovs]: ovs1
Enter the Oracle VM Manager database schema password:
Invalid password.
Passwords need to be between 8 and 16 characters in length.
Passwords must contain at least 1 lower case and 1 upper case letter.
Passwords must contain at least 1 numeric value.
Enter the Oracle VM Manager database schema password:
Enter the Oracle VM Manager database schema password (confirm):
Oracle Weblogic Server 11g
------
Enter the Oracle WebLogic Server 11g user [weblogic]:
Enter the Oracle WebLogic Server 11g user password:
Enter the Oracle WebLogic Server 11g user password (confirm):
Passwords do not match
Enter the Oracle WebLogic Server 11g user password:
Enter the Oracle WebLogic Server 11g user password (confirm):
Oracle VM Manager application
```

Enter the username for the Oracle VM Manager administration user [admin]: Enter the admin user password: Enter the admin user password (confirm): Verifying configuration ... Start installing the configured components: 1: Continue 2: Abort Select Number (1-2): 1 Step 1 of 9 : Database ... Installing Database ... Database installation skipped ... Step 2 of 9 : Java ... Installing Java ... Step 3 of 9 : Database Schema ... Creating database schema 'ovs1' ... Step 4 of 9 : WebLogic ... Retrieving Oracle WebLogic Server 11g ... Installing Oracle WebLogic Server 11g ... Step 5 of 9 : ADF ... Retrieving Oracle Application Development Framework (ADF) ... Unzipping Oracle ADF ... Installing Oracle ADF ... Installing Oracle ADF Patch... Step 6 of 9 : Oracle VM ... Retrieving Oracle VM Manager Application ... Extracting Oracle VM Manager Application ... Installing Oracle VM Manager Core ... Step 7 of 9 : Domain creation ... Creating Oracle WebLogic Server domain ... Starting Oracle WebLogic Server 11g ... Configuring data source 'OVMDS' ... Creating Oracle VM Manager user 'admin' ... Step 8 of 9 : Deploy ... Deploying Oracle VM Manager Core container ... Deploying Oracle VM Manager UI Console ... Deploying Oracle VM Manager Help ... Enabling HTTPS ... Granting ovm-admin role to user 'admin' ... Step 9 of 9 : Oracle VM Manager Shell ... Retrieving Oracle VM Manager Shell & API ... Extracting Oracle VM Manager Shell & API ... Installing Oracle VM Manager Shell & API ... Retrieving Oracle VM Manager Upgrade tool ... Extracting Oracle VM Manager Upgrade tool ... Installing Oracle VM Manager Upgrade tool ... Copying Oracle VM Manager shell to '/usr/bin/ovm_shell.sh' ... Installing ovm_admin.sh in '/u01/app/oracle/ovm-manager-3/bin' Installing ovm_upgrade.sh in '/u01/app/oracle/ovm-manager-3/bin' ... Enabling Oracle VM Manager service ...

```
Shutting down Oracle VM Manager instance ...
Restarting Oracle VM Manager instance ...
Waiting 15 seconds for the application to initialize ...
Oracle VM Manager is running ...
Oracle VM Manager installed.
Please wait while WebLogic configures the applications... This can take up to 5
minutes.
Installation Summary
Database configuration:
 Database host name
                             : ovmmanager
 Database instance name (SID): orcl
  Database listener port
                           : 1521
 Application Express port : None
  Oracle VM Manager schema : ovs1
Weblogic Server configuration:
  Administration username
                             : weblogic
Oracle VM Manager configuration:
  Username
                             : admin
  Core management port
                             : 54321
                             : 0004fb00000100000a5c59c7f7487ffe
  UUID
Passwords:
There are no default passwords for any users. The passwords to use for Oracle VM
Manager, Oracle Database 11g XE, and Oracle WebLogic Server have been set by you
during this installation. In the case of a default install, all passwords are the
same.
Oracle VM Manager UI:
 http://ovmmanager:7001/ovm/console
 https://ovmmanager:7002/ovm/console
Log in with the user 'admin', and the password you set during the installation.
Please note that you need to install tightvnc-java on this computer to access a
virtual machine's console.
For more information about Oracle Virtualization, please visit:
 http://www.oracle.com/virtualization/
Oracle VM Manager installation complete.
Please remove configuration file /tmp/ovm_configzFYrq_.
```

Post OVM Manager installation, apply Oracle VM Manager 3.1.1 Patch Update (Build 365) [ID 1530546.1]. This would help in resolution of time out issues on creation of Oracle VM 3.1.1.

Oracle VM Configuration

Some of the important steps to configure Oracle VM environment are shown in Figure 48.

Figure 48 Oracle VM Configuration Steps



7. Discover Oracle VM Servers. The servers will be listed as Unassigned Server under Servers and VMs tab.

1

1



ORACLE [®] VM Manager				
Servers and VMs Repositories Network	ing St <u>o</u> rage Tools an	d R <u>e</u> sources <u>J</u> obs		
	View ▼ <u>P</u> erspective: Eve	nts 💌 🛷 Acknowledge	Acknowledge	All Display
Server Pools	Timestamp	Туре	Severity	Summary
V 🗓 Unassigned Servers	> Jul 03, 2013 2:13:03 pm	InformationalEvent	Informational	Discover Server
 ide-ovm6 Unassigned Virtual Machines 				

8. Configure VM Network as shown in Figure 50.

Figure 50

Γ

Network Configuration

OVM Server Network Architecture



9. Create Server Pool with the cluster LUN as the repository.

Figure 5 I Cluster Pool	Figure 51	Cluster Pool
-------------------------	-----------	--------------

```
Logged in as: admin Logout
                                                                                                                                                                       He<u>l</u>p •
ORACLE: VM Manager
  Servers and VMs
                   Repositories Networking Storage Tools and Resources Jobs
     🖳 🛅 📑 🖌 🖉 👯 🗙 🗌 🔍 🕑
                                                  Perspective: Info
                                                                              •
  ✓ P Server Pools
✓ P JDE_Cluster
                                                     Server Pool Name: JDE_Cluster
         jde-ovm1
         jde-ovm3
                                                    Server Count:
                                                                                          3
                                                                                                                   Secure VM Migrate:
                                                                                                                                                         No
         jde-ovm5
                                                    Clustered:
                                                                                          Yes
                                                                                                                   Pool File System Type:
                                                                                                                                                         Storage Element
  Unassigned Servers
                                                                                          jde-ovm5
                                                                                                                                                         Owned by You
                                                    Master Server:
                                                                                                                   Pool File System Ownership:
     Unassigned Virtual Machines
                                                                                          172.76.0.247
                                                                                                                                                         Local FS jde-ovm1, Local
                                                    Virtual IP:
                                                                                                                                                         FS jde-ovm3, Local FS jde-
ovm5, Local FS jde-ovm6
                                                                                                                   File Servers:
                                                    Keymap used for VM Creation:
                                                                                          en-us
                                               1
                                                                                Unmanaged FibreChannel Storage Array:/dev/mapper/3600601604c30290094d7f83380d5e211
                                                    Pool File System:
                                                    Pool File System Storage Device: ClusterPool
                                                    NFS/NAS File System:
                                                                                0004fb00000200000853b4249134817f
                                                    ID:
                                                    Description:
```

10. Create Storage Repository for each of the data luns configured for OVM Server. Ensure that the luns are shared across each of the Storage Group configured in EMC UniSphere.

RACLE: VM Manager						Logged in as: adm
ervers and VMs <u>R</u> epositories	letworking	St <u>o</u> rage	Tools and Resour	ces <u>J</u> obs		
Show My Repositories		Perspective: Info	T			
C Show All Repositories		Repository Ownership: File System: Share Path: File System Size File System Use Used %: ID:	(GiB): 550.0 d (GiB): 373.24 68%	ou		00601604c302900d66fbfa67bd5e211
▼ 🛃 REP-OVM3		Presented to Ser	vers:			
VM Templates Assemblies		Server Name	Server Pool	Status	IP Address	
ISOs		jde-ovm1	JDE_Cluster	Running	172.76.0.241	
Virtual Disks		ide-ovm3	JDE Cluster	Running	172.76.0.243	

Figure 52 Storage Repository

 Create VMs for each of the Oracle JDE tiers as shown in Figure 53. In accordance with Oracle recommendations, PVM Guest VMs are created. We would create two Guest VMS for each of the Oracle RAC nodes, two VMS for JDE App Servers and two VMs for JDE HTML Servers.

Figure 53 Guest VMs Details

ORACLE: VM Manager								Lo	ogged in as:	admin <u>L</u>	ogout He <u>l</u> p -
Servers and VMs Repositories Net	working		_	Resources	Jobs		1 2 U C 1		1		
 ✓ I Server Pools ✓ II JDE_Cluster 		Name	Status	Event Severity			N Memory (MB)	Max. Processors	-	Keymap	Operating System
Jde ovm1		💟 vm-db-node1	Running	Normal	7	126976	126976	10	10	en-us	Oracle Linux 5
jde-ovm3		Configurati	ion 💽	Networks	🕞 Di	sks					
> 🔟 Unassigned Servers		Name:		vm-db-node1		Memory (MB):		126976	Boot Orde	er:	Disk, Netv
📋 Unassigned Virtual Machines		Status: Operating Syste		Running Oracle Linux 5	J	Processor Ca Priority:	ap:	100 100	Network E	Boot Path	http://172. 01-OEL5.
		Keymap:		en-us		Mouse Type:		Default			
		Max. Processors	S:	10		Domain Type	:	Xen PVM			
		Processors:		10		High Availabil	lity:	false			
		Max. Memory (M	B):	126976		Repository for	r Configuration Fi	le: REP-OVM3			
		ID:		0004fb0000060	0008822	19df27131717					
		Domain ID:		13							
		Origin:									
		Description:									
		▷ vm-jdeapp1	Running	Normal	8	63488	63488	10	10	en-us	Oracle Linux 5
		> vm-jdehtml1	Running	Normal	16	65536	65536	8	8	en-us	Oracle Linux 5

Figure 54

I

ORACLE: VM Manager Servers and VMs and Re 📰 🖻 đ 戡 🗙 🛛 🔍 📀 View -Perspective: Virtual Machines • ∥ 🗙 ⊳ Server Pools Processors P Name →▼ Status Event Severity Server Memory (MB) JDE_Cluster vm-jdehtml2 Running Normal jde-ovm1 65536 8 jde-ovm1 vm-jdehtml1 Running Normal jde-ovm3 65536 8 1 jde-ovm3 vm-jdebatch1 Running Normal ide-ovm1 63488 10 63488 10 vm-jdeapp1 Running Normal jde-ovm3 ì Unassigned Servers vm-db-node2 Running Normal jde-ovm1 126976 10 Unassigned Virtual Machines vm-db-node1 Running Normal 126976 10 jde-ovm3

Guest VMs

- 12. Ensure that Oracle RAC node VMs are configured with Private network nics, as shown in Figure 50.
- **13.** JDE HTML and App Servers are configured with Virtual Disk, whereas the Oracle RAC Guest VMs are configured with Virtual Disk for OS and DB binary installation and physical disk for ASM, DATA and LOG luns. Each of these configurations is shown in Figure 55.

Figure 55 Disk Configuration for JDE Application Server

🚽 Edit V	/irtual Machine <mark>rym-jdeap</mark>	p1					
Confi	iguration Networks	Boot Order					
Slot	Disk Type	Contents	Action	S			1
0	Virtual Disk	VD-app1	9	÷	Í	×	
1	Empty 💌					_	

Figure 56 Disk Configuration for Oracle RAC Nodes

Edit Virtual Machine vm-db-node1

Confi	iguration Network:	Boot Order				
Slot	Disk Type	Contents	Action	s		
0	Virtual Disk	vd-vm-db-node1	Q	÷	I	×
1	Physical Disk	orcl-data-a	Q			
2	Physical Disk	orcl-log-a	9			
3	Physical Disk	orcl-asm	Q			
4	Physical Disk	orcl-data-b	9			
5	Physical Disk	orcl-log-b	0			

Once the Guest VMs are created we would proceed to Installation of Oracle Linux 5.8 on each of the VMs.

Oracle Linux Installation

Some of the important steps during Oracle Linux installation are:

1. Configure HTTP server location for PVM Guest Installation.

Figure 57 http Setup for PVM Installation



2. Ensure Text Mode is selected for PVM installation.



3. Select Virtual Disk for OS installation.



4. Once OS is installed Reboot the VM and proceed to post installation steps.



Some of the important steps executed post Oracle Linux installation are:

- 1. Edit private network vNIC of Oracle RAC nodes with MTU=9000
- **2.** Configure private and public IPs for Oracle RAC node VMs and public IPs JDE App and THML Servers.
- **3.** Edit Network, to add IP configuration for VLAN 760 (Public) and VLAN191 (for Private Interconnect traffic) to the respective ethernet interfaces.
- 4. Once the IP is updated, we would apply iptables patch to the all the Guest VMs. At high concurrent users we see following error messages on the /var/log/messages logs.

kernel: nf_conntrack: table full, dropping packet. kernel: nf_conntrack: table full, dropping packet.

Download package iptables-1.3.5-9.2.0.2.el5_8.x86_64 from URL= https://linux.oracle.com => Home > Channels > Channel: Oracle Linux 5 Update 10 Patch (x86_64)>Packages.

Update the rpm with rpm -Uvh iptables-1.3.5-9.2.0.2.el5_8.x86_64.rpm.

Apply the above patch to the all the Guest VMs with Oracle Linux 5.8 (uek kernel).

Once we complete the post-installation steps we would proceed to Oracle RAC setup on Guest VMs.

Oracle RAC Setup

This section describes the deployment of Oracle Database 11g R2 GRID Infrastructure with RAC option for Oracle JD Edwards EnterpriseOne deployment on Oracle Virtualized environment. After installation of Oracle Linux 5.8 on each RAC node, verify that all the required rpms are installed as part of OS installation which is required for Oracle GRID Installation.

As a best practice recommended from Oracle, ready-to-go Oracle VM Templates for Oracle RAC can be downloaded from Oracle Software Delivery Cloud for faster deployment.

Use the following Oracle document for pre-installation tasks, such as setting up the kernel parameters, RPM packages, user creation, and so on.

(http://download.oracle.com/docs/cd/E11882_01/install.112/e10812/prelinux.htm#BABHJHCJ)

Follow the steps to complete the Oracle Database 11g R2 GRID Infrastructure with RAC option Installation. For this solution the user, group, directory structure, kernel parameters and user limits can be created as shown in the steps below. One can resize the kernel parameter, user limits and rename the directory structure, user name, groups as per the business requirement.

1. Create required oracle users and groups in each RAC nodes.

```
groupadd -g 1000 oinstall
groupadd -g 1200 dba
useradd -u 2000 -g oinstall -G dba grid
passwd grid
useradd -u 1100 -g oinstall -G dba oracle
passwd oracle
```

```
Note
```

"grid" user owns the Oracle GRID installation whereas "oracle" user owns the Oracle Database Installation. In the present setup, we used OS LUN directory for GRID Installation and Database binary Installation.

- 2. Identify the virtual IP addresses and SCAN IPs and have them setup in DNS per Oracle's recommendation. Alternatively, you can update the /etc/hosts file with all the details (private, public, SCAN and virtual IP) if you do not have DNS services available
- **3.** List all the physical disk mounted on Oracle RAC VM nodes. Physical disk are shared across both the Oracle VM nodes.

```
Disk /dev/xvdb: 429.4 GB, 429496729600 bytes - orcl-data-a
Disk /dev/xvdc: 214.7 GB, 214748364800 bytes- orcl-log-a
Disk /dev/xvdd: 107.3 GB, 107374182400 bytes - orcl-asm
Disk /dev/xvde: 429.4 GB, 429496729600 bytes - orcl-data-b
Disk /dev/xvdf: 214.7 GB, 214748364800 bytes - orcl-log-b
Disk /dev/xvdg: 107.3 GB - orcl-asm1
```

4. Create partition on each of the physical disk. This has to be executed only in one of the Oracle RAC nodes. Following is the listing for each of the partitions.

I

[root@vm-db-node1 ~] # fdisk -1

Disk /dev/xvda: 322.1 GB, 322122547200 bytes 255 heads, 63 sectors/track, 39162 cylinders Units = cylinders of 16065 * 512 = 8225280 bytes

Device Boot	Start	End	Blocks	Id	-
/dev/xvda1 * /dev/xvda2	1 14	13 39162	104391 314464342+	83 8e	Linux Linux LVM
Disk /dev/dm-0: 210 255 heads, 63 secto Units = cylinders o	ors/track, 2	6357 cylin	ders		
Disk /dev/dm-0 does	sn't contain	a valid p	artition tab	le	
Disk /dev/dm-1: 10 255 heads, 63 secto Units = cylinders o	ors/track, 1	2789 cylin	ders		
Disk /dev/dm-1 does	sn't contain	a valid p	artition tab	le	
Disk /dev/xvdb: 429 255 heads, 63 secto Units = cylinders o	ors/track, 52	2216 cylin	ders		
Device Boot /dev/xvdb1	Start 1	End 52216	Blocks 419424988+	Id 83	-
Disk /dev/xvdc: 214	4.7 GB. 2147	48364800 b	vtes		
255 heads, 63 secto	ors/track, 2	6108 cylin	ders		
Units = cylinders o	of 16065 * 5:	12 = 82252	80 bytes		
Device Boot /dev/xvdc1	Start 1	End 26108	Blocks 209712478+	Id 83	System Linux
Disk /dev/xvdd: 10 255 heads, 63 secto Units = cylinders o	ors/track, 1	3054 cylin	ders		
Device Boot	Start	End	Blocks	Id	System
/dev/xvdd1	1	1305	10482381	83	Linux
/dev/xvdd2	1306	2710	11285662+		
/dev/xvdd3	2711	4015	10482412+	83	Linux
Disk /dev/xvde: 429					
255 heads, 63 secto Units = cylinders o		_			
Device Boot	Start	End	Blocks	Id	System
/dev/xvde1	1	52216	419424988+	83	-
Disk /dev/xvdf: 214 255 heads, 63 secto Units = cylinders o	ors/track, 2	6108 cylin	ders		
Device Boot	Start	End	Blocks	Id	System
/dev/xvdf1	1	26108	209712478+	83	Linux
Disk /dev/xvdg: 10 255 heads, 63 secto Units = cylinders o	ors/track, 1	3054 cylin	ders		
Device Boot	Start	End	Blocks	Id	System
/dev/xvdg1	1	1305	10482381	83	Linux
/dev/xvdg2	1306	2710	11285662+	83	Linux

L

Γ



For OCR voting disk, we have created 5 partitions 10G each, we had to allocated 2 luns of 100G as we can only have 4 partitions (primary or extended) on each physical. Hence, we created three 10G partitions on /dev/xvdd and two partitions on /dev/xvdg

5. Configure OracleASM.

[root@vm-db-nodel /]# /etc/rc.d/init.d/oracleasm configure Configuring the Oracle ASM library driver.

Default user to own the driver interface [grid]: Default group to own the driver interface [grid]: oinstall Start Oracle ASM library driver on boot (y/n) [y]: Scan for Oracle ASM disks on boot (y/n) [y]: Writing Oracle ASM library driver configuration: done Initializing the Oracle ASMLib driver: [OK] Scanning the system for Oracle ASMLib disks: [OK]

6. Create OCR voting disks.

[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk ocrvote1 /dev/xvdd1
Marking disk "ocrvote1" as an ASM disk: [OK]
[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk ocrvote2 /dev/xvdd2
Marking disk "ocrvote2" as an ASM disk: [OK]
[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk ocrvote3 /dev/xvdd3
Marking disk "ocrvote3" as an ASM disk: [OK]
[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk ocrvote4 /dev/xvdg1
Marking disk "ocrvote4" as an ASM disk: [OK]
[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk ocrvote4 /dev/xvdg1
Marking disk "ocrvote4" as an ASM disk: [OK]
[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk ocrvote5 /dev/xvdg2
Marking disk "ocrvote5" as an ASM disk: [OK]

Create data and log disk

[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk data_A /dev/xvdb1
Marking disk "data_A" as an ASM disk: [OK]
[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk data_B /dev/xvde1
Marking disk "data_B" as an ASM disk: [OK]
[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk log_A /dev/xvdc1
Marking disk "log_A" as an ASM disk: [OK]
[root@vm-db-nodel etc]# /etc/rc.d/init.d/oracleasm createdisk log_B /dev/xvdf1
Marking disk "log_B" as an ASM disk:

7. List ASM disks.

[root@vm-db-node1 etc]# /etc/rc.d/init.d/oracleasm listdisks DATA_A DATA_B LOG_A LOG_B OCRVOTE1 OCRVOTE2 OCRVOTE3 OCRVOTE4 OCRVOTE5

8. Scan ASM disk on second Oracle Node.

[root@vm-db-node2 ~]# /etc/rc.d/init.d/oracleasm scandisks Scanning the system for Oracle ASMLib disks: [OK] [root@vm-db-node2 ~]# /etc/rc.d/init.d/oracleasm listdisks

1

DATA_A DATA_B

LOG_A LOG_B OCRVOTE1 OCRVOTE2 OCRVOTE3 OCRVOTE4 OCRVOTE5

Once ASM disks are configured on the both the Oracle RAC node VMs, we would proceed to Oracle Grid Installation.

Oracle Grid Installation

ſ

Some of the important steps to configure Oracle Grid Infrastructure are:

1. Attach VNC session on one the Oracle RAC VM as grid user and execute Grid installer.



Figure 61 Execute Grid Installer

- 2. Click the Skip Software Updates radio button.
- 3. Click the Install and configure Oracle Grid Infrastructure for a cluster radio button.

F	Figure 62	Select Grid Installation		
Oracle Grid	Infrastructure	- Setting up Grid Infrastructure -	Step 2 of 9	_ = ×
Select Installation Option				11 ^g
🙊 Download Software Updates	Select any of the	e following installation options		
Installation Option	Install and C	Configure Oracle Grid Infrastructure for a <u>C</u> luster		
Installation Type Cluster Configuration	🔵 Configure O	Pracle Grid Infrastructure for a <u>S</u> tandalone Server		
Install Locations	O <u>U</u> pgrade Ora	acle Grid Infrastructure or Oracle Automatic Stor	rage Management	
Prerequisite Checks Summary Install Product Finish) Install Oracle	le <u>G</u> rid Infrastructure Software Only		
Help		<u>k</u> .	k Next > Install	Cancel

4. Select Advance Installation and move on to Grid Plug and Play Information.

1

	Figure 63	Scan and Cluster Name
Oracle Grid Infrastructure - S	Setting up Grid In	nfrastructure - Step 5 of 16 巴
Grid Plug and Play Informa	ation	
Download Software Updates Installation Option Installation Type Product Languages Grid Plug and Play Cluster Node Information Network Interface Usage Storage Option		vm-db-SCAN 1521 NS
OCR Storage Voting Disk Storage Operating System Groups Installation Location Prerequisite Checks Summary Install Product Finish	GNS <u>V</u> IP Add	
Help		< <u>Back</u> <u>N</u> ext > [Install] Cancel

L

Γ

5. Define Oracle RAC cluster node2 information.

	Figure 64	Add Cluster No	ode Informatio	n
Oracle Grid Infrastructure -	Setting up Grid Infra	astructure - Step 6 of 16		巴
Cluster Node Information	1	غبر		ORACLE 11g
Complead Software Updates	Virtual Hostname. If Oracle Grid Nam automatically conf	ting Service (GNS) has been se figured for each Public Node.	elected and DHCP is enab	oled, then the Virtual Hostname is
Product Languages	vm-db-node1	Public Hostname	vm-db-node1-vip	Virtual Hostname
Grid Plug and Play	om-ab-noder			
Q Cluster Node Information	Add Cluster	Node Information		து
Network Interface Usage				
🔍 Storage Option	Cuasification	name for the public IP addres	. If	
OCR Storage	virtual host	thame for the public iP addres thame manually, instead of all- illy, then you will be prompted	owing it to be configured	: I I I I I I I I I I I I I I I I I I I
Voting Disk Storage				
Operating System Groups	Public <u>H</u> ost	iname: vm-db-hodez		
Installation Location	Virtual Host	tname: vm-db-node2-vip		
Prerequisite Checks				
ý Summary			<u>o</u> k	Cancel
↓ ♀ Install Product				
J Finish	SSH <u>C</u> onnectivity	<u>U</u> se	Cluster Configuration F	ile <u>A</u> dd <u>E</u> dit <u>R</u> emove
Help			< <u>B</u> ack []	Next > Install Cancel

1

6. Establish ssh connectivity for both the Oracle RAC nodes.

	Figure 65	SSH Connectivit	t y	
Oracle Grid Infrastructure - S	Setting up Grid Infra	astructure - Step 6 of 16		빈
Cluster Node Information				ORACLE 118
Cownload Software Updates	Virtual Hostname. If Oracle Grid Nam			with their Public Hostname and ubled, then the Virtual Hostname is
Q Product Languages		Public Hostname		Virtual Hostname
	vm-db-nodel		vm-db-nodel-v	
Grid Plug and Play	vm-db-node2		vm-db-node2-vi	ip
Copy Copy Copy Copy Copy Copy Copy Copy		shing SSH connectivity between th . This may take several minutes. Pl	ease wait	File] Add] Edit] Remove
A Installation Location	<u>O</u> S Username: g	grid	OS Pass <u>w</u> ord:	****
Prerequisite Checks	Ulser home is	shared by the selected nodes		
y Summary				
↓ ♀ Install Product	Reuse private	and public <u>k</u> eys existing in the us	erhome	
	N			<u>T</u> est Setu <u>p</u>
Help			< <u>B</u> ack	Next > Install Cancel

Γ

7. Specify Network Interface Usage.

F	Figure 66 Spec	cify Interface Type		
Oracle Grid Infrastructure - S	Setting up Grid Infrastructure -	Step 7 of 16		四
Specify Network Interface	Usage			11 ^g
Download Software Updates Installation Option Installation Type Product Languages	Use. Private interfaces are use	ich global interface shown in the l d by Oracle Grid Infrastructure fo et associated with an interface, th with the additional subnets.	r internode traffic.	
Grid Plug and Play	Interface Name	Subnet	Interface T	vne
Cluster Node Information	eth0	172.76.0.0	Public	
	eth1	191.168.1.0	Private	-
Network Interface Usage	virbr0	192.168.122.0	Do Not Use	
🗼 Storage Option				
OCR Storage				
Voting Disk Storage				
operating System Groups				
L Installation Location				
Prerequisite Checks				
ý Summary				
 Install Product 				
 Finish 				
b .				
r.				
Help		< <u>B</u> ac	tk <u>N</u> ext > Install	Cancel

1

8. Select Oracle ASM as the storage Options.

 Oracle Grid Infrastructure - Setting up Grid Infrastructure - Step 8 of 16 Storage Option Information Download Software Updates Installation Option Installation Type Product Languages Grid Plug and Play Cluster Node Information Shared File System Shared File System 	I	Figure 67	Storage Options	
Pownload Software Updates You can place Oracle Cluster Registry (OCR) files and voting disk files on Oracle ASM storage, or on a file system. Installation Option Installation Type Product Languages Oracle Automatic Storage Management (Oracle ASM) Choose this option to configure OCR and voting disk files on Oracle ASM storage. Cluster Node Information Network Interface Usage	Oracle Grid Infrastructure - S	nfrastructure - Setting up Grid Infr	astructure - Step 8 of 16	E
system. System. System. System. Oracle Automatic Storage Management (Oracle ASM) Choose this option to configure OCR and voting disk files on Oracle ASM storage. Crid Plug and Play Cluster Node Information Network Interface Usage Stared File System Cluster Node Information Network Interface Usage System Choose this option to configure OCR and voting disk files on Oracle ASM storage. Stared File System Stared File System Stared File System Choose this option to configure OCR and voting disk files on Oracle ASM storage.	Storage Option Information	n Information		DATABASE 11
Choose this option to configure OCR and voting disk files on an existing shared file system. OCR Storage Operating System Groups Installation Location Prerequisite Checks Summary Install Product Finish	 Installation Option Installation Type Product Languages Grid Plug and Play Cluster Node Information Network Interface Usage Storage Option OCR Storage Voting Disk Storage Operating System Groups Installation Location Prerequisite Checks Summary Install Product 	Invate Opdates system. system. system. Oracle Autom Choose this of Choose this of Shared File Sy Choose this of Choose	atic Storage Management (Oracle ASM) option to configure OCR and voting disk file stem	es on Oracle ASM storage.
Help < Back Next > Install Cancel	Help		<	<u>Back Next > Install</u> Cancel

Γ

9. Scan ASM disk and create OCR disk group.

	Figure 68	ASM Disk Group	
Oracle Grid Infrastructure - Create ASM Disk Group	Setting up Grid Infra	istructure - Step 9 of 16	ORACLE 11 ^g
Download Software Updates Installation Option Installation Type Product Languages Grid Plug and Play Cluster Node Information	Select Disk Group (<u>D</u> isk Group Name Redundancy AU <u>S</u> ize	Characteristics and select disks OCRVOTE O High O Normal External	
Network Interface Usage Storage Option Create ASM Disk Group ASM Password Operating System Groups Installation Location Prerequisite Checks Summary	Change Dis	K Discovery Path	Size (in MB) Status
Install Product Finish			Change Discovery Path
Help		< <u>B</u> ac	k <u>N</u> ext > Install Cancel

1

	Figure 69 Select Disks	
Oracle Grid Infrastructure -	Setting up Grid Infrastructure - Step 9 of 16	巴
Create ASM Disk Group		ORACLE 118
Dowmload Software Updates Installation Option Installation Type Product Languages Grid Plug and Play Cluster Node Information Network Interface Usage Storage Option Create ASM Disk Group ASM Password Operating System Groups Installation Location Prerequisite Checks Summary Install Product Finish	Select Disk Group Characteristics and select disks Disk Group Name OCRVOTE Redundancy High Normal External AU Size Add Disks Candidate Disks Candidate Disks Disk Path //dev/oracleasm/disks/LOC_A //dev/oracleasm/disks/LOC_B //dev/oracleasm/disks/OCRVOTE1 //dev/oracleasm/disks/OCRVOTE2 //dev/oracleasm/disks/OCRVOTE3 //dev/oracleasm/disks/OCRVOTE3 //dev/oracleasm/disks/OCRVOTE4 //dev/oracleasm/disks/OCRVOTE4 //dev/oracleasm/disks/OCRVOTE5 //dev/oracleasm/disks/OCRVOTE5 //dev/oracleasm/disks/OCRVOTE5 //dev/oracleasm/disks/OCRVOTE5 //dev/oracleasm/disks/OCRVOTE5 //dev/oracleasm/disks/OCRVOTE5 //dev/oracleasm/disks/OCRVOTE5 //dev/oracleasm/disks/OCRVOTE5 //dev/oracleasm/disks/OCRVOTE5	Size (in M8) Size (in M8) Status 204797 Candidate 204797 Candidate 10236 Candidate 10236 Candidate 10236 Candidate 10236 Candidate 10236 Candidate 10236 Candidate 10236 Candidate 10236 Candidate 10236 Candidate
Heip	< <u>B</u> ack	Next > Install Cancel

Γ

10. Specify ASM password, and move on to specify Installation location.

F	igure 70	Specify Insta	llation Location	1	
Oracle Grid In	frastructure -	Setting up Grid Inf	astructure - Step	13 of 17	_ 🗆 ×
Specify installation Locatio	n			ORACLE DATABASE	11 ^g
Download Software Updates Installation Option Installation Type Product Languages Grid Plug and Play Cluster Node Information Network Interface Usage Storage Option OCR Storage Voting Disk Storage Failure Isolation Operating System Groups Installation Location Prerequisite Checks Summary Install Product Finish	installed in a path owner. <u>O</u> racle Base: /u Specify a location directory. This so	le Grid Infrastructure for a (h indicating the Oracle Grid 101/app/grid n for storing Oracle softwar oftware directory is the Ora n: //u01/app/11.2.0/grid	Infrastructure release an	d grid infrastructure so	oftware B <u>r</u> owse
Нер			< <u>B</u> ack	Next >	Cancel

11. Verify all the pre-requisite check are completed successfully and verify the installation Summary.

1

Oracle Grid Infrastructure - Summary	Setting up Grid Infrastructure - Step 16 of 18
Download Software Updates Installation Option Installation Type Product Languages Grid Plug and Play Cluster Node Information Network Interface Usage Storage Option Create ASM Disk Group ASM Password Failure Isolation Operating System Groups Installation Location Create Inventory Prerequisite Checks	Oracle Grid Infrastructure Global Settings Disk Space: required 5.5 GB available 177.51 GB Install Option: Install and Configure Oracle Grid Infrastructure for a Cluster Oracle base for Oracle Grid Infrastructure: /u01/app/grid Grid home: /u01/app/11.2.0/grid Source Location: /dump/grid/install//stage/products.xml Privileged Operating System Groups: oinstall (OSASM) Inventory Information Inventory Information: Central inventory (oralnventory) group: oinstall Grid Infrastructure Settings Cluster Name: vm -db-cluster Local Node: vm -db-node1 Remote Nodes: vm -db-node2 Single Client Access Name (SCAN): vm -db-SCAN SCAN Port: 1521 Public Interfaces: etb0
Summary Summar	Save Response File

Figure 71 Installation Summary

I

Γ

- **12**. Continue to Install Oracle Grid Infrastructure.
- **13.** Execute root scripts on each of the Oracle RAC node VMs.



Figure 72 Execute Configuration Script

```
peer cert
  pa cert
  profile reader root cert TP
  pa peer cert TP
  profile reader peer cert TP
  peer user cert
  pa user cert
 dding Clusterware entries to inittab
CRS-2672: Attempting to start 'ora.mdnsd' on 'vm-db-node1'
 RS-2676: Start of 'ora.mdnsd' on 'vm-db-node1' succeeded
CRS-2672: Attempting to start 'ora.gpnpd' on 'vm-db-node1'
CRS-2676: Start of 'ora.gpnpd' on 'vm-db-node1' succeeded
CRS-2672: Attempting to start 'ora.cssdmonitor' on 'vm-db-node1'
CRS-2672: Attempting to start 'ora.gipcd' on 'vm-db-node1'
CKS-2672: Attempting to start 'ora.giptcd' on 'vm-db-nodel'
CRS-2676: Start of 'ora.cssdmonitor' on 'vm-db-nodel' succeeded
CRS-2676: Start of 'ora.giptcd' on 'vm-db-nodel' succeeded
CRS-2672: Attempting to start 'ora.cssd' on 'vm-db-nodel'
CRS-2672: Attempting to start 'ora.diskmon' on 'vm-db-nodel'
 CRS-2676: Start of 'ora.diskmon' on 'vm-db-node1' succeeded
CRS-2676: Start of 'ora.cssd' on 'vm-db-node1' succeeded
ASM created and started successfully.
Disk Group OCRVOTE created successfully.
clscfg: -install mode specified
Successfully accumulated necessary OCR keys.
Operation successful.
CRS-4256: Updating the profile
Successful addition of voting disk 62dc91ed52e24fb3bf14c557c0dc91be.
 Successful addition of voting disk 1a5923fb08054f59bf5705b37bddd270.
 Successful addition of voting disk 4291b2bc44834fe3bfbf6a4acc249d16.
 Successfully replaced voting disk group with +OCRVOTE.
CRS-4256: Updating the profile
                                                             File Name Disk group
## STATE
                File Universal Id
 1. ONLINE
                62dc91ed52e24fb3bf14c557c0dc91be (/dev/oracleasm/disks/OCRVOTE1) [OCRVOTE]
               1a5923fb08054f59bf5705b37bddd270 (/dev/oracleasm/disks/OCRVOTE2) [OCRVOTE]
4291b2bc44834fe3bfbf6a4acc249d16 (/dev/oracleasm/disks/OCRVOTE3) [OCRVOTE]
 2. ONLINE
 3. ONLINE
  ocated 3 voting disk(s)
```

14. Once root scripts are executed, we will get the Installation Complete window.

I



Once Oracle RAC Grid infrastructure is installed, proceed to Oracle Database Installation. For more information on Oracle RAC Grid, see Grid Infrastructure Installation Guide for Linux: http://www.oracle.com/pls/db112/to_toc?pathname=install.112/e10812/toc.htm

Oracle Database Installation

Some of the important steps to configure Oracle Grid Infrastructure are:

1. Attach VNC session on one of the Oracle RAC VM as oracle user and execute database installer.



Figure 74 Execute Database Installer

ſ

2. Click the Install database software only radio button. We can configure the database once we have the DB binaries



3. Select both the nodes on Oracle RAC database installation.

Configure Security Updates Select the type of database installation you want to perform. Download Software Updates Single instance database installation Installation Option Oracle Read Ong Node database installation Oracle RAC Ong Node database installation Prerequisite Checks Summary Install Product Finish SISH Connectivity Select All SISH Connectivity Select All	Oracle Database 11g Release Grid Installation Options	2 Installer - Installing database - Step 4 of 10
	Download Software Updates Installation Option Grid Installation Options Install Type Typical Installation Prerequisite Checks Summary Install Product	 Single instance database installation Oracle Real Application Clusters database installation Oracle RAC Ong Node database installation Select nodes (in addition to the local node) in the cluster where the installer should install Oracle RAC or Oracle RAC One. Node Name 1 vm-db-node1 2 vm-db-node2

Figure 76 Select Nodes

Γ

4. Configure ssh connectivity.

Oracle Database 11g Relea	se 2 installer - Installing database - Step 4 of 10
id Installation Options	
Configure Security Updates Download Software Updates Installation Option Grid Installation Options Install Type Typical Installation Prerequisite Checks	Select the type of database installation you want to perform.
Summary Install Product Finish	✓ 2 lym-db-node2 SSH Conny-tivity Select All Deselect A
	OS Username: oracle OS Password: ****** User home is shared by the selected nodes Reuse private and public keys existing in the user home Test Setup

5. Once the installation location and connectivity between Oracle RAC nodes is verified, we can see them in the Installation Summary window.

1

Summary	Ee 11g Release 2 Installer - Installing database - Step 10 of 12
Configure Security Updates Download Software Updates Installation Option Grid Installation Options Product Languages Database Edition Installation Location Operating System Groups Prereouisite Checks Summary Install Product Finish	Oracle Database 11g Release 2 Installer Global settings Disk space: required 4.5 GB available 180.29 GB Source location: /dump/database/install//stage/products.xml Database edition: Enterprise Edition (Install database software only) Oracle base: /u01/app/oracle Software location: /u01/app/oracle/product/11.2.0/dbhome_1 Cluster Nodes: vm-jdedb1, vm-jdedb2 Privileged Operating System Groups: dba (OSDBA)
	Save Response File
Help	<back next=""> Install Cancel</back>

Figure 78 Installation Summary

I

Γ

6. Execute root scripts on each of the Oracle RAC nodes



Figure 79 Execute Root Scripts

7. Verify that the Database installation is completed successfully.

Finish		DATABASE 118
Configure Security Updates Download Software Updates Installation Option Product Languages Database Edition Installation Location Operating System Groups Prerequisite Checks Summary Install Product	The installation of Oracle Database was successful.	
Finish		

Figure 80 Installation Successful

For complete details on Oracle RAC database installation, see Real Application Clusters Installation Guide for Linux and UNIX for detailed installation instructions (http://www.oracle.com/pls/db112/to_toc?pathname=install.112/e10813/toc.htm)

Oracle RAC Post Installation

I

After successfully installation Grid Infrastructure and Oracle Database binaries we would proceed to configure of Oracle RAC instance. This involves creation of ASM disk group for Oracle Data & Oracle Logs through asmca and configuration of DB instance through dbca.

Following are some of the important Oracle RAC Post installation steps:

1. VNC as grid user and execute asmca. Select Oracle Data path for creation of DATA disk group.

28.01	roup Name data						
Red	undancy						
two o	indancy is achieved by storing multip different failure groups, and high red High Normal External (None) 					ancy needs dis	ks from at least
0.140	ct Member Disks						
	how Eligible () Show All						
2) 21	now Eligible O Show All						
Juor	rum failure groups are used to store	voting files in exter	nded clusters a	nd do not con	tain any user dat	a. They require	e A SM
	patibility of 11.2 or higher.				121010000000000000000000000000000000000		
F	Disk Path	Header Status	Disk Name	Size (MB)	Failure Group	Quorum	1
P	/dev/oracleasm/disks/DATA_A	PROVISIONED	Disk Name	409594	railure Group	Quorum	
V.		PROVISIONED		409594			
Ě	/dev/oracleasm/disks/DATAC6 /dev/oracleasm/disks/LOG_A	PROVISIONED		204797		- <u>-</u>	
'n	/dev/oracleasm/disks/LOG_B	PROVISIONED		204797		i i i	5
1.00	Juel of acleasing disks/200_0	TROVIDIONED	-	204757			53 C
	: If you do not see the disks which yo Disk Discovery Path limits set of disks			isk Discovery	Path and read/w	rite permission	ns on the disks.
	bisk biscovery Patri innits set bi disks	considered for dis	scovery.			-	
	Disk Discovery Path:/dev/oracleasm/disks/*					Change Disk Discovery Path	
The I							
he l			k arous stribut	es. Disk Grou	n compatibility a	ttributes may r	eed to be modi
The l	n the Show Advanced Ontions buttor	to change the dist					recure be mound
The I Disk ck o	n the Show Advanced Options buttor					2012/2012/2011/2012/1	
The I Disk ick o	n the ShowAdvanced Options buttor on the usage of disk group for differ						

Figure 81 Select Oracle Data path for Creation of DATA Disk Group

I

- 2. Create Disk Group.
- Figure 82 Create Disk Group

Create Disk Group		
Disk Group Name	data	
Redundancy		
	s, and high redundancy from at least three different fa	e groups. Normal redundancy needs disks from at least ilure groups.
Select Member Disks		
Show Eligible Show	A.U.	
Quorum failure group		비 auire A SM
compatibility of 11.2 d	Creating Disk Gr	oup data
Disk Path	ATT THE REAL PROPERTY AND A DECIMAL OF A DEC	
✓ /dev/oracleas		
/dev/oracleas	1 Barrier	
/dev/oracleas /dev/oracleas	- Contraction of the second se	
	e disks which you believe are available, check the Disk D mits set o Ndisks considered for discovery.	iscovery Path and read/write permissions on the disks.
Disk Discovery Path:/dev	Change Disk Discovery Path	
		isk Group compatibility attributes may need to be modifi
ased on the usage of disk	group for different versions of databases or ASM Clust	er File Systems.
	ShowAdvanced Options OK C	ancel Help
3. Similarly create Oracle LOG disk group.

Figure 83	Create Oracle LOG Disk Group
-----------	------------------------------

isk Group Name	redo		
Redundancy			
	ps, and high redundancy from a	: data on different failure groups. Norm at least three different failure groups.	nal redundancy needs disks from at leas
Select Member Disks			
Show Eligible O Show	All		
Quorum failure group	Disk Group: Creation		auire ASM
compatibility of 11.2 c	Two which we have the control of the second s		
Disk Path	distantion of	Creating Disk Group redo	
✓ /dev/oracleas	-332		
✓ /dev/oracleas	A BANK		
	and the second s		
	e disks which you believe are av imits set of disks considered for		and read/write permissions on the disks
Disk Discovery Path:/dev	lavaelaaren (dieke (*		Change Disk Discovery Pat
Disk Discovery Path./dev	oracleasm/disks/~		Change Disk Discovery Pat
lick on the Show Advance		disk group attributes. Disk Group com databases or ASM Cluster File Systems.	patibility attributes may need to be mod
	group for different versions of	decapases of ASM cluster the systems	

- **4.** Now VNC with Oracle User and execute dbca Select +DATA and +LOG as path for Oracle Data and Oracle Log files.
- 5. Once dbca is executed successfully we would see instances of Oracle RAC on each of the VM.

Figure 84 Oracle RAC Instance on Each VM

🛃 root@	vm-db-node1	line .					_ 🗆 ×
[root@v	m-db-node	1 ~]#	ps -e	f grep p	mon		2
root	1818 1	0798	0 13:	16 pts/0	00:00:00	grep pmon	
grid	17745	1	0 13:	14 ?	00:00:00	asm pmon +ASM1	
oracle	19584	1	0 13:	14 ?	00:00:00	ora pmon orcl1	
[root@v	m-db-node	1 ~]#	Π				
			1.1.1				
🚽 root@	vm-db-node2						_ 🗆 🗙
[root@v	m-db-node.	2 ~]#	ps -e	f grep p	mon		-
oracle	1217	1	0 13:	13 ?	00:00:00	ora_pmon_orcl2	
	14385 1	2509	0 13:	15 pts/0	00:00:00	grep pmon	
root	11000 A						
		1	0 13:	12 ?	00:00:00	asm pmon +ASM2	

Oracle JD Edwards EnterpriseOne Installation

The Installation of Oracle JD Edwards (JDE) 9.0.2 suite on Oracle VM with Oracle Linux 5.8 and Oracle RAC 11.2.0.3 as the RDBMS is described in the sections below:

Pre-Requisites

- See the latest JDE MTRs for the most up-to-date information regarding the pre-requisites for your install http://docs.oracle.com/cd/E24902_01/nav/installation.htm.
- All the required JDE software were downloaded from Oracle eDelivery and Oracle UpdateCenter
- Network connectivity between all the machines involved.

General Install Requirements

Following are generic pre-requisites before installing the Oracle JDE Enterprise Server.

- Make sure the Disk space is sufficient enough for the installation, for detailed space requirements, see: https://support.oracle.com/epmos/faces/DocumentDisplay?id=747323.1
- Database Server Software has to be installed in JDE Database Server.
- Database client software has to be installed in other JDE Servers like Application Server and Deployment Server.
- Make sure enough temporary disk space is available for the installers and wizards.

Oracle JD Edwards EnterpriseOne Specific Install Requirements

The below mentioned are some of the requirements to be considered for JD Edwards EnterpriseOne installation



It is strongly recommended that installation be performed by running installers using the 'run as administrator' option.

Server Type	Install Requirements
JDE Deployment Server	• Installation of JDE Deployment server for JDE version 9.0
	• Installation of Application update 2 for 9.0 JDE applications
	• Installation of JDE Deployment server tools version 8.98.4.10
	• Installation of JDE ServerManager for 8.98.4.6
	Installation of Microsoft VisualStudio 2008 SP1
	• Installation of Microsoft Windows SDK v6.0A
	• Visual Studio 2005sp1 runtime libraries should be installed on deployment server.
JDE Enterprise Server	• Installation of JDE Enterprise server tools version 8.98.4.10
	Installation of Oracle Linux 5.8

Table 7

7 JD Edwards EnterpriseOne Installation Requirements

JDE Database Server	• Installation of JDE 9.0 databases in Database Server machine.
	• Installation of Oracle Linux 5.8
	• Oracle 11.2.0.3 RAC DB
JDE HTML Server	Installation of Oracle Linux 5.8
	• Installation of JDK or jrockit-jdk1.6.0_29-R28.2.2-4.1.0 in Web Server machine before doing the Web logic server installation.
	• Installation of Oracle Weblogic 10.3.6 in web server machine.
	• Installation of Oracle HTTP server
	• Installation of JDE HTML server 8.98.4.10

Table 7 JD Edwards EnterpriseOne Installation Requirements

JDE Install Port Numbers

Table 8 shows the port numbers that are used for WLS, JDE, HTTP ports, and so on.

Port	Port Number	
WLS	7503-7581	
JDE Enterprise Server	9700	
НТТР	7777	
SQLServer	14501	

Table 8Port numbers

The steps followed to install Oracle JD Edwards on Cisco UCS are shown in Figure 85:





Oracle JDE Deployment Server Install

The Deployment server is used as a repository of JD Edwards installation and upgrade software and data artifacts. This section shows the steps for installing the JD Edwards deployment server. The installation steps shown here forth are specific to the JD Edwards 9.0.2 application suite used in conjunction with JD Edwards tools release 8.98.4.10.

To Install the JDE Deployment Server, follow these steps:

1. Download the Deployment Server binaries from Oracle eDelivery into a directory and extract the zip files in place using tools like Winzip or 7zip.

Run the steps below, as referenced from Oracle solution ID: Document 1310036.1

Follow the below mentioned steps to download the installer for the database and the installer for the .NET Framework from Microsoft. In addition, you must follow these directions to download a program from Oracle that runs the two Microsoft installers, passing them parameters that EnterpriseOne needs to run properly.



Referenced from Oracle solution ID: Document 1310036.1

2. To download the Microsoft SQL Server Express 2005 SP3 Installer on the Deployment server, follow these steps:

- a. Go to the Microsoft Download Center: http://www.microsoft.com/downloads
- **b.** In the search field near the top of the screen, enter SQL Server 2005 Express Edition SP3 and click **Search**.
- c. Click the link SQL Server 2005 Express Edition SP3.
- d. Next to the file called SQLEXPR.EXE, click Download.
- e. Save the file to your Deployment Server in this location: <dep_svr_install_dir>\OneWorld Client Install\ThirdParty\SSE
- **3.** The .NET Framework contains new Windows files that applications such as SSE can use. Oracle highly recommends that you install at least version 4.0 of the Microsoft .NET Framework. For this procedure, you should download the installer to the Deployment Server as described below.
 - a. Go to the Microsoft Download Center: http://www.microsoft.com/downloads
 - b. In the menu bar at the top of the screen, click Downloads A-Z and type N and NET
 - c. Click the link Microsoft .NET Framework 4 (Web Installer).
 - d. Next to the file called dotNetFx40_Full_setup.exe, click Download.
- 4. Save the file to your deployment server in this location: <dep_svr_install_dir>\OneWorld Client Install\ThirdParty\SSE
- 5. The DotNetSSESetup.exe program runs the .NET Framework and SSE installers. Locate and download the EnterpriseOne DotNetSSESetup.exe and related file called settings.ini from E-Delivery using this part number and description:

V24818-01 JD Edwards EnterpriseOne Tools 8.98.4.2 - Microsoft SQL Server 2005 Express SP3 Local Database Installer for Deployment Server and Development Client

Place the SSE 2005 SP3 installer SQLEXPR.exe and the .NET Framework 4 installer dotNetFx40_Full_setup.exe onto your Deployment Server in this directory: <dep_svr_install_dir>\OneWorld Client Install\ThirdParty\SSE

- 6. Edit the settings.ini file in this directory: <dep_svr_install_dir>\OneWorld Client Install\ThirdParty\SSE The settings.ini file contains settings for installing the .NET Framework and SSE. For completeness, these settings include those for .NET Framework 2.0/SSE 2005 prior to SP3 and for .NET Framework 4.0/SSE 2005 SP3.
- 7. In the settings.ini file, uncomment the settings for the set of installers that you will be using, and comment out (by adding a semicolon at the start of the line) the settings for the set of installers that you will not be using. Note: Only one set must be uncommented, and only one set must be commented out.
- 8. Save the settings.ini file.
- 9. Run the DotNetSSESetup.exe file as administrator.
- **10.** After the .NET Framework is installed successfully, download the appropriate SQL Server JDBC driver for SQL server 2005 SP3 from MSDN.
- **11.** Place the SQL Server JDBC drivers in a folder named JDBC.
- **12.** Now execute the RunInstaller in Admin mode from the deployment server disk1 folder that was unzipped in Step 1.
- **13.** Choose the directory for installing deployment server as well as the directory which contains the SQLServer driver.
- **14.** Install the Deployment Server Installer and then Install the Deployment Server. After the successful Installation proceed to next installation.

Figure 86

D JD Edwards EnterpriseOne Deployment Server 9.00 Installer				
	Installing JD Edwards EnterpriseOne Deployment Server. Please wait			
JD Edwards EnterpriseOne Deployment Server	Attaching the planner data, please wait 7%			

15. Install Microsoft Visual Studio C Runtime libraries using the vcredist.exe (download the relevant platform from msdn) for VisualStudio 2005 SP1.

JD Edwards Enterprise One Deployment Server Installation Progress

16. Run the vcredist.exe as administrator. Click **Yes** to accept the license agreement, and proceed to Install the Microsoft Visual Studio C Runtime Libraries.

Figure 87

Installing the Visual Studio C Runtime libraries



Figure 88

Accepting the License Agreement Prior to Install



Tools Upgrade on the Deployment Server

I

After the deployment server install is completed successfully, a tools upgrade to 8.98.4.10 is performed. To upgrade the tools release, follow these steps:

- 1. Download the appropriate tools release (8.98.4.10 deployment server in this case) from update center and run the InstallManager.exe as an administrator. Choose Workstation Install, which encapsulates most installs on client workstations, to get options regarding available tools releases.
- 2. Install the chosen tools release for the deployment server (8.98.4.10 in this case).

Figure 89 Installing the JD Edwards Enterprise One Workstation

🛃 JD Edwards Install Manager			
	ORACLE		
	JD EDWARDS ENTERPRISEONE		
install:			

3. Click **Next** to proceed with the Installation, and click the **Tools Release** radio button to define the setup type. Click **Finish** to complete the tools upgrade.

Figure 90 Selecting Options to Proceed Installation

Workstation Install

JD Edwards EnterpriseOne Client Install	Welcome to the JD Edwards® EnterpriseOne Client installation program. The Tools Release installation program cannot update shared files if the files are in use. Before continuing, please close any open applications.
ORACLE	Click Next to continue or Cancel to quit. If you would like to know more about the setup process, click the Help button. In the following setup screens, click Help to obtain a more detailed description of the setup screen or its options.



Figure 91 Selecting the Tools Upgrade Setup Type

Install Planner ESU

To download and install the Install Planner ESU, follow these steps:

1. Download the appropriate planner ESU from Oracle update center onto the deployment server and unzip the contents. Run the executable as an administrator. The planner is installed using the EnterpriseOne client workstation installation program.

Figure 92 Sign in to the JD Edwards EnterpriseOne Client Install Using the JDE User

🔒 Client Workstation Setup	Package Selection	×
JD Edwards EnterpriseOne Client Install	This package requires an EnterpriseOne User and password so it can apply the update.	
ORACLE		
	< <u>B</u> ack <u>N</u> ext≻ Cancel Help	

-	Client Workstation Insta	llation Setup Type	×
	JD Edwards EnterpriseOne Client Install	Select Setup Type UL18560 JL18560 Install Path: C:\JDEdwards\E900	
	ORACLE	Drive Space Available Space Required ■ C:\ 101910 MB 63 MB	
-		< <u>B</u> ack Finish Cancel Help	·

Selecting the Setup Type

- 2. After the Planner has installed successfully, run the Special Instructions for the planner. Open windows cmd prompt in administrator mode.
- 3. In the cmd prompt, change the directory to the scripts directory of the planner ESU.

Figure 94 Changing the Directory to Scripts

Figure 93

I



4. Run specialInstrs.bat command in the command prompt.

Figure 95 Running the command SpecialInstrs



5. Choose the SQL Server Express option and type S in the command prompt.

Figure 96 Selecting the SQL Server Express



6. Run the R98403XB XJDE0002 report, which copies control records from the shipped XML database into the local planner databases, since ESUs are shipped with an XML database, starting with Apps 9.0.

Figure 97 Copying the Control Records



- Edit jdbj.ini in the OC4J webclient deployment on the deployment server (C:\JDEdwards\E900\SYSTEM\OC4J\j2ee\home\applications\webclient.ear\webclient\WEB-INF\ classes).
- 8. Comment as 400 and Oracle drivers with #.

Figure 98 Commenting the AS400 and Oracle Drivers



9. In the Connection Pooling Settings, increase the connectionTimeout in jdbj.ini to 3600000.

Figure 99 Incrementing the Connection Timeout

📕 jdbj - Notepad	- O ×
File Edit Format View Help	
# JDBC drivers	<u> </u>
DDBC drivers This defines DDBC drivers and DDBC specific settings.	
[JOBJ-JDBC DRIVERS] #ORACLE=oracle.jdbc.driver.OracleDriver #AS400=com.itom.as400.access.AS400JOBCDriver SQLSERVER=com.microsoft.sqlserver.jdbc.SQLServerDriver #UDB=COM.itom.db2.jdbc.app.DeDoriver	
[JDB]-ORACLE] tns=tnsnames.ora	
[Job]=LGGS] jdbcTrace=false	
[JOB]-SERVER] dbcsConversionTolerant=true	
Connection pool settings These are used only when J2EE connection pooling is not available.	
These are used only when J2EE connection pooling is not available.	
[JOB]-CONNECTION POOL] [JDcFooling=false micConnection=1 maxConnection=5 InitialConnection=1 poolgrowth=1 connectionTimeout=3600000 cleanPoolInterval=600000 maxS12e=50	
1	25

- **10.** Run report R98403XB, which copies control records from the shipped XML database into the local planner databases. Open ActiveConsole in administrator mode.
- 11. Sign in using the JDE user credentials using Environment-JDEPLAN, Role-ALL.
- 12. Type BV in fastpath text boxes, to open the batch versions.

ſ

13. Type in R98403XB in Batch Application text box and click **Search**.

Figure 100	Searching for the Batch Application
------------	-------------------------------------

Batch Versions - [1 File Edit Preferen				ns]				_0 _8
Select Find Add	Copy Del	× 1 <u>C</u> lose Seg_	🔐 🧬	Abo	alla 🗿 OLE	Internet		
Batch Application Read Only Report				2				
Version		Ve	rsion Title		User	Last Modified	Security	Description

1

14. Select the Copy Control Tables to planner environment batch version.

elect Find Ad Batch Applicatio Read Only Repo	n Report-L	oad XML Data to Table			
Version	Version Title	User	Last Modified	Security	Description
XJDE0001	Load Data Dictionary Glossary from XML to Table	JDE	5/1/2008 1		Medium Security
XJDE0002	Copy Control Tables to planner environment	JDE	5/1/2008 1		Medium Security
UDE0030	Language Update - Copy System Control Tables	JDE	5/1/2008 1		Medium Security
XJDE0031	Language Update - Copy Data Dictionary Tables	JDE	5/1/2008 1		Medium Security
XJDE0032	Language Update - Copy Central Objects	JDE	5/1/2008 1		Medium Security
UDE0033	Language Update - Copy Control Tables	JDE	5/1/2008 1		Medium Security

Figure 101 Selecting the Batch Application Version

Set the processing options for the selected version of the UBE selected. Choose Copy Control Tables to planner environment > Row > Processing Options to launch the Processing Option window.

Select Find Ad	id Copy Del. Close Seg. New. I	Abo L	nks 🖣	🕶 Availa 🚺 OLE 🛛	Internet		
Batch Applicatio Read Only Repo		Rep	iort - L	oad XML, Data to Table			
Version	Version Title			User	Last Modified	Security	Description
XJDE0001	Load Data Dictionary Glossary from X	ML to Table		JDE	5/1/2008 1	-	Medium Security
XJDE0002	Copy Control Tables to planner enviro	What's This?		JDE	5/1/2008 1		Medium Security
XJDE0030	Language Update - Copy System Cc			JDE	5/1/2008 1		Medium Security
XJDE0031	Language Update - Copy Data Dictic	Grid	·	JDE	5/1/2008 1		Medium Security
XJDE0032	Language Update - Copy Central Ob	Cell	2	JDE	5/1/2008 1		Medium Security
KJDE0033	Language Update - Copy Control Tat	Column		In F	5/1/2008 1		Medium Security
		Export Import Format	, ,	Data Selection Data Sequencing Incoercies Version Detail			

Figure 102 Setting the Processing Options

16. Enter the path to the planner data folder, which contains the planner ESU folder and enter target environment name. Click **OK** to proceed.

Select Find Ad	🕨 🐚 🗶 🎜 🔗 🧬 🍀 Id Copy Del Close Seg New Dis Abo	Links - Availa_ @OLE_ @Internet	
Batch Applicatio		Processing Options Advanced R96403A appends data from XML data to the target table. Option 5 controls how duplicate data is treated in the target table (replace or preserve) Option 6 will clear the target table, then copy data from XML.	
Version	Version Title		ion
XUDE0002 XUDE0030 XUDE0031 XUDE0032 XUDE0033	Copy Control Tables to planner environment Language Update - Copy System Control Table Language Update - Copy Data Dictionary Table Language Update - Copy Central Objects Language Update - Copy Control Tables	2. Enter the name of the Target Environment to copy the table to. (If the report is called from another process, the Target Environment will be passed in.)	
•[3 or Enter the name of the Target Data Source to copy the table to.	

Figure 103 Defining the Path to the Planner Data Folder

17. Check the Data Selection checkbox, and click Submit.

ſ

🕖 Bat	ch Versions - [Version Prompting]			
🕕 Fik	Edit Preferences Form Window Help			
Can		t 💽 OLE	Internet	
	Submit			
	Prompt For			
	Prompt P or			
	-			_
	Data Selection			Data Sequencing

1

Figure 104 Submitting the Data Selection

18. Click the **On Screen** radio button to define the report output destination.

Figure 105 Selecting the Report Destination

Batch Versions - [Report Ou			
X ♣ ♣ ₩ QKQan Dis Abo	 OLE	 Internet 	
- Report Destination			Output Stream Access
C On Screen			C OSAInterface Name
C To Printer			
C Export to CSV			

19. After the report completes, verify it for any errors. The copies completed successfully above. This concludes the JD Edwards Deployment Server Installation.

Batch Applicatio Read Only Repo		Report - Load XML Data to Table Download complete Download Complete	3
Version	Version Title	Downloaded 116K8 in 1 sec	Description
XIDE0001 XIDE0002 XIDE0030 XIDE0031 XIDE0032 XIDE0033	Load Data Dictionary Glossary from XML to Tab Copy Control Tables to planner ermonment Language Update - Copy System Control Tables Language Update - Copy Data Dictionary Tables Language Update - Copy Central Objects Language Update - Copy Control Tables	Download fo:	from Security from Security from Security from Security from Security from Security

Figure 106 Completion of the Report download

Enterprise Server Install

In this setup, the JDE Enterprise server and JDE database server are on different machines. The platform pack software pertaining to these two JDE servers has to be installed separately onto these two machines. Download the relevant platform pack software (part id V12449-01 -> V12452-01) from Oracle eDelivery and extract its contents by unzipping the zip files. Please note that all zip files must be extracted in place within a folder as sub-folders disk1, disk2 etc.

To install the enterprise server, follow these steps:

1. After extracting the zip files, go to subfolder disk1, open a xWindows session, cd the disk1 directory and run install.sh.

Figure 107 Running the install.sh command



2. Launch the InstallShield Wizard. Click Next.





3. Choose the directory where the JDE Enterprise server binaries are to be installed.



JD Edwards Enterprise	One 9.00 Platform Pac	k Installer			Ľ
JD Edwards	Click Next to install "J directory, or click Bro Directory Name:				
EnterpriseOne	/u01/jdedwards/e9	00			
Platform Pack				Browse	
ORACLE					
InstallShield					
		< Back	Next >	Cancel	

4. Click the Install EnterpriseOne radio button. Click Next.

) Edwards nterpriseOne	Would you like to install or upgrade EnterpriseOne?
tform Pack	Install EnterpriseOne
	O Upgrade EnterpriseOne
ORACLE'	
IShield	

Figure 110 Selecting the Install option

5. Click the **Custom** radio button, to define the installation type.

.....

Figure 111	Selecting the installation type	

. . .

I



6. Check the JD Edwards EnterpriseOne Enterprise Server checkbox, and all the components. Click Next.

Note

The DB components are not chosen since DB is installed on a different server.

JD Edwards EnterpriseOne 9.00 Platform Pack Installer Select the features for "JD Edwards EnterpriseOne UNIX Platform Pack" you would like to install: **Product Installation** JD Edwards 💡 🗹 JD Edwards EnterpriseOne Enterprise Server EnterpriseOne EnterpriseOne Foundation Platform Pack ES Prototype 🕑 ES Pristine ES Production ES Development P D Edwards EnterpriseOne Database Server System Database Prototype Databases Pristine Databases ORACLE Production Databases Development Databases InstallShield < Back Next > Cancel

Figure 112 Selecting the Features to be Installed

7. Type the Database Server Name and Database Type in the text boxes. Select the Database creation options. Use the default password. Click **Next**.

I

	Database Options	
JD Edwards	Database Type	Oracle Server
EnterpriseOne	Database Server Name	Vm-db-SCAN
Platform Pack	Database creation optio	ns:
	Edit and Deploy DB scri	pts only. Run manually later.
		atabase users) annot be longer than 10 characters.
	Re-type your password:	
ORACLE	creates a password for	ge the default value (DEFAULT), the system each user that is the same as their user ID. For JDE, then by default the system creates a t user.

Figure 113 Defining the DB Attributes

8. Set the ini for the appropriate number of users. Click the Yes radio button. Click Next.

	Please enter the number of concurrent users that will be using this system
	200
JD Edwards EnterpriseOne Platform Pack	Will any of the following be used by the EnterpriseOne system? - Sales Order Processing - Configurator - Journal Entry - Job Cost - Advance Pricing - Purchase Order - Inventory • Yes • No

Figure 114 Defining the concurrent user number

Γ

9. Enter the Oracle DB SID and the name of the UNIX account for Oracle DB. Click Next.

1

ID E I		he database Instance you want to confi Note: Leave blank if you intend to use t	
JD Edwards EnterpriseOne	Oracle Connect String	orci	
Platform Pack	UNIX account for Oracle	oracle	
ORACLE'			
toliChield	1		
stallShield			

Figure 115 Naming the Database Instance

10. Verify the selections used for installing the enterprise Server in the summary page. Click Next.

	Please read the summary information below.
JD Edwards EnterpriseOne Platform Pack	JD Edwards EnterpriseOne UNIX Platform Pack will be installed in the following location: /u01/jdedwards/e900 with the following features: JD Edwards EnterpriseOne Enterprise Server EnterpriseOne Foundation ES Prototype ES Pristine ES Production ES Development for a total size: 4221.3 MB
ORACLE'	< <u>₿</u> ack <u>N</u> ext > <u>C</u> ancel

Figure 116 Summary of the Enterprise Server features

11. Click Finish.

DB Server Install

Γ

The PlatformPack binaries used for the Enterprise server are copied onto the DB server.



- 1. Choose the directory where the JDE Enterprise server binaries are to be installed. Click Next.

I

	Click Next to install "JD directory, or click Brow			rm Pack" to this
JD Edwards	Directory Name:			
EnterpriseOne	/data_A/jdedwards/e	900		
Platform Pack				Browse
ORACLE				
stallShield				
	Г	< Back	Next >	Cancel

Figure 118 **Defining the Directory**

2. Click the Install EnterpriseOne radio button. Click Next.

JD Edwards Enterprise(If you are planning to upgrade EnterpriseOne, please backup your databases and files.			
JD Edwards EnterpriseOne	Would you like to install or upgrade EnterpriseOne?			
Platform Pack	Install EnterpriseOne			
	O Upgrade EnterpriseOne			
ORACLE				
InstallShield				
	< Back Next > Cancel			

Figure 119 Defining the Install Option

I

Γ

3. Click the Custom install radio button. Click Next.

	Choose the installation type that best suits your needs.
D Edwards interpriseOne latform Pack	 Typical The program will be installed with the suggested configuration. Recommended for most users. Custom The program will be installed with the features you choose. Recommended for advanced users.
ORACLE [®]	

4. Check the JD Edwards EnterpriseOne Database Server checkbox, and all the components. Click Next.

1

Figure 120 Defining the Installation type

	Select the features for "JD Edwards EnterpriseOne UNIX Platform Pack" you would like to install:
JD Edwards EnterpriseOne Platform Pack	Product Installation D Edwards EnterpriseOne Enterprise Server EnterpriseOne Foundation
Platform Pack	ES Prototype ES Pristine ES Production
	ES Development JD Edwards EnterpriseOne Database Server System Database Prototype Databases
ORACLE	Pristine Databases Production Databases Development Databases
istallShield	
	< <u>B</u> ack <u>N</u> ext > <u>C</u> ancel

Figure 121 Selecting the DB Server features

5. Type the Database Server Name and Database Type in the text boxes. Select the Database creation options. Use the default password. Click **Next**.

	Database Options		
ID E I	Database Type	Oracle Server	
JD Edwards EnterpriseOne	Database Server Name	vm-db-node1	
Platform Pack	Database creation optio	ns:	
attorn r dek		pts only. Run manually later.	
	Secure Password: (for database users) The secure password cannot be longer than 10 characters.		
	Re-type your password		

ORACLE	creates a password for	ge the default value (DEFAULT), the system each user that is the same as their user ID. For JDE, then by default the system creates a t user.	
	•		
stallShield			

Figure 122 Defining the DB Options

Γ

6. Enter the UNIX owner and group owning the oracle install, connect string, sysadmin user and password in the corresponding text boxes. Define the directory.

1

] JD Edwards Enterprise(Dine 9.00 Platform Pack Installer Please enter the following informati want to use.	on refering to the clatal	base instance you
JD Edwards EnterpriseOne	UNDX user owning oracle install UNDX group owning Oracle install	oracle	^
Platform Pack	CONNECT STRING	orcl	
	SYSADMIN USER	sys	
	SYSADMIN PASSWORD	*****	
ORACLE	Have you already created Oracle Yes No Please enter the directory where y tables:		database
	/data_A/jdedwards/ORCL		
			Browse
InstallShield			
	< Back	Next >	Cancel

Figure 123 Defining the Database Instance References

- 7. Click the Yes radio button to install the database. Click Next.
- Figure 124 Verifying the Creation of new database



8. Verify the selections made in the summary page. Click **Next** to complete Installation. Click **Finish** to exit.

	Please read the summary information below.	
JD Edwards	JD Edwards EnterpriseOne UNIX Platform Pack will be installed in the following location:	
EnterpriseOne	/data_A/jdedwards/e900	
Platform Pack	with the following features:	
	JD Edwards EnterpriseOne Database Server System Database Prototype Databases Pristine Databases Production Databases Development Databases for a total size: 57669.7 MB	
ORACLE		
stallShield	J	
taisnieid -		
	< Back Next > Cancel	

Figure 125 Summary of the Database Server Features

The DB platform pack is installed successfully.

Installation Plan

ſ

To Install the Installation Plan, follow these steps:

- 1. Open JDE admin console on Deployment Server by using run as admin. Login as JDE user in JDEPLAN environment.
- 2. Type GH961 in the Fast Path text box, to go to the Installation Plan.
- 3. Right-click Custom Installation Plan. Choose Prompt For > Values.
- **4.** In the Processing Options Window type 2 in the Prompt Mode text box(2 for verbose mode). Click **OK**.

Processing Opt	ions		2	×
Prompt Mode	Process Mode	Default Mode	Status Ch: 4	•
Enter a '1' for Addi addition of multiple Enter a '2' for Verb	nt Mode, This mode w tions Prompt Mode, T e servers, This is the o lose mode, This Mode les of Prompt forms,	his mode will prompt lefault mode.	for the	
Prompt Mode		2]	
 ✓ <u>0</u>K 	<u>H</u> t	21p	X Cancel	

1

Figure 126 Defining the Verbose Mode

5. Click the **Process Mode** tab. Type 1 in the Installation text box. Click **OK**.

Figure 127 Defining the Process Mode

Processing Options X					
Prompt Mode	Process Mode	Default Mode	Status Ch: 4 🕨		
Enter a '1' if you are adding servers to your existing setup. This will step through the process of adding different types of servers (Deployment, Enterprise, Data, JAS) to your existing configuration. Enter a '0' or leave blank if not adding servers to your existing setup. This is the default.					
Additional Servers	3]		
This value must a	This value must always be a '1' for the Installation process.				
Installation		1]		
✓ 0K	He	:lp	X <u>C</u> ancel		

6. Click the **Default** tab. Type 1 as prompt value for all default options at runtime. Click **OK**.

Figure 128	Defining the Default Mode Values
------------	----------------------------------

Γ

Processing Options		×
Prompt Mode Process Mode	Default Mode	Status Ch: 💶 🕨
Enter one of the following values for ea '0' - Do not take defaults and do not p '1' - Prompt for defaults option at runtin '2' - Always take defaults without prom	rompt. ne.	ult
Default Data Source Information	1]
Default Environments	1]
Default Data Load	1]
Default Advanced Parameters	1]
Default Languages	1	
<u>✓ 0K</u>	elp	X <u>C</u> ancel

7. Click the **Status Change** tab. Type the values in the text boxes, Mark as complete must always be 60:60; Disbale:70; Enable:10. Click **OK**.

Processing Opti	ons			>
rocess Mode	Default Mode	Status Change	Completi 🖣	
Enter the Detail Sta actions are taken:	itus for the line to be	changed to when the I	following	
Mark as Complete r	nust always be 60	60		
Disable		70		
Enable		10		
		elp	X Cance	

Figure 129 Defining the Detail Status

8. Click the **Completion** tab. Type 2 (run automatically) in finalize and validate plan text boxes. Click **OK**.

1

👑 Processing Opl	ions			>
Default Mode	Status Change	Completion	Replication	
	e run.		n be run. For	
Finalize Plan. The to run automatical	default for this proces ly.	s is '2' 2		
Validate Plan. The to run automatical	e default for this proces ly.	:s is '2' 2		
✓ <u>0</u> K	<u>H</u> e	:lp	🗙 <u>C</u> an	cel

Figure 130 Defining the Process after Completion

9. Click the **Replication** tab. Type 1 to prompt for options at runtime in all text boxes. Click **OK**.

Figure 131 Defining the Values for Replication

Γ

👑 Processing Opti	ons			×
Status Change	Completion	Replication	Packages	• •
Enter one of the foll '0' - Do not use ar '1' - Prompt for op '2' - Always use w	nd do not prompt. tion at runtime.	each remote location This is the default.	·	-
Replicate System T	ables	1		
Replicate Data Dict	tionary Tables	1		
Replicate Control T	ables	1		
Replicate Constant	Tables	1		
Replicate Master T	ables	1		_
✓ <u>0</u> K		<u>H</u> elp	× <u>c</u>	ancel

10. Click the Packages tab. Type 1 for prompt for pushing at runtime in the text box. Click OK.

1

Figure 132 Defining the Package Push Options

🞬 Processing Opti	ons				×
Status Change	Completion	Replicati	on Pack	ages	• •
Enter one of the fol option. '0' - Do not push p '1' - Prompt for pus '2' - Do not prompl '3' - Always push o	- ackages shing at runtime for pushing but di	isplay valid pa	ckages	ge push	
Remote Location P	ackage Push		1		
V OK		<u>H</u> elp		<u>× c</u>	ancel

11. Click **Add**, to add the custom installation plan.

Figure 133 Adding the Custom Installation Plan



12. Enter name, description, and Status in the text boxes. Click the Install radio button.

	n Plan - [Installation Planner] xees Form Window Help		_ 0 ×
	No Links - Deale Dours	(a) Internet	
Plan Information: Name		P3TINSTALL	
Description		Cisco UCS-bare metal install	
Status		10 In Planning	
Install Type: -	C Upgrade	C Software Update (ASU/ESU)	
Release:	< Opgrade	 onimals obnais (voorcoo) 	
ridlease.		To Release	E900

Figure 134 Define the Name and Description for the Plan

13. After adding the plan, define a location that would be associated with the Plan. Click **OK** in the Location message box.

Figure 135 Adding the Location

🕕 Custom Installation Plan - [Work with Installation Pla	ns]	_ 0
File Edit Preferences Row Window Help		_ 6
Select Find Add Del Close Seg New Dis		
🗉 🦳 Plan Information		
	Aplan must be associated with a location. If you would like to	
	define a new location press OK. To select an existing location press select.	
	V OK Select X Cancel	

14. Type the location properties, and click OK.

ſ

Figure 136 Defining the Location Parameters

iet
Cisco
Cisco India

15. For various JDE servers type the Machine Name, Description, Release, and primary User in the text boxes. Define the Deployment Server Share Path.

1

Dustom Installation Plan - [Deployment Server	r Revisions]		
Ele Edit Preferences Form Window Help			X
OK Can Dis Abo	OLE I Internet		
Machine Usage 15	Deployment Server	Location	Cisco
Machine Name JDE	EDEPMGR	Primary User	JDE
Description	ployment sv		
Release	00		
Host Type 50	Intel NT		
Workstation Deployment Deployment Enterprise	Data HTML Crystal CMS		
Primary Deployment Server	1		
Server Share Path	1E900		

Figure 137 Defining the JDE Servers Details

16. Type Enterprise Server installation path and description. Type the name of deployment server.

Figure 138	Defining the	Installation	Path and	Server Details
riguic 100	Denning the	motunation	i atiri ana	OCIVEI Detallo

K Can Dis Ago	w DLE Dinternet		
Machine Usage	20 Enterprise Server	Location	Cisc
Machine Name	JDEAPP1	Primary User	jide9
Description	ENT SVR1	-	
Release	E900		
Host Type	35 Linux		
Port Number Logical Machine Name	6015 J.DEAPP1		
Database Type	O ORACLE		
Server Map Data Source	DEAPP1 - 900 Server Map	2	
Installation Path	U01.9dedwards/e900		
Deployment Server Name	DEDEPMOR		

17. Click OK to go through DataSource revisions so as to confirm default data source information.

Belect	Find	4 Add	1 Del	× <u>C</u> lose	Seg	New.	Dis	Abo	Links	▼ Expand	OLE	Internet
	Plan											
	9- P	3TINST	ALL(CI	sco UC	S-bare	metalli	nstall)					
								in the	Source			
								Daca	Source			
							1	Data	source			
								lfyd	ou are i	using JDEdv		ards, you can take the
								lfyd	ou are i	using JDEdv		
								lfyd	ou are i	using JDEdv	press OK, to	ards, you can take the

Figure 139 Confirming the Data Source

- **18.** Verify the installation information for the HTML server in the HTML tab. Input the ports, server url and installation path. Type the Deployment Server Name.
- **19.** Verify Database specific installation plan information as database resides on separate Server. Click **OK** to define Data Server properties.

Figure 140 Defining the Data Server on Separate Server

I

Plan Information P3TINSTALL(Cisco UCS-bare metal install) Data Server If your database resides on a seperate server, press OK define your data server. To select an existing data serve press select. If you do not want to define a data server press select. If you do not want to define a data server press select. If you do not want to define a data server press select. If you do not want to define a data server press select. If you do not want to define a data server press select. If you do not want to define a data server press select.	dd Del	× 1 4 Close Seg., New		ks 🔻 Expand 🛛	OLE 🔋 I	nternet
Data Server If your database resides on a seperate server, press OK define your data server. To select an existing data serve press select. If you do not want to define a data server pre		sco UCS-bare metal	linstall)			
If your database resides on a seperate server, press OK define your data server. To select an existing data serve press select. If you do not want to define a data server pre	 					
define your data server. To select an existing data serve press select. If you do not want to define a data server pre			Data Serv	ver		_0
define your data server. To select an existing data serve press select. If you do not want to define a data server pre						
			define y	our data server. To	select an exist	ing data server
				ect il you do not w		lata server press
			press ser		skip.	

- 20. Type Datasource type, Platform, Database Server Name and Database Name and ID.
- **21.** Verify the Data Dictionary data source configuration values- platform, server name and datasource type for all the datasources.

ata Source Name	Data Dictionary - 900	
ata Source Use	DB Local Data Source	
ata Source Type	O ORACLE	
	D Data Dictionary	
ationm	LINUX	
	and the second s	
atabase Server Name	jdedb-scan	
JESEMSDE ODBO SOLJMEDE OLEDB CRACKE DB2 OS	1400 DB2.008 Access Legicar Lecar.Oracle	
UBSEMISDE ODBC SOLIMISDE OLEOB Oracle C DB2 Of Object Owner ID	1400 DB2.UDB Access Logical Local Oracle	
JESEMSDE ODBO SOLJMEDE OLEDB CRACKE DB2 OS	1400 DB2.008 Access Legicar Lecar.Oracle	

1

Figure 141 Verify all Data Sources

22. Check the **Default Environments**, and **Default Data Load** checkboxes to configure valid environments and load relevant environment data.



•	Eustom Installation Plan - [Environment Selection]	
0	Die Edit Bieleieunden Ander	_161 ×
J	V X 🚓 № Links 🕶 Displ Internet	
	Default Environments To configure all valid environments for your installation, check the Default Environments box. Otherwise uncheck the Default Environments box to select individual environments.	
	Default Data Load To utilize EntepriseOne's data load options default for loading environment data, check the Default Data Load box. Otherwise, uncheck the Default Data Load box to override the data load options.	

23. Click No in the Location message box, since we are not adding another location.


Figure 143 Not Defining Other Location

24. Information Prompt message box confirms the plan is finalized.

Figure 144 Completion of Plan

I



25. Click the On Screen radio button to choose the report destination. Click OK.



Figure 145 Running the Planner Validation Report

26. Run the Planner Validation Report, R9840B, and validate all records.

Installation Workbench

To install the JDE Workbench, follow these steps:

- 1. Execute the custom plan created previously.
- 2. Sign into JDEPLAN on Deployment Server, fastpath to GH961.
- 3. Choose Installation workbench > Prompt For > Values. The Processing Options window opens.

4. In the Process tab, type1 for unattended workbench mode, and 60 in the Plan Detail Status text box. Click **OK**.

Processing Options	
Process	
Enter the new Plan Detail Status	60
Enter a '1' for Unattended Workbench Mode a '0' for Attended Mode. The default is '1' for Unattended Mode.	or 1
✓ <u>ОК</u> <u>H</u> еlp	🗙 <u>C</u> ancel

Figure 146 Defining the Workbench Mode

5. Search for the available plan Status.

Γ

Figure 147 Search the Plans Available

File Edit Preferences	- [Work with Installation Plan] Window Help						
✔ 🔀 ¥ elect Find <u>C</u> lose S	an Angle An	I OLE	Internet				
Pian Status							
						1	
	Description		Plan Status	Status Description	Date Updated	User ID	
Plan Name	Description.						

6. Select the custom plan that was created in the previous section.

Figure 148	Selecting the Plan
------------	--------------------

Installation Workbench	Installation Workbench - [Work with Installation Plan]						
File Edit Preferences	Window Help						للح
Select Find Glose Seg. New Dis Abo							
Plan Status *							
	1						
				Ride.			_
Plan Name	l Description		Plan Status	Status Description	Date Updated	User ID	_

7. For unattended workbench mode, all workbenches are completed without any intervention no task breaks was set.

1

🜒 Installation Workbench - [Congratulationst]	. 🗆 🗵
File Print Screen Print Setup Edit Preferences Form Window Help	le x
Finish Dis Abo	
Installation Plan completed successfully	

Figure 149 Completion of the Installation Plan

8. After the Installation Plan is completed, the status changes from Validated to Installed.

Figure 150	Verifying the Plan Status
------------	---------------------------

						_ 0
✓ 🔂 × i Select Find <u>C</u> lose Se	Î 🐣 📌 🤻 Links 🕶 Displ i∎OLE ig New Dis Abo	Internet				
Plan Status T						
Plan Name	Description	Plan Status	Status Description	Date Updated	User ID	

Change Assistant

To download and install the Change assistant, follow these steps:

- 1. Download change assistant from Oracle updateCenter onto the Deployment Server.
- 2. Install the change assistant on the Deployment Server.

Name *		Date modified	Туре	Size	
)JDBC		2/19/2012 10:07 AM	File folder		
鷆 ServerMnager		2/20/2012 5:34 AM	File folder		
🎉 WinClient		2/20/2012 4:56 AM	File folder		
ChangeAssistant.inl	p	2/20/2012 8:14 AM	JNLP File	3 KB	-
🔬 jre-6u24-v Starting	j installer			×	3
12428-01 Down	nloading deployme	enttoole iar		S.	
1 V12429-01	ritodaling acproving	enttooranjar		Java	
🔒 V12430-01				Java	
🚹 V12431-01					
1 V12432-01 Nam		CUSTOMER			
1 V12433-01 Pub	lisher: Oracle USA, Inc.				
From	m: https://updateceni	ter.oracle.com:443			
Read	2.5M of 4.4M (57%)				
				Cancel	

Figure 151 Downloading the Change Assistant

Baseline ESU Install

I

To Install the Baseline ESU, follow these steps:

- 1. On the Deployment Server, sign into the change assistant using Oracle support credentials.
- 2. Choose Search for Packages > JD Edwards > Electronic Software Update 9.0 baseline ESUs. Choose the unattended mode and click OK.

Figure 152 Selecting the Unattended Mode

Change Assistant (DEDEPMGP)		anced Search		b 9.0 Baseline ESUS (1)									
News and Links View SAR/BLIG Details	1 × ×	w -1	A -	8 - 2	-			Results 54 of 54		_	_		_	3 10
Search for Packages		-	-	- mainter		Reform	Enimate	2.44	Dep.	. Saie	1.1		524	-
- 😭 My Queries			ane .	Cescription	7,94				Dep.			Date		
😑 🤹 XD Edwards		A 18706		ESU_3.18796_1/24/12	Dectronic So		9.0	Cownloaded	Yes	Yes		Jan 25, 2012	3 MD	-
8 🙆 Configurations		110023		ESU_3.10423_12/13/11	Electronic So	. CLENT	9.0	Cownisaded	Yes	Yes	158	Dec 14, 2011	1 MB	
8-3 Dectronic Software Updates			-	BRI BARRA ARTICL	A. 1. 1. A.	A.101.0	**	Cownicaded	Yes	Yes	689	Dec 8, 2011	3 MB	
8 2 6.10	Softw	are Update I	and one	ment Selection			8	Cownicaded	Yes	Yes	309	Dec 8, 2011	510	-
8 2 8.11 8 2 8.11 91	20	K XC	Cancel					Covribaded	Ves	Yes		Nov 23, 2011	418	
8 (2) 6.11 (2)			ted tora	and and				Covribaded	Ves			Nov 9, 2011	216	
8-02.8.9	Generic	from the select	and has a						165	Yes				
8 2 30	Deth		_					Cownloaded	Yes	Yes		Aug 4, 2011	5140	
R-C 9.0 Fix Current			-					Cownicaded	Yes	Yes	308	Jun 15, 2011	216	
R-Q 9.0 Performance and Memory	D:	Betch13	0121571	1221				Cownicaded	Yes	Yes	1141	Apr 19, 2011	3 MB	
R G Asset Lifecycle Management	Name	drettor	oky 90	Saceline	_			Countraded	Yes	Tes	3754	Apr 7, 2011	316	
R G Business Services		-			_			Cowritaded	Yes	Yes		Apr 5, 2011	316	
R G CM	Cescrpt	ion: Batch or	eated on	Download and Deploy										
Gebrbution	17 UN	Ended P	Exchap .	Create OMM Protect an	(Padage Journ)			Cownloaded	Yes	Yes		Apr 5, 2011	15 MB	
8 G Feancials								Autobarded	1011	711	14,01	Mail Anti-Antis a	1.100	-
B G Honebulder Management	<pre>/X</pre>	54 Package	s Select	ed										×
🛞 🤹 Human Resources		1000 CO.		12.000.000										
8 🙆 Manufacturing	Select	Envernment		Description	Pi G		ec Herge							
(8- 😫 Payrol			-											
B G Project & Gov't Contract Accounting		5V900		weispnert Ervasnnert	DV900		• •							
B Q Project Management	L C	P\$900	E900 Pr	utine Environment	P5900		F 1							
8 😳 Real Estate 9: 😳 Time and Labor	1						1.5							
8-Call time and Labor (8-Call 109 Sets			_											
- Call Revenue (CSUs	Ready													
-GE ESUs since Update 2 (9/14/2010) No Localizations	T		_											
Construction of the c														
8-0 EPP 8.0														
R Q Localizations														
8 Q Parver E9/s														
8-0 14														
R- Cil Tear End		_	_		_	_	_	_	_	_	_	_	_	
R G EnterpriseOne Tools Releases				Nation	d uniected packs	and the second second	he hat he ta					03:02:00	0 F [II	als:
	-1			1000	Contraction of the local distance	1000	of the state of the					44.00.00		

3. Wait for the ESUs to be downloaded and get applied. After the Baseline ESUs are applied the summary window appears.

1

Ohange Assistant (IDEDEPMSR)	Advanced Search 🕐 Help 💙 9.0 Baseline ESUs (1)							
A News and Links A News AR/BUG Details	* X # - & - 8 - 8		tesuits 54 of 54					> 14
🗟 🌞 Search for Packages		Release	Sabui	Inen I	Base	of Date	520	-
My Queries X0 Edwards	FT A success terms shades let a real success and	-	Completed	_	Tes		3 MB	-
B- Configurations	Change Assistant Deployment Summary		Completed		Tes		1 140	-
Gergarators Gertronic Software Updates	808	0	Completed			691 Dec 8, 2011	3 MB	
R 3 8.10	1000				Tes			
8 0 8.11	TRY5_90_ESU_Baseline	10	Completed		Tes	392 Dec 8, 2011	5 MB	
8 😫 6.11 991			Completed		Yes	a de la de la del a de la del del del de la del del de la del de la del de la del de la del	4 MB	
8 2 8.12			Completed	Yes	Tes	190 Nov 9, 2011	2148	
÷ 3 8.9 ⇒ 3 9.0		-	Completed	Yes	Tes	1278 Aug 4, 2011	5 MB	
8-00 9.0 Fix Current			Completed	Yes	Tes	390 Jun 15, 2011	2148	
			Completed	Yes	Yes	1143 Apr 19, 2011	3 MB	
Asset Lifecycle Management			Completed	Yes	Tes	3758 Apr 7, 2011	3148	
Dusiness Services	① <u>112093</u> - Not Run		Completed	Yes	Yes	380 Apr 5, 2011	3 MB	
8 Q CM	① 115573 - Not Run		Consisted		Tes	2397 Apr 5, 2011	15 HB	
8 G Distribution			Completed				0.000	-
B - O Pinancials R - O Homebulder Management	AL4664 - Not Pun							ж
O Homebulder Management Homebulder Management Homebulder Management	(i) 16757-Not Run							-
R Q Manufacturing								
B Q Payrol	① 3.18796 - Not Pun							
Project & Govit Contract Accounting	① 3.11935-Not Run							
8 QL Project Management. 8 QL Real Estate	() 312914-Not Run							
(R-O) Time and Labor	C ALCOLY MICHAN							
(8 Q) 10P Sets	① 113739-Net Run	-						
- O V.O Baseline ESUs								
- C) ESUs since Update 2 (9/14/2010) No Localizations C) Inime Visual Assist	Show Details 0 Surt 0 Pause X Cos	68						
C CRP 6.0								
R C Localizations								
R Q Parver E9.8								
8 0 74								
R Q Tear End		_		_	_			
ContempriseOne Tools Releases Image: Tools Releases Image	Download completed successfully. 80 of 80 packages (including dependencies) succ	centralially dow	inloaded to Crit	19.01baselin	eltry5	30:31:000) II	

Figure 153 Downloading the Baseline ESU

4. Summary of the ESU Downloaded

Figure 154 Summary of the ESU Downloaded

📙 Change Assistant Deployment Summary	X
TRY5_90_ESU_Baseline	
V JL12U12 - Succeeded	A
Succeeded	
O <u>JL18803</u> - Succeeded	
Succeeded	
Succeeded	•
Show Details Start Pause X Close	



Apply the special instructions for the baseline ESUs. Some special instructions pertaining to localizations for specific countries might not be relevant for the install, so it is essential to read through the special instructions.

UL2 Install

I

The Oracle-JDE DIL kit, which best represents a standard customer workload for JD Edwards applications, needs the JDE application level to be at 9.0 update level 2, so UL2 was applied to the installed base application.

To install the UL2, follow these steps:

- **1.** Download The UL2 file from eDelivery and extracted via winzip. Run the RunInstall.exe using run as administrator.
- 2. Click the 9.0 Update 2 Installation link in the JD Edwards Install Manager window.

Figure 155 Clicking the UL2 Update Installation

🛃 JD Edwards Install Manag	er	×
	ORACLE'	
	JD EDWARDS ENTERPRISEONE	
install:		
9.0 Update 2 Instal	lation	

3. The Client Workstation Setup window launches. Click Next.

JD Edwards	Welcome to the JD Edwards® EnterpriseOne Client installation program.
EnterpriseOne Client Install	The Application Update - UL2 installation program cannot update shared files if the files are in use. Before continuing, please close any open applications.
	Click Next to continue or Cancel to quit.
ORACLE'	If you would like to know more about the setup process, click the Help button. In the following setup screens, click Help to obtain a more detailed description of the setup screen or its options.

1

Figure 156 Proceeding with the UL2 Installation

- 4. Click Next, after disk check completes. Click Finish.
- 5. Click **OK** in the Installation message box.

Figure 157 Successful Installation of the UL2



6. Go to work with software update after signing into Active console on deployment server and apply UL2 to the chosen environments.

	1964	70 - [Work wi	th So	ftware Up	dates]										_ @ X
0	File	Edit Preferen	vces	Form Roy	v Wind	ov Help	>								_ie ×
	ind (¥ 🗿	- B4	S Dgw.	Neg	Dis	Abo L	inks -	▼ Downi.	. DOLE Dinternet	1				
	Software Update Type											Hide Clean			
	De	wnloaded Affe	r Dað	•				_		_		Built After D	ate	*	_
	Ins	talled After Da	te				Γ	_		_		Release N	umber	E800	-
١ř	Т		-												
	A	Update Name			Descrip	rtion			wnioad Date	Download Status	install Date	instal Status	Duild Date	Updated Environments	
	L.	K.2	9.	0 Update :	2				3/9/2012	Completed Normally			9/9/2010		

Figure 158 Defining the Software Update Parameters



2×2	Can. New. E	yev. Negt Dis Ago Links 🛩	Down! 💽 OLE	(e) internet
5	elected Updates	UL2;;		
1	Unattended Workbe	inch 17	Backup	Create OMW Project and Package Assembly
A	Environment	Description	Path Code	
4	Environment	Description E900 Development Emirorment		
~			Code	

Figure 160 Uncheck the Create OMW Project and Package Assembly

1	Can. New. E	rex. Negt Dig. At	ko Links 🕶 (Downi 💽 OLE .	@internet
	elected Updates	pu	t		
	Unatlended Workbe	nch	E	Backup	Create OMW Project and Package Assembly
-	Unationded Workbe	Descrip		Path Code	Create OMW Project and Package Assembly
-			ption	Path	Create OMV Project and Package Assembly
A /	Environment	Descrip	ption Invironment	Path Code	Create OMW Project and Package Assembly

ſ

nd <u>C</u> lose Seg.	Bew. Dgw. Neg Dis Ap	(a)			
Software Update	Туре	02	Hide Cleaned	Updates	N
Downloaded After	Date		Built After Date		*
nstalled After Dat			Release Num	ber	E900
			Dipdate Completion		
Update Name	Description	Download Date	The Update completion The Update completed successfully. Use the Update Status' exit is check the status of this update.		Updated Environments

Figure 161 Completion of the Software Update

HTML Server Install

Download the Weblogic (WLS) 10.3.6 binaries from Oracle eDelivery, and install the WLS Sever on the HTML server. To install Oracle Weblogic Server 10.3.6, see, http://docs.oracle.com/cd/E21764_01/doc.1111/e14142.pdf.

After the installation of WLS, perform the steps described in this section to create a cluster on WLS and deploy JDE Html server on it. A cluster defines groups of Weblogic Server servers that work together to improve scalability and reliability.

Create a domain. Configure the admin server port to 7501 as shown in above link in Appendix B.

Configuring the Cluster

To configure a cluster, follow these steps:

1. Sign into the admin console using the user and password configured during WLS install.

1

🕒 🔕 🕶 🕡 http://jdehenit:/%01.jconsol	e/console.portal?_vfpb=trueti_paget.abel=HonePaget		🗷 🔁 🐓 🗶 📴 ting	9			
Sie Edit View Favorites Jools Help							
Pavortes							
	web size casesy						
Home Page - E1_WS - WLS Console			💁 • 💭 - 🗅 👼 • Der	• Salvty • Tgols • 😝			
ORACLE WebLogic Serve	Administration Console			0			
hange Center	🔒 Home Log Out Preferences 🔛 Record Help		Welcome, weblog	Connected to: E1_JAS			
New changes and restarts	Henne						
Click the Lock & Edit button to modify, add or	Home Page						
delete items in this domain.	- Information and Resources						
Lock & Bolt							
Release Configuration	Helpful Tools	General Information					
	Configure applications	 Common Administration Task Descriptions 					
Iomain Structure	 Configure GridLink for RAC Data Source 	 Read the documentation 					
1_345	 Recent Task Status 	 Ask a question on My Oracle Support 					
8 Enveranment Deployments	 Set your conside preferences 	Oracle Guardian Overview					
8 Services	- Domain Configurations						
-Security Realms							
B ⁻ Intersperability	Domain	Services	Interoperability				
R Chagnestics	- Domain	 Messaging 	 WTC Servers 				
		 245 Servers 	 Juit Connection Pools 				
	Environment	 Store-and-Forward Agents 					
	Servers	 JPG Hoduks 	Diagnostics				
	Outers	 Path Services 	 Log files 				
	 Virtual Hosts 	 Bridges 	 Diagnostic Modules 				
tere do L.	Higratable Targets	 Data Sources 	 Diagnostic Images 				
	Coherence Servers	 Persistent Stores 	 Request Performance 				
 Search the configuration 	Coherence Clusters	 XML Registries 	ties • Archives				
Use the Change Center	Machines	 XML Entity Caches 	 Cartert 				
Record WLST Scripts	Work Managers	 Foreign 3/DE Providers 	- 949				
Change Console preferences	 Startup And Shutdown Classes 	 Work Contents 					
Monitor servers		+ KOM	Charts and Graphs				

Figure 162 Weblogic Admin Console Page

2. Choose Environment > Cluster > Lock and Edit > New. Type Cluster E1C1 in the Name field.

10.104.109.41 - Remote Desktop Connection	and the second se	the set the state of the		0.
Create a New Cluster - EL_JAS - WLS Console -1	Windows Internet Explorer			
🕢 🕶 🔊 http://jdefenil: 7501./console/console	partal Appletones_pages.abel=CoreClusterCreateC	star	💌 🔁 🍁 🗶 🔽 ting	
Fevorites 👍 🖉 Suggested Sites - 🖉 Web Si	ka Galery •			
Create a New Cluster - E1_JAS - WLS Console	1-1		A • D · D m + be	. Salatura Taulara
	1000		3.0	
ORACLE WebLogic Server® Adm				c
inge Center	Home Log-Out Preferences 🚾 Record Help	<u>a</u>	Welcome, weblog	pic Connected to: E1
w changes and restarts	Home Humanary of Clusters			
	reate a New Cluster			
Aquiration button to allow others to edit the ain.	OK Cancel			
Lock & Edit	and lower			
Release Configuration	Cluster Properties			
	The following properties will be used to create your n	w Outer.		
wain Structure	Indicates required fields			
Als				
Servers	What would you like to name your new Ouster?			
	*Name:	Cluster-0		
Vetual Hosts Higratable Targets				
-Coherence Servers	Ousters use messaging for sharing session, load balan technology that enables multiple applications to subscr	ing and fallover, JHS, and other information between duster members. Outre to to a given IP address and port number and laten for messages, but require	rs can use either Unicast or Multicast messaging. Multicast is is hardware configuration and support. Unicast does not har	is a single broadcast we these requirements.
Coherence Clusters Machines	what nessaging node should this duster use?			
-Work Managers	Messaging Mode:	Unicast		
Startup and Shutdown Classes				
ervices	Unicast Broadcast Channelt			
ieosty Rodes				
do L 8	Multicast Address:	239.192.0.0		
anfigure dusters				
asign servers to clusters	Multicast Port:	2001		
onfigure server migration in a cluster	OK Cancel			
Configure cross-duster replication				

Figure 163 Naming the Cluster

3. Click **OK**, to finish creating the cluster.

Γ

Figure 164

Summary of Ousters - E1_JAS - WLS Console						6	• 🖸 · 🖄 🖷 • Baar S	afety = Tgols =	
ORACLE WebLogic Server®	Administration Cor	sole						0	
Change Center	A Home Log Out	Preferences 🔛 Rec	ad Help	9			Welcome, weblogic Co	metted to: E1_3M	
New changes and restarts	Hone sheemaary of Cholters								
Pending changes exist. They must be activated to take effect.	Messages © Outer created successfully								
Activate Courses Summary of Clusters									
Domain Structure			ave been configured in the current rver servers that work together to						
Content Servers Dutters Virtual Hosts Monatable Targets	© Customize the Clusters (Filter	ed - More Columns D	met)						
Coherence Servers Coherence Clusters	New Core	Delete					Showing 1 to 1 of 1	Previous Next	
- Machines - Work Managers	T Name 🙃	Cluster Address	Cluster Messaging Mode	Migration Basis	Default Load Algorithm	Replication Type	Ouster Broadcast Channel	Servers	
Startup and Shutdown Classes	E 60		Unical	Database	Round Robin	(None)			
Deployments 8 Services - Senato Radius	New Core	Delete					Showing 1 to 1 of 1	Previous Next	

Summary of the Clusters Created

4. Click Activate changes, and then choose Machines to configure the machine that needs to be configured in the current WebLogic Server domain.

1

Figure 165 Create a new Machine entry

ORACLE WebLogic Server®	Administration Console		0
Change Center	A Home Log Out Preferences Record Help	9	Welcome, weblogic Connected to: E1_3AS
Yiew changes and restarts	Home s Summary of Outlans s Summary of Machines Messages		
Click the Lock & Edit button to modify, add or delete items in this domain.	# All changes have been activated. No restarts are necessary.		
Lock & Bill Release Configuration	Summary of Machines		
Domain Structure	A machine is the logical representation of the computer that hosts one or to which certain tasks, such as HTTP session replication, are delegated. T		erver uses configured machine names to determine the optimum server in a duster conjunction with Node Manager to start remote servers.
EL_MS *	This page displays key information about each machine that has been con	nigured in the current WebLogic Server domain.	
Clusters Virtual Hosts	© Customize this table		
Migratable Targets	Machines		
Coherence Servers Coherence Clusters	Click the Local & Edit button in the Change Center to activate all the but	tons on this page.	
Work Managers Start Machines, Level 2, 7 of 9, Selected	New Clone Detets		Showing 0 to 0 of 0 Previous Next
Deployments	E Name in		Type
8-Services		There are no items to display	
How do L 8	New Clone Delete		Showing 0 to 0 of 0 Previous Next
Oreste and configure machines			

hange Center	A Hone Log Out Preferences Ascord Help		Welcome, weblogic Connected to: E1_3
lew changes and restarts	Hone sQuemary of Queters >Summary of Machines		
kk the Lock & Edit button to modify, add or elete items in this domain.	Messages # All changes have been activated. No restarts are necessary.		
Lock & Ext	Summary of Machines		
amain Structure	A machine is the logical representation of the computer that hosts one or none WebLogic Se to which certain tasks, such as HTIP session replication, are delegated. The Administration 1		
Environment Servers Outlins	This page displays key information about each machine that has been configured in the cum © Constantize this table	nt Weblage Server domain.	
Everyment Servers Custers Virtual Hosts Mguituble Targets	This page displays key information about each machine that has been configured in the curre	nt Vindicagi; Sarvar danah.	
Envers Servers Outers Virtual Hosts	The page diplays key information about each machine that has been configured in the cum © Contamize this table	rt VidLogi, Serve donah.	
Dreament Serves Outlers Materia Material holes Hightable Targets Cohereice Outles Cohereice Outles Sochereits Managers	This page diplays key information about each mattern that has been configured in the com § Containing this table Machines	rt Widdoge Server donain.	Showing I to 1 of 1 Previous Next
Dreament Serves Outers May studie Targets -Coherence Outers -Coherence Outers -Coherence Outers -Stachines -Stachines -Stachines -Stachines -Studies -Studies -Studies -Studies -Studies -Studies -Studies	This page displays key information about each machine that has been configured in the com § Containize this table Machines Cick the Lock & Lifetbutton in the Change Center to activate all the buttors on the page.	rt Widdoge Server donain.	Showing I to I of I Previous Next
Diversert Servers Outers May table Fargets Coherence Servers Coherence Outers Stable and Subtown Gases Stable and Studioun Gases	This page digites key information about each mathem that has been configured in the com () Contramize this table: Machines Oct the Lock & Ediffution in the Overge Center to activite all the buttors on the page. Inter-Conner: Center Center: Conner: Center		Showing I to I of I Previous Next

Figure 166 Summary of Machines Added

5. Type the Cluster Node name and other properties for the new Server. Click Next.

Figure 167 Defining Properties for the New Server

ORACLE WebLogic Server®	Administration Console		0
Change Center	🏦 Hone Log Out Preferences 🔐 Record Help		Welcome, weblogic Connected to: E1_3AS
View changes and restarts	Hone >Summary of Outliers >Summary of Machines >XDD	CHLI >Summary of Servers >AdminServer >Summary of Serve	*1
No pending changes exist. Click the Release Configuration button to allow others to edit the domen. Lock & Exit Release Configuration	Create a New Server	n jerup.	
Jomain Structure	* Indicates required fields		
1. XK Characterization of the second secon	What would you like to name your new server? * Server Name: Where will this server liaten for incoming connections? Server Liaten Address: * Server Liaten Port: Should this server belong to a Quiter?	VCC1	
tow do L. 🛛	C No, this is a stand-alone server.		
Create Managed Servers Configure default network connections Evolvem Status	⁽²⁾ Yes, make this server a member of an existin Select a cluster:	ng chanter.	
Health of Running Servers	C Yes, create a new cluster for this server.		

6. Select the machine, cluster, from dropdown menu.

ſ

DRACLE WebLogic Server®	Administration Co	wache													, C
hange Center	nome Log Ou	J. Preference	s 🐼 Record	Help			<u>a</u>						Welcome,	weblogic	Connected to: E1_3
lew changes and restarts	Home xSummary	of Outlets x5	unmary of Ha	hines a	00/741 10	ummary of t	Servers >AdminS	eve stam	ery of Serve	es xVCC1 xS	annary of Servers >W	663			
ending changes exist. They must be activated take effect.	Settings for VCC														
Activate Changes	Configuration	Protocols	Logging 0	ebug	Hunkoring	Control	Deployments	Services	Security	Notes					
Undo All Changes	General Out	Aar Service	s Keystore	6 55	S. Federal	ion Services	Depkyment	Hightion	Turing	Overkad	Health Monitoring	Server Start	Web Services	1	
omain Structure	Seve														
MS *	Use this page to	Use this page to configure general features of this server such as default network communications.													
-Outers - What Holts	Name				WCCI					An alphanumeric name for this server instance. More Info					
Higratable Targets Coherence Servers Coherence Ousters	(Machine:				(10000AC) •				The WebLogic Server host computer (machine) on which this server is meant to n.m. Mare July				r is meant to		
Hachines Work Managers Startup and Shubdown Classes	d Chaten				E1C1					The cluster, or group of WebLogic Server instances, to which this server belongs. More ${\rm More}$ Mo				server	
Deployments Services	💰 Listen Address:									The ${\mathbb P}$ address or DNS name this server uses to listen for incoming connections. Here ${\sf DMs}_{-1}$				1	
eer de L	17 Listen Part	17 Uniter Part Enabled								Specifies whether this server can be reached through the default plain-text (non- 53.) laten port. Nore bries				plain-best (non-	
Configure default network connections Create and configure machines Configure duaters	Listen Part:				7503						The default TCP port connections. Hore		r uses to laten fo	r regular (no	r~55L) incoming
Compute Guidens Start and stop servers Configure WLDP degnostic volume	□ SSL Laten I	59. Listen Port Enabled								Indicates whether the server can be reached through the default 55k listen port. More 340				55. listen	
	55L Listen Port	t			2002		_				The TCP/IP port at +	each this server	lateria for 554 co	nnection red	write. Nore

Figure 168 Configuring the General Features

7. Sign into ServerManager, and select create a managed instance of type HTML server. Use the port configured in previous step.

1

Figure 169	Defining the Instance	Properties
------------	-----------------------	------------

Create/Register A Managed Instance		💁 • 🖸 - 🗅 📾 • Page • Safety • Tools • 😝 •
ORACLE JD Edwards EnterpriseOne	The second second second	Server Manager Documentation EnterpriseOne Documentation Logost
Management Dashboard D JDEHTML1 [C:\DE_HOME] D		
Create/Register A Managed Instance		
contain the characters [a-ch-2_0-9]; spaces or other special characters are not penelted. Server Group Instance Name 328E Server HTTP Port	E1_JAS_C1 Cracle VMbLogic Instance: wts_1025, Domain: E1_JAS, Cluster: E1C1, Server: VCC1 2 7503	s name muit be unique within this management domain and may only
		Cancel Continue

8. Type the configuration items for the JDV900 environment. Click Continue.

Create/Register A Managed Instance		💁 • 🖸 - 🖾 📾 • Page • Safety • Tools • 😜
DRACLE [®] JD Edwards EnterpriseOne		Server Manager Documentation Enterprise/One Documentation Logout
nagement Dashboard IP .JDEHTML1[C'UDE_HOME] IP		
Create/Register A Managed Instance		
The values were saved at Thu Mar 01 0445151 2012, please check for error Boutstrap Environment Node Name Node Parsword Path Codes	CGLOBALNODE CGLOBALNODE	
Default Environment		
Default Role Install WSRP	ALL	

Figure 170 Validating the Configuration Items

9. Click Create Instance.

Figure 171 Completing the Creation of the Managed Instance

Create(Register A Managed Instance	🛐 • 🖸 - 📼 👼 • Page • Safety • Tools • 🚯 •
	Server Manager Documentation Entreprise/One Documentation Logost
tanagement Deshboard IP .JDEHTML1 (CNDE_HOME) IP	
Create/Register A Managed Instance	
Please wait while the managed instance is created/registered. Once complete you will be redirected to the management page for the newly created inst Instance Type Instance Properties	arce.
The final step includes deploying the EnterpriseOne HTPR, server to the 32EE application server. This process may take five or more minutes to complete	. Once complete the HTTP server associated with the 32EE application server must be restarted manually. Create Instance Create Instance

Oracle HTTP Server Installation

Install the Oracle HTTP server on the JDE HTML server.

To install Oracle JRF and Oracle HTTP server, see:

- ADF/JRF: http://www.oracle.com/technetwork/developer-tools/adf/documentation/index.html
- Oracle HTTP Server: http://docs.oracle.com/cd/E23943_01/doc.1111/e14260/overview.htm

JDE User Creation

I

To create the JDE user sign into the DEP900 environment on the deployment server, and follow these steps:

1. Type the Name and other credentials to login to Oracle JDE.

Figure 172 Logging into the Deployment Server

Create/Register A Managed Instance		🚰 • 🖸 · 🖾 📾 • Page • Safety • Tools • 🚷
		Server Manager Documentation Enterprise/One Documentation Logout
anagement Dashboard JDEHTML1[C\UDE_HOME]		
Create/Register A Managed Instance		
The values were saved at The Mar 01 0445151 2012, please check for em Bootstrap Environment Node Passeord Path Codes Default Environment Default Role Bootal WSBP	GLOBALNODE GLOBALNODE GLOBALPWD GLOBALPWD GV9809 GV9809 GV9800	Cancel

1

2. Fastpath to P980001.

Figure 173 Loading the P980001

Create,Register A Managed Instance	🤷 • 🖸 - 🖻 👼 • Page • Safety • Tools • 🔞 •
	Server Manager Documentation Enterprisedne Documentation Logost
Management Dashboard	
Create/Register A Managed Instance	
Please wait while the managed instance is created/ingistered. Once complete you will be indirected to the management page for the newly created instance. Instance Type Instance Properties Confermation	Preh
The final step includes deploying the EnterpriseOne HTPIL server to the XEE application server. This process may take five or more minutes to complete. Once complete to	he HTTP server associated with the JZEE application server must be restarted manually. Cancel Create Instance

3. Click Add, to add users.



JD	EDWARDS ENTERPRISEONE
User ID:	JDE
Password:	***
Environment:	DEP900
Role:	*ALL
ОК	Cancel Options <<

- 4. Type the JDE user and set the password. Data Source is default.
- 5. To verify the user created, search for the user.



Figure 175 Searching for the User Created

Figure 176 Verifying the User

System User	6	· >
	-	2
	-	<u>بر</u>
System User	Data Source	

6. Fastpath to P98OWSEC.

ſ

Figure 177 Loading the P98OWSEC



7. Search for JDE user created in previous steps.

Figure 178	Verifying the User
------------	--------------------

e Edit Preferen	with User Security ces Form Row W	ndow Help												
nct Find Add	Copy Del Ch	e Beg. N	ew. Dis.	Ro Link	s 🔻 User	OLE	() internet							
						_							_	
User ID / Role		JÜE				_								
Data Source														
ia 🔄 User / Ri	,ie			_		her		Data	System	User	Change	Allowed	Retry	Security
D.CE						D		Source	System User	Status	frequency	Attempts	Count	Changed

1

8. Perform configuration for system user mapping and password management.

Figure 179 Setting the Password Management Options

K 🔮 💐 Links 🛩 Securi. @OLE [Gan Dis Ago	Internet			
User D Role	ļce	_		
Cata Source System User Password	permut poe	<u>.</u>	User Status IF Enabled IF Disabled	
Allowed Password Attempts	100	Paseword Charge Frequency	[500
Invalid Password Alternats Daily Password Change Limit	0	Password Changed Security Changed		_
Daily Paseword Change Limit	P			

File Edit Preferences Form Window Help				- (6)
OK Gan. Dis. Ago Lasks → Secun. @OLE	indernet			
UserID	LOE .			
	L			
Data Source	DEFAULT		User Status	
System User	[i0€	-	/ Enabled	
Password	l	_	Cossibled	
Allowed Pasaword Atlamats	100	Password Change Frequency	1	
Invalid Password Attempts		Password Changed	1	
Daily Pastword Change Limit	9	Security Changed	I.	
Foto Immediate Password Change				
Save record				0

Figure 180 Modifying the Password Change Frequency

Oneworld Client Install

ſ

Use the shared location for client installation binaries on deployment server to install the client.

To Install the Oneworld Client, follow these steps:

1. Right-click InstallManager, and select Run as administrator. This launches the Oracle JD Edwards Install Manager.

Figure 181 Running the OneWorld Install Files

Organize = 🔂 Open	Burn Ne	Run as administrator Troubleshoot compatibility		_	
★ Favorites ■ Desktop 3 Downloads	Name	Run with graphics processor 7-Zip TextPad	• ed • 002 PM 231 AM	Type File folder File folder	Size
1 Recent Places	Puch Install ThirdParty	Scan for threats Always available offline	2:31 AM	File folder File folder	
Documents	Setup.ex.	Restore previous versions	1:32 PM	DC, File HL, File	910 KD 5 KD
 Music Pictures 	40comupd.	Send to Cut	* 1:32 PM	DL_File DL_File	481 KB 53 KB
Videos Videos	addit.d.	Сору	1:32 PM	DL_File EX_File	59 KB 808 KB
👰 Computer 🏯 System (C:)	CLIENT_SP	Create shortcut Delete	1:32 PM 1:32 PM	Setup Information SDF File	1 KB 3,782 KB
Network	hdor/g.d.	Rename Properties	132 PM	DL_File Setup Information	123 KB 1 KB

2. Click the Workstation Install link to launch the client.

Figure 182

Clicking Workstation Installation Link

1



3. Click Next and proceed with the installation.

Figure 183 Proceeding with the Installation

🛃 Client Workstation Setup	
JD Edwards EnterpriseOne Client Install	Welcome to the JD Edwards® EnterpriseOne Client installation program. Client Workstation Setup cannot update shared files if the files are in use. Before continuing, please close any open applications.
ORACLE	Click Next to continue or Cancel to quit. If you would like to know more about the setup process, click the Help button. In the following setup screens, click Help to obtain a more detailed description of the setup screen or its options.
	< <u>B</u> ack [<u>Next</u> >] Cancel Help

4. Choose the DV900FA (Development full package) DV900FA package to install.

	-			
	Please selec	t a package to install.		Filters ON
	Name	Description	Path Code	Build Date
JD Edwards	DV900FA	Development full package A	DV900	Mon Sep 22 00:00:00 20
EnterpriseOne	PS900FA	Pristine full package A	PS900	Mon Sep 22 00:00:00 20
Client Install		Prototype full package A	PY900	Mon Sep 22 00:00:00 20

Figure 184 Selecting the Development Full Package

Full Package Build

I

To Build the Full package, follow these steps:

- 1. Login to Oracle JDE and open the Active Console
- 2. Type GH9083 and Fastpath to the Package and Deployment Tools menu.



📍 20 Edwards Solution Explorer
Be Edit Vew Icols Applications Help
Feat Path OH3000
/ ** Menu Design Menu Pitening
🖂 👔 EnterpriseOne Life Cycle Tools / All My Roles
🙁 🛄 Application Development
🛞 🔐 Report Management
🚊 🔐 System Administration Tools
🙁 🛄 Workflow Management
🚊 🔐 View Development

3. Select the Package Assembly from the Package and Deployment Tools menu.

le Est Yew Tools gaplications Heb Fast Path	
Penu Design Menu Pittering	X Come Run
 ContrepriseOne Life Cycle Tools / All My Roles All Application Development Preport Management System Administration Tools View Development View Development 	Package and Deployment Tools Buildings Services Astemaby Package Astemaby Package Baild Package Baild Package Deployment Monitoring Machine Identification Machine Identification Package Installation Results Package Installation Results Package Installation Results

Figure 186 Selecting the Package Assembly



I

1

Figure 187 Defining the new Package Assembly

5. The Package Assembly Director opens. Click Next.





6. Type package name, description and pathcode. Click the Express radio button.

Gan. Neg Dis. Ago Le	ks ▼ Next @OLE . @Internet	
To begin, order basic information at Give the package a unique name, a	ind yor backage. meaningful description, and the Path Code with which it is associated.	
The Express Option determines if y	ou go through the Package Assembly Director or right to the Assembly Revisions Form.	
Express Option		
C Director		
G Express		
Package Name	[DNROANCES]	
Description	for prg	

Figure 189 Defining the Package Information

7. Verify the Package Assembly properties. Click End.

Figure 190 Summary of the Package Features

Package Name	Evenesces Marke	
Path Code	Dvissources Bull page	
a Ful	F Boort Walks Characterization	
C Opdate Parent Package	Build Business Services	
Foundation	Default E930	
Catabone	Der(wd)(E900)	
Cards	CarlautoCarettal Obaieda - (04/06)	<u> </u>
Festares	No Features Selected	- f
Language	Default	
Bally Contractions()	Everyweeting Databasies 0	
Business Services	Build Business Sentces	

8. Select the package and click Activate. Click Define Build.

Γ

ige Assembl	ly - [Work With Packages]		
	ences Form Bow Window Help		
i L	Find Add Copy Del. Close Seg. New	Dis_ Algo Links - Build DOLE	@ Internet
	Package Name	DV90BUCB5	Mil pkg
	Path Code	DV900	
	 Packages OV900UCS5(bill pkg) 		

1

Figure 191 Selecting the Package Build

9. Click Next.

Figure 192 Proceeding to Package Building



10. Check the Client, Server, and Share Specs checkboxes in the Build Location area.



Figure 193 Defining the Package Build Location

11. Click **Next** to get a list of available Enterprise servers. Select the Enterprise server.

Figure 194 Selecting Enterprise Servers

	n Window Help	-		
Select Fit	d Close Seg. New. Prev. N	Negt Dis_ Abo	▼ Previo OLE Internet	
		Next		
11				
You ha	re indicated that you would like to be	uild this package for a serve	r. Select the servers you wish to build for b	y double-clicking on the ro
		1.		
		0		
	Secure Huma	Data Source	Database	
8.	Server Name	Data Source Type	Database Name	
₿. ✓ .064				
JOEA			Name	
JOEA	RP1		Name JCEAPP1 - 900 Server Mixs	
JOEA	991 PP1 - Logic		Name DDEAPP1 - 900 Server Mitp JDEAPP1 - 900 Server Map	
AGC	PP1 - Logic PP1 - RTE PP1 - XAP1		Name CEAFP1 - 900 Server Map JCEAPP1 - 900 Server Map JCEAPP1 - 900 Server Map JCEAPP1 - 900 Server Map	
AGC	FP1 - Logic PP1 - Logic PP1 - RTE PP1 - XAP1 ATCH1		Name CEAPP1 - 900 Server Map JCEAPP1 - 900 Server Map	
↓ 0000 ↓ 000	SPT PPT - Logic PPT - RTE PPT - XAPT ATCHT - Logic ATCHT - Logic		Name CCEANST - SCO Brown Map JCEAPPT - 900 Brown Map JCEAPPT - 900 Brown Map JCEAPPT - 900 Brown Map JCEAPTCH - 900 Brown Map JCEATCHT - 900 Server Map	
JOEA JOEA JOEA JOEA JOEA JOEA JOE8 JOE8	991 PP1 - Logic PP1 - RTE PP1 - XXP1 ATCH1 - ATCH1 - Logic ATCH1 - RTE		Name CCEXPF1-9200 Server Map JCEAPF1-9200 Server Map JCEAPF1-9200 Server Map JCEAPF1-9200 Server Map JCEBATCH1-900 Server Map JCEBATCH1-900 Server Map	
↓ 0000 ↓ 000	SPT PPT - Logic PPT - RTE PPT - XAPT ATCHT - Logic ATCHT - Logic		Name CCEANST - SCO Brown Map JCEAPPT - 900 Brown Map JCEAPPT - 900 Brown Map JCEAPPT - 900 Brown Map JCEAPTCH - 900 Brown Map JCEATCHT - 900 Server Map	

12. Verify the Server specifications. Click End.

Γ

ly-{Package Duild Rev more Form igndow (
Package Name Path Code	End Dis. App Links + Control Dis. App Control Dist. App Control Dist. Co	All plg		
P Client				
F Server(x)				
🕼 Share Spec				
Shared Locate	n Central Objects - DV900			
Hubi Specification Op	Betiness Function Options Compre-	ssion Options		
P Build Spr	icification Options			1
1	ccRcator Options * Al Specification Tables * Individual Specification Tables	Stop-Build Option	Gamma Continue Build on All Errors	
	All Specification Tables		Dit Continue Build on All Errors	
	All Specification Tables Individual Specification Tables	F Papers (25.74		
	Al Specification Tables Individual Specification Tables Advects Advects Advects Advects Advects	F Person 252.74 F Cottan, F Cottan, F Cottan, F Cottan,	r Filosof Filosof Filosof	
1 1 1 1	Al Specification Tables Individual Specification Tables Almont Almont Advects Advects Advects Advects	F Portus 252 PF	r Figures Figures Figures Figures	
1 1 1 1	Al Specification Tables Individual Specification Tables Advects Advects Advects Advects Advects	F Person 252.74 F Cottan, F Cottan, F Cottan, F Cottan,	r Filosof Filosof Filosof	

1

Figure 195 Server Build Specifications

13. Click Sequence.

Figure 196 Adding the Package Sequence

Burk and form	nbly - [Work With Package Build Definition]			
	ferences Form Bow Window Help			
Tools Form	Find add Del. Slose Fra hirw	of the second s	E 🕑 internet	
Row Build Venticat	Package Name	DAMONDAL DA	_	
Build Revisions	Path Code	Dv900	_	
Actived	Packages Poysoucss (Dv900 Poysoucss (Dv900 Poysoucss (Dv900 Poysoucss (Dv900 Poysoucss (Dv900 Poysoucss (Dv900 Poysoucss			
Submit Build	B CLENT B JOEAPP1			
Deploy.				
Advanced				
Allach				

14. Click Active/Inactive.

Package Asser	mbly - [Work With Package Build Definition]			
C Ele Edit Evel	ferences Form Bow Window Help			
Tools	Find Add DeL. Close Drg., New., Dr	Links 🔻 View 💽 OLE	. Dinternet	
Form Row Duild Verticat	Package Name	pvsoeuces	_	
	Path Code	0/900	—	
		p		
Build Revisions				
ActiveInA ctive Suant Dealo Deploy	 ⇒ ◆ Patkages ⇒ ◆ Patkages ⇒ ◆ Patkages ⇒ ◆ Comb Capeta - Dv800 ⇒ ◆ CUENT ⇒ ◆ J0EAPP1 			
Advanced Adlach				

Figure 197 Activating the Package Build

15. Click Submit Build.

ſ

Figure 198 Submitting the Package Build Defined

	Package Assembly - [Work With Package Dubl Definition]				
	ferences Form Bow Window Help				
Tools Form	Find Add Det. Close Seg. New. D	■ No. Links ▼ View @ OLE @ Internet			
Row Build Venticat.	Package Name	DV8004C85			
Build	Path Code	[over			
Activel.	● ◆ Pactages ● Pactages				
Atlach					

16. Click On Screen radio button to print report to screen.

Figure 199 Selecting the Report Output Destination

Package Assembly - [Report Output Destination]				
	references <u>Window</u> Belp			
Tools	X 🔗 🦃 Links 🕶 Displ @ OLE @ Internet			
Calendar				
	Report Destination	Output Stream Access		
Calcula				
Nork View				
Center				
Internal Mail	6 On Screen	CSAInterface Name		
@ Edemai				
Mail				
Internet	C To Printer			
e				
Create Shortcut				
e Send				
Shortcut	C Export to CSV			



The full package build usually takes between 4-6 hours to finish. Deploy the successfully built package on the Enterprise server

Summary

The above sections described the approach taken for installing JD Edwards 9.0.2 on a Oracle Virtualized environment with two-node Oracle RAC database. The benchmarking effort required the use of a weblogic cluster with an Oracle Http server front end to load balance the users among the various cluster nodes. It is very important to check Oracle support documents for information regarding the latest support statements in the various JDE MTRs as well as to check for recently released patches.

Oracle JD Edwards EnterpriseOne Performance and Scalability

Workload Description

The Oracle JD Edwards Day in the life (DIL) kit is an attempt to capture how a typical customer interacts with the JDE system during the course of a typical day. The DIL kit accomplishes this with a set of scripts for 17 interactive applications as well as a set of JDE reports (UBEs) which processes a specific set of data which is part of the DIL database. Due to the availability of this standard set of scripts and UBEs, various hardware vendors, including Cisco have endeavored to characterize JDE implementations on their hardware platform to deliver a value proposition for prospective customers.

The DIL kit interactive application workload skews more towards SRM applications which feature prominently in the application workloads used by the large JDE customer base in the mid-scale manufacturing industry segment. The UBE workload is also representative of the type of reports that would be run by customers in this segment, though it does incorporate reports that cater to a larger audience of customers.

The DIL workload incorporates a good mix of applications ranging from multiple line items Sales Order and Purchase Order entries, coupled with light weight applications like supplier ledger enquiry. Similarly, the UBEs range from long running MRP processing and General Ledger Post reports to the short running Company constants and Business unit reports.

The LoadRunner scripts for the JDE interactive applications that the DIL kit incorporates measure the response times for certain key, representative transactions and these are incorporated in this whitepaper. The UBE performance is measured in terms of the total time taken to generate the report, as measured by timings recorded in the JDE logs for those UBEs.

Test Methodology

The interactive and batch version of the JDE E1 DIL kit was run to capture the end-user response time variation and Batch execution rate with important system characteristics such as CPU, memory, and I/O across the servers in the test system. All four components of the JDE E1 deployment—HTML server, Enterprise Server for interactive user, Enterprise Server for Batch and Oracle database server—were monitored through nmon Linux monitoring tool. EMC nar files were used to measure the total IOPs and latency on EMC VNX5300.

I

Test scenarios included a broad range of JDE applications ensuring that they closely mimic how a potential customer would utilize Oracle JD Edwards EnterpriseOne. The documented response times and the best practices to deploy Oracle JDE E1 server would give customers a good indication on how they could expect such a configuration to perform when deployed in their production environments.

Cisco endeavored to truly stress the hardware configuration, as well as provide customers with scenarios which provide a mix of interactive and batch processes running concurrently. Cisco devised various scenarios to test and record the impact of running a mixed batch workload would have on the interactive performance of JDE applications, since batch processes are typically resource hungry, thereby impacting the responsiveness of JDE interactive applications.

The elaborate test scenarios executed for JDE deployment on Cisco UCS are as follows:

- Interactive Scaling: Scaling of JDE interactive users from 1000 to 7,000 concurrent users
- Individual UBEs: Execution of individual long running UBEs on JDE E1 Server for batch/UBE processes
- Only Batch: Execution of batch/UBE processes on JDE Enterprise Server Virtual Machine without interactive apps

Interactive Workload Mix

The JDE E1 DIL kit is a set of 17 scripts that include Oracle SCM, SRM, HCM, CRM, and Financials applications.

Table 9 shows the transaction mix used for the JD Edwards EnterpriseOne interactive test with the JDE E1 DIL kit.

Oracle Application	Percentage Weight
Financial Management System	20
Supplier Relationship Management	24
Supply Chain Management	49
Customer Relationship Management	5
Human Capital Management	2
	100%

Table 9 Workload Mix

Interactive workload Scaling

The test scenario for Interactive Scaling was executed to determine the variation in end-user response time in the event of increasing interactive users from 1000 to 7,000 concurrent users. The system resource utilization such as CPU, memory and disk IO was captured across all the three tiers i.e. HTML Server, JDE E1 Server and Oracle Database server. For 2500 concurrent interactive users, a single HTML Server VM and E1 server VM with two-node Oracle RAC VMs was utilized. For users beyond 2500 concurrent users two HTML VMs and two E1 servers VMs with a common two-node Oracle RAC VM was utilized. This was deployed to enable high interactive user scaling as well as demonstrate failover setup for HTML and E1 server.

Oracle's JDE E1 DIL Kit Illustrating Weighted Average Response Time for Interactive UsersShows the weighted average response time for 1000 to 7,000 interactive users.



Figure 200 Oracle's JDE E1 DIL Kit Weighted Average Response Time for Interactive Users

As illustrated in Figure 200, JDE E1 deployment on a Cisco UCS blade server infrastructure on Oracle Virtualized environment scales exceptionally well, with an almost flat response time of around 0.14 second for 1000 to 7,000 concurrent users. It elaborates how well Oracle JD Edwards EnterpriseOne can be consolidated on just two Cisco UCS B200 M3 servers, with peak of 7000 users.

User Response Time

User response time was captured at the LoadRunner Controller for all 17 interactive JDE E1 DIL test scripts. The five important JD Edwards EnterpriseOne applications measured using the JDE E1 DIL Kit were:

- Financial Management System (FMS)
- Supplier Relationship Management (SRM)
- Supply Chain Management (SCM)
- Customer Relationship Management (CRM)
- Human Capital Management (HCM)

The transaction mix for these applications is detailed in the Workload Mix section of this document.

Oracle's JDE E1 DIL Kit Weighted Average Response Time, shows the weighted average response time for all 17 JDE E1 DIL kit scripts and for the five JD Edwards applications.



Figure 201 Oracle's JDE E1 DIL Kit Weighted Average Response Time

As detailed in Figure 201, the average response time of any of the JD Edwards application for interactive user tests was around 0.6 seconds during the scalability from 1000 to 7,000 concurrent users.

CPU Utilization

I

Each of the tiers; HTML server, Enterprise Server and two-node Oracle RAC database was deployed on separate Oracle VMs deployed on just two Cisco UCS B200 M3 Blade Servers, equipped with two-socket Intel Xeon E5-2690 processors. Figure 202 illustrates the average CPU utilization across the 3-Tier JD Edwards Technology Stack.



Figure 202 JDE E1 CPU Utilization

Observations:

- The average CPU utilization for each of the Oracle Virtual Servers was around 70 to 75% for a peak of 7000 interactive users.
- Each of the JD Edwards EnterpriseOne VMs with 10 vCPUs each was just around 35% for a peak of 7000 users.
- The average CPU utilization for each of the Oracle RAC nodes VMs deployed with 10 vCPUs each was at around 40%.
- The average CPU utilization recorded on each of HTML servers VMs deployed with 8 vCPUs each was around 70%.
- CPU utilization across all tiers gradually increased, reflecting the linear scalability of the workload.

Memory Utilization

Memory utilization across each of the Oracle Guest VMs for the test with 1000 to 7,000 Interactive users across the 3-Tier JD Edwards technology stack is illustrated JDE E1 Memory Utilization.

Each of the JDE OVM Servers was deployed on Cisco UCS B200 M3 server equipped with 256 GB of memory.

I



Figure 203 JDE E1 Memory Utilization

Observations:

- Each of JDE HTML Server VM was configured with 64 GB of memory. The memory utilization for each of the VM was at around 55 GB. This was due to the fact that for 3500 concurrent users on each VM, around 20 JVM instances with heap size of 2 GB each were configured in Oracle Weblogic. These instances were load balanced through Oracle HTTP Server which was installed on the same HTML Server VM.
- Each of JDE EnterpriseOne Server VM was configured with 64 GB of memory. The memory utilization for each of the VM was at around 42 GB.
- Oracle RAC database nodes was configured with 120 GB of physical memory. The peak utilization was at around 88 GB for total users 3500 users on each of the VM.

I/O Performance

The EMC VNX5300 was configured as the storage system for each of the three components of the JDE E1 deployment: HTML server, JDE E1 server, and Oracle RAC database server. The Cisco UCS servers were booted from the SAN (EMC VNX5300), which allows unleashing of the full capabilities of Cisco UCS statelessness. Cisco UCS stateless configuration allows migration of Cisco UCS service profiles from a failed physical server to a standby server.

JDE E1 Average IOPs on VNX5300 illustrates total disk I/O performance captured with the help of EMC NAR files, during the scalability test for 1000 to 7000 JDE E1 interactive users.



Figure 204 JDE E1 Average IOPs on VNX5300

Observations:

- The number of I/O operations per second (IOPS) generated on EMC VNX5300 scaled linearly, reflecting the gradual increase in the user count.
- The response time observed from the EMC generated NAR files was less than 5 ms for the duration
 of the test.
- The VNX5300 is capable of handling a higher number of IOPS than reflected in this graph. The IOPS shown are a result of what was driven by this JDE DIL kit workload

Individual UBEs

Batch processing is another critical activity in Oracle JD Edwards EnterpriseOne environment and it was important to test and determine the execution time for long running individual UBE processes. This helps in proper sizing of batch servers for a Oracle JD Edwards deployment. In real-world JD Edwards deployment, several long running UBEs are run after business hours, and they must complete within a fixed duration of time since they are end of day reports and should not spill over to the following day affecting interactive users. The performance characteristics of these UBEs are summarized in Table 10, with a brief description of what the UBE provides and what dataset they operate on. These long running reports ran on a fixed set of data with a standard set of processing options against the JDE DIL database, as described below.

UBE	Time Taken (mm:ss)	Description
R43500	17:25	This Purchase Order Print UBE processed records in F4311 table (Purchase Order Detail File) with a status code of 280 in one business unit. 255,471 records were processed using this data range
R3483	15:20	This MRP UBE processed 50,000 records in F4102 using one business unit. This is a night only process.

I

Table 10	Long Running UBE Execution Time
----------	---------------------------------

R31410	26:45	The Work Order Processing UBE acts on the document invoice numbers in the Work Order Master File, F4801 and 28,751 records processed with the data selection
R09801	7:05	This General Ledger post UBE acts on records located in the Batch Control Records table, F0011 the data selection used a batch status "A" and batch type "G." and processed 990,099 records.
R31802a	24:30	The Manufacturing Account Journal UBE acted on document invoice numbers in the Work Order Master File, F4801 with a status code of "95." and processed 1,501 records for our data selection criterion.

Table 10 Long Running UBE Execution Time

Only Batch Execution

There are customers who run only JDE Batch processing for many business functions during a dedicated window and it was imperative on Cisco to test and provide enough information for such customers to make an informed decision regarding their deployment of JDE on Cisco UCS using Oracle Virtualization. For such customers a test scenario was configured wherein, high volume of short running UBEs as well as 3 long running UBEs were executed, and the impact of running this test scenario was measured in terms of CPU and memory consumed on the Enterprise server, Database server and each of the two Oracle Virtual Servers.

The test successfully achieved 320 UBEs/minute. The average IOPS measure on the EMC VNX5300 was around 3200. It would be a good strategy for real-world JD Edwards EnterpriseOne customers, to schedule very high volume of UBEs during those non-peak hours when minimal interactive users are logged in to the JDE system

Resource Utilization for Only Batch Execution, illustrates the CPU and memory utilization on JDE Enterprise Server and two-node Oracle RAC database during the execution of Only Batch Processes.



Figure 205 Resource Utilization for Only Batch Execution

Best Practices & Tuning Recommendations

Oracle JD Edwards EnterpriseOne deployed on Cisco UCS with EMC Storage system with Oracle VM was configured for small to medium scale ERP deployment. The benchmark of JDE DIL Kit demonstrated exceptional performance for JDE interactive users and JDE Batch processes. The subsequent sections elaborate on the tuning parameters and best practices incorporated across hardware and software stack.

System Configuration

All the tests were executed using two Cisco UCS B200 M3 servers. Each server was equipped with two E5-2690 processor and 256 GB of physical memory. Six Guest VMs were carved on the two B200 M3, with two instance each of HTML Server, JDE EnterpriseOne Server and Oracle RAC node.

Both of the Cisco UCS Blade Servers were attached to a BIOS policy. BIOS policy is one of the features of UCS Service Profiles which enable users to incorporate similar BIOS settings all across the deployed servers. This helps a consistent configuration and the Administrators do not need to interrupt the boot process on each server to alter the BIOS setting. The BIOS policy configured for Oracle JDE deployment is shown in Figure 206.

I

当 BIOS Policy	
Main Advanced Boot Options Server Management Events	
Processor Intel Directed IO RAS Memory Serial Port USB PCI Configuration	
Turbo Boost: C disabled C Platform Default	
Enhanced Intel Speedstep: C disabled C Platform Default	
Hyper Threading: C disabled C Platform Default	
Core Multi Processing: all	
Execute Disabled Bit: 🔘 disabled 🔘 enabled 💿 Platform Default	
Virtualization Technology (VT): C disabled C Platform Default	
Direct Cache Access: C disabled C enabled C Platform Default	
Processor C State: C disabled C enabled C Platform Default	
Processor C1E: C disabled C enabled C Platform Default	
Processor C3 Report: 💽 disabled 🔿 acpi-c2 🔿 acpi-c3 💭 Platform Default	
Processor C6 Report: C disabled C enabled C Platform Default	
Processor C7 Report: C disabled C enabled C Platform Default	
CPU Performance: C enterprise C high-throughput C hpc C Platform Default	
Max Variable MTRR Setting: C auto-max C 8 C Platform Default	
	OK Apply Cancel Help

Figure 206 BIOS setting for CPU Performance

Γ

_						
BIOS Policy						
	Main Advanced Boot Options Server Management Events					
Processor Intel Directed IO	RAS Memory Serial Port USB PCI Config	uration				
VT For Directed IO:	C disabled C enabled C Platform Defau	lt				
Interrupt Remap:	○ disabled ⊙ enabled ○ Platform Defau	it				
Coherency Support:	O disabled O enabled O Platform Defau	lt				
ATS Support:	C disabled C enabled C Platform Defau	lt				
Pass Through DMA Support:	○ disabled enabled Platform Defau	lt				
, 			ок	Apply	Cancel	

1

Figure 207 BIOS setting for Indirect IO

텰 BIOS Policy				
Main Advanced Boot Options Server Management Events				
Processor Intel Directed IO RAS Memory Serial Port USB PCI Configuration				
Memory RAS Config: maximum-performance				
NUMA: C disabled C Platform Default				
LV DDR Mode: C power-saving-mode C performance-mode C Platform Default				
OK Apply Cancel				

Figure 208 BIOS Setting for Physical Memory

Disable I/O MMU Virtualization Settings (VT-d). See,

http://docs.oracle.com/cd/E27300_01/E27307/html/vmrns-bugs.html

Jumbo Frames

Jumbo frames are supported in Oracle VM 3.1.1, this enables utilization of 10G ports for Oracle RAC interconnect traffic. Please ensure to use Oracle VM 3.1.1 Build 819 and above to successfully configure jumbo frames Oracle RAC private network.

Configuration of jumbo frames is demonstrated in the Infrastructure Setup Section of this document.

TCP Parameter Configuration

Default TCP parameters in most Linux VM distributions are conservative, and are tuned to handle 100Mb/s or 1Gb/s port speeds, and result in buffer sizes that are too small for 10Gb networks. Modifying these values can lead to significant performance gain in a 10Gbs VM network.

Buffer sizes should be adjusted to permit the maximum number of bytes in transit and prevent traffic throttling. The following values can be set on the virtual machines as well as dom0. Edit /etc/sysctl.conf for the below mentioned changes. These can be changed both on virtual machines as well as dom0. (See, Oracle VM 3: 10GbE Network Performance Tuning whitepaper

```
net.core.rmem_max = 134217728
net.core.wmem_max = 134217728
net.ipv4.tcp_rmem = 4096 87380 134217728
net.ipv4.tcp_wmem = 4096 65536 134217728
net.core.netdev_max_backlog = 300000
net.ipv4.tcp_moderate_rcvbuf =1
```

Additionally, for Oracle VM Server for x86 prior to version 3.2, netfilter should be turned off on bridge devices. This is done automatically in OVM version 3.2 and later.

net.bridge.bridge-nf-call-iptables=0
net.bridge.bridge-nf-call-arptables=0
net.bridge.bridge-nf-call-ip6tables=0

Oracle RAC Configuration

Several Settings were changed on Oracle RAC cluster VMs to support the high load that the RDBMS was handling. Some of the important tuning parameters are:

- The data files where configured on RIAD5 with 7 SSDs on EMC VNX5300. This provided low read and write latency thus helping lower response time for JD Edwards EnterpriseOne interactive Apps.
- Virtual machines may run in one of two main modes, paravirtualized (PVM) or hardware virtualized (HVM). In paravirtualized mode, the kernel of the guest operating system is recompiled to be made aware of the virtual environment. This allows the paravirtualized guest to run at near native speed, since most memory, disk and network accesses are optimized for maximum performance. Oracle recommends creating paravirtualized virtual machines if possible, as the performance of a paravirtualized virtual machine is superior to that of a hardware virtualized guest.
- Each of the data and log LUN were attached as physical disk to each of the Oracle RAC VM nodes. This provides better IO performance for both data and log disks.
- To understand the memory required for high interactive and batch workloads, awr report was analyzed and the SGA target and PGA target was set to 36GB and 16GB respectively.
- In general, JDE Edwards online user consumes around 150 to 200 process per 100 concurrent interactive users. For high interactive user test, the process limit was increased to 10,000.

For more details on Disk layout for Oracle RAC database, please refer Table 11. LUN Configuration for JD Edwards EnterpriseOne deployment

Some of the important Oracle RAC configuration parameters are detailed below:

NAME	VALUE
memory_max_target	0
memory_target	0
parallel_servers_target	512
pga_aggregate_target	16 GB
sga_target	36 GB
processes	10000
session_cached_cursors	4000
sessions	30030

Table 11Oracle RAC Configuration parameters

Each of the Oracle RAC VM resided on a separate B200M3 server (Ref: Figure 14. Guest OS configuration of Oracle JD Edwards EnterpriseOne on OVM). Oracle RAC VM was configured with 10 vCPU and 120 GB of physical memory. There is a significant impact to the database memory consumption with dedicated connections that can be avoided by using shared server connections. (Ref:

Doc ID 1188240.1 on https://support.oracle.com. In order to scale to 7000 users and with limited available memory for Oracle RAC VM, the present Oracle RAC setup was configured in shared connection mode.

WebLogic Server Configuration

The JRockit Java Virtual Machine (JVM) was used along with WebLogic 10.3.6. A vertical cluster of up to 20 JVMs was created and Oracle HTTP Server was used to load balance the load among the various nodes of the vertical cluster

Some of the important configuration details for the WebLogic Server are:

- For optimal performance, about 150 to 200 JDE interactive users were hosted per cluster node/JVM.
- The minimum and maximum heap size for each node was set to 2 GB.
- The garbage collection policy was set to gencon since the pattern of object creation and destruction on the JDE HTML server indicated that a large number of short lived objects were created and destroyed frequently.
- The nursery size was set to 512 MB.
- The number of 'gethreads' was set to 6, java flight recorder was switched off for formal runs, and a minimum TLA size of 4k was chosen, with the preferred size being 1024 kb

Oracle JD Edwards Enterprise Server Configuration

The JD Edwards tools release 8.98.4.10 was used with JD Edwards application release 9.0.2. The number of interactive users per callobject peaked at around 9/callobject kernel.

Some of the important configuration settings for JDE initialization files are detailed below

- JDE.ini
 - Kernel configurations:
 - Security kernels 70
 - Call Object kernels 400
 - Workflow kernels 30
 - Metadata kernels 1
 - [JDENET]
 - maxNetProcesses=60
 - maxNetConnections=8000
 - maxKernelProcesses=1000
 - maxNumSocketMsgQueue=1000
 - maxIPCQueueMsgs=600
 - maxLenInlineData=4096
 - maxLenFixedData=16384
 - maxFixedDataPackets=2000
 - internalQueueTimeOut=90
 - [JDEIPC]

- maxNumberOfResources=4000
- maxNumberOfSemaphores=2000
- startIPCKeyValue=6001
- avgResourceNameLength=40
- avgHandles=200
- hashBucketSize=53
- maxMsgqMsgBytes=5096
- maxMsgqEntries=1024
- maxMsgqBytes=65536
- msgQueueDelayTimeMillis=40
- jdbj.ini
 - JDBj-CONNECTION POOL
 - minConnection=5
 - maxConnection=800
 - poolGrowth=5
 - initialConnection=25
 - maxSize=500
- jas.ini
 - OWWEB
 - MAXUser=500
 - OWVirtualThreadPoolSize=800
 - JDENET
 - maxPoolSize=500

Conclusion

This CVD demonstrates how Cisco UCS servers on Oracle VM along with the latest EMC VNX storage technologies, form a highly reliable, robust solution for Oracle JDE Edwards implementation.

Enterprise Resource Planning (ERP) has been around for many decades and has provided agile IT practices to the Business. Organizations that have used the ERP Packages have immensely benefitted by streamlining their back end processes to improve management and improve ROI.

ERP being a business critical Application, takes a long time to implement and test; there is always a concern to move to newer technologies or experiment with the advanced features that are available today. Since this is a Business Critical Application, one of the most important concerns is predictability; will it work for us, how and at what cost?

Cisco has invested considerable time and effort to test, validate and characterize Oracle JD Edwards on Cisco UCS Platform using EMC VNX Storage with Oracle VM, thus providing comprehensive scalable architecture and best practices. By leveraging the best practices and expertise in our extensive Oracle JDE benchmark activity, customers can confidently deploy and consolidate JD Edwards EnterpriseOne on Cisco UCS platform with Oracle VM virtualization and EMC VNX storage family.

I

Cisco Oracle Competency Center has provided considerable information in this document by testing and characterizing the Cisco UCS on Oracle Virtual environment using the Oracle JD Edwards EnterpriseOne software stack. With the scalability demonstrated by the test results, Cisco is confident that these astounding results will prove that Cisco UCS, Oracle VM and EMC VNX storage is a solid fit for any customer considering virtualization of Oracle JD Edwards EnterpriseOne.

Bill of Materials

I

Table 12 and Table 13 give details of all the hardware and software components used in the CVD.

Description	Part #
Cisco Unified Computing System	N20-Z0001
Cisco UCS 5108 Blade Server Chassis	N20-C6508
Cisco UCS 6248UP 1RU Fabric Int/No PSU/32 UP/ 12p LICfans/no SFP+	UCS-FI-6248UP
Cisco UCS 2208XP Fabric Extender/ 8 external 10Gb ports	UCS-IOM-2208XP
Cisco UCS B200 M3 Blade Server w/o CPU, mem, HDD, mLOM/mezz	UCSB-B200-M3-CH
Intel Xeon E5-2690CPUs (2.9 GHz & 8 Cores)	UCS-CPU-E5-2690=
16GB DDR3-1600-MHz RDIMM/PC3-12800/dual rank/1.35v	UCS-MR-1X162RY-A=
8GB DDR3-1600-MHz RDIMM/PC3-12800/dual rank/1.35v	UCS-MR-1X082RY-A=
Cisco Nexus 5548UP	N5K-C5548UP-FA
Cisco Nexus 5548UP Storage Protocols Services License	N5548P-SSK9
10GBASE-SR SFP Module	SFP-10G-SR
10GBASE-CU SFP+ Cable 3 Meter	SFP-H10GB-CU3M
8 Gbps Fibre Channel LW SFP+, LC	DS-SFP-FC8G-LW=
EMC VNX Storage System	VNX5300

 Table 12
 Component Description

Table 13Software Details

Platform	Software Type	Name	Value
UCS 6248	Management	UCSN	2.1(1a)
UCS 6248	OS	NX-OS	2.1(1a)
Nexus 5548 up	OS	NX-OS	5.0(3)N2 (1)
Blade servers	Virtualization Technology	Oracle VM 3.1.1, Build 819 and above	Oracle VM 3.1.1 (2.6.39-200.37.1.el 5uek)

Guest OS	OS	Oracle Linux 5.8 (2.6.32-300.10.1.el5uek)	OL 5.8
Virtualization	Virtualization Technology	Oracle VM 3.1.1, Build 819 and above	Oracle VM 3.1.1 (2.6.39-200.37.1.el 5uek)
Database	Database	Oracle RAC	11.2.0.3
Application	Application Software	Oracle JD Edwards 9.02 with Tools 8.98.4.10	9.02/ 8.98.4.10

Table 13Software Details

Appendix A – Workload Mix for Batch and Interactive Test

JBE name Description		Long/short	
R03b31	Activity Log Report	Short	
R03b155	A/R Summary Analysis	Short	
r0004p	UDC Records Types Print	Short	
r0006p	Business Unit Report	Short	
r0008p	Date Patterns Report	Short	
r0010p	Company Constants Report	Short	
r0012p1	AAI Report	Short	
r0014	Payment terms Report	Short	
r0018p	Tax Detail Report	Short	
r01402w	Who's Who Report	Short	
r41542	Item Ledger As Of Record Generation	Short	
r42072	Price Category Print	Short	
r41411	Select Items Cost Count	Short	
R31410	Work Order Processing	Long	
R43500	Purchase Order Print	Long	
R3483	MRP report	Long	

Table 14 Batch Workload Mix

Table 15 JD Edwards Enterprise One Interactive Transactions

Transaction Name		Virtual Users per transaction for 500 interactive user workload
H03B102E_OK	Apply Receipts	50
H0411I_1_FIND	Supplier Ledger inquiry	50

H051141E_Row_OK	Daily Time Receipt	10
H17500E_Find	Case Management Add	25
H31114U_OK	Work Order Completion	15
H3411AE_Post_OK	MRP Messages (WO Orders)	10
H3411BE_Post_OK	MRP Messages (OP Orders)	10
H3411CE_Post_OK	MRP Messages (OT Orders)	10
H4113E_OK	Inventory Transfer	25
H42101E_Submit_Close	Sales Order Entry – 10 Line Items	125
H42101U_SubmitClose	Sales Order Update	25
H4310E_Post_OK	Purchase Order Entry – 25 Line Items	100
H4312U_OK	Purchase Order Receipts	10
H4314U_Row_OK	Voucher Match	10
H4915AU_Find	Ship Confirmation – Approval only	15
H4915CE_Find	Ship Confirmation – Confirm/Ship only	5
H4915CU_Find	Ship Confirmation – Confirm and Change Entry	5

Table 15 JD Edwards Enterprise One Interactive Transactions

Appendix B – Reference Documents

- Oracle VM 3.1.1 User Guide
- JD Edwards MTRs for Windows client, enterprise servers server and database server
- Oracle-JD Edwards 9.0.2 Release notes
- JD Edwards EnterpriseOne Applications Release 9.0 Installation Guide for Oracle On Linux
- JD Edwards EnterpriseOne 8.98.3 Clustering Best Practices with Oracle WebLogic Server

Appendix C – Reference Links

- The racking, power and installation of the chassis are described in the Install Guide: http://www.cisco.com/en/US/docs/unified_computing/ucs/hw/chassis/install/ucs5108_install.html
- Cisco Unified Computing System CLI Configuration Guide: http://www.cisco.com/en/US/docs/unified_computing/ucs/sw/cli/config/guide/2.1/b_UCSM_CLI_ Configuration_Guide_2_1_chapter_010.html
- Cisco UCS Manager GUI configuration Guide:

http://www.cisco.com/en/US/docs/unified_computing/ucs/sw/gui/config/guide/2.1/b_UCSM_GUI _Configuration_Guide_2_1.html

• VP for Unified Storage System – A Detailed Review, see:

http://www.emc.com/collateral/software/white-papers/h8058-fast-vp-unified-storage-wp.pdf

• EMC FAST Cache – A Detailed Review, see: http://www.emc.com/collateral/software/white-papers/h8046-clariion-celerra-unified-fast-cache-w p.pdf

- EMC FAST VP for Unified Storage System A Detailed Review, see: http://www.emc.com/collateral/software/white-papers/h8058-fast-vp-unified-storage-wp.pdf
- Additional information on the VNX Series, see:

http://www.emc.com/collateral/hardware/data-sheets/h8520-vnx-family-ds.pdf