



Understanding Route Plans

The Route Plan drop-down list on the menu bar allows you to configure Cisco Unified CallManager route plans by using route patterns, route filters, route lists, and route groups, as well as hunt pilots, hunt lists, and line groups.

This section describes the following route plan topics:

- [Automated Alternate Routing, page 17-1](#)
- [Route Plan Overview, page 17-4](#)
- [Route Groups and Route Lists, page 17-5](#)
- [Route Patterns, page 17-6](#)
- [Hunt Lists, page 17-10](#)
- [Hunt Pilots, page 17-10](#)
- [Call Coverage, page 17-11](#)
- [Closest Match Routing, page 17-12](#)
- [Static Digit Analysis, page 17-13](#)
- [Special Characters and Settings, page 17-16](#)
- [Calling and Called Party Transformations, page 17-26](#)
- [Caller Identification and Restriction, page 17-29](#)
- [External Route Plan Wizard, page 17-34](#)
- [Route Plan Report, page 17-38](#)
- [Where to Find More Information, page 17-38](#)

Automated Alternate Routing

Automated alternate routing (AAR) provides a mechanism to reroute calls through the PSTN or other network by using an alternate number. As a subset of the AAR feature, Cisco Unified CallManager automatically reroutes calls through the PSTN or other networks when Cisco Unified CallManager blocks a call due to insufficient location bandwidth. With automated alternate routing, the caller does not need to hang up and redial the called party.

When a call is made from the device of one location to the device of another location, location bandwidth gets deducted from the maximum available bandwidth that is available for the call at either location. If not enough location bandwidth for the call exists at either location, instead of blocking the call,

Cisco Unified CallManager uses the table of AAR groups and the external number of the terminating directory number to supply the alternate number that is used to reroute the call through the PSTN or other network. The Cisco Unified IP Phone displays the message “Network congestion, rerouting.” (Configure this message by using Service Parameters Configuration for the Cisco CallManager service.) Cisco Unified CallManager automatically attempts to reroute the call by using the alternate number. If the reroute is successful, the caller connects to the called party.

AAR supports the following call scenarios for insufficient bandwidth:

- Call originates from a line or directory number (DN) of an IP phone within one location and terminates to a line or DN of another IP phone within another location. This scenario includes calls that terminate at the shared line with terminating IP phone devices that are resident in multiple locations and calls that terminate at the Cisco voice-mail port.
- Incoming call through a gateway device within one location terminates to a line or DN of an IP phone within another location. This scenario includes calls that terminate at the shared line with terminating IP phone devices that are resident in multiple locations and calls that terminate at the Cisco voice-mail port.

Cisco Unified CallManager automatically attempts to reroute calls, due to insufficient bandwidth, through the PSTN or other network only when the AAREnable enterprise parameter is set to true. Cisco Unified CallManager uses the device-based AAR calling search space, which is assigned to Cisco Unified IP Phone station devices and gateway devices, when it attempts to route the call to the gateway device that connects to the PSTN or other network. Cisco Unified CallManager uses the external phone number mask and the directory number of the line or DN and the Cisco voice-mail port to derive the alternate number that is used to reroute the call.

Automated Alternate Routing Example

In the following scenario, line/DN 5000 in the Richardson AAR group calls line 5001 in the San Jose AAR group. If not enough location bandwidth exists, the call attempts to reroute through the PSTN or other network. To route the call from AAR group Richardson to AAR group San Jose, Cisco Unified CallManager needs to know the access digit(s) to dial out to the PSTN or other network, the long-distance dialing requirement, if any, and the alternate number. Cisco Unified CallManager retrieves the information from the AAR dial prefix matrix table, which is indexed by the originating line AAR group value and the terminating line AAR group value. [Table 17-1](#) shows how the AAR group field is data filled in the line/DN table:

Table 17-1 *Line/DN and AAR Group Association*

Line/DN	AAR Group
5000	Richardson
5001	San Jose
5002	Dallas

Cisco Unified CallManager retrieves the prefix digits from the AAR dial prefix matrix table based on the AAR group value of the originating line/DN and gateway device and the AAR group value of the terminating line, and Cisco voice-mail port, to transform the derived alternate number. Table 17-2 shows an example of how the AAR dial prefix matrix table is data filled:

Table 17-2 AAR Dial Prefix Matrix Table Example

From AAR Group	To AAR Group	Prefix Digits
Richardson	San Jose	91
Richardson	Dallas	9
Richardson	Richardson	9
San Jose	Richardson	91
San Jose	Dallas	91
San Jose	San Jose	9
Dallas	Richardson	9
Dallas	San Jose	91
Dallas	Dallas	9

Cisco Unified CallManager prepends the prefix digits that are retrieved from the AAR dial prefix matrix table to the derived alternate number. Digit analysis uses the transformed digits, plus the AAR calling search space, to route the call to the PSTN or other network.

A much greater rate of success for automated alternate routing occurs when a gateway is located in the same location as the originating or terminating device. Therefore, a call that is outgoing to the PSTN or other network from a gateway that is located in the same location as the originating device and that is also incoming from a gateway located in the same location as the terminating device describes the best scenario. In other scenarios, the call remains subject to location bandwidth validation between the originating device and outgoing gateway, and between the terminating device and incoming gateway.

Automated Alternate Routing Enable Service Parameter

Besides configuring AAR groups, ensure that the Automated Alternate Routing Enable clusterwide service parameter is set to *True*. (The default value for this service parameter specifies *False*.)

The Clusterwide Parameters (System - CCMAutomated Alternate Routing) section of the service parameters for the Cisco CallManager service includes the parameter.

Automated Alternate Routing and Hunt Pilots

In previous Cisco Unified CallManager releases, if the voice messaging system is in a central location and the user is in a remote location, when the remote user tries to reach the voice messaging system and bandwidth is not available on the WAN link, Cisco Unified CallManager can reroute the call through the PSTN to the voice messaging system.

In the current Cisco Unified CallManager release, AAR does not automatically work with hunt pilots. Because the fully qualified directory number (DN) of the remote agent is unknown, AAR cannot initiate the reroute.

To enable AAR to work with hunt pilots, two additional fields display in the Hunt Pilot Configuration window: AAR Group and External Number Mask. For each hunt pilot, you must configure these fields in the Hunt Pilot Configuration window for AAR groups to work with hunt pilots. Refer to the “[Hunt Pilot Configuration](#)” chapter in the *Cisco Unified CallManager Administration Guide* for details.

Route Plan Overview

Cisco Unified CallManager uses route plans to route internal calls within a Cisco Unified CallManager cluster, and external calls to a private network or the public switched telephone network (PSTN).

Route patterns, route filters, route lists, route groups, line groups, hunt lists, and hunt pilots provide flexibility in network design. Route patterns work in conjunction with route filters to direct calls to specific devices and to include or exclude specific digit patterns. Use route patterns to include and exclude digit patterns. Use route filters primarily to include digit patterns. Route lists control the selection order of the route groups. Route groups set the selection order of the gateway devices.

You can assign route patterns to gateways, to trunks, or to a route list that contains one or more route groups. Route groups determine the order of preference for gateway and trunk usage. Route groups allow overflows from busy or failed devices to alternate devices.

Route lists determine the order of preference for route group usage. If a route list is configured, you must configure at least one route group. One or more route lists can point to one or more route groups.

Route filters may restrict certain numbers that are otherwise allowed by a route pattern from being routed. Tags, or clauses, provide the core component of route filters. A tag applies a name to a portion of the dialed digits. For example, the North American Numbering Plan (NANP) number 972-555-1234 contains the LOCAL-AREA-CODE (972), OFFICE-CODE (555), and SUBSCRIBER (1234) tags.



Note

The NANP designates the numbering plan for the PSTN in the United States and its territories, Canada, Bermuda, and many Caribbean nations. NANP includes any number that can be dialed and is recognized in North America.

Route patterns represent all valid digit strings. Cisco Analog Access Trunk Gateways, Cisco Digital Access Trunk Gateways, Cisco MGCP gateways, H.323-compliant gateways, and trunks also use route patterns. Cisco gateways can route ranges of numbers with complex restrictions and manipulate directory numbers before the Cisco Unified CallManager passes them on to an adjacent system. The adjacent system can include a central office (CO), a private branch exchange (PBX), or a gateway on another Cisco Unified CallManager system.

Line groups consists of list of DNs. Line groups specify a distribution algorithm (such as Top Down) for the members of the line group. Line groups also specify the hunt options to use in cases where the line group members do not answer, are busy, or are not available. Beginning with Release 4.1 of Cisco Unified CallManager, a directory number may belong to more than one line group.

Hunt lists comprise ordered groupings of line groups. A line group may belong to more than one hunt list. A hunt list must specify at least one line group before the hunt list can accept calls.

Hunt pilots represent route patterns that are used for hunting. A hunt pilot can specify a partition, numbering plan, route filter, and hunt forward settings. A hunt pilot must specify a hunt list.

Route Groups and Route Lists


Route groups contain one or more devices, and route lists contain one or more route groups.

Cisco Unified CallManager may restrict the gateways that you can include in the same route group and the route groups that you can include in the same route list. For the purpose of route group and route list restrictions, Cisco Unified CallManager divides gateways into three types:

- Type 1—MGCP QSIG gateways and QSIG-enabled intercluster trunks
- Type 2—MGCP non-QSIG, Skinny, T1-CAS gateways; non-QSIG intercluster trunks
- Type 3—H.225 and H.323 gateways, and all other trunk types

Route lists can contain a mixture of route group types, although you cannot combine an H225 trunk with a Type 1 (QSIG) route group. Cisco Unified CallManager does not allow you to add route groups that contain gateways that use the H.323 or H.225 protocol (Type 3) and route groups that contain MGCP gateways that use a QSIG protocol (Type 1) to the same route list. You can create route lists with any combination of Type 1 route groups and Type 2 route groups as well as with any combination of Type 2 route groups and Type 3 route groups, as illustrated in [Figure 17-1](#).

Figure 17-1 Valid Route Lists Example



For more information on creating route groups, refer to the [“Configuring a Route Group”](#) section in the *Cisco Unified CallManager Administration Guide*. For more information on creating route lists, refer to the [“Adding a Route List”](#) section in the *Cisco Unified CallManager Administration Guide*.



Note

As of Release 4.1 of Cisco Unified CallManager, you cannot combine route groups and line groups, and route lists and hunt lists become separate entities. Thus, route groups make up route lists, and line groups make up hunt lists. In Release 4.0 of Cisco Unified CallManager, possible components of route/hunt lists included both route groups and line groups.



Note

In Release 4.0 of Cisco Unified CallManager, possible members of route/hunt lists included both line groups and route groups. In Release 4.1 of Cisco Unified CallManager, if an existing route/hunt list includes a line group as a member, Cisco Unified CallManager migrates the route/hunt list to a hunt list.

Route Patterns

Cisco Unified CallManager uses route patterns to route or block both internal and external calls.

**Note**

Prior to Release 4.1 of Cisco Unified CallManager, configuration of route patterns and hunt pilots occurred in a single window, since Route Pattern and Hunt Pilot were integrated. Route List and Hunt list were part of the same list. A list could have a Line Group and/or Route Groups.

**Note**

Starting with Release 4.1, Route Group and Route lists are part of Route Pattern configuration. Line groups and Hunt lists are part of Hunt pilot configuration. Route Patterns and Hunt Pilots are configured separately. Route Groups or Route Lists cannot be added to Hunt Pilot and Line Groups. Hunt Lists cannot be added to Route Pattern. If an existing route pattern/hunt pilot associates with a hunt list, Cisco Unified CallManager migrates the route pattern/hunt pilot to a hunt pilot.

The simplest route pattern specifies a set of one or more digits. For example, the number 8912 specifies a route pattern.

Gateways and Cisco Unified IP Phones can also use more complex route patterns that can contain wildcards. A wildcard represents a range of numbers; for example, X represents any digit 0 through 9.

To classify a call as OnNet or OffNet, administrators can set the Call Classification field to OnNet or OffNet, respectively, on the Route Pattern Configuration window. Administrators can override the route pattern setting and use the trunk or gateway setting by checking the Allow Device Override check box on the Route Pattern Configuration window.

**Caution**

If a gateway has no route pattern that is associated with it, or it does not belong to a route group, it cannot route any calls.

You can use route patterns to invoke network-specific services/facilities on a call-by-call basis by configuring the fields in the ISDN Network-Specific Facilities Information Element section on the Route Pattern Configuration window. Cisco Unified CallManager uses the network-specific services/facilities when the user dials the route pattern.

**Note**

Cisco Unified CallManager only uses the network-specific information with PRI protocol gateways. H.323 gateways do not support network-specific facilities, but they support SDN when the dial peers are configured accordingly. Cisco Unified CallManager codes the bearer capability as Speech for the ACCUNET service.

Route Pattern Usage

You can assign a route pattern directly to a Cisco Access Gateway, or you can assign it to a route list for more flexibility. For example, [Figure 17-2](#) shows Cisco Digital Access Gateway 1 designated as the first choice for routing outgoing calls to the PSTN when a matching route pattern is dialed.

**Tip**

If a gateway does not have a route pattern, it cannot place calls to the PSTN or to a PBX. To assign a route pattern to an individual port on a gateway, you must assign a route list and a route group to that port.

Figure 17-2 shows the effects of using route patterns with Cisco Digital Gateways. This example assigns the route pattern to a route list, and that route list associates with a single route group. The route group supports a list of devices that are selected based on availability.

When the system initially presents a call to a member of a route list, Cisco Unified CallManager reroutes for all cause codes other than Out of Bandwidth, User Busy, and Unallocated Number. The value of the associated service parameters for the Cisco CallManager service determines the rerouting decision for those cause codes. The Clusterwide Parameters (Route Plan) grouping includes the Stop Routing on Out of Bandwidth Flag, Stop Routing on User Busy Flag, and Stop Routing on Unallocated Number Flag service parameters. You can set each service parameter to True or False.

After a route list locks onto a trunk, no rerouting occurs. The media connect time of the endpoints and the Stop Routing service parameters determine when a route list stops hunting for the next route group. When media negotiation begins, the route list or hunt list loses the ability to reroute.

**Note**

If a route pattern is associated with a gateway, and all the resources of that gateway are used, then the call does not get routed.



Figure 17-2 Route Plan Summary Diagram for Cisco Digital Gateways

Figure 17-3 shows the effects of using route patterns with Cisco Analog Gateways. This example assigns the route pattern to a route list, and that route list associates with two route groups. Route group 1 associates with ports 1 through 8 on gateway 1, which routes all calls to interexchange carrier 1 (IXC 1). Route group 1 also associates with ports 1 through 4 on gateway 2. Route group 2 associates with ports 5 through 8 on gateway 2 and all ports on gateway 3.

Each route group supports a list of devices that are chosen on the basis of availability. For route group 1, if ports 1 through 8 on the first-choice gateway are busy or out of service, calls route to ports 1 through 4 on the second-choice gateway. If all routes in route group 1 are unavailable, calls route to route group 2. For route group 2, if ports 5 through 8 on the first-choice gateway are busy or out of service, calls route to ports 1 through 8 on the second-choice gateway. If no ports on any gateway in either route group are available, the call routes to an all trunks busy tone.

Figure 17-3 Route Plan Summary Diagram for Cisco Analog Access Gateways

Line Groups

Line groups contain one or more directory numbers. A distribution algorithm, such as Top Down, Circular, Longest Idle Time, or Broadcast, associates with a line group. Line groups also have an associated Ring No Answer reversion timeout value.

The following descriptions apply to the members of a line group:

- An *idle* member designates one that is not serving any call.
- An *available* member designates one that is serving an active call but can accept a new call(s).
- A *busy* member cannot accept any calls.

For information on configuring line groups, refer to the [“Line Group Configuration”](#) section in the *Cisco Unified CallManager Administration Guide*.

**Note**

Prior to Release 4.1 of Cisco Unified CallManager, line groups could belong to route/hunt lists. Beginning with Release 4.1 of Cisco Unified CallManager, line groups belong to hunt lists, whereas route groups belong to route lists.

Beginning with Release 4.1 of Cisco Unified CallManager, a directory number may belong to more than one line group.

Hunt Lists

Hunt lists comprise ordered groupings of line groups. A line group may belong to more than one hunt list. Hunt pilots associate with hunt lists. A hunt list may associate with more than one hunt pilot.

For information on configuring hunt lists, refer to the [“Hunt List Configuration”](#) section in the *Cisco Unified CallManager Administration Guide*.

**Note**

Prior to Release 4.1 of Cisco Unified CallManager, configuration of hunt lists and route lists occurred in a single window. Starting with Release 4.1, configuration of hunt lists and route lists occurs separately.

**Note**

In Release 4.0 of Cisco Unified CallManager, both line groups and route groups represent possible members of route/hunt lists. In Release 4.1 of Cisco Unified CallManager, if an existing route/hunt list has a line group as a member, Cisco Unified CallManager migrates the route/hunt list to a hunt list.

**Note**

TOD settings comes into effect when the lines are included in a Hunt List. The settings only apply to the Hunt Pilot and not to the lines within that Hunt List.

Hunt Pilots

Hunt pilots are sets of digits. They comprise lists of route patterns that are used for hunting. A hunt pilot can specify a partition, numbering plan, route filter, and hunt forward settings. A hunt pilot must specify a hunt list.

For information on configuring hunt pilots, refer to the [“Hunt Pilot Configuration”](#) section in the *Cisco Unified CallManager Administration Guide*.

**Note**

Prior to Release 4.1 of Cisco Unified CallManager, configuration of hunt pilots and route patterns occurred in a single window. Starting with Release 4.1, configuration of hunt pilots and route patterns occurs separately.

**Note**

In Release 4.0 of Cisco Unified CallManager, both route lists and hunt lists associated with route patterns/hunt pilots. In Release 4.1 of Cisco Unified CallManager, if an existing route pattern/hunt pilot associates with a hunt list, Cisco Unified CallManager migrates the route pattern/hunt pilot to a hunt pilot.

**Note**

TOD settings comes into effect when the lines are included in a Hunt List. The settings only apply to the Hunt Pilot and not to the lines within that Hunt List.

Call Coverage

The Call Coverage feature, implemented first in Release 4.1 of Cisco Unified CallManager, comprises the following Cisco Unified CallManager capabilities:

- Forwarding provides separate configuration based on whether the call originator is an internal user or an external user. Refer to the [“Internal and External Calls” section on page 17-12](#).
- Hunting supports personal forwarding. Refer to the [“Personal Preferences” section on page 17-12](#).
- In Cisco Unified CallManager 4.0, route patterns and hunt pilots are in one feature. In Cisco Unified CallManager 4.1 and subsequent releases, they are separated in two different features.

Hunting and Call Forwarding

The concept of hunting differs from that of call forwarding. Hunting allows Cisco Unified CallManager to extend a call to one or more lists of numbers, where each such list can specify a hunting order that is chosen from a fixed set of algorithms. When a call extends to a hunt party from these lists and the party fails to answer or is busy, hunting resumes with the next hunt party. (The next hunt party varies depending on the current hunt algorithm.) Hunting thus ignores the Call Forward No Answer (CFNA), Call Forward Busy (CFB), or Call Forward All (CFA) settings for the attempted party.

Call forwarding allows detailed control as to how to extend (*divert* and *redirect* represent equivalent terms for *extend*) a call when a called party fails to answer or is busy and hunting is not taking place. For example, if the CFNA setting for a line is set to a hunt-pilot number, a call to that line that is not answered diverts to the hunt-pilot number and thus begins hunting.

Starting with Release 4.1 of Cisco Unified CallManager, Cisco Unified CallManager offers the ability to redirect a call when hunting fails (that is, when hunting terminates without any hunt party answering, due either to exhausting the list of hunt numbers or to timing out). If used, this final redirection comprises a Call Forwarding action. Therefore, the Hunt Pilot Configuration window includes Call Forwarding configuration concepts that are similar to those found on the Directory Number Configuration window.

Example of Call Hunting

Although hunting differs from forwarding, hunting often originates as a call that gets forwarded to a hunt-pilot number. The call coverage feature extends hunting to allow final forwarding after hunting either exhausts or times out.

A typical call that invokes hunting can include the following phases:

1. A call extends to the original called party.
2. The call forwards to hunting (for example, due to the Call Forward All [CFA], CFNA, or CFB setting for the original called line).
3. The call hunts through provisioned hunt groups according to provisioned algorithms for each group. Hunting either succeeds (if a hunt party answers), exhausts (if all hunt parties are attempted, but none answer), or times out (if the time specified in the Maximum Hunt Timer runs out before all

parties are attempted, and none of the parties that were attempted answer).

For the purpose of this example, we assume that hunting does not succeed.

4. If some form of final forwarding is configured, the call forwards to a next destination; otherwise, the call gets released.

Maximum Hunt Timer

The Maximum Hunt Timer field on the Hunt Pilot Configuration window allows the administrator to enter a value (in seconds) to limit the time for hunting through a hunt list. After the specified time lapses, if hunting has not succeeded, the call gets forwarded to a voice-messaging system, a specific dialed number, or some personal treatment (if configured), or the call gets released.

For more details about the Maximum Hunt Timer, refer to the field description in the [“Hunt Pilot Configuration”](#) section of the *Cisco Unified CallManager Administration Guide*.

Internal and External Calls

Forwarding provides separate configuration based on whether the originator of a call is an internal user or an external user. This distinction applies to Call Forward Busy (CFB), Call Forward No Answer (CFNA), and Call Forward No Coverage (CFNC) cases.

Personal Preferences

Hunting supports the capability to provide a final forwarding treatment to voice-messaging system, a specific dialed number, or some personal treatment (based on the original called party) when hunting either exhausts or times out. The capability to provide separate final forwarding treatment based on whether the call was internal or external also exists. Hunting supports a separate, configurable maximum hunt timer for each hunt-pilot number.

In the Hunt Pilot configuration settings, Use Personal Preferences Destination fields are available to enable the Call Forward No Coverage (CFNC) settings for the original called number that forwarded the call to the hunt pilot. Refer to the [“Hunt Pilot Configuration Settings”](#) section in the *Cisco Unified CallManager Administration Guide*.

Closest Match Routing

Closest match routing process routes a call by using the route pattern that most closely matches the dialed number. When the Cisco Unified CallManager encounters a dialed number that matches multiple route patterns, it uses closest match routing to determine which route pattern most closely matches the number and directs the call by using that route pattern.

When two configured route patterns exactly match the same number of addresses in different partitions, Cisco Unified CallManager chooses the route pattern on the basis of the order in which the partitions are listed in the calling search space. (Cisco Unified CallManager chooses the route pattern from the partition that appears first in the calling search space.)

If two configured route patterns exactly match the same number of addresses in a partition, the Cisco Unified CallManager arbitrarily chooses one. The following paragraphs explain why such exact matches signify an unusual occurrence.

Several route patterns can match a single number. For instance, the number 8912 matches all the following route patterns: 8912, 89XX, and 8XXX.

In this example, the route pattern 8912 matches exactly one address. The route pattern 89XX matches 8912 plus 99 other addresses, and the route pattern 8XXX matches 8912 plus 999 other addresses.

If the user dials 8913, the call routes differently. Using the preceding example, this address matches only the routing patterns 89XX and 8XXX. Because 89XX matches a narrower range of addresses than 8XXX, the Cisco Unified CallManager delivers the call to the device that is assigned the routing pattern 89XX.

Using the @ Wildcard Character in Route Patterns

Using the @ wildcard character in a route pattern provides a single route pattern to match all NANP numbers, and requires additional consideration.

The number 92578912 matches both of the following route patterns: 9.@ and 9.XXXXXXX. Even though both these route patterns seem to equally match the address, the 9.@ route pattern actually provides the closest match. The @ wildcard character encompasses many different route patterns, and one of those route patterns is [2-9][02-9]XXXXX. Because the number 2578912 more closely matches [2-9][02-9]XXXXX than it does XXXXXXX, the 9.@ route pattern provides the closest match for routing.

When configuring route patterns, take the following considerations into account:

- When @ is used in a routing pattern, the system recognizes octothorpe (#) automatically as an end-of-dialing character for international calls. For routing patterns that do not use @, you must include the # in the routing pattern to be able to use the # character to signal the end of dialing.
- If the route pattern contains an at symbol (@), the Discard Digits field can specify any discard digits instructions (DDIs).

The “[Special Characters and Settings](#)” section on page 17-16 lists DDIs and describes the effects of applying each DDI to a dialed number.

Discard Digits Instructions

A discard digits instruction (DDI) removes a portion of the dialed digit string before passing the number on to the adjacent system. Portions of the digit string must be removed, for example, when an external access code is needed to route the call to the PSTN, but the PSTN switch does not expect that access code.

**Note**

With non-@ patterns, you can use only Discard Digits instructions <None>, NoDigits, and PreDot.

Static Digit Analysis

Prior to Release 4.0 of Cisco Unified CallManager, unregistered devices without configured forwarding got removed from the digit analysis (DA) table and required dynamic digit analysis. Prior to Release 4.0, when a phone unregistered, call processing allowed a call to pass to the next closest match in the Calling Search Space (CSS) list. With the introduction of static DA in Release 4.0, whether a phone is registered or not, the device remains in the DA table, and the directory number intercepts the call.

Configuration Tip

- Administrators should note that Cisco Unified CallManager Assistant does not use translation patterns for failover. Instead, administrators must set up Call Forward No Answer (CFNA) with the data that was in the translation pattern for all Unified CM Assistant failed route points, and these route points must be removed.

Beginning with Release 4.0 of Cisco Unified CallManager, the digit analysis process builds a static digit analysis engine with the patterns that are configured in the database during system initialization. This digit analysis engine reduces the propagation of patterns within a cluster of Cisco Unified CallManagers and makes Cisco Unified CallManager more scalable.

In previous releases, the individual device control process read pattern information from the database and dynamically registered the patterns to the digit analysis process to build its digit analysis engine. Each pattern had a mapping to its control process ID in the digit analysis engine. The control process ID of a pattern got changed dynamically if its associated device was reset or if a Cisco Unified CallManager server restarted. If a change to the control process ID took place, the digit analysis engine had to be changed dynamically, and its contents required propagation to other Cisco Unified CallManager servers. During call processing, the digit analysis engine returned the control process ID of a matched pattern.

Beginning with Release 4.0 of Cisco Unified CallManager, the digit analysis process reads the pattern information directly from the database to build the static digit analysis engine during Cisco Unified CallManager initialization. With the static digit analysis engine, each pattern has a mapping to its callable endpoint name, which is a NumPlanPkID of the pattern in the database, a unique identifier to a configured pattern in Cisco Unified CallManager. The static digit analysis engine no longer holds the control process ID of a pattern.

Static digit analysis integrates with the changes to the device manager to support all existing functions and features. The device manager includes a table where a NumPlanPkID shows a one-to-one mapping to the control process ID of a pattern. When processing a call, digit analysis asks the device manager to get the control process ID for a matched pattern.

Feature Description

Cisco Unified CallManager includes these pattern types: Call Park, Call Forward, Meet-Me Conference, Device, Translation, Call Pickup Group, Route, and Message Waiting. The Device, Translation, and Route pattern types represent static patterns. The digit analysis process reads these patterns directly and inserts them into the static digit analysis engine during the initialization of a Cisco Unified CallManager. Other pattern types (Call Park, Call Forward, Meet-Me Conference, Call Pickup Group, and Message Waiting), which are intercept patterns, remain dynamic patterns. Their individual control process reads the pattern information from the database and then asks the digit analysis process to insert the pattern into the static digit analysis engine via registration messages.

All static patterns remain unchanged until their records are changed in the database. Static patterns do not require propagation because the database change notification is broadcast to the servers within a cluster. Dynamic patterns still use the existing propagating and updating mechanism to update the static digit analysis engines.

Regardless of its pattern type, each static pattern in the static digit analysis engine has a mapping to its PkID in the NumPlan table in the database. When a device registers its patterns to the device manager, the same PkID gets saved and mapped to its control process ID in the device manager. A new interface between the digit analysis and device manager retrieves the control process ID when a matched pattern is found in the static digit analysis engine during call processing.

Caveat 1

A potential loss of change notification exists in the current Cisco Unified CallManager release. This loss could cause a device that is registered with Cisco Unified CallManager to become unreachable by other devices. The following paragraphs provide troubleshooting for this potential problem.

The most common cause for this problem occurs when the DN that is assigned to the device belongs to a partition that is not contained in the calling search space of other devices. If the calling search space of other devices does contain the partition for that DN, other reasons may apply. For example, the DN changed only for that device, and the change notification from the database to Cisco Unified CallManager was lost. Beginning with Release 4.0 of Cisco Unified CallManager, resetting the device may not resolve the problem.

To resolve this problem, remove the DN and add the DN to the system again. Remove the DN from its device on the Directory Number Configuration window and on the Route Plan Report window. After you remove the DN, add it back in with the same partition, pattern, and other configuration information. The process should resolve the problem after you add the new DN to Cisco Unified CallManager again.

The same workaround applies to route patterns and translation patterns if similar problems exist.



Tip

Be sure to document all configurations before removing the patterns.

Caveat 2

Static digit analysis disables the configuration of several applications. These applications rely on the provision of duplicate patterns in the same calling search space. For example, the CTI application may be pattern 5000 in partition A, and a particular phone may be pattern 5000 in partition B. In previous releases, if the CTI route point is down, the phone will ring. With static digit analysis, however, the caller receives a busy tone. This limitation implies that the application failure does not get handled.

Administrators would normally use Call Forward No Answer and Call Forward on failure to handle application failure, but when the pattern on the CTI route point is 5XXX, you cannot configure a forward destination of 5XXX. To resolve this limitation, you can now perform configuration of X characters in Call Forward destinations.

The following example demonstrates the functionality of digit analysis prior to Release 4.0 (with dynamic digit analysis) and in Release 4.0 and subsequent releases (with static digit analysis) for the Cisco Unified CallManager Assistant application.

IPMA Example with Digit Analysis Prior to Release 4.0

Given the following configuration

```
Partitions: IPMA, Managers, Everyone
CSS-I-E: IPMA:Everyone
CSS-M-E: Managers:Everyone
Line-1/CSS-I-E: Everyone/1000
Line-2/CSS-M-E: Manager/1001
CTI RP: IPMA/1XXX
Translation Pattern/CSS-M-E: Everyone/1XXX
```

If the CTI route point (RP) is up, 1000/IPMA:Everyone calls 1001. The call routes by using the CTI route point *IPMA/1XXX*.

If the CTI route point is down, 1000/IPMA:Everyone calls 1001. The call goes through the translation pattern *Everyone/1xxx*, and the call reaches Manager/1001 after the translation and achieves the goal of the IPMA application.

Cisco Unified CallManager Assistant Example with Static Digit Analysis in Release 4.0 and Subsequent Releases

Given an identical configuration, in Release 4.0 and in subsequent releases, you must make the following modification: configure *1xxx* as a CFNA mask and CSS-E as a CFNA calling search space for the CTI route point to handle the CTI route point failure case.

When static digit analysis gets used, the following processing takes place:

- If the CTI route point (RP) is up, 1000/IPMA:Everyone calls 1001. The call routes through CTI route point *IPMA/IXXX*. (Routing does not change from previous releases.)
- If the CTI route point is down, 1000/IPMA:Everyone calls 1001. The call goes to the CTI route point, and its CFNA is triggered. The forwarding feature routes the call through the translation pattern *Everyone/IXxx*, and the call reaches Manager/1001 after translation.

Without configuring the CFNA in the CTI route point, the translation pattern never gets matched, and the Cisco Unified CallManager Assistant application fails.

Special Characters and Settings

Cisco Unified CallManager Administration allows you to use special characters and settings to perform the following tasks:

- Allowing a single route pattern or hunt pilot to match a range of numbers
- Removing a portion of the dialed digit string
- Manipulating the appearance of the calling party number for outgoing calls
- Manipulating the dialed digits, or called party number, for outgoing calls

For more information on how to use special characters and settings, see the following topics:

- [Wildcards and Special Characters in Route Patterns and Hunt Pilots, page 17-16](#)
- [Discard Digits Instructions, page 17-19](#)

Wildcards and Special Characters in Route Patterns and Hunt Pilots

Wildcards and special characters in route patterns and hunt pilots allow a single route pattern or hunt pilot to match a range of numbers (addresses). Use these wildcards and special characters also to build instructions that enable the Cisco Unified CallManager to manipulate a number before sending it to an adjacent system.

[Table 17-3](#) describes the wildcards and special characters that Cisco Unified CallManager supports.

Table 17-3 Wildcards and Special Characters

[illegible]

Table 17-3 Wildcards and Special Characters (continued)

Character	Description	Examples
.	<p>The dot (.) character, used as a delimiter, separates the Cisco Unified CallManager access code from the directory number.</p> <p>Use this special character, with the discard digits instructions, to strip off the Cisco Unified CallManager access code before sending the number to an adjacent system.</p> <p>Each route pattern can have only one dot (.) character.</p>	The route pattern 9.@ identifies the initial 9 as the Cisco Unified CallManager access code in an NANP call.
*	The asterisk (*) character can provide an extra digit for special dialed numbers.	You can configure the route pattern *411 to provide access to the internal operator for directory assistance.
#	<p>The octothorpe (#) character generally identifies the end of the dialing sequence.</p> <p>Ensure the # character is the last character in the pattern.</p>	The route pattern 901181910555# routes or blocks an international number that is dialed from within the NANP. The # character after the last 5 identifies this digit as the last digit in the sequence.

Table 17-4 lists Cisco Unified CallManager Administration fields that require route patterns or hunt pilots and shows the valid entries for each field.

Table 17-4 Field Entries

Field	Valid entries
Call Park Number/Range	[^ 0 1 2 3 4 5 6 7 8 9 -] X * #
Calling Party Transform Mask	0 1 2 3 4 5 6 7 8 9 X A B C D * #
Called Party Transform Mask	0 1 2 3 4 5 6 7 8 9 X A B C D * #
Caller ID DN (Gateways)	0 1 2 3 4 5 6 7 8 9 X * #
Directory Number	[^ 0 1 2 3 4 5 6 7 8 9 -] + ? ! X * # +
Directory Number (Call Pickup Group)	0 1 2 3 4 5 6 7 8 9
External Phone Number Mask	0 1 2 3 4 5 6 7 8 9 X * #
Forward All	0 1 2 3 4 5 6 7 8 9 * #
Forward Busy	0 1 2 3 4 5 6 7 8 9 * #
Forward No Answer	0 1 2 3 4 5 6 7 8 9 * #
Meet-Me Conference Number	[^ 0 1 2 3 4 5 6 7 8 9 -] X * #
Prefix Digits	0 1 2 3 4 5 6 7 8 9 A B C D * #
Prefix DN (Gateways)	0 1 2 3 4 5 6 7 8 9 * #
Route Filter Tag Values	[^ 0 1 2 3 4 5 6 7 8 9 -] X * #
Route Pattern	[^ 0 1 2 3 4 5 6 7 8 9 A B C D -] + ? ! X * # + . @

Table 17-4 *Field Entries (continued)*

Field	Valid entries
Translation Pattern	[^ 0 1 2 3 4 5 6 7 8 9 A B C D -] + ? ! X * # + . @
Hunt Pilot	[^ 0 1 2 3 4 5 6 7 8 9 A B C D -] + ? ! X * # + . @

Discard Digits Instructions

A discard digits instruction (DDI) removes a portion of the dialed digit string before passing the number on to the adjacent system. A DDI must remove portions of the digit string, for example, when an external access code is needed to route the call to the PSTN, but the PSTN switch does not expect that access code.

[Table 17-5](#) lists DDIs and describes the effects of applying each DDI to a dialed number.

Table 17-5 *Discard Digits Instructions*

DDI	Effect	Example
10-10-Dialing	This DDI removes <ul style="list-style-type: none"> IXC access code 	Route pattern: 9.@ Dialed digit string: 910102889728135000 After applying DDI: 99728135000
10-10-Dialing Trailing-#	This DDI removes <ul style="list-style-type: none"> IXC access code End-of-dialing character for international calls 	Route pattern: 9.@ Dialed digit string: 9101028801181910555# After applying DDI: 901181910555
11/10D->7D	This DDI removes <ul style="list-style-type: none"> Long-distance direct-dialing code Long-distance operator-assisted dialing code IXC access code Area code Local area code <p>This DDI creates a 7-digit local number from an 11- or 10-digit dialed number.</p>	Route pattern: 9.@ Dialed digit string: 919728135000 or 99728135000 After applying DDI: 98135000

Table 17-5 *Discard Digits Instructions (continued)*

DDI	Effect	Example
11/10D->7D Trailing-#	This DDI removes <ul style="list-style-type: none"> • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code • Area code • Local area code • End-of-dialing character for international calls This DDI creates a 7-digit local number from an 11- or 10-digit dialed number.	Route pattern: 9.@ Dialed digit string: 919728135000 or 99728135000 After applying DDI: 98135000
11D->10D	This DDI removes <ul style="list-style-type: none"> • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code 	Route pattern: 9.@ Dialed digit string: 919728135000 After applying DDI: 99728135000
11D->10D Trailing-#	This DDI removes <ul style="list-style-type: none"> • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • End-of-dialing character for international calls • IXC access code 	Route pattern: 9.@ Dialed digit string: 919728135000 After applying DDI: 99728135000
Intl TollBypass	This DDI removes <ul style="list-style-type: none"> • International access code • International direct-dialing code • Country code • IXC access code • International operator-assisted dialing code 	Route pattern: 9.@ Dialed digit string: 901181910555 After applying DDI: 9910555
Intl TollBypass Trailing-#	This DDI removes <ul style="list-style-type: none"> • International access code • International direct-dialing code • Country code • IXC access code • International operator-assisted dialing code • End-of-dialing character 	Route pattern: 9.@ Dialed digit string: 901181910555# After applying DDI: 9910555

Table 17-5 *Discard Digits Instructions (continued)*

DDI	Effect	Example
NoDigits	This DDI removes no digits.	Route pattern: 9.@ Dialed digit string: 919728135000 After applying DDI: 919728135000
Trailing-#	This DDI removes <ul style="list-style-type: none"> End-of-dialing character for international calls 	Route pattern: 9.@ Dialed digit string: 901181910555# After applying DDI: 901181910555
PreAt	This DDI removes all digits prior to the NANP portion of the route pattern, including <ul style="list-style-type: none"> Cisco Unified CallManager external access code PBX external access code 	Route pattern: 8.9@ Dialed digit string: 899728135000 After applying DDI: 9728135000
PreAt Trailing-#	This DDI removes all digits prior to the NANP portion of the route pattern, including <ul style="list-style-type: none"> Cisco Unified CallManager external access code PBX external access code End-of-dialing character for international calls 	Route pattern: 8.9@ Dialed digit string: 8901181910555# After applying DDI: 01181910555
PreAt 10-10-Dialing	This DDI removes all digits prior to the NANP portion of the route pattern, including <ul style="list-style-type: none"> Cisco Unified CallManager external access code PBX external access code IXC access code 	Route pattern: 8.9@ Dialed digit string: 8910102889728135000 After applying DDI: 9728135000
PreAt 10-10-Dialing Trailing-#	This DDI removes all digits prior to the NANP portion of the route pattern, including <ul style="list-style-type: none"> Cisco Unified CallManager external access code PBX external access code IXC access code End-of-dialing character for international calls 	Route pattern: 8.9@ Dialed digit string: 89101028801181910555# After applying DDI: 01181910555

Table 17-5 Discard Digits Instructions (continued)

DDI	Effect	Example
PreAt 11/10D->7D	<p>This DDI removes all digits prior to the NANP portion of the route pattern, including</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • PBX external access code • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code • Area code • Local area code <p>This DDI creates a 7-digit local number from an 11- or 10-digit dialed number.</p>	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8919728135000 or 899728135000</p> <p>After applying DDI: 8135000</p>
PreAt 11/10D->7D Trailing-#	<p>This DDI removes all digits prior to the NANP portion of the route pattern, including</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • PBX external access code • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code • Area code • Local area code • End-of-dialing character for international calls <p>This DDI creates a 7-digit local number from an 11- or 10-digit dialed number.</p>	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8919728135000 or 899728135000</p> <p>After applying DDI: 8135000</p>
PreAt 11D->10D	<p>This DDI removes all digits prior to the NANP portion of the route pattern, including</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • PBX external access code • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code 	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8919728135000</p> <p>After applying DDI: 9728135000</p>

Table 17-5 Discard Digits Instructions (continued)

DDI	Effect	Example
PreAt 11D->10D Trailing-#	<p>This DDI removes all digits prior to the NANP portion of the route pattern, including</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • PBX external access code • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code • End-of-dialing character for international calls 	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8919728135000</p> <p>After applying DDI: 9728135000</p>
PreAt Intl TollBypass	<p>This DDI removes all digits prior to the NANP portion of the route pattern, including</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • PBX external access code • International access code • International direct-dialing code • Country code • IXC access code • International operator-assisted dialing code 	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8901181910555</p> <p>After applying DDI: 910555</p>
PreAt Intl TollBypass Trailing-#	<p>This DDI removes all digits prior to the NANP portion of the route pattern, including</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • PBX external access code • International access code • International direct-dialing code • Country code • IXC access code • International operator-assisted dialing code • End-of-dialing character 	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8901181910555#</p> <p>After applying DDI: 910555</p>

Table 17-5 *Discard Digits Instructions (continued)*

DDI	Effect	Example
PreDot	This DDI removes <ul style="list-style-type: none"> • Cisco Unified CallManager external access code 	Route pattern: 8.9@ Dialed digit string: 899728135000 After applying DDI: 99728135000
PreDot Trailing-#	This DDI removes <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • End-of-dialing character for international calls 	Route pattern: 8.9@ Dialed digit string: 8901181910555# After applying DDI: 901181910555
PreDot 10-10-Dialing	This DDI removes <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • IXC access code 	Route pattern: 8.9@ Dialed digit string: 8910102889728135000 After applying DDI: 99728135000
PreDot 10-10-Dialing Trailing-#	This DDI removes <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • IXC access code • End-of-dialing character for international calls 	Route pattern: 8.9@ Dialed digit string: 89101028801181910555# After applying DDI: 901181910555
PreDot 11/10D->7D	This DDI removes <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code • Area code • Local area code <p>This DDI creates a 7-digit local number from an 11- or 10-digit dialed number.</p>	Route pattern: 8.9@ Dialed digit string: 8919728135000 or 899728135000 After applying DDI: 98135000

Table 17-5 *Discard Digits Instructions (continued)*

DDI	Effect	Example
PreDot 11/10D->7D Trailing-#	<p>This DDI removes</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code • Area code • Local area code • End-of-dialing character for international calls <p>This DDI creates a 7-digit local number from an 11- or 10-digit dialed number.</p>	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8919728135000 or 899728135000</p> <p>After applying DDI: 98135000</p>
PreDot 11D->10D	<p>This DDI removes</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code 	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8919728135000</p> <p>After applying DDI: 99728135000</p>
PreDot 11D->10D Trailing-#	<p>This DDI removes</p> <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • Long-distance direct-dialing code • Long-distance operator-assisted dialing code • IXC access code • End-of-dialing character for international calls 	<p>Route pattern: 8.9@</p> <p>Dialed digit string: 8919728135000</p> <p>After applying DDI: 99728135000</p>

Table 17-5 *Discard Digits Instructions (continued)*

DDI	Effect	Example
PreDot Intl TollBypass	This DDI removes <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • International access code • International direct-dialing code • Country code • IXC access code • International operator-assisted dialing code 	Route pattern: 8.9@ Dialed digit string: 8901181910555 After applying DDI: 9910555
PreDot Intl TollBypass Trailing-#	This DDI removes <ul style="list-style-type: none"> • Cisco Unified CallManager external access code • International access code • International direct-dialing code • Country code • IXC access code • International operator-assisted dialing code • End-of-dialing character 	Route pattern: 8.9@ Dialed digit string: 8901181910555# After applying DDI: 9910555

Calling and Called Party Transformations

Cisco Unified CallManager Administration allows you to manipulate the calling party number and the called party number that Cisco Unified CallManager sends with each call setup message.

The following topics provide information on these settings:

- [Calling Party Number Transformations Settings, page 17-26](#)
- [Called Party Number Transformations Settings, page 17-28](#)

Calling Party Number Transformations Settings

Calling party transformations settings allow you to manipulate the appearance of the calling party number for outgoing calls. Cisco Unified CallManager uses the calling party number for calling line identification (CLID). During an outgoing call, the CLID passes to each private branch exchange (PBX), central office (CO), and interexchange carrier (IXC) as the call progresses. The called party receives the calling line identification (CLID) when the call is offered to the called party.

Configuration for calling party transformations settings that are used in route lists occurs in the individual route groups that comprise the list. The calling party transformations settings that are assigned to the route groups in a route list override any calling party transformations settings that are assigned to a route pattern that is associated with that route list.

You can set the following calling party transformation settings in the route group configuration:

- Use Calling Party's External Phone Number Mask
- Calling Party Transform Mask
- Prefix Digits (Outgoing Calls)

Table 17-6 describes the fields, options, and values that are used to specify calling party number transformations.

Table 17-6 *Calling Party Number Transformations Settings*

Field Name	Description
Use Calling Party's External Phone Number Mask	<p>This field determines whether the full, external phone number is used for calling line identification (CLID) on outgoing calls. (Configure the external number by using the Directory Number Configuration window.)</p> <p>You can set the following Calling Party Transformations settings for the route group by clicking the members in the Route List Details panel of the Route List Configuration window:</p> <ul style="list-style-type: none"> • Default: This setting indicates that the route group does not govern the calling party external phone number and calling party transform masks. If a calling party external phone number mask or transform mask is chosen for the route pattern, calls that are routed through this route group use those masks. • Off: This setting indicates that the calling party external phone number is not used for CLID. If no transform mask is entered for this route group, calls that are routed through this group do not get associated with a CLID. • On: This setting indicates that the calling party full, external number is used for CLID. <p>The external phone number mask can contain up to 24 digits.</p>
Calling Party Transform Mask	<p>This field specifies the calling party transform mask for all calls that are routed through this route group. Valid values for this field range from 0 through 9, the wildcard character X, and the characters * and #. You can also leave this field blank. If it is blank and the preceding field is set to Off, this means that no calling party number is available for CLID.</p> <p>The calling party transform mask can contain up to 50 digits.</p>
Prefix Digits (Outgoing Calls)	<p>This field contains a prefix digit or a set of Prefix Digits (Outgoing Calls) that are appended to the calling party number on all calls that are routed through this route group. Valid values for this field range from 0 through 9, the characters * and #, and blank. Prefix Digits (Outgoing Calls) can contain up to 50 digits on route patterns or up to 24 digits on DNs.</p>

Called Party Number Transformations Settings

Called party transformations settings allow you to manipulate the dialed digits, or called party number, for outgoing calls. Examples of manipulating called numbers include appending or removing prefix digits (outgoing calls), appending area codes to calls dialed as seven-digit numbers, appending area codes and office codes to interoffice calls dialed as four- or five-digit extensions, and suppressing carrier access codes for equal access calls.

Configuration of called party transformations settings that are used in route lists occurs in the individual route groups that comprise the list. The called party transformations settings that are assigned to the route groups in a route list override any called party transformations settings that are assigned to a route pattern or translation pattern that is associated with that route list.

You can set the following called party transformation settings in the route group, route pattern, and translation pattern configuration:

- Discard Digits
- Called Party Transform Mask
- Prefix Digits (Outgoing Calls)

Table 17-7 describes the fields, options, and values that are used to specify called party number transformations.

Table 17-7 *Called Party Number Transformations Settings*

Field Name	Description
Route Group Configuration	
Discard Digits	<p>This field contains a list of discard patterns that control the discard digit instructions. For example, in a system where users must dial 9 to make a call to the public switched telephone network (PSTN), the PreDot discard pattern causes the 9 to be stripped from the dialed digit string. See the “Closest Match Routing” section on page 17-12 for more information.</p> <p>Note Any setting other than the default setting of <None> overrides the setting in the route pattern. The <None> setting means “do not discard digits.”</p>
Called Party Transform Mask	<p>This field specifies the called party transform mask for all calls that are routed through this route group. Valid values for this field range from 0 through 9, the wildcard character X, and characters * and #. You can also leave this field blank. If this field is blank, no transformation takes place; Cisco Unified CallManager sends the dialed digits exactly as dialed.</p> <p>The called party transform mask can contain up to 50 digits.</p>
Prefix Digits (Outgoing Calls)	<p>This field contains a prefix digit or a set of Prefix Digits (Outgoing Calls) that are appended to the called party number on all calls that are routed through this route group. Valid values for this field range from 0 through 9, the characters * and #, and blank. Prefix Digits (Outgoing Calls) can contain up to 50 digits on route patterns or up to 24 digits on DNs.</p>

Related Topics

- [Special Characters and Settings, page 17-16](#)
- [Closest Match Routing, page 17-12](#)

- [Caller Identification and Restriction, page 17-29](#)
- [Understanding Route Plans, page 17-1](#)

Caller Identification and Restriction

Cisco Unified CallManager provides the following types of caller identification information:

- Calling Line Identification (CLID)—Provides the called party with the calling party's extension or directory number on a display.
- Calling Name Identification—Provides the called party with the calling party's name on a display.
- Connected Line Identification—Provides the calling party with the connected party's phone number on a display.
- Connected Name Identification—Provides the calling party with the connected party's name on a display

Cisco CallManger provides flexible configuration options to allow and to restrict the display of the line and name information for both calling and connected parties.

For more information on how to use caller identification settings, see the following topics:

- [Calling Party Presentation and Restriction Settings, page 17-29](#)
- [Connected Party Presentation and Restriction Settings, page 17-31](#)

Calling Party Presentation and Restriction Settings

Calling party presentation information controls whether to display the phone number and name information that Cisco Unified CallManager sends with setup messages for an outgoing call.

Cisco Unified CallManager uses the following fields to provide these supplementary services:

- Calling Line ID Presentation field—Calling line identification presentation (CLIP) or calling line identification restriction (CLIR)
- Calling Name Presentation field—Calling name presentation (CNIP) or calling name restriction (CNIR)

You can use the Calling Line ID Presentation field in the Gateway Configuration window to control whether the CLID displays for all outgoing calls on the gateway. To control the CLID display on a call-by-call basis, you use the Calling line ID Presentation field in Route Pattern Configuration or Translation Pattern Configuration windows.



Note

Configure Calling Line ID Presentation and Connected Line ID Presentation, in combination with the Ignore Presentation Indicators (internal calls only) device-level parameter, to set up call display restrictions. Together, these settings allow you to selectively present or block calling and/or connected line display information for each call. For more information about the Ignore Presentation Indicators (internal calls only) field, refer to the [Device Profile Configuration](#) chapter and the [Cisco Unified IP Phone Configuration](#) chapter in the *Cisco Unified CallManager Administration Guide*. For more information about call display restrictions, refer to the [Call Display Restrictions](#) chapter in the *Cisco Unified CallManager Features and Services Guide*.

The following example describes how calling line ID presentation works. When a user makes a call, Cisco Unified CallManager checks whether the dialed number matches a translation pattern. Cisco Unified CallManager finds a match and sets the presentation indicator to the value in the translation pattern Calling Line ID Presentation field, which specifies “restricted” in this example. Next, Cisco Unified CallManager checks and finds a match on a route pattern that is configured for the dialed number. Cisco Unified CallManager checks the Calling Line ID Presentation field and finds that the value specifies “default.” The presentation indicator remains as “restricted” because the previous setting is unchanged when default is set.

The gateway Calling Line ID Presentation field gets checked last. In this example, the value specifies “allowed” and overrides the previous calling line ID presentation indicator to allow the calling party number to display on the called party phone. Therefore, the calling line ID presentation field indicator changed from “restricted” at the time that the calling party initiated the call to “allowed” by the time that Cisco Unified CallManager sends the call setup message to the endpoint device.

You can configure line and name presentation or restriction on a call-by-call basis for outgoing calls and incoming calls by using the Route Pattern Configuration or Translation Pattern Configuration pages.

For the gateway, you can only configure calling line ID presentation for outgoing calls. For incoming calls, Cisco Unified CallManager uses the Connected Line ID Presentation field for the gateway to specify whether to allow or restrict the connected party number to display on the calling party phone. Gateway settings only apply in these two situations, and these settings override all other settings. For the gateway, you can only configure calling and connected line presentation. No settings exist to control name presentation on the gateway.

The type of device control protocol that handles the call limits caller name and number information. See [Table 17-10](#) for a list of protocols with the supported caller name and number information.

**Note**

To control the name display for non-QSIG trunks, you must enable the Display IE Delivery field or Send Calling Name in Facility IE field in the Gateway Configuration window.

[Table 17-8](#) describes the fields, options, and values that are used to specify calling party presentations.

Table 17-8 **Calling Party Presentation Settings**

Field Name	Description
Calling Line ID Presentation (outgoing call)	<p>This field determines whether the calling party phone number displays on the called party phone display screen. The Gateway Configuration, the Route Pattern Configuration, and the Translation Pattern Configuration windows use the Calling Line Presentation field.</p> <p>The following list gives the options for this field:</p> <ul style="list-style-type: none"> • Default: If default is set, calling line ID presentation does not get modified. • Allowed: Use this setting to permit the calling party phone number to display in the called party phone display. • Restricted: Use this setting to display “Private” in the called party phone display and block the display of the calling party phone number.

Table 17-8 *Calling Party Presentation Settings (continued)*

Field Name	Description
Calling Name Presentation (outgoing call)	<p>This field determines whether the calling party's name displays on the called party phone display. The Route Pattern Configuration and Translation Pattern Configuration windows use the Calling Name Presentation field.</p> <p>The following list gives the options for this field:</p> <ul style="list-style-type: none"> • Default: If default is set, calling name presentation does not get modified. • Allowed: Use this setting to display the calling party name in the called party phone display. • Restricted: Use this setting in the route patterns or translation patterns configuration displays "Private" in the called party phone display. <p>Note The gateway has no setting for calling name presentation.</p>
Calling Line ID Presentation (incoming call)	<p>If the incoming call goes through a translation pattern or route pattern and the calling line ID presentation setting is allowed or restricted, the calling line presentation gets modified with the translation or route pattern setting. If the call comes into the Cisco Unified CallManager system and then goes out to a PBX or the PSTN, the outgoing call rules apply as stated in the "Calling Party Presentation and Restriction Settings" section on page 17-29.</p> <p>Note The gateway calling line ID presentation setting controls outgoing calls only.</p>
Calling Name Presentation (incoming call)	<p>If the incoming call goes through a translation pattern or route pattern and the calling name presentation setting is allowed or restricted, the calling name presentation gets modified with the translation or route pattern setting. If the call comes into the Cisco Unified CallManager system and then goes out to a PBX or the PSTN, the outgoing call rules apply as stated in the "Calling Party Presentation and Restriction Settings" section on page 17-29.</p> <p>Note The gateway has no settings to control name information.</p>

Connected Party Presentation and Restriction Settings

Connected party presentation information controls whether to display the phone number and name information that Cisco Unified CallManager receives with an incoming call. Cisco Unified CallManager uses the following fields to provide these supplementary services:

- Connected Line ID Presentation field—Connected line identification presentation (COLP) or connected line identification restriction (COLR)
- Connected Name Presentation field—Connected name presentation (CONP) or calling name restriction (CONR)

Connected party settings allow you to display or restrict the display of the phone number and name of the connected party on the calling party's phone. Translation Pattern Configuration and Route Pattern Configuration windows include these two settings. The calling party receives the connected name information after the call connects to Cisco Unified CallManager and the terminating phone.

The following example describes how connected line ID works. When Cisco Unified CallManager receives an incoming call, it checks whether a translation pattern is configured for the incoming number. Cisco Unified CallManager uses the value in the Connected Line ID Presentation field that specifies "restricted" for this example. Next, if a route pattern is configured for the incoming call, the value in the Connected Line ID Presentation field gets checked. In this example, the value specifies "default," so the indicator remains as "restricted," which prevents the connected party number from displaying on the calling party's phone.

For incoming calls only, the gateway Connected Line ID Presentation field value gets checked last and is set for "allowed" in this example. The gateway setting specifies whether the connected party number can display on the calling party phone. In this case, Cisco Unified CallManager sends "allowed" in the CONNECT message, so the connected line can display on the originating caller's phone display.

You can configure connected line and name presentation or restriction on a call-by-call basis for outgoing calls and incoming calls by using the Route Pattern Configuration or Translation Pattern Configuration windows.

For incoming calls on the gateway, you use the Connected Line ID Presentation field to specify whether to allow or restrict the display of the connected party number on the calling party's phone. Gateway settings only apply to line presentation settings and override all other settings.

**Note**

For the gateway, you can only configure calling and connected line presentation options. No settings exist for name presentation on the gateway.

[Table 17-9](#) describes the fields, options, and values that are used to specify connected party presentations.

Table 17-9 Connected Party Presentation Settings

Field Name	Description
Connected Line ID Presentation (outgoing call)	<p>In the Route Pattern Configuration and the Translation Pattern Configuration windows, this field determines whether the connected party number displays on the calling party phone display.</p> <p>The following list gives the options for this field:</p> <ul style="list-style-type: none"> • Default: If default is set, connected line ID presentation does not get modified. • Allowed: Use this setting to display the connected line number that Cisco Unified CallManager received in protocol messages on the calling party phone display. • Restricted: Use this setting to block the connected party number from displaying in the calling party phone display, and "Unknown Number" displays instead. <p>Note This setting applies to internal calls and calls on QSIG connections only.</p>

Table 17-9 **Connected Party Presentation Settings (continued)**

Field Name	Description
Connected Name Presentation (CONP/CONR) (outgoing call)	<p>This field determines whether the connected party name displays on the calling party phone display. The Route Pattern Configuration and Translation Pattern Configuration windows use the Connected Name Presentation field.</p> <p>The following list gives the options for this field:</p> <ul style="list-style-type: none"> • Default: If default is set, calling name presentation does not get modified. • Allowed: Use this setting to display the connected party name that Cisco Unified CallManager received in protocol messages in the calling party phone display. • Restricted: Use this setting to block the connected party name from displaying, and display “Unknown” in the calling party phone display.
Connected Line ID Presentation (incoming call)	<p>If the incoming call goes through a translation or route pattern and the connected line ID presentation field is set to allowed or restricted, the connected line presentation indicator gets modified with the translation or route pattern setting.</p> <p>Note The Connected Line ID Presentation setting on the gateway determines if the connected party number can display on the originating party’s phone.</p> <p>If the call comes into the Cisco Unified CallManager system and then goes out to a PBX or the PSTN, the outgoing call rules apply as stated in the “Connected Party Presentation and Restriction Settings” section on page 17-31.</p>
Connected Name Presentation (incoming call)	<p>If the incoming call goes through a translation or route pattern and the connected name presentation setting is set to allowed or restricted, the connected name presentation gets modified with the translation or route pattern setting. If the call comes into the Cisco Unified CallManager system and then goes out to a PBX or the PSTN, the outgoing call rules apply as stated in the “Connected Party Presentation and Restriction Settings” section on page 17-31.</p> <p>Note The gateway has no settings to control name information.</p>

Caller Identification Support with Device Control Protocols in Cisco Unified CallManager

Cisco Unified CallManager provides support for caller name and number identification presentation based on the device control protocols that handle the call. Not all device protocols provide caller number and name information in the protocol messages. [Table 17-10](#) summarizes which protocols support caller identification services.

Table 17-10 *Caller Identification Information Supported by Device Control Protocols*

Device Control Protocol	Calling Line	Calling Name	Connected Line	Connected Name
IP Phones with SCCP	provides line number	provides name associated with DN	displays number when received	displays name when received
MGCP Stations (FXS)	provides line number	provides name associated with DN	not supported	displays name when received
MGCP Trunk (FXO, T1 CAS)	not supported	not supported	not supported	not supported
H.323 Trunk	calling line sent in H.225 SETUP	supported by using DISPLAY IE in H.225 messages for intercluster trunks only	supported by H.225 NOTIFY for intercluster trunks only	supported by DISPLAY IE in H.225 messages for intercluster trunks only
PRI Trunk	calling line in PRI SETUP	supported by using FACILITY IE in PRI messages	not supported	supported by using FACILITY IE in PRI messages
QSIG Trunk	calling line in QSIG SETUP	supported by using FACILITY IE in QSIG messages	supported by QSIG CONNECT	supported by using FACILITY IE in QSIG messages
SIP Trunk	calling line included in From and Remote-Party-ID headers	calling name included in From and Remote-Party-ID headers	connected line included in Remote-Party-ID header	connected name included in Remote-Party-ID header

Related Topics

- [Calling and Called Party Transformations, page 17-26](#)
- [Special Characters and Settings, page 17-16](#)
- [Enhanced Call Identification Services, page 41-9](#)

External Route Plan Wizard

The external route plan wizard generates a single-tenant, multilocation, partitioned route plan for the North American Numbering Plan (NANP) area by using information that the administrator provides through a series of prompts.

The route plan that the external route plan wizard generates includes the following elements:

- Route filters
- Route groups
- Route lists
- Route patterns
- Partitions
- Calling search spaces
- Calling party and calling party transformations
- Access code manipulation

The following topics describe the basic concepts that are used when you generate route plans with the external route plan wizard:

- [Generated Route Filters, page 17-35](#)
- [Generated Route Groups, page 17-36](#)
- [Generated Route Lists, page 17-36](#)
- [Generated Route Patterns, page 17-37](#)

Generated Route Filters

A generated route filter permits or restricts access through a route list by using route patterns. The external route plan wizard associates each route list with a particular route filter. It names route filters by using the TenantLocationCalltype convention and appends the suffix RF to each route filter for easy identification.

[Table 17-11](#) shows the seven types of route lists that use route filters. The table shows examples that use specific route filter names and actual access and area codes for better readability.

Table 17-11 **Route Lists and Associated Route Filters**

Route List Type	Route Filter Name and Content Examples
911 calls	Name: CiscoDallas911RF Content: 9.@ where (SERVICE == 911)
Local calls with metro (7- and 10-digit) dialing	Name: CiscoDallasLocalRF Content: 9.@ where (INTERNATIONAL-ACCESS DOES-NOT-EXIST) AND (LOCAL-AREA-CODE DOES-NOT-EXIST) AND (AREA-CODE DOES-NOT-EXIST) AND (SERVICE DOES-NOT-EXIST) OR (LOCAL-AREA-CODE == 972) OR (LOCAL-AREA-CODE == 214)
Local calls with 10-digit dialing	Name: CiscoDallasLocal10DCallRF Content: 9.@ where (LOCAL-AREA-CODE == 972) OR (LOCAL-AREA-CODE == 214)
Local calls with 7-digit dialing	Name: CiscoDallasLocal7DCallRF Content: 9.@ where (INTERNATIONAL-ACCESS DOES-NOT-EXIST) AND (AREA-CODE DOES-NOT-EXIST) AND (SERVICE DOES-NOT-EXIST)
Toll bypass calls	Name: CiscoTollByPassToDallasRF Content: 9.@ where (AREA-CODE == 972) OR (AREA-CODE == 214)
Long-distance calls	Name: CiscoDallasLongDistanceRF Content: 9.@ where (AREA-CODE EXISTS)
International calls	Name: CiscoDallasIntlRF Content: 9.@ where (INTERNATIONAL-ACCESS EXISTS)

Generated Route Groups

A generated route group sets the order of preference for gateway and port usage. The external route plan wizard assigns one gateway to each generated route group. The wizard uses all ports on the gateways. It does not support using partial resources for generated external route plans.

The external route plan wizard names route filters by using the TenantLocationGatewayTypeNumber convention for easy identification. The following list shows the gateway type abbreviations:

- AA: analog access
- DA: digital access
- HT: H.323 trunk
- MS: MGCP station
- MT: MGCP trunk

The external route plan wizard identifies route groups that are associated with multiple gateways of the same type by attaching a number suffix to all route groups. For example, if three MGCP trunk gateways exist at the Cisco Dallas location, the external route plan wizard names the associated route groups CiscoDallasMT1, CiscoDallasMT2, and CiscoDallasMT3.

If a route list includes more than one route group and more than one gateway (with one gateway for each route group), an arbitrary order designates how the external route plan wizard lists the route groups. The only order that is imposed ensures that route groups that are associated with the local gateways are listed before the route groups that are associated with remote gateways. If needed, manually change the order after the route plan is generated.

**Note**

Cisco Unified CallManager treats all gateways that belong to a location as shared resources for that location.

Generated Route Lists

A generated route list sets the order of preference for route group usage and defines the route filters that are applied to those route groups. The external route plan wizard creates between five and seven route lists for each location depending on the types of local dialing choices that are available. Therefore, the total number of route lists depends on the local dialing scheme and the number of locations that the route plan serves.

Using the TenantLocationCalltype convention, the external route plan wizard names route lists and appends the suffix RL to each route list for easy identification.

[Table 17-12](#) shows the various types of route lists. The examples shown in this table use specific route list names for better readability.

Table 17-12 *Route List Types*

Route List Type	Example Route List Name and Usage
911 calls	Name: CiscoDallas911RL Use: This route list type applies for 911 emergency calls.
Enterprise calls	Name: CiscoDallasEnterpriseRL Use: This route list type applies for route plans that include Cisco Unified CallManager to adjacent PBX calls. If the route plan does not include routing to an adjacent PBX, the wizard does not generate this route list type.
Local calls with metro dialing	Name: CiscoDallasLocalRL Use: This route list type applies for route plans that encompass both 7- and 10-digit dialing areas. This route list type generates two route lists: one for 7-digit dialing and another for 10-digit dialing. If you chose to generate a route plan that uses metro route lists, you cannot also choose 7- or 10-digit dialing route lists.
Local calls with 10-digit dialing	Name: CiscoDallasLocal10DCallRL Use: This route list type applies for route plans that use 10-digit dialing. This route list type generates one route list for 10-digit dialing. If you chose to generate a route plan that uses a 10-digit dialing route list, you cannot also choose 7-digit or metro dialing route lists.
Local calls with 7-digit dialing	Name: CiscoDallasLocal7DCallRL Use: This route list type applies for route plans that use 7-digit dialing. This route list type generates one route list for 7-digit dialing. If you chose to generate a route plan that uses a 7-digit dialing route list, you cannot also choose 10-digit or metro dialing route lists.
Toll bypass calls	Name: CiscoTollByPassToDallasRL Use: This route list type applies for intracluster calls that originate from a remote location and that get routed out the local gateway as local calls.
Long-distance calls	Name: CiscoDallasLongDistanceRL Use: This route list type applies for long-distance toll calls.
International calls	Name: CiscoDallasIntlRL Use: This route list type applies for international toll calls.

Generated Route Patterns

A generated route pattern directs calls to specific devices and either includes or excludes specific dialed-digit strings. The external route plan wizard only generates route patterns that require an access code prefix. The typical route pattern for routing a call to the PSTN includes the prefix construction 9.@. The typical route pattern for routing a call to the PBX includes the prefix construction 9.9@.

The external route plan wizard associates a route list, a route filter, and a partition with each route pattern. The route pattern provides the appropriate calling party transform mask, called party transform mask, discard digits instructions, and prefix digits for the associated route list.

The wizard bases route patterns for calls to an adjacent PBX on the access code and the range of directory numbers that are served by that PBX. For example, if the access code that is used to direct calls to the adjacent PBX is 9 and the range of directory numbers that is served by that PBX is 1000 through 1999, the external route plan wizard generates the route pattern 9.1XXX for enterprise calls.

Route Plan Report

The route plan report comprises a listing of all unassigned directory numbers (DN), call park numbers, call pickup numbers, conference numbers (Meet-Me numbers), directory numbers, route patterns, translation patterns, voice-mail ports, message-waiting indicators, and attendant console numbers in the system.

The route plan report allows you to view either a partial or full list and to go directly to the associated configuration windows by choosing a route pattern, partition, route group, route list, directory number, call park number, call pickup number, conference number (Meet-Me number), or gateway.

Using the route plan report, you can get a list of unassigned directory numbers and delete those numbers from the Cisco Unified CallManager database, if required.

In addition, the route plan report allows you to save report data into a .csv file that you can import into other applications such as the Bulk Administration Tool (BAT). The .csv file contains more detailed information, including directory numbers (DN) for phones, route patterns, and translation patterns. Refer to the [“Route Plan Report”](#) section in the *Cisco Unified CallManager Administration Guide* for more information.

Where to Find More Information

Related Topic

- [Partitions and Calling Search Spaces, page 15-1](#)

Related Cisco Documentation

- [Partition Configuration](#), *Cisco Unified CallManager Administration Guide*
- [Calling Search Space Configuration](#), *Cisco Unified CallManager Administration Guide*
- [Route Group Configuration](#), *Cisco Unified CallManager Administration Guide*
- [Route List Configuration](#), *Cisco Unified CallManager Administration Guide*
- [Route Pattern Configuration](#), *Cisco Unified CallManager Administration Guide*
- [Line Group Configuration](#), *Cisco Unified CallManager Administration Guide*
- [Hunt List Configuration](#), *Cisco Unified CallManager Administration Guide*
- [Hunt Pilot Configuration](#), *Cisco Unified CallManager Administration Guide*
- [Presence](#), *Cisco Unified CallManager Features and Services Guide*
- *Cisco Unified Communications Solution Reference Network Design (SRND)*