



## **Cisco IOS Multitopology Routing Command Reference**

### **Americas Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
<http://www.cisco.com>  
Tel: 408 526-4000  
800 553-NETS (6387)  
Fax: 408 527-0883

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: <http://www.cisco.com/go/trademarks>. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

© 2013 Cisco Systems, Inc. All rights reserved.



## CONTENTS

---

### CHAPTER 1

#### A through R 1

address-family ipv4 (BGP)	3
address-family ipv4 (EIGRP MTR)	7
address-family ipv4 (IS-IS)	9
address-family ipv4 (OSPF)	10
all-interfaces	12
area capability default-exclusion	14
bgp tid	16
clear ip bgp topology	18
clear ip eigrp topology	22
clear ip interface	24
clear ip route multicast	25
clear ip route topology	27
clear ip traffic (MTR)	29
debug topology	30
eigrp delay	32
eigrp next-hop-self	34
eigrp shutdown	36
eigrp split-horizon	38
eigrp summary-address	39
exit-global-af	41
exit-if-topology	42
exit-topo	43
forward-base	45
global-address-family ipv4	47
import topology	49
ip multicast rpf multitopology	51
ip ospf cost (MTR)	52

[ip ospf topology disable](#) 53  
[ip route topology](#) 54  
[ip topology-accounting](#) 56  
[isis topology disable](#) 57  
[maximum routes \(MTR\)](#) 59  
[neighbor translate-topology](#) 61  
[neighbor transport](#) 63  
[ping \(MTR\)](#) 67  
[policy-map type class-routing ipv4 unicast](#) 70  
[priority \(OSPF\)](#) 72  
[router eigrp \(MTR\)](#) 74  
[route-replicate](#) 75

---

## CHAPTER 2

### **S through U** 79

[scope](#) 81  
[select-topology](#) 83  
[service-policy type class-routing](#) 84  
[show ip bgp topology](#) 86  
[show ip eigrp topology](#) 94  
[show ip interface \(MTR\)](#) 101  
[show ip ospf interface](#) 103  
[show ip ospf topology-info](#) 107  
[show ip protocols topology](#) 109  
[show ip route multicast](#) 112  
[show ip route topology](#) 114  
[show ip static route](#) 117  
[show ip static route bfd](#) 119  
[show ip static route summary](#) 121  
[show ip traffic \(MTR\)](#) 122  
[show isis neighbors](#) 124  
[show mtm table](#) 127  
[show policy-map type class-routing ipv4 unicast](#) 129  
[show snmp context mapping](#) 131  
[show topology](#) 133  
[shutdown \(MTR\)](#) 137

snmp context	139
topology (BGP)	142
topology (EIGRP)	144
topology (global)	146
topology (interface)	148
topology (IS-IS)	150
topology (OSPF)	152
topology-accounting	154
traceroute	156
use-topology	160





## A through R

---

- [address-family ipv4 \(BGP\), page 3](#)
- [address-family ipv4 \(EIGRP MTR\), page 7](#)
- [address-family ipv4 \(IS-IS\), page 9](#)
- [address-family ipv4 \(OSPF\), page 10](#)
- [all-interfaces, page 12](#)
- [area capability default-exclusion, page 14](#)
- [bgp tid, page 16](#)
- [clear ip bgp topology, page 18](#)
- [clear ip eigrp topology, page 22](#)
- [clear ip interface, page 24](#)
- [clear ip route multicast, page 25](#)
- [clear ip route topology, page 27](#)
- [clear ip traffic \(MTR\), page 29](#)
- [debug topology, page 30](#)
- [eigrp delay, page 32](#)
- [eigrp next-hop-self, page 34](#)
- [eigrp shutdown, page 36](#)
- [eigrp split-horizon, page 38](#)
- [eigrp summary-address, page 39](#)
- [exit-global-af, page 41](#)
- [exit-if-topology, page 42](#)
- [exit-topo, page 43](#)
- [forward-base, page 45](#)
- [global-address-family ipv4, page 47](#)

- [import topology](#), page 49
- [ip multicast rpf multitopology](#), page 51
- [ip ospf cost \(MTR\)](#), page 52
- [ip ospf topology disable](#), page 53
- [ip route topology](#), page 54
- [ip topology-accounting](#), page 56
- [isis topology disable](#), page 57
- [maximum routes \(MTR\)](#), page 59
- [neighbor translate-topology](#), page 61
- [neighbor transport](#), page 63
- [ping \(MTR\)](#), page 67
- [policy-map type class-routing ipv4 unicast](#), page 70
- [priority \(OSPF\)](#), page 72
- [router eigrp \(MTR\)](#), page 74
- [route-replicate](#), page 75

## address-family ipv4 (BGP)

To enter address family or router scope address family configuration mode to configure a routing session using standard IP Version 4 (IPv4) address prefixes, use the **address-family ipv4** command in router configuration or router scope configuration mode. To exit address family configuration mode and remove the IPv4 address family configuration from the running configuration, use the **no** form of this command.

### Syntax Available Under Router Configuration Mode

**address-family ipv4** [**mdt** | **tunnel** | {**multicast** | **unicast**} [**vrf vrf-name**] | **vrf vrf-name**]

**no address-family ipv4** [**mdt** | **tunnel** | {**multicast** | **unicast**} [**vrf vrf-name**] | **vrf vrf-name**]

### Syntax Available Under Router Scope Configuration Mode

**address-family ipv4** [**mdt** | **multicast** | **unicast**]

**no address-family ipv4** [**mdt** | **multicast** | **unicast**]

### Syntax Description

<b>mdt</b>	(Optional) Specifies an IPv4 multicast distribution tree (MDT) address family session.
<b>tunnel</b>	(Optional) Specifies an IPv4 routing session for multipoint tunneling.
<b>multicast</b>	(Optional) Specifies IPv4 multicast address prefixes.
<b>unicast</b>	(Optional) Specifies IPv4 unicast address prefixes. This is the default.
<b>vrf vrf-name</b>	(Optional) Specifies the name of the VPN routing and forwarding (VRF) instance to associate with subsequent IPv4 address family configuration mode commands.

### Command Default

IPv4 address prefixes are not enabled.

### Command Modes

Router configuration (config-router)

Router scope configuration (config-router-scope)

### Command History

Release	Modification
12.0(5)T	This command was introduced. This command replaced the <b>match nlri</b> and <b>set nlri</b> commands.

Release	Modification
12.0(28)S	This command was modified. The <b>tunnel</b> keyword was added.
12.0(29)S	This command was modified. The <b>mdt</b> keyword was added.
12.0(30)S	This command was modified. Support for the Cisco 12000 series Internet router was added.
12.2(33)SRA	This command was integrated into Cisco IOS Release 12.2(33)SRA.
12.2(31)SB2	This command was integrated into Cisco IOS Release 12.2(31)SB2.
12.2(33)SRB	This command was modified. Support for router scope configuration mode was added. The <b>tunnel</b> keyword was deprecated.
12.2(33)SXH	This command was integrated into Cisco IOS Release 12.2(33)SXH.
12.2(33)SB	This command was integrated into Cisco IOS Release 12.2(33)SB.
Cisco IOS XE Release 2.1	This command was introduced on Cisco ASR 1000 Series Aggregation Services Routers.
12.4(20)T	This command was modified. The <b>mdt</b> keyword was added. The <b>tunnel</b> keyword was deprecated.
Cisco IOS XE Release 3.6S	This command was modified. VRF-based multicast support was added.
15.2(4)S	This command was implemented on the Cisco 7200 series router.
15.1(2)SNG	This command was implemented on the Cisco ASR 901 Series Aggregation Services Routers.

### Usage Guidelines

The **address-family ipv4** command replaces the **match nlri** and **set nlri** commands. The **address-family ipv4** command places the device in address family configuration mode (prompt: config-router-af), from which you can configure routing sessions that use standard IPv4 address prefixes. To leave address family configuration mode and return to router configuration mode, type **exit**.



#### Note

Routing information for address family IPv4 is advertised by default for each Border Gateway Protocol (BGP) routing session configured with the **neighbor remote-as** command unless you enter the **no bgp default ipv4-unicast** command before configuring the **neighbor remote-as** command.

The **tunnel** keyword is used to enable the tunnel subaddress family identifier (SAFI) under the IPv4 address family identifier. This SAFI is used to advertise the tunnel endpoints and the SAFI-specific attributes (which contain the tunnel type and tunnel capabilities). Redistribution of tunnel endpoints into the BGP IPv4 tunnel SAFI table occurs automatically when the tunnel address family is configured. However, peers need to be activated under the tunnel address family before the sessions can exchange tunnel information.

The **mdt** keyword is used to enable the MDT SAFI under the IPv4 address family identifier. This SAFI is used to advertise tunnel endpoints for inter-AS multicast VPN peering sessions.

If you specify the **address-family ipv4 multicast** command, you will then specify the **network** *network-number* [**mask** *network-mask*] command. The **network** command advertises (injects) the specified network number and mask into the multicast BGP database. This route must exist in the forwarding table installed by an Interior Gateway Protocol (IGP) (that is, by EIGRP, OSPF, RIP, IGRP, static, or IS-IS), but not BGP.

In Cisco IOS Release 12.2(33)SRB and later releases, the ability to use address family configuration under the router scope configuration mode was introduced. The scope hierarchy can be defined for BGP routing sessions and is required to support Multitopology Routing (MTR). To enter the router scope configuration mode, use the **scope** command, which can apply globally or for a specific VRF. When using the scope for a specific VRF, only the **unicast** keyword is available.

## Examples

The following example places the device in address family configuration mode for the IPv4 address family:

```
Device(config)# router bgp 50000
Device(config-router)# address-family ipv4
Device(config-router-af)#
```

The following example places the device in address family configuration mode and specifies only multicast address prefixes for the IPv4 address family:

```
Device(config)# router bgp 50000
Device(config-router)# address-family ipv4 multicast
Device(config-router-af)#
```

The following example places the device in address family configuration mode and specifies unicast address prefixes for the IPv4 address family:

```
Device(config)# router bgp 50000
Device(config-router)# address-family ipv4 unicast
Device(config-router-af)#
```

The following example places the device in address family configuration mode and specifies **cisco** as the name of the VRF instance to associate with subsequent IPv4 address family configuration mode commands:

```
Device(config)# router bgp 50000
Device(config-router)# address-family ipv4 vrf cisco
Device(config-router-af)#
```



### Note

Use this form of the command, which specifies a VRF, only to configure routing exchanges between provider edge (PE) and customer edge (CE) devices.

The following example places the device in tunnel address family configuration mode:

```
Device(config)# router bgp 100
Device(config-router)# address-family ipv4 tunnel
Device(config-router-af)#
```

The following example shows how to configure a device to support an IPv4 MDT address-family session:

```
Device(config)# router bgp 45000
Device(config-router)# address-family ipv4 mdt
Device(config-router-af)#
```

The following example shows how to configure the IPv4 address family under router scope configuration mode. In this example, the scope hierarchy is enabled globally. The device enters router scope address family configuration mode, and only multicast address prefixes for the IPv4 address family are specified:

```
Device(config)# router bgp 50000
Device(config-router)# scope global
Device(config-router-scope)# address-family ipv4 multicast
Device(config-router-scope-af)#
```

#### Related Commands

Command	Description
<b>address-family ipv6</b>	Places the device in address family configuration mode for configuring routing sessions, such as BGP, that use standard IPv6 address prefixes.
<b>address-family vpn4</b>	Places the device in address family configuration mode for configuring routing sessions such as BGP, RIP, or static routing sessions that use standard VPN Version 4 address prefixes.
<b>bgp default ipv4-unicast</b>	Enables the IPv4 unicast address family on all neighbors.
<b>neighbor activate</b>	Enables the exchange of information with a BGP neighboring device.
<b>neighbor remote-as</b>	Adds an entry to the BGP or multiprotocol BGP neighbor table.
<b>scope</b>	Defines the scope for a BGP routing session and enters router scope configuration mode.

## address-family ipv4 (EIGRP MTR)

To enter router address family configuration mode to configure the Enhanced Interior Gateway Routing Protocol (EIGRP) for Multitopology Routing (MTR), use the **address-family ipv4** command in router configuration mode. To remove the address family from the EIGRP configuration, use the **no** form of this command.

**address-family ipv4** [**unicast**| **mcast**| **vrf** *vrf-name*] **autonomous-system** *as-number*

**no address-family ipv4** [**unicast**| **mcast**| **vrf** *vrf-name*] **autonomous-system** *as-number*

### Syntax Description

<b>unicast</b>	(Optional) Specifies the unicast subaddress family.
<b>mcast</b>	(Optional) Specifies the multicast subaddress family.
<b>vrf</b> <i>vrf-name</i>	(Optional) Specifies the name of the VRF.
<b>autonomous-system</b> <i>as-number</i>	Specifies the autonomous system number.

### Command Default

This command is disabled by default.

### Command Modes

Router configuration (config-router)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

The **address-family ipv4** command is used to enter router address family or subaddress family configuration mode to configure the exchange of address-family and subaddress-family prefixes.



#### Note

If Enhanced Routing and Forwarding is not available, then the **mcast** keyword is also not available.

### Examples

The following example shows how to configure an IPv4 address family to associate with the MTR topology named VIDEO:

```
Device(config)# router eigrp mtr
```

```
Device(config-router)# address-family ipv4 autonomous-system 5  
Device(config-router-af)# topology VIDEO tid 100
```

## address-family ipv4 (IS-IS)

To enter router address family configuration mode under Intermediate System-to-Intermediate System (IS-IS) router configuration mode, use the **address-family ipv4** command in router configuration mode. To remove the address family or subaddress family configuration from the router configuration, use the **no** form of this command.

**address-family ipv4** [**multicast**| **unicast**]

**no address-family ipv4** [**multicast**| **unicast**]

### Syntax Description

<b>multicast</b>	(Optional) Specifies multicast subaddress family prefixes.
<b>unicast</b>	(Optional) Specifies unicast subaddress family prefixes.

### Command Default

Unicast subaddress family configuration mode is entered if no optional keywords are entered.

### Command Modes

Router configuration (config-router)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

### Usage Guidelines

The **address-family ipv4** command is used to enter router address family or subaddress family configuration mode to configure the exchange of address-family and subaddress-family prefixes.

### Examples

The following example show how to configure IS-IS to exchange IPv4 unicast prefixes in unicast subaddress family configuration mode:

```
Device(config)# router isis 1
Device(config-router)# address-family ipv4 unicast
Device(config-router-af)# end
```

## address-family ipv4 (OSPF)

To enter router address family configuration mode under Open Shortest Path First (OSPF) router configuration mode, use the **address-family ipv4** command in router configuration mode. To remove the address family or subaddress family configuration from the router configuration, use the **no** form of this command.

**address-family ipv4** [**multicast**| **unicast**]

**no address-family ipv4** [**multicast**| **unicast**]

### Syntax Description

<b>multicast</b>	(Optional) Specifies multicast subaddress family prefixes.
<b>unicast</b>	(Optional) Specifies unicast subaddress family prefixes.

### Command Default

Unicast router subaddress family configuration mode is entered if no optional keywords are entered.

### Command Modes

Router configuration

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.

### Usage Guidelines

The **address-family ipv4** command is used to enter router address family or router subaddress family configuration mode to configure the exchange of address-family and subaddress-family prefixes.

### Examples

The following example show how to configure OSPF to exchange IPv4 unicast prefixes in unicast subaddress family configuration mode:

```
Device(config)# router ospf 1
Device(config-router)# address-family ipv4 unicast
Device(config-router-af)# end
```

### Related Commands

Command	Description
<b>area capability default-exclusion</b>	Configures an OSPF process to allow interfaces to be excluded from the base topology.

Command	Description
<b>ip ospf cost</b> (MTR)	Configures the OSPF interface cost under a topology instance.
<b>ip ospf topology disable</b>	Prevents an OSPF process from advertising the interface as part of the topology.
<b>topology</b> (OSPF)	Configures an OSPF process to route IP traffic under the specified topology instance.

# all-interfaces

To configure a topology instance to use all interfaces on a device, use the **all-interfaces** command in address family topology configuration mode. To remove all interfaces from the topology instance configuration, use the **no** form of this command.

**all-interfaces**

**no all-interfaces**

## Syntax Description

This command has no arguments or keywords.

## Command Default

This command is disabled by default. No interfaces are included in class-specific topologies unless explicitly configured.

The configuration applied with this command does not override the configuration applied at the interface level with the **topology** interface configuration command.

## Command Modes

Address family topology configuration (config-af-topology)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

The **all-interfaces** command is used to include or exclude all interfaces on the device from a global topology configuration.

## Examples

The following example shows how to configure all local interfaces on the device to be used by the VOICE topology:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# all-interfaces
Device(config-af-topology)# end
```

## Related Commands

Command	Description
<b>maximum routes</b> (MTR)	Sets the maximum number of routes that a topology instance will accept and install into the RIB.

Command	Description
<b>shutdown</b>	Temporarily disables a topology instance without removing the topology configuration.
<b>topology</b> (global)	Configures a topology instance.

## area capability default-exclusion

To configure an Open Shortest Path First (OSPF) process to allow interfaces to be excluded from the base topology, use the **area capability default-exclusion** command in router configuration mode. To return the OSPF process to default operation, use the **no** form of this command.

**area** *area-id* **capability default-exclusion**

**no area** *area-id* **capability default-exclusion**

### Syntax Description

<i>area-id</i>	Area ID number. This argument can be entered in the IP address format or as a number. The range is 0 to 4294967295.
----------------	---

### Command Default

The base topology cannot be excluded from an interface.

### Command Modes

Router configuration

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.

### Examples

The following example shows how to configure OSPF to allow interfaces to be excluded from the base topology:

```
Device(config)# router ospf 1
Device(config-router)# area 10 default-cost 100
Device(config-router)# area 10 capability default-exclusion
Device(config-router)# end
```

### Related Commands

Command	Description
<b>address-family ipv4 (OSPF)</b>	Configures address family and subaddress family IP prefix exchange.
<b>ip ospf cost (MTR)</b>	Configures the OSPF interface cost under a topology instance.
<b>ip ospf topology disable</b>	Prevents an OSPF process from advertising the interface as part of the topology.

Command	Description
<b>priority</b> (OSPF)	Sets the priority that an OSPF process assigns to a topology instance for SPF calculations.
<b>topology</b> (OSPF)	Configures an OSPF process to route IP traffic under the specified topology instance.

# bgp tid

To configure a Border Gateway Protocol (BGP) routing session to accept routes with a specified Multitopology Routing (MTR) topology ID, use the **bgp tid** command in router scope address family topology configuration mode. To disassociate the topology ID from the BGP process, use the **no** form of this command.

**bgp tid** *number*

**no bgp tid**

## Syntax Description

<i>number</i>	Topology ID number. The range is 1 to 255.
---------------	--

## Command Default

No ID is associated with an MTR topology instance.

## Command Modes

Router scope address family topology configuration

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

## Usage Guidelines

The **bgp tid** command is used to associate an ID with an MTR topology instance. Each topology must be configured with a unique topology ID. The topology ID is used to identify and group routes for each topology in BGP updates.

## Examples

The following example shows how to configure a topology ID of 100 under the VOICE topology instance:

```
Device(config)# router bgp 50000
Device(config-router)# scope global
Device(config-router-scope)# address-family ipv4
Device(config-router-scope-af)# topology VOICE
Device(config-router-scope-af-topo)# bgp tid 100
Device(config-router-scope-af-topo)# end
```

## Related Commands

Command	Description
<b>clear ip bgp topology</b>	Resets BGP neighbor session information under a topology instance.

Command	Description
<b>neighbor translate-topology</b>	Configures BGP to translate or move routes from a topology on another device to a topology on the local device.
<b>scope</b>	Defines the scope for a BGP routing session and enters router scope configuration mode.
<b>show ip bgp</b>	Displays entries in the BGP routing table.
<b>topology (BGP)</b>	Configures a BGP routing session to route IP traffic for a specified topology instance.

## clear ip bgp topology

To reset Border Gateway Protocol (BGP) neighbor session information for a topology instance, use the **clear ip bgp topology** command in privileged EXEC mode.

**clear ip bgp** [*vrf vrf-name*] **topology** {*\**| *topology-name*} [*as-number*] **dampening** [*network-address* [*network-mask* ]]| **flap-statistics** [*network-address* [*network-mask* ]]| **peer-group** *peer-group-name*| **table-map**| **update-group** [*number*| *ip-address*]} [**in** [*prefix-filter*]| **out**| **soft** [**in** [*prefix-filter*]| **out**]]

### Syntax Description

<b>vrf</b>	(Optional) Specifies an instance of a routing table.
<i>vrf-name</i>	(Optional) Name of the Virtual Private Network (VPN) routing and forwarding (VRF) table to use for storing data.
<b>*</b>	Clears session and peering information for all topology instances.
<i>topology-name</i>	Name of a topology instance.
<i>autonomous-system-number</i>	Autonomous system to clear.
<b>dampening</b>	Specifies that dampening statistic counters will be cleared.
<i>network-address</i> [ <i>network-mask</i> ]	(Optional) Network address and network mask to clear dampening or flap-statistic counters.
<b>flap-statistics</b>	Specifies that session flap statistic counters will be cleared.
<b>peer-group</b> <i>peer-group-name</i>	Clears peer group information for the specified peer group name.
<b>table-map</b>	Clears table-map configuration information.
<b>update-group</b>	Clears update group session information for the specified group number or IP address.
<i>number</i>	(Optional) Update group number.
<i>ip-address</i>	(Optional) IP address of peer for which update group session information is to be cleared.
<b>in</b>	(Optional) Initiates inbound reconfiguration. If neither the <b>in</b> keyword nor <b>out</b> keyword is specified, both inbound and outbound sessions are reset.

<b>prefix-filter</b>	(Optional) Clears the inbound prefix filter.
<b>soft</b>	(Optional) Initiates a soft reset. Does not tear down the session.
<b>out</b>	(Optional) Initiates outbound reconfiguration. If neither the <b>in</b> keyword nor <b>out</b> keyword is specified, both inbound and outbound sessions are reset.

**Command Modes**

Privileged EXEC (#)

**Command History**

Release	Modification
12.2(33)SRB	This command was introduced.
15.1(2)T	This command was modified. The <b>vrf vrf-name</b> keyword and argument were added.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

**Usage Guidelines**

The **clear ip bgp topology** command clears BGP session information under the specified topology or for all topologies. This command can be used to initiate a hard reset or soft reconfiguration. A hard reset tears down and rebuilds the specified peering sessions and rebuilds the BGP routing tables. A soft reconfiguration uses stored prefix information to reconfigure and activate BGP routing tables without tearing down existing peering sessions. Soft reconfiguration uses stored update information, at the cost of additional memory for storing the updates, to allow you to apply new BGP policy without disrupting the network. Soft reconfiguration can be configured for inbound or outbound sessions.

**Generating Updates from Stored Information**

To generate new inbound updates from stored update information (rather than dynamically) without resetting the BGP session, you must preconfigure the local BGP device using the **neighbor soft-reconfiguration inbound** command. This preconfiguration causes the software to store all received updates without modification regardless of whether an update is accepted by the inbound policy. Storing updates is memory intensive and should be avoided if possible.

Outbound BGP soft configuration has no memory overhead and does not require any preconfiguration. You can trigger an outbound reconfiguration on the other side of the BGP session to make the new inbound policy take effect.

Use this command whenever any of the following changes occur:

- Additions or changes to the BGP-related access lists
- Changes to BGP-related weights
- Changes to BGP-related distribution lists
- Changes to BGP-related route maps

### Dynamic Inbound Soft Reset

The route refresh capability, as defined in RFC 2918, allows the local device to reset inbound routing tables dynamically by exchanging route refresh requests to supporting peers. The route refresh capability does not store update information locally for non-disruptive policy changes. It instead relies on dynamic exchange with supporting peers. Route refresh is advertised through BGP capability negotiation. All BGP devices must support the route refresh capability.

To determine if a BGP device supports this capability, use the **show ip bgp neighbors** command. The following message is displayed in the output when the device supports the route refresh capability:

Received route refresh capability from peer.

If all BGP devices support the route refresh capability, use the **clear ip bgp topology** command with the **in** keyword. You need not use the **soft** keyword, because soft reset is automatically assumed when the route refresh capability is supported.



#### Note

After configuring a soft reset (inbound or outbound), it is normal for the BGP routing process to hold memory. The amount of memory that is held depends on the size of routing tables and the percentage of memory chunks that are utilized. Partially used memory chunks will be used or released before more memory is allocated from the global device memory pool.

### Examples

The following example shows how to configure soft reconfiguration for the inbound sessions with neighbors in the autonomous system 45000. The outbound sessions are unaffected.

```
Device# clear ip bgp topology VOICE 45000 soft in
```

### Related Commands

Command	Description
<b>bgp tid</b>	Configures BGP to accept routes with a specified topology ID.
<b>import topology</b>	Configures BGP to import or move routes from one topology to another on the same device.
<b>neighbor soft-reconfiguration</b>	Configures the Cisco IOS software to start storing updates.
<b>neighbor translate-topology</b>	Configures BGP to translate or move routes from a topology on another device to a topology on the local device.
<b>scope</b>	Defines the scope for a BGP routing session and enters router scope configuration mode.
<b>show ip bgp neighbors</b>	Displays information about BGP and TCP connections to neighbors.

Command	Description
<b>show ip bgp neighbors topology</b>	Displays entries in the BGP routing tables for a topology instance.
<b>topology</b> (BGP)	Configures a process to route IP traffic under the specified topology instance.

# clear ip eigrp topology



## Note

Effective with Cisco IOS Release 12.2(33)SRE, **clear ip eigrp topology** command is not available in Cisco IOS software.

To clear an Enhanced Interior Gateway Routing Protocol (EIGRP) process for a topology instance, use the **clear ip eigrp topology** command in privileged EXEC mode.

**clear ip eigrp** [ *as-number* ] **topology** [ *topology-name* ] *topo-entry* [ *entry-mask* ]

## Syntax Description

<i>as-number</i>	(Optional) The autonomous system number to clear.
<i>topology-name</i>	(Optional) The name of the topology instance.
<i>topo-entry</i>	The topology table entry. The <i>topo-entry</i> argument is entered as an IP address.
<i>entry-mask</i>	(Optional) The topology table entry mask. The <i>entry-mask</i> argument is entered as a wild-card mask.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was removed.

## Usage Guidelines

The **clear ip eigrp topology** command can be used to reset EIGRP process and session information for a specific topology.

## Examples

The following example resets the EIGRP process under the VOICE topology and clears the topology table entry 10.32.40.2:

```
Device# clear ip eigrp topology VOICE 10.32.40.2
```

**Related Commands**

Command	Description
<b>clear ip eigrp topology eigrp next-hop-self</b>	Configures EIGRP to advertise itself as the next hop.
<b>eigrp shutdown</b>	Disables an EIGRP process under a topology interface configuration.
<b>eigrp split-horizon</b>	Configures split horizon under a topology interface configuration.
<b>eigrp summary-address</b>	Configures an EIGRP summary address under a topology configuration.
<b>topology</b> (EIGRP)	Configures an EIGRP process to route IP traffic under the specified topology instance.
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

# clear ip interface

To reset interface-level statistics, use the **clear ip interface** command in privileged EXEC mode.

**clear ip interface** *type number* [**topology** {*name*| **all**| **base**}] [**stats**]

## Syntax Description

<i>type</i>	Interface type.
<i>number</i>	Interface number.
<b>topology</b>	(Optional) Specifies topology statistics.
<i>name</i>	(Optional) Statistics related to a particular topology.
<b>all</b>	(Optional) Statistics for all topologies. This keyword can be used as the <i>name</i> argument.
<b>base</b>	(Optional) Clears base topology statistics.
<b>stats</b>	(Optional) Clears IP traffic statistics without topology awareness, that is, an aggregate of all topologies is cleared.

## Command Default

If no topology is specified, only interface level aggregate statistics are reset.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

Use the **clear ip interface** command to reset interface-level statistics. If a topology name is specified, only the statistics for that topology are cleared. If all topologies need to be reset, use the **all** keyword as the topology name.

## Examples

The following example shows how to clear statistics for all topologies:

```
Device# clear ip interface FastEthernet 1/10 topology all
```

# clear ip route multicast

To clear multicast routes from the routing table, use the **clear ip route multicast** command in privileged EXEC mode.

**clear ip route multicast** {*vrf vrf-name*|\*|*destination* [*mask* ]|**dhcp** *ip-address*}

## Syntax Description

<i>vrf vrf-name</i>	Specifies a VPN routing and forwarding (VRF) instance.
*	Deletes all routes.
<i>destination</i>	Address of the destination network.
<i>mask</i>	(Optional) Mask of the destination network.
<b>dhcp</b>	Specifies a route added by a DHCP server or relay agent.
<i>ip-address</i>	Destination host route to delete.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
15.0(1)M	This command was integrated into Cisco IOS Release 15.0(1)M.
15.0(1)SY	This command was integrated into Cisco IOS Release 15.0(1)SY.

## Usage Guidelines

The **clear ip route multicast** command is used to clear specific multicast entries from the routing table or all multicast entries (by entering the \* character).

## Examples

The following example shows how to clear all multicast routes from the routing table:

```
Device# clear ip route multicast *
```

**Related Commands**

<b>clear ip route topology</b>	Clears entries from the routing table of a topology.
<b>ip route topology</b>	Configures static routing under a topology instance.

# clear ip route topology

To clear entries from the routing table of a topology, use the **clear ip route topology** command in privileged EXEC mode.

**clear ip route topology** *topology-name* {*\**| *destination* [*mask* ]} **dhcp** *ip-address*}

## Syntax Description

<i>topology-name</i>	Name of the topology.
<i>*</i>	Specifies all routes.
<i>destination</i>	Address of the destination network.
<i>mask</i>	(Optional) Mask of the destination network.
<b>dhcp</b>	Specifies routes added by a DHCP relay agent.
<i>ip-address</i>	IP address of the DHCP relay agent.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

The **clear ip route topology** command is used to clear entries from the routing table for the specified topology instance or all topology instances (by entering the *\** character).

## Examples

The following example shows how to clear all routes from the routing table of the VOICE topology:

```
Device# clear ip route topology VOICE *
```

## Related Commands

<b>ip route topology</b>	Configures static routing under a topology instance.
<b>ping (MTR)</b>	Diagnoses basic network connectivity through a topology instance.

<b>show ip protocols topology</b>	Displays the configuration and state of active routing protocol processes under a topology instance.
<b>show ip route topology</b>	Displays the current state of a topology routing table.
<b>show topology</b>	Displays status and configuration information for topologies configured with MTR.

## clear ip traffic (MTR)

To clear IP traffic statistics, use the **clear ip traffic** command in privileged EXEC mode.

**clear ip traffic** [**topology** {*name*| **all**| **base**}]

### Syntax Description

<b>topology</b>	(Optional) Clears IP traffic statistics related to a particular topology.
<i>name</i>	(Optional) Topology name.
<b>all</b>	(Optional) Clears statistics for all topologies.
<b>base</b>	(Optional) Clears base topology statistics.

### Command Default

If no topology name is specified, global statistics are cleared.

### Command Modes

Privileged EXEC (#)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

Use the **clear ip traffic** command to clear IP traffic statistics. If no topology name is specified, global statistics are cleared. If a topology name is specified, only the statistics for that topology are cleared. If all topologies need to be reset, use the **all** keyword as the topology name.

### Examples

The following example shows how to clear all topology statistics:

```
Device# clear ip traffic topology all
```

### Related Commands

Command	Description
<b>show ip traffic</b> (MTR)	Displays statistics about IP traffic.

# debug topology

To enable debugging for topology related events, use the **debug topology** command in privileged EXEC mode. To disable debugging output, use the **no** form of this command.

**debug topology** {**accounting**| **all**| **cache**| **db**| **event**| **ha**| **interface**| **locking**| **sb**| **state**| **topoid**| **vrf**}

**no debug topology** {**accounting**| **all**| **cache**| **db**| **event**| **ha**| **interface**| **locking**| **sb**| **state**| **topoid**| **vrf**}

## Syntax Description

<b>accounting</b>	Enables debugging for topology accounting.
<b>all</b>	Enables debugging for all topology routing events.
<b>cache</b>	Enables debugging for topology ID cache activity.
<b>db</b>	Enables debugging for topology DB events.
<b>event</b>	Enables debugging for topology notification events.
<b>ha</b>	Enables debugging for topology High Availability (HA) events.
<b>interface</b>	Enables debugging for topology interface association.
<b>locking</b>	Enables debugging for topology client locking activity.
<b>sb</b>	Enables debugging for topology sub-block.
<b>state</b>	Enables debugging for topology state change events.
<b>topoid</b>	Enables debugging for topology ID management events.
<b>vrf</b>	Enables debugging for topology VRF association.

## Command Default

Debugging output for topology related events is disabled.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.

Release	Modification
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Examples

The following example shows how to enable debugging for topology HA events:

```
Device# debug topology ha
```

### Related Commands

Command	Description
<b>show topology</b>	Displays status and configuration information for topologies configured with MTR.

# eigrp delay

To configure the delay value that Enhanced Interior Gateway Routing Protocol (EIGRP) uses for interface metric calculation, use the **eigrp delay** command in interface topology configuration mode. To return the delay value to the default, use the **no** form of this command.

**eigrp** *as-number* **delay** *value*

**no eigrp** *as-number* **delay** *value*

## Syntax Description

<i>as-number</i>	Specifies the autonomous system number of the EIGRP process.
<i>value</i>	Specifies the delay value, in tens of microseconds. The range is 1 to 4294967295.

## Command Default

Delay values are inherited from the global interface configuration.

## Command Modes

Interface topology configuration (config-if-topology)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

The **eigrp delay** command is used to set the interface delay value used by the EIGRP process for routing calculation.

## Examples

The following example shows how to set the EIGRP delay calculation on Ethernet interface 0/0 to 100 milliseconds:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast VOICE
Device(config-if-topology)# eigrp 1 delay 100000
Device(config-if-topology)# end
```

**Related Commands**

Command	Description
<b>topology</b> (EIGRP)	Configures an EIGRP process to route IP traffic under the specified topology instance.
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

## eigrp next-hop-self

To configure an Enhanced Interior Gateway Routing Protocol (EIGRP) process to advertise itself as the next hop when advertising routes under a topology instance, use the **eigrp next-hop-self** command in interface topology configuration mode. To configure EIGRP to advertise the source of the route as the next hop, use the **no** form of this command.

**eigrp** *as-number* **next-hop-self**

**no eigrp** *as-number* **next-hop-self**

### Syntax Description

<i>as-number</i>	Autonomous system number of the EIGRP process.
------------------	--

### Command Default

This command is enabled by default.

### Command Modes

Interface topology configuration (config-if-topology)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

The **eigrp next-hop-self** command is used to configure EIGRP next hop resolution. By default, EIGRP sets the next-hop to itself for routes it advertises, even if the route is advertised through the interface, from which it was learned. Entering the **no** form of this command configures EIGRP to advertise the IP address of the route source as the next hop.

### Examples

The following example shows how to configure EIGRP process 1 to advertise the source of a route as the next hop under the topology VOICE:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast VOICE
Device(config-if-topology)# no eigrp 1 next-hop-self
Device(config-if-topology)# end
```

### Related Commands

Command	Description
<b>clear ip eigrp topology</b>	Resets EIGRP process information for a topology.

Command	Description
<b>topology</b> (EIGRP)	Configures an EIGRP process to route IP traffic under the specified topology instance.
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

# eigrp shutdown

To disable an Enhanced Interior Gateway Routing Protocol (EIGRP) process under a topology interface configuration, use the **eigrp shutdown** command in interface topology configuration mode. To restart the EIGRP process under a topology interface configuration, use the **no** form of this command.

**eigrp** *as-number* **shutdown**

**no eigrp** *as-number* **shutdown**

## Syntax Description

<i>as-number</i>	Autonomous system number of the EIGRP process.
------------------	--

## Command Default

The EIGRP process is in the no shutdown state.

## Command Modes

Interface topology configuration (config-if-topology)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

The **eigrp shutdown** command is used to disable an EIGRP process under an interface topology configuration without removing the EIGRP or topology configuration from the device.

## Examples

The following example shows how to place the EIGRP process in a shutdown state:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast RED
Device(config-if-topology)# eigrp 1 delay 2000
Device(config-if-topology)# eigrp 1 split-horizon
Device(config-if-topology)# eigrp 1 shutdown
Device(config-if-topology)# end
```

## Related Commands

Command	Description
<b>clear ip eigrp</b>	Resets EIGRP process and neighbor session information.
<b>topology</b> (EIGRP)	Configures an EIGRP process to route IP traffic under the specified topology instance.

Command	Description
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

# eigrp split-horizon

To configure Enhanced Interior Gateway Routing Protocol (EIGRP) to use split horizon under a topology interface configuration, use the **eigrp split-horizon** command in interface topology configuration mode. To disable split horizon on the topology interface, use the **no** form of this command.

**eigrp** *as-number* **split-horizon**

**no eigrp** *as-number* **split-horizon**

## Syntax Description

<i>as-number</i>	Autonomous system number of the EIGRP process.
------------------	--

## Command Default

This command is enabled by default.

## Command Modes

Interface topology configuration (config-if-topology)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

The **eigrp split-horizon** command is used to enable or disable split horizon under the topology interface configuration.

## Examples

The following example shows how to disable split horizon:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast VOICE
Device(config-if-topology)# no eigrp 1 split-horizon
Device(config-if-topology)# end
```

## Related Commands

Command	Description
<b>topology</b> (EIGRP)	Configures an EIGRP process to route IP traffic under the specified topology instance.
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

## eigrp summary-address

To configure an Enhanced Interior Gateway Routing Protocol (EIGRP) summary address under a topology interface configuration, use the **eigrp summary-address** command in interface topology configuration mode. To remove the summary address from the topology interface configuration, use the **no** form of this command.

**eigrp** *as-number* **summary-address** *ip-address wildcard-mask* [ *distance* ]

**no eigrp** *as-number* **summary-address** *ip-address wildcard-mask* [ *distance* ]

### Syntax Description

<i>as-number</i>	Autonomous system number of the EIGRP process.
<i>ip-address wildcard-mask</i>	Summary address to be created. The mask is entered in the form of a wildcard mask.
<i>distance</i>	(Optional) Administrative distance to routes summarized by this command. The range is 1 to 255.

### Command Default

No summary addresses are predefined.

The default administrative distance metric for EIGRP is 90.

The default administrative distance for an EIGRP summary is 5.

### Command Modes

Interface topology configuration (config-if-topology)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

The **eigrp summary-address** command is used to configure a summary address on an interface for a topology instance. EIGRP summary routes are given an administrative distance value of 5 to allow the summary to be advertised without being installed in the routing table.

### Examples

The following example shows how to create a summary of the 10.100.1.0/24 network and apply an administrative distance of 65 to routes summarized by this statement:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast RED
Device(config-if-topology)# eigrp 1 summary-address 10.100.1.0 0.0.0.255 65
Device(config-if-topology)# end
```

**Related Commands**

Command	Description
<b>topology</b> (EIGRP)	Configures an EIGRP process to route IP traffic under the specified topology instance.
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

# exit-global-af

To exit global address family configuration mode and enter global configuration mode, use the **exit-global-af** command in global address family configuration mode.

**exit-global-af**

**Syntax Description** This command has no arguments or keywords.

**Command Default** No default behavior or values.

**Command Modes** Global address family configuration (config-af)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines** The **exit-global-af** command is used to exit global address family configuration mode without removing global topology configuration.

**Examples** The following example shows how to exit from global address family configuration mode:

```
Device(config-af) # exit-global-af
Device(config) #
```

Related Commands	Command	Description
	<b>global-address-family ipv4</b>	Enters enter address family topology configuration mode to configure MTR.
	<b>service-policy type class-routing</b>	Attaches the service policy to the policy map for MTR traffic classification and to enable MTR.

# exit-if-topology

To exit interface topology configuration mode, use the **exit-if-topology** command in interface topology configuration mode.

## exit-if-topology

### Syntax Description

This command has no arguments or keywords.

### Command Default

No default behavior or values.

### Command Modes

Interface topology configuration (config-if-topology)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Examples

The following example, starting in global configuration mode, shows how to exit interface topology configuration mode:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast RED
Device(config-if-topology)# exit-if-topology
Device(config-if-topology)# end
```

### Related Commands

Command	Description
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

# exit-topo

To exit address family topology configuration mode and enter global address family configuration mode, use the **exit-topo** command in address family topology configuration mode.

## exit-topo

### Syntax Description

This command has no arguments or keywords.

### Command Default

No default behavior or values.

### Command Modes

Address family topology configuration (config-af)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

The **exit-topo** command is used to exit from address family topology configuration mode.

### Examples

The following example shows how to exit address family topology configuration mode and enter global address family configuration mode:

```
Device(config-af-topology) # exit-topo  
Device(config-af) #
```

### Related Commands

Command	Description
<b>all-interfaces</b>	Configures a topology instance to use all interfaces on a device.
<b>forward-base</b>	Configures the forwarding mode under a topology instance.
<b>maximum routes (MTR)</b>	Sets the maximum number of routes that a topology instance will accept and install into the RIB.
<b>shutdown</b>	Temporarily disables a topology instance without removing the topology configuration.

Command	Description
<b>topology</b> (global)	Configures a topology instance.

# forward-base

To configure the forwarding mode under a topology instance, use the **forward-base** command in address family topology configuration mode. To return to strict forwarding mode, use the **no** form of this command.

**forward-base**  
**no forward-base**

**Syntax Description** This command has no arguments or keywords.

**Command Default** Strict forwarding mode

**Command Modes** Address family topology configuration (config-af-topology)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines** The **forward-base** command is used in incremental deployment.

The **forward-base** command is used to configure the forwarding rule, under which traffic is forwarded for a topology. MTR supports both full and incremental deployment configurations. For full deployment, MTR supports a strict forwarding mode (default) longest-match lookup in only the forwarding table of the corresponding class-specific topology. If no route is found, the packet is dropped. For incremental deployment, MTR supports a longest-match lookup first in the forwarding table for the corresponding class-specific topology, and subsequently, in the base topology if no class-specific entry is found. If a route is not found in the base topology, the packet is then dropped.

**Examples** The following example shows how to configure strict forwarding mode under the VOICE topology:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# no forward-base
Device(config-af-topology)# end
```

Related Commands	Command	Description
	<b>all-interfaces</b>	Configures a topology instance to use all interfaces on a device.

Command	Description
<b>exit-topo</b>	Exits routing topology configuration mode, and enters global address family topology configuration mode.
<b>maximum routes</b> (MTR)	Sets the maximum number of routes that a topology instance will accept and install into the RIB.
<b>shutdown</b>	Temporarily disables a topology instance without removing the topology configuration.
<b>topology</b> (global)	Configures a topology instance.

# global-address-family ipv4

To enter global address family configuration mode to configure Multitopology Routing (MTR), use the **global-address-family ipv4** command in global configuration mode. To disable and remove all topology configuration from the device configuration, use the **no** form of this command.

**global-address-family ipv4** [**multicast**| **unicast**]

**no global-address-family ipv4** [**multicast**| **unicast**]

Cisco IOS Release 15.2(3)T and later releases

**global-address-family ipv4 multicast**

**no global-address-family ipv4 multicast**

## Syntax Description

<b>multicast</b>	(Optional) Enters multicast subaddress family configuration mode.  In Cisco IOS Release 15.2(3)T and later releases, the <b>multicast</b> keyword is required.
<b>unicast</b>	(Optional) Enters unicast subaddress family configuration mode. This is the default.

## Command Default

Unicast global address family configuration mode is the default when no optional keywords are entered.

## Command Modes

Global configuration (config)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
15.2(3)T	This command was modified. In Cisco IOS Release 15.2(3)T, the <b>multicast</b> keyword is no longer optional and the <b>unicast</b> keyword is not supported.

## Usage Guidelines

The **global-address-family ipv4** command is used to enter global address family configuration mode to configure MTR. Global topology configurations are entered in this configuration mode. Independent routing and forwarding tables are maintained for each topology, allowing you to configure separate forwarding rules on a per-topology basis. Cisco Express Forwarding (CEF) and IP routing must be enabled before MTR can be configured. The **topology** (global) command is entered to configure the base or a class-specific topology.

To completely remove all topologies from the device configuration, use the **no global-address-family ipv4** command in global configuration mode. To disable a topology without removing it from the configuration of the device, use the **shutdown** command in address family topology configuration mode. If the **no ip routing** global configuration command is used, all topology configuration is retained, but topologies will be operationally disabled.

## Examples

The following example creates a topology instance named VOICE. The device is configured to use all interfaces for the VOICE topology.

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# all-interfaces
Device(config-af-topology)# end
```

The following example shows how to create a topology instance named VIDEO and places this topology in a shutdown state:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VIDEO
Device(config-af-topology)# shutdown
Device(config-af-topology)# end
```

## Related Commands

Command	Description
<b>exit-global-af</b>	Exits global address family configuration and enters global configuration mode.
<b>shutdown</b>	Temporarily disables a topology instance without removing the topology configuration.
<b>topology (global)</b>	Configures a topology instance.

# import topology

To configure Border Gateway Protocol (BGP) to import routes from one Multitopology Routing (MTR) topology to another on the same device, use the **import topology** command in router scope address family topology configuration mode. To disable the import configuration, use the **no** form of this command.

**import topology** {*topology-name*| **base**} [**route-map** *map-name*]

**no import topology** {*topology-name*| **base**} [**route-map** *map-name*]

## Syntax Description

<i>topology-name</i>	Name of topology instance.
<b>base</b>	Imports routes from the base topology.
<b>route-map</b> <i>map-name</i>	(Optional) Specifies a route map to filter imported routes.

## Command Default

No routes are imported from other topologies.

## Command Modes

Router scope address family topology configuration

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

## Usage Guidelines

The **import topology** command is used to configure BGP to import routes from one topology to another when multiple topologies are configured on the same device. The name of the class-specific topology or the base topology is specified when entering this command. Best-path calculations are run on the imported routes before they are installed into the topology routing information base (RIB). If a duplicate route is imported, BGP will select and install only one instance of the route per standard BGP best-path calculation behavior. This command also includes a **route-map** keyword to allow you to filter routes that are moved between class-specific topologies.

## Examples

The following example configures BGP to import routes from a topology instance named VIDEO into the local topology instance. Imported routes are filtered through the route map named 10NET, which permits routes from the 10.0.0.0 network.

```
Device(config)# ip prefix-list 10 permit 10.0.0.0/8
Device(config)# route-map 10NET
```

```

Device(config-route-map)# match ip address prefix-list 10
Device(config-route-map)# exit
Device(config)# router bgp 50000
Device(config-router)# scope global
Device(config-router-scope)# address-family ipv4
Device(config-router-scope-af)# topology VOICE
Device(config-router-scope-af-topo)# import topology VIDEO route-map 10NET
Device(config-router-scope-af-topo)# end

```

## Related Commands

Command	Description
<b>bgp tid</b>	Configures BGP to accept routes with a specified topology ID.
<b>clear ip bgp topology</b>	Resets BGP neighbor session information under a topology instance.
<b>neighbor translate-topology</b>	Configures BGP to translate or move routes from a topology on another device to a topology on the local device.
<b>scope</b>	Defines the scope for a BGP routing session and enters router scope configuration mode.
<b>topology (BGP)</b>	Configures a process to route IP traffic under the specified topology instance.

# ip multicast rpf multitopology

To enable Multitopology Routing (MTR) support for IP multicast routing, use the **ip multicast rpf multitopology** command in global configuration mode. To disable MTR support for IP multicast routing, use the **no** form of this command.

**ip multicast rpf multitopology**

**no ip multicast rpf multitopology**

**Syntax Description** This command has no arguments or keywords.

**Command Default** No default behavior or values

**Command Modes** Global configuration (config)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
	15.0(1)M	This command was integrated into Cisco IOS Release 15.0(1)M.
	15.0(1)SY	This command was integrated into Cisco IOS Release 15.0(1)SY.

**Examples** The following example shows how to enable MTR support for IP multicast routing:

```
Device(config)# ip multicast-routing
Device(config)# ip multicast rpf multitopology
```

## ip ospf cost (MTR)

To configure the Open Shortest Path First (OSPF) interface cost under a topology instance, use the **ip ospf cost** command in interface topology configuration mode. To remove the interface cost configuration, use the **no** form of this command.

**ip ospf cost** *value*

**no ip ospf cost**

### Syntax Description

<i>value</i>	Cost for the interface. The range is 1 to 65535.
--------------	--

### Command Default

The cost configured in interface configuration is inherited.

### Command Modes

Interface topology configuration (config-if-topology)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.

### Examples

The following example configures the interface cost to be 1000:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast DATA
Device(config-if-topology)# ip ospf cost 1000
Device(config-if-topology)# end
```

# ip ospf topology disable

To prevent an Open Shortest Path First (OSPF) process from advertising the interface as part of the topology, use the **ip ospf topology disable** command in interface topology configuration mode. To enable the OSPF process to advertise the interface as a part of the topology, use the **no** form of this command.

**ip ospf topology disable**

**no ip ospf topology disable**

## Syntax Description

This command has no arguments or keywords.

## Command Default

The OSPF process advertises the interface as a part of the topology.

## Command Modes

Interface topology configuration (config-if-topology)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.

## Usage Guidelines

The **ip ospf topology disable** command is used to prevent an OSPF process from advertising the interface as a part of the topology, without removing the OSPF or topology configuration from the interface.

## Examples

The following example disables OSPF routing under the topology instance named VOICE on Ethernet interface 0/0:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast VOICE
Device(config-if-topology)# ip ospf topology disable
Device(config-if-topology)# end
```

## Related Commands

Command	Description
<b>area capability default-exclusion</b>	Configures an OSPF process to allow interfaces to be excluded from the MTR base topology.

## ip route topology

To configure static routing under a topology instance, use the **ip route topology** command in global configuration mode. To remove the static route, use the **no** form of this command.

**ip route topology** *topology-name destination-address destination-mask {forwarding-address| interface [forwarding-address ]} [dhcp] [ distance ] [multicast] [name name] [permanent] [tag value] [track number]*

**no ip route topology** *topology-name {\*| destination-address destination-mask {forwarding-address| interface [forwarding-address ]}} [dhcp] [ distance ] [multicast] [name name] [permanent] [tag value] [track number]*

### Syntax Description

<i>topology-name</i>	Name of the topology instance.
<i>destination-address</i>	IP address of the destination.
<i>destination-mask</i>	IP address mask of the destination.
<i>forwarding-address</i>	IP forwarding address (next hop) to the destination network.
<i>interface</i>	Interface type and interface number.
<b>dhcp</b>	(Optional) Enables a Dynamic Host Configuration Protocol (DHCP) server to assign a static route to a default gateway (option 3). <ul style="list-style-type: none"> <li>Specify the <b>dhcp</b> keyword for each routing protocol.</li> </ul>
<i>distance</i>	(Optional) An administrative distance metric for the route.
<b>multicast</b>	(Optional) Configures the route as a multicast static route.
<b>name name</b>	(Optional) Applies a name to the specified route.
<b>permanent</b>	(Optional) Specifies that the route will not be removed, even if the interface is shut down.
<b>tag value</b>	(Optional) Tag value that can be used as a “match” value for controlling redistribution via route maps.
<b>track number</b>	(Optional) Installs the static route based on the conditions set for the tracked object. The argument specifies an object number, which can be a number from 1 to 500.

*	Specifies all static routes. This keyword can be entered only with the <b>no</b> form of this command.
---	--

**Command Default** No static route is configured.

**Command Modes** Global configuration (config)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines** The **ip route topology** command is used to configure static routing under a topology instance. The global topology name is entered when the static route is created in global configuration mode.

**Examples** The following example configures a static route to the 10.0.0.0 network through Ethernet interface 0/0:

```
Device(config)# ip route topology VOICE 10.0.0.0 255.0.0.0 Ethernet 0/0
```

Related Commands	Command	Description
	<b>clear ip route topology</b>	Clears entries from the routing table of a topology.
	<b>ping (MTR)</b>	Diagnoses basic network connectivity through a topology instance.
	<b>show ip protocols topology</b>	Displays the configuration and state of active routing protocol processes under a topology instance.
	<b>show ip route topology</b>	Displays the current state of a topology routing table.
	<b>show topology</b>	Displays status and configuration information for topologies configured with MTR.

# ip topology-accounting

To enable topology accounting for all IPv4 unicast topologies in the VPN Routing/Forwarding (VRF) associated with a particular interface, use the **ip topology-accounting** command in interface configuration mode. To disable topology accounting, use the **no** form of this command.

**ip topology-accounting**

**no ip topology-accounting**

**Syntax Description** This command has no arguments or keywords.

**Command Default** No topology accounting statistics are collected.

**Command Modes** Interface configuration (config-if)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines** This command enables topology accounting for all IPv4 unicast topologies in the VRF associated with a particular interface regardless of whether those topologies are enabled on the interface or not. In Cisco IOS release 12.2(33)SRB, this topology accounting is only supported for the default VRF.

**Examples** The following example shows how to enable topology accounting on FastEthernet interface 1/10:

```
Device(config)# interface FastEthernet 1/10
Device(config-if)# ip topology-accounting
```

Related Commands	Command	Description
	<b>topology-accounting</b>	Enables topology accounting on all of the interfaces in the global address family.

# isis topology disable

To prevent an Intermediate System-to-Intermediate System (IS-IS) process from advertising the interface as part of the topology, use the **isis topology disable** command in interface topology configuration mode. To enable the IS-IS process to advertise the interface as a part of the topology, use the **no** form of this command.

**isis topology disable**

**no isis topology disable**

## Syntax Description

This command has no arguments or keywords.

## Command Default

The IS-IS process advertises the interface as a part of the topology.

## Command Modes

Interface topology configuration (config-if-topology)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

## Usage Guidelines

The **isis topology disable** command is used to prevent an IS-IS process from advertising the interface as a part of the topology without removing the IS-IS or topology configuration from the interface.

## Examples

The following example disables IS-IS routing under the topology instance named VOICE on Ethernet interface 0/0:

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 unicast VOICE
Device(config-if-topology)# isis topology disable
Device(config-if-topology)# end
```

## Related Commands

Command	Description
<b>address-family</b> (IS-IS)	Configures the exchange of address family and subaddress family prefixes.
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

Command	Description
<b>topology</b> (IS-IS)	Configures an IS-IS process to route IP traffic under the specified topology instance.

## maximum routes (MTR)

To set the maximum number of routes that a topology instance will accept and install into the routing information base (RIB), use the **maximum routes** command in address family topology configuration mode. To remove the route limit for the topology instance, use the **no** form of this command.

**maximum routes** *number* [*threshold* [**reinstall** *threshold*]] **warning-only**

**no maximum routes** *number* [*threshold* [**reinstall** *threshold*]] **warning-only**

### Syntax Description

<i>number</i>	Maximum number of routes. The range is 1 to 4294967295.
<i>threshold</i>	(Optional) Threshold percentage, at which warning messages are generated. The range is 1 to 100.
<b>reinstall</b> <i>threshold</i>	(Optional) Configures the threshold percentage, at which routes are reinstalled into the routing table. The range is 1 to 100.
<b>warning-only</b>	(Optional) Configures the device to only display a warning when the maximum route limit has been reached or exceeded.

### Command Default

No default behavior or values.

### Command Modes

Address family topology configuration (config-af-topology)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

The **maximum routes** command is used to set a limit for the number of routes that will be accepted for a topology instance and installed into the RIB. This command can be configured to set the absolute maximum limit, to generate warning messages when the specified percentage of the limit has been reached, and to configure the percentage (low-water mark), at which routes are reinstalled into the RIB after the maximum limit has been reached.

## Examples

The following example shows how to configure the device to accept a maximum of 10000 routes for the VOICE topology and to generate warning messages when 80 percent of the maximum limit has been reached. This example also configures the device to accept routes after the limit has been exceeded but then receded to 40 percent of the maximum number.

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# maximum routes 10000 80 reinstall 40
Device(config-af-topology)# end
```

## Related Commands

Command	Description
<b>all-interfaces</b>	Configures a topology instance to use all interfaces on a device.
<b>exit-topo</b>	Exits routing topology configuration mode, and enters global address family topology configuration mode.
<b>forward-base</b>	Configures the forwarding mode under a topology instance.
<b>shutdown</b>	Temporarily disables a topology instance without removing the topology configuration.
<b>topology (global)</b>	Configures a topology instance.

## neighbor translate-topology

To configure the Border Gateway Protocol (BGP) to translate or move routes from a topology on another device to a topology on the local device, use the **neighbor translate-topology** command in router scope address family topology configuration mode. To disable the topology translation configuration, use the **no** form of this command.

**neighbor** *ip-address* **translate-topology** *number*

**no neighbor** *ip-address* **translate-topology** *number*

### Syntax Description

<i>ip-address</i>	IP address of the neighbor.
<i>number</i>	Topology ID of the neighbor. The range is 1 to 4095.

### Command Default

No routes are translated from a topology on another device.

### Command Modes

Router scope address family topology configuration (config-router-scope-af-topo))

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

### Usage Guidelines

The **neighbor translate-topology** command is used to translate or move routes from a Multitopology Routing (MTR) class-specific topology on a neighbor device to the local topology under which the BGP session is configured. The topology ID identifies the class-specific topology of the neighbor. The routes in the class-specific topology of the neighbor are moved into a local class-specific topology RIB. BGP performs best-path calculation on imported routes and installs these routes into the local class-specific RIB. If a duplicate route is translated, BGP will select and install only one instance of the route per standard BGP best-path calculation behavior.

### Examples

The following example shows how to configure BGP to translate the topology with the 255 ID from the 192.168.3.1 neighbor:

```
Device(config)# router bgp 50000
Device(config-router)# scope global
Device(config-router-scope)# bgp default ipv4-unicast
Device(config-router-scope)# neighbor 192.168.3.1 remote-as 45000
Device(config-router-scope)# address-family ipv4 unicast
Device(config-router-scope-af)# topology VOICE
```

```

Device(config-router-scope-af-topo) # bgp tid 100
Device(config-router-scope-af-topo) # neighbor 192.168.3.1 activate
Device(config-router-scope-af-topo) # neighbor 192.168.3.1 translate-topology 255
Device(config-router-scope-af-topo) # end

```

### Related Commands

Command	Description
<b>bgp tid</b>	Configures BGP to accept routes with a specified topology ID.
<b>clear ip bgp topology</b>	Resets BGP neighbor session information under a topology instance.
<b>import topology</b>	Configures BGP to import or move routes from one topology to another on the same device.
<b>scope</b>	Defines the scope for a BGP routing session and enters router scope configuration mode.
<b>topology (BGP)</b>	Configures a process to route IP traffic under the specified topology instance.

# neighbor transport

To enable a TCP transport session option for a Border Gateway Protocol (BGP) session, use the **neighbor transport** command in router or address family configuration mode. To disable a TCP transport session option for a BGP session, use the **no** form of this command.

**neighbor** {*ip-address*|*peer-group-name*} **transport** {**connection-mode** {**active**|**passive**}|**path-mtu-discovery** [**disable**]|**multi-session**|**single-session**}

**no neighbor** {*ip-address*|*peer-group-name*} **transport** {**connection-mode**|**path-mtu-discovery**|**multi-session**|**single-session**}

## Syntax Description

<i>ip-address</i>	IP address of the BGP neighbor.
<i>peer-group-name</i>	Name of a BGP peer group.
<b>connection-mode</b>	Specifies the type of connection (active or passive).
<b>active</b>	Specifies an active connection.
<b>passive</b>	Specifies a passive connection.
<b>path-mtu-discovery</b>	Enables TCP transport path maximum transmission unit (MTU) discovery. TCP path MTU discovery is enabled by default.
<b>multi-session</b>	Enables a separate TCP transport session for each address family.
<b>single-session</b>	Enables all address families to use a single TCP transport session.
<b>disable</b>	Disables TCP path MTU discovery.

## Command Default

If this command is not configured, TCP path MTU discovery is enabled by default, but no other TCP transport session options are enabled.

## Command Modes

Router configuration (config-router)  
Address family configuration (config-router-af)

## Command History

Release	Modification
12.4	This command was introduced.

Release	Modification
12.2(33)SRA	This command was modified. The <b>path-mtu-discovery</b> keyword was added.
12.2(33)SRB	This command was modified. The <b>multi-session</b> , <b>single-session</b> , and <b>disable</b> keywords were added.
12.2SX	This command is supported in the Cisco IOS Release 12.2SX train. Support in a specific 12.2SX release of this train depends on your feature set, platform, and platform hardware.
12.4(20)T	This command was modified. The <b>path-mtu-discovery</b> keyword was added.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

### Usage Guidelines

This command is used to specify various transport options. An active or passive transport connection can be specified for a BGP session. TCP transport path MTU discovery can be enabled to allow a BGP session to take advantage of larger MTU links. Use the **show ip bgp neighbors** command to determine whether TCP path MTU discovery is enabled.

In Cisco IOS Release 12.2(33)SRB and later releases, options can be specified for the transport of address family traffic using a single TCP session or to enable a separate TCP session for each address family. Multiple TCP sessions are used to support Multitopology Routing (MTR), and the single session option is available for backwards compatibility for non-MTR configurations and for scalability purposes.

In Cisco IOS Release 12.2(33)SRB and later releases, the ability to disable TCP path MTU discovery, for a single neighbor or for an inheriting peer or peer group, was added. If you use the **disable** keyword to disable discovery, discovery is also disabled on any peer or peer group that inherits the template in which you disabled discovery.

### Examples:

The following example shows how to configure the TCP transport connection to be active for a single internal BGP (iBGP) neighbor:

```
router bgp 45000
 neighbor 172.16.1.2 remote-as 45000
 neighbor 172.16.1.2 activate
 neighbor 172.16.1.2 transport connection-mode active
end
```

The following example shows how to configure the TCP transport connection to be passive for a single external BGP (eBGP) neighbor:

```
router bgp 45000
 neighbor 192.168.1.2 remote-as 40000
 neighbor 192.168.1.2 activate
 neighbor 192.168.1.2 transport connection-mode passive
end
```

The following example shows how to disable TCP path MTU discovery for a single BGP neighbor:

```
router bgp 45000
 neighbor 172.16.1.2 remote-as 45000
 neighbor 172.16.1.2 activate
 no neighbor 172.16.1.2 transport path-mtu-discovery
end
```

The following example shows how to reenable TCP path MTU discovery for a single BGP neighbor, if TCP path MTU discovery is disabled:

```
router bgp 45000
 neighbor 172.16.1.2 remote-as 45000
 neighbor 172.16.1.2 activate
 neighbor 172.16.1.2 transport path-mtu-discovery
end
```

The following example shows how to enable a separate TCP session for each address family for an MTR topology configuration:

```
router bgp 45000
 scope global
  neighbor 172.16.1.2 remote-as 45000
  neighbor 172.16.1.2 transport multi-session
  address-family ipv4
    topology VIDEO
    bgp tid 100
  neighbor 172.16.1.2 activate
end
```

The following example shows how to disable TCP path MTU discovery and verify that it is disabled:

```
router bgp 100
 bgp log-neighbor-changes
 timers bgp 0 0
 redistribute static
 neighbor 10.4.4.4 remote-as 100
 neighbor 10.4.4.4 update-source Loopback 0
!end
Device# show ip bgp neighbors 10.4.4.4 | include path
    Used as bestpath:          n/a          0
    Used as multipath:         n/a          0
    Transport(tcp) path-mtu-discovery is enabled
Option Flags: nagle, path mtu capable
Device#
Device# configure terminal
Device(config)# router bgp 100
Device(config-router)# neighbors 10.4.4.4 transport path-mtu-discovery disable
Device(config-router)# end
Device# show ip bgp neighbor 10.4.4.4 | include path
    Used as bestpath:          n/a          0
    Used as multipath:         n/a          0
    Transport(tcp) path-mtu-discovery is disabled
```

## Related Commands

Command	Description
<b>bgp tid</b>	Configures BGP to accept routes with a specified topology ID.
<b>bgp transport</b>	Enables transport session parameters globally for all BGP neighbor sessions.
<b>scope</b>	Defines the scope for a BGP routing session and enters router scope configuration mode.
<b>show ip bgp neighbors</b>	Displays information about BGP and TCP connections to neighbors.
<b>topology (BGP)</b>	Configures a process to route IP traffic under the specified topology instance.



## ping (MTR)

To ping a destination within a specific topology for Multitopology Routing (MTR), use the **ping** command in user EXEC or privileged EXEC mode.

**ping** [*vrf vrf-name*] **topology** *topology-name* [*protocol*] [*target-address*] [*source-address*]

### Syntax Description

<b>vrf</b> <i>vrf-name</i>	(Optional) Specifies the name of a VPN routing and forwarding (VRF) instance.
<b>topology</b> <i>topology-name</i>	(Optional) Specifies the name of a topology.
<i>protocol</i>	Supported protocol. The default is IP. If a protocol is not specified at the command line, it will be required in the <b>ping</b> system dialog.
<i>target-address</i>	(Optional) Target IP address or hostname of the system to ping. If a target IP address or a hostname is not specified at the command line, it will be required in the <b>ping</b> system dialog.
<i>source-address</i>	(Optional) Source address initiating the ping. If a source address is not specified at the command line, it will be required in the <b>ping</b> system dialog.

### Command Default

No default behavior or values.

### Command Modes

User EXEC (>)  
Privileged EXEC (#)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

The **ping** (MTR) command is used to send an echo request to a topology instance. The functionality of this command is similar to the standard **ping** command used in Cisco software. Ping output can help you evaluate path-to-host reliability, delays over the path, and whether the host can be reached or is functioning.

The **topology** *topology-name* keyword and argument and the DiffServ Code Point (DSCP) option in the extended ping system dialog are displayed only if there is a topology configured on the device.

If you enter the **ping** command without any other syntax (**ping**<cr>), an interactive system dialog prompts you for the additional syntax appropriate to the protocol you specify (see the “Examples” section).

## Examples

After you enter the **ping** command in privileged EXEC mode, the system prompts you for a protocol. The default protocol is IP.

If you enter a hostname or address on the same line as the **ping** command, the default action is taken as appropriate for the protocol type of that name or address.

The following example is sample dialog from the **ping** command using default values. The specific dialog varies somewhat from protocol to protocol.

```
Device# ping
Protocol [ip]:
Target IP address: 192.168.7.27
Repeat count [5]:
Datagram size [100]:
Timeout in seconds [2]:
Extended commands [n]:y
Source address of interface: 10.0.20.1
DSCP Value [0]:
! The Type of Service (TOS) is displayed below only if the DSCP value is 0.
Type of Service [0]:
Set DF bit in IP header? [no]:
Validate reply data? [no]:
Data pattern [0xABCD]:
Loose, Strict, Record, Timestamp, Verbose [none]:
Sweep range of sizes [n]:
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 192.168.7.27, timeout is 2 seconds:
!!!!
Success rate is 100 percent, round-trip min/avg/max = 1/2/4 ms
```

The table below describes the significant fields shown in the display.

**Table 1: ping Field Descriptions for IP**

Field	Description
Protocol [ip]:	Prompts for a supported protocol. Default is IP.
Target IP address:	Prompts for the IP address or hostname of the destination node you plan to ping. If you have specified a supported protocol other than IP, enter an appropriate address for that protocol here. Default: none.
Repeat count [5]:	Number of ping packets that will be sent to the destination address. Default: 5.
Datagram size [100]:	Size of the ping packet (in bytes). Default: 100 bytes.
Timeout in seconds [2]:	Timeout interval. Default: 2 (seconds).

Field	Description
Extended commands [n]:	Specifies whether a series of additional commands appears.
DSCP Value [10]:	DiffServ Code Point. Six bits in the ToS. These are the bits used to mark the packet.
Sweep range of sizes [n]:	Allows you to vary the sizes of the echo packets being sent. This capability is useful for determining the minimum sizes of the maximum transmission units (MTUs) configured on the nodes along the path to the destination address. Packet fragmentation contributing to performance problems can then be reduced.
!!!!	Each exclamation point (!) indicates receipt of a reply. A period (.) indicates that the network server timed out while waiting for a reply. Other characters may appear in the ping output display, depending on the protocol type.
Success rate is 100 percent	Percentage of packets successfully echoed back to the device. Anything less than 80 percent is usually considered problematic.
round-trip min/avg/max = 1/2/4 ms	Round-trip travel time intervals for the protocol echo packets, including minimum/average/maximum (in milliseconds).

### Related Commands

Command	Description
<b>clear ip route topology</b>	Clears entries from the routing table of a topology.
<b>ip route topology</b>	Configures static routing under a topology instance.
<b>show ip protocols topology</b>	Displays the configuration and state of active routing protocol processes under a topology instance.
<b>show ip route topology</b>	Displays the current state of a topology routing table.
<b>show topology</b>	Displays status and configuration information for topologies configured with MTR.

## policy-map type class-routing ipv4 unicast

To create or modify a policy map for Multitopology Routing (MTR) and enter policy map configuration mode, use the **policy-map type class-routing ipv4 unicast** command in global configuration mode. To delete the policy map, use the **no** form of this command.

**policy-map type class-routing ipv4 unicast** *policy-map-name*

**no policy-map type class-routing ipv4 unicast** *policy-map-name*

### Syntax Description

<i>policy-map-name</i>	Name of the MTR policy map.
------------------------	-----------------------------

### Command Default

An MTR policy map name is not created.

### Command Modes

Global configuration (config)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

The policy map name created by the **policy-map type class-routing ipv4 unicast** command is referenced by the **service-policy type class-routing** command to enable MTR.

### Examples

In the following example, an MTR policy map named BLUE is created that will be attached to the service policy to enable MTR:

```
Device(config)# policy-map type class-routing ipv4 unicast BLUE
Device(config-pmap)# class DATA
Device(config-pmap-c)# select-topology VOICE
Device(config-pmap-c)# exit
Device(config-pmap)# exit
Device(config)# global-address-family ipv4
Device(config-af)# service-policy type class-routing BLUE
Device(config-af)# end
```

### Related Commands

Command	Description
<b>service-policy type class-routing</b>	Attaches the service policy to the policy map for MTR traffic classification and enables MTR.



## priority (OSPF)

To set the priority that an Open Shortest Path First (OSPF) process assigns to a topology instance for shortest path first (SPF) calculations, use the **priority** command in router address family topology configuration mode. To return the priority to the default value, use the **no** form of this command.

**priority** *number*

**no priority**

### Syntax Description

<i>number</i>	Priority number for a topology instance. The range is 0 to 127. The default is 64.
---------------	--

### Command Default

The default priority number is 64.

### Command Modes

Router address family topology configuration (config-router-af-topology)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.

### Usage Guidelines

The **priority** command is used to set the OSPF processing order for topology instances when an SPF calculation is scheduled and ready to run for multiple topologies. The topology with the highest priority number is processed first. The default priority value is 64.

### Examples

The following example assigns the VOICE topology instance the highest possible priority for SPF calculations:

```
Device(config)# router ospf 1
Device(config-router)# address-family ipv4
Device(config-router-af)# topology VOICE tid 10
Device(config-router-af-topology)# priority 127
Device(config-router-af-topology)# end
```

### Related Commands

Command	Description
<b>address-family</b> (OSPF)	Configures address family and subaddress family IP prefix exchange.
<b>topology</b> (OSPF)	Configures an OSPF process to route IP traffic under the specified topology instance.



## router eigrp (MTR)

To configure the Enhanced Interior Gateway Routing Protocol (EIGRP) process for Multitopology Routing (MTR) and enter router configuration mode, use the **router eigrp** command in global configuration mode. To shut down an EIGRP routing process, use the **no** form of this command.

**router eigrp** *block-name*

**no router eigrp** *block-name*

### Syntax Description

<i>block-name</i>	Routing configuration block name.
-------------------	-----------------------------------

### Command Default

This command is disabled by default.

### Command Modes

Global configuration (config)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

The **router eigrp** *block-name* command allows access to MTR topology commands in router address family configuration mode. The topology commands are blocked if using the legacy **router eigrp** *as-number* command. You can use the **router eigrp** *block-name* command if MTR is not configured, but the topology defaults to the base topology.

### Examples

The following example shows how to configure EIGRP for MTR and how to configure an IPv4 address family to associate with the MTR service topology named VIDEO:

```
Device(config)# router eigrp mtr
Device(config-router)# address-family ipv4 autonomous-system 5
Device(config-router-af)# topology VIDEO tid 100
```

### Related Commands

Command	Description
<b>router eigrp</b>	Configures the EIGRP process.

## route-replicate

To enable the replication of routes from one topology to another, use the **route-replicate** command in address family topology configuration mode. To disable route replication, use the **no** form of this command.

**route-replicate from** {multicast|unicast}[**topology** {base| *name*}] *protocol* [**route-map** *map-tag* | **vrf** *name*]  
**no route-replicate from** {multicast|unicast}[**topology** {base| *name*}] *protocol* [**route-map** *map-tag* | **vrf** *name*]

### Syntax Description

<b>from</b>	Specifies from which topology route replication is enabled.
<b>multicast</b>	Specifies a multicast subaddress family identifier (SAFI).
<b>unicast</b>	Specifies a unicast SAFI.
<b>topology</b>	(Optional) Specifies the source topology.
<b>base</b>	Specifies the base topology.
<i>name</i>	Topology instance name.

<i>protocol</i>	<p>The owning protocol that is the source of the route. Valid keywords include:</p> <ul style="list-style-type: none"> <li>• <b>all</b>—Specifies all routes.</li> <li>• <b>bgp</b>—Specifies Border Gateway Protocol. An autonomous system number must be specified with this keyword. The range is 1 to 65535.</li> <li>• <b>eigrp</b>—Specifies Enhanced Interior Gateway Routing Protocol. An autonomous system number or a routing configuration block name must be specified with this keyword. The range is 1 to 65535; the block name can be up to 32 characters in length.</li> <li>• <b>isis</b>—Specifies ISO Intermediate System-to-Intermediate System (IS-IS). An optional ISO area routing tag or the <b>route-map</b> keyword can be used.</li> <li>• <b>mobile</b>—Specifies mobile routes. The optional <b>route-map</b> keyword can be used.</li> <li>• <b>odr</b>—Specifies on-demand stub routes. The optional <b>route-map</b> keyword can be used.</li> <li>• <b>ospf</b>—Specifies Open Shortest Path First (OSPF). A process ID must be specified with this keyword. The range is 1 to 65535. The optional <b>route-map</b> keyword or <b>vrfname</b> keyword and argument can be used.</li> <li>• <b>rip</b>—Specifies Routing Information Protocol. The optional <b>route-map map-tag</b> keyword and argument can be used.</li> <li>• <b>static</b>—Specifies static routes. The optional <b>route-map map-tag</b> keyword and argument can be used.</li> </ul>
<b>route-map</b> <i>map-tag</i>	(Optional) Specifies a route map filter.
<b>vrf</b> <i>name</i>	(Optional) Specifies a VPN routing and forwarding (VRF) instance name.

**Command Default**      Route replication is disabled.

**Command Modes**      Address family topology configuration (config-af-topology)

**Command History**

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
15.2(1)S	This command was modified. The behavior of the command changed, and the software does not allow you to replicate routes from a multicast RIB to a unicast RIB. For more information, see the "Usage Guidelines."

**Usage Guidelines**

Use this command to replicate routes from one topology to another. Route replication supports legacy multicast behavior and may be used to support scenarios in which not all protocols support multiple topologies.

In Cisco IOS Release 15.2(1)S, you cannot replicate routes from a multicast RIB to a unicast RIB. However, you can replicate routes from a multicast RIB to a multicast RIB or replicate routes from a unicast RIB to a multicast RIB.

For the **multicast** and **unicast** keywords, the address family identifier (AFI) is the same as the AFI of the destination table.

If the forwarding mode of the destination topology is set to incremental mode (forward-base), the route replication configuration commands are rejected.

If the **mobile**, **odr**, **rip**, or **static** keyword is used for the *protocol* argument, the optional **vrf name** keyword and argument cannot be used.

**Examples**

The following example shows how to configure the multicast topology to replicate OSPF routes from the VOICE topology. The routes are filtered through the map1 route map before they are installed in the multicast routing table.

```
Device(config)# ip multicast-routing
Device(config)# ip multicast rpf multitopology
Device(config)# global-address-family ipv4 multicast
Device(config-af)# topology base
Device(config-af-topology)# route-replicate from unicast topology VOICE ospf 3 route-map
map1
```





## S through U

---

- [scope, page 81](#)
- [select-topology, page 83](#)
- [service-policy type class-routing, page 84](#)
- [show ip bgp topology, page 86](#)
- [show ip eigrp topology, page 94](#)
- [show ip interface \(MTR\), page 101](#)
- [show ip ospf interface, page 103](#)
- [show ip ospf topology-info, page 107](#)
- [show ip protocols topology, page 109](#)
- [show ip route multicast, page 112](#)
- [show ip route topology, page 114](#)
- [show ip static route, page 117](#)
- [show ip static route bfd, page 119](#)
- [show ip static route summary, page 121](#)
- [show ip traffic \(MTR\), page 122](#)
- [show isis neighbors, page 124](#)
- [show mtm table, page 127](#)
- [show policy-map type class-routing ipv4 unicast, page 129](#)
- [show snmp context mapping, page 131](#)
- [show topology, page 133](#)
- [shutdown \(MTR\), page 137](#)
- [snmp context, page 139](#)
- [topology \(BGP\), page 142](#)
- [topology \(EIGRP\), page 144](#)

- [topology \(global\), page 146](#)
- [topology \(interface\), page 148](#)
- [topology \(IS-IS\), page 150](#)
- [topology \(OSPF\), page 152](#)
- [topology-accounting, page 154](#)
- [traceroute, page 156](#)
- [use-topology, page 160](#)

# scope

To define the scope for a Border Gateway Protocol (BGP) routing session and to enter router scope configuration mode, use the **scope** command in router configuration mode. To remove the scope configuration, use the **no** form of this command.

**scope** {**global**| **vrf** *vrf-name*}

**no scope** {**global**| **vrf** *vrf-name*}

## Syntax Description

<b>global</b>	Configures BGP to use the global routing table or a specific topology table.
<b>vrf</b>	Configures BGP to use a specific VRF routing table.
<i>vrf-name</i>	Name of an existing VRF.

## Command Default

No scope is defined for a BGP routing session.

## Command Modes

Router configuration (config-router)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

## Usage Guidelines

A new configuration hierarchy, named scope, has been introduced into the BGP protocol. To implement Multitopology Routing (MTR) support for BGP, the scope hierarchy is required, but the scope hierarchy is not limited to MTR use. The scope hierarchy introduces some new configuration modes such as router scope configuration mode. Router scope configuration mode is entered by configuring the **scope** command in router configuration mode, and a collection of routing tables is created when this command is entered. The scope is configured to isolate routing calculation for a single network (globally) or on a per-VRF basis, and BGP commands configured in routing scope configuration mode are referred to as scoped commands. The scope hierarchy can contain one or more address families.

The BGP command-line interface (CLI) has been modified to provide backwards compatibility for pre-MTR BGP configuration and to provide a hierarchal implementation of MTR. From router scope configuration mode, MTR is configured first by entering the **address-family** command to enter the desired address family and then by entering the **topology** command to define the topology

**Note**

Configuring a scope for a BGP routing process removes CLI support for pre-MTR-based configuration.

**Examples**

The following example defines a global scope that includes both unicast and multicast topology configurations. Another scope is specifically defined only for the VRF named DATA.

```
Device(config)# router bgp 45000
Device(config-router)# scope global
Device(config-router-scope)# bgp default ipv4-unicast
Device(config-router-scope)# neighbor 172.16.1.2 remote-as 45000
Device(config-router-scope)# neighbor 192.168.3.2 remote-as 50000
Device(config-router-scope)# address-family ipv4 unicast
Device(config-router-scope-af)# topology VOICE
Device(config-router-scope-af)# bgp tid 100
Device(config-router-scope-af)# neighbor 172.16.1.2 activate
Device(config-router-scope-af)# exit
Device(config-router-scope)# address-family ipv4 multicast
Device(config-router-scope-af)# topology base
Device(config-router-scope-af-topo)# neighbor 192.168.3.2 activate
Device(config-router-scope-af-topo)# exit
Device(config-router-scope-af)# exit
Device(config-router-scope)# exit
Device(config-router)# scope vrf DATA

Device(config-router-scope)# neighbor 192.168.1.2 remote-as 40000

Device(config-router-scope)# address-family ipv4
Device(config-router-scope-af)# neighbor 192.168.1.2 activate

Device(config-router-scope-af)# end
```

**Related Commands**

Command	Description
<b>bgp tid</b>	Configures BGP to accept routes with a specified topology ID.
<b>topology (BGP)</b>	Configures a process to route IP traffic under the specified topology instance.

# select-topology

To attach the policy map to the topology, use the **select-topology** command in policy map class configuration mode. To remove the association of the policy map with the topology, use the **no** form of this command.

**select-topology** *topology-name*

**no select-topology** *topology-name*

## Syntax Description

<i>topology-name</i>	Name of the topology.
----------------------	-----------------------

## Command Default

No policy map is attached to the topology.

## Command Modes

Policy map class configuration (config-pmap-c)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Examples

In the following example, the topology VOICE is configured to be attached to the policy map BLUE:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# all-interfaces
Device(config-af-topology)# exit
Device(config-af)# exit
Device(config)# class-map match-any DATA
Device(config-cmap)# match ip dscp 9
Device(config-cmap)# exit
Device(config)# policy-map type class-routing ipv4 unicast BLUE
Device(config-pmap)# class DATA
Device(config-pmap-c)# select-topology VOICE
Device(config-pmap-c)# exit
Device(config-pmap)# exit
Device(config)# global-address-family ipv4
Device(config-af)# service-policy type class-routing BLUE
Device(config-af)# end
```

# service-policy type class-routing

To attach the service policy to the policy map for Multitopology Routing (MTR) traffic classification and to activate MTR, use the **service-policy type class-routing** command in global address family configuration mode. To detach the service policy from the policy map, use the **no** form of this command.

**service-policy type class-routing** *policy-map-name*

**no service-policy type class-routing** *policy-map-name*

## Syntax Description

<i>policy-map-name</i>	Policy map name.
------------------------	------------------

## Command Default

The service policy is not attached.

## Command Modes

Global address family configuration (config-af)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

The **service-policy type class-routing** command is used to attach a service policy to a policy map for MTR traffic classification. MTR traffic classification is used to configure topology-specific forwarding behaviors when multiple topologies are configured on the same device. Class-specific packets are associated with the corresponding topology table forwarding entries.

After the **service-policy type class-routing** command is entered, MTR is activated.

## Examples

The following example shows how to configure traffic classification for a topology instance named VOICE:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# all-interfaces
Device(config-af-topology)# exit
Device(config-af)# exit
Device(config)# class-map match-any DATA
Device(config-cmap)# match ip dscp 9
Device(config-cmap)# exit
Device(config)# policy-map type class-routing ipv4 unicast BLUE
Device(config-pmap)# class DATA
Device(config-pmap-c)# select-topology VOICE
Device(config-pmap-c)# exit
Device(config-pmap)# exit
Device(config)# global-address-family ipv4
```

```
Device(config-af)# service-policy type class-routing BLUE
Device(config-af)# end
```

**Related Commands**

Command	Description
<b>class-map</b>	Creates a class map to match packets to a specific class of traffic.
<b>global-address-family ipv4</b>	Enters global address family configuration mode to configure MTR.
<b>exit-global-af</b>	Exits global address family configuration mode and enters global configuration mode.
<b>policy-map type class-routing ipv4 unicast</b>	Creates or modifies a policy map for MTR and enters policy map configuration mode.

# show ip bgp topology

To display topology instance information from the Border Gateway Protocol (BGP) table, use the **show ip bgp topology** command in privileged EXEC mode.

## With BGP show Command Argument

```
show ip bgp topology {*| topology} [ bgp-keyword ]
```

## With IP Prefix and Mask Length Syntax

```
show ip bgp topology {*| topology} [ip-prefix/length [bestpath] [longer-prefixes [injected]] [multipaths] [shorter-prefixes [ mask-length ]] [subnets]]
```

## With Network Address Syntax

```
show ip bgp topology {*| topology} [network-address [mask] bestpath| multipaths] [bestpath] [longer-prefixes [injected]] [multipaths] [shorter-prefixes [ mask-length ]] [subnets]]
```

## Syntax Description

<i>*</i>	Displays all routing topology instances.
<i>topology</i>	Name of topology for which information is displayed.
<i>bgp-keyword</i>	(Optional) Argument representing a <b>show ip bgp</b> command keyword that can be added to this command. See the Additional show ip bgp Commands and Descriptions table below.
<i>ip-prefix / length</i>	(Optional) The IP prefix address (in dotted decimal format) and the length of the mask (0 to 32). The slash mark must be included.
<b>bestpath</b>	(Optional) Displays the bestpath for the specified prefix.
<b>longer-prefixes</b>	(Optional) Displays the route and more specific routes.
<b>injected</b>	(Optional) Displays more specific routes that were injected because of the specified prefix.
<b>multipaths</b>	(Optional) Displays the multipaths for the specified prefix.
<b>shorter-prefixes</b>	(Optional) Displays the less specific routes.
<i>mask-length</i>	(Optional) The length of the mask is 0 to 32. Prefixes longer than the specified mask length are displayed.

<b>subnets</b>	(Optional) Displays the subnet routes for the specified prefix.
<i>network-address</i>	(Optional) The IP address of a network in the BGP routing table.
<i>mask</i>	(Optional) The mask of the network address, in dotted decimal format.

**Command Modes**

Privileged EXEC (#)

**Command History**

Release	Modification
12.2(33)SRB	This command was introduced.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

**Usage Guidelines**

The table below displays optional additional **show ip bgp** command keywords that can be configured with the **show ip bgp topology** command. Replace the *bgp-keyword* argument with the appropriate keyword from the table. For more details about each command in its **show ip bgp *bgp-keyword*** form, see the Cisco IOS IP Routing Protocols Command Reference.

**Table 2: Additional show ip bgp Commands and Descriptions**

Command	Description
<b>cidr-only</b>	Display only routes with non-natural netmasks.
<b>community</b>	Displays routes that match a specified community.
<b>community-list</b>	Displays routes that match a specified community list.
<b>dampening</b>	Displays paths suppressed because of dampening (BGP route from peer is up and down).
<b>extcommunity-list</b>	Displays routes that match a specified extcommunity list.
<b>filter-list</b>	Displays routes that conform to the filter list.
<b>import</b>	Display route topology import and/or export activity.
<b>inconsistent-as</b>	Displays only routes that have inconsistent autonomous systems of origin.

Command	Description
<b>injected-paths</b>	Displays all injected paths.
<b>labels</b>	Displays labels for IPv4 NLRI specific information.
<b>neighbors</b>	Displays details about TCP and BGP neighbor connections.
<b>oer-paths</b>	Displays all OER-managed path information.
<b>paths</b> [ <i>regex</i> ]	Displays autonomous system path information. If the optional <i>regex</i> argument is entered, the autonomous system paths that are displayed match the autonomous system path regular expression.
<b>peer-group</b>	Displays information about peer groups.
<b>pending-prefixes</b>	Displays prefixes that are pending deletion.
<b>prefix-list</b>	Displays routes that match a specified prefix list.
<b>quote-regex</b>	Displays routes that match the quoted autonomous system path regular expression.
<b>regex</b>	Displays routes that match the autonomous system path regular expression.
<b>replication</b>	Displays the replication status update groups.
<b>rib-failure</b>	Displays bgp routes that failed to install in the routing table (RIB).
<b>route-map</b>	Displays routes matching the specified route map.
<b>summary</b>	Displays a summary of BGP neighbor status.
<b>template</b>	Displays peer-policy or peer-session templates.
<b>update-group</b>	Displays information on update groups.

## Examples

The following example shows summary output for the **show ip bgp topology** command. Information is displayed about BGP neighbors configured to use the MTR topology named VIDEO.

```
Device# show ip bgp topology VIDEO summary
```

```
BGP router identifier 192.168.3.1, local AS number 45000
BGP table version is 1, main routing table version 1
Neighbor      V    AS MsgRcvd MsgSent  TblVer  InQ  OutQ  Up/Down  State/PfxRcd
```

```

172.16.1.2      4 45000      289      289      1      0      0 04:48:44      0
192.168.3.2    4 50000      3         3         1      0      0 00:00:27      0

```

The table below describes the significant fields shown in the display.

**Table 3: show ip bgp topology summary Field Descriptions**

Field	Description
BGP router identifier	IP address of the networking device.
local AS number	Number of the local autonomous system.
BGP table version	Internal version number of the table. This number is incremented whenever the table changes.
main routing table version	Last version of the BGP database that was injected into the main routing table.
Neighbor	IP address of a neighbor.
V	BGP version number communicated to that neighbor.
AS	Autonomous system number.
MsgRcvd	BGP messages received from that neighbor.
MsgSent	BGP messages sent to that neighbor.
TblVer	Last version of the BGP database that was sent to that neighbor.
InQ	Number of messages from that neighbor waiting to be processed.
OutQ	Number of messages waiting to be sent to that neighbor.
Up/Down	The length of time that the BGP session has been in the Established state, or the current state if it is not Established.
State/PfxRcd	<p>Current state of the BGP session/the number of prefixes that the device has received from a neighbor or peer group. When the maximum number (as set by the <b>neighbor maximum-prefix</b> command) is reached, the string "PfxRcd" appears in the entry, the neighbor is shut down, and the connection is Idle.</p> <p>An (Admin) entry with Idle status indicates that the connection has been shut down using the <b>neighbor shutdown</b> command.</p>

The following is partial output for the **show ip bgp topology** command when the **neighbors** keyword is used. Information is displayed for each neighbor that is configured to use the topology named VIDEO, and the output is similar to the output for the **show ip bgp neighbors** command with the addition of topology-related information.

Device# **show ip bgp topology VIDEO neighbors**

```

BGP neighbor is 172.16.1.2, remote AS 45000, internal link
  BGP version 4, remote router ID 192.168.2.1
  BGP state = Established, up for 04:56:30
  Last read 00:00:23, last write 00:00:21, hold time is 180, keepalive interval is 60
seconds
  Neighbor sessions:
    1 active, is multisession capable
  Neighbor capabilities:
    Route refresh: advertised and received(new)
  Message statistics, state Established:
    InQ depth is 0
    OutQ depth is 0

    Sent      Rcvd
  Opens:          1      1
  Notifications:  0      0
  Updates:        0      0
  Keepalives:    296    296
  Route Refresh:  0      0
  Total:         297    297
  Default minimum time between advertisement runs is 0 seconds
For address family: IPv4 Unicast topology VIDEO
Session: 172.16.1.2 session 1
BGP table version 1, neighbor version 1/0
Output queue size : 0
Index 1, Offset 0, Mask 0x2
1 update-group member
Topology identifier: 100
.
.
.
  Address tracking is enabled, the RIB does have a route to 172.16.1.2
  Address tracking requires at least a /24 route to the peer
  Connections established 1; dropped 0
  Last reset never
  Transport(tcp) path-mtu-discovery is enabled
Connection state is ESTAB, I/O status: 1, unread input bytes: 0
Minimum incoming TTL 0, Outgoing TTL 255
Local host: 172.16.1.1, Local port: 11113
Foreign host: 172.16.1.2, Foreign port: 179
.
.
.
BGP neighbor is 192.168.3.2, remote AS 50000, external link
  BGP version 4, remote router ID 192.168.3.2
  BGP state = Established, up for 00:08:24
  Last read 00:00:21, last write 00:00:20, hold time is 180, keepalive interval is 60 seconds

  Neighbor sessions:
    1 active, is multisession capable
  Neighbor capabilities:
    Route refresh: advertised and received(new)
  Message statistics, state Established:
    InQ depth is 0
    OutQ depth is 0

    Sent      Rcvd
  Opens:          1      1
  Notifications:  0      0
  Updates:        0      0
  Keepalives:    10     10
  Route Refresh:  0      0
  Total:         11     11
  Default minimum time between advertisement runs is 30 seconds
For address family: IPv4 Unicast topology VIDEO
Session: 192.168.3.2 session 1

```

```

BGP table version 1, neighbor version 1/0
Output queue size : 0
Index 2, Offset 0, Mask 0x4
2 update-group member
Topology identifier: 100
.
.
.
Address tracking is enabled, the RIB does have a route to 192.168.3.2
Address tracking requires at least a /24 route to the peer
Connections established 1; dropped 0
Last reset never
Transport(tcp) path-mtu-discovery is enabled
Connection state is ESTAB, I/O status: 1, unread input bytes: 0
Minimum incoming TTL 0, Outgoing TTL 1
Local host: 192.168.3.1, Local port: 11133
Foreign host: 192.168.3.2, Foreign port: 179
.
.
.

```

The table below describes the significant fields shown in the display.

**Table 4: show ip bgp topology neighbors Field Descriptions**

Field	Description
BGP neighbor	IP address of the BGP neighbor.
remote AS	Autonomous system number of the neighbor.
local AS 300 no-prepend (not shown in display)	Verifies that the local autonomous system number is not prepended to received external routes. This output supports the hiding of the local autonomous systems when migrating autonomous systems.
internal link	“internal link” is displayed for internal BGP (iBGP) neighbors. “external link” is displayed for external BGP (eBGP) neighbors.
BGP version	BGP version being used to communicate with the remote device.
remote router ID	IP address of the neighbor.
BGP state	Finite state machine (FSM) stage of session negotiation.
up for	Time, in hh:mm:ss, for which the underlying TCP connection has been in existence.
Last read	Time, in hh:mm:ss, since BGP last received a message from this neighbor.
last write	Time, in hh:mm:ss, since BGP last sent a message to this neighbor.

Field	Description
hold time	Time, in seconds, for which BGP will maintain the session with this neighbor without receiving a messages.
keepalive interval	Time interval, in seconds, at which keepalive messages are transmitted to this neighbor.
Neighbor sessions	Number of BGP neighbor sessions configured and whether they are enabled as a single TCP session or as multiple TCP sessions.
Neighbor capabilities	BGP capabilities advertised and received from this neighbor. "advertised and received" is displayed when a capability is successfully exchanged between two devices.
Route refresh	Status of the route refresh capability.
Message statistics	Statistics organized by message type.
InQ depth	Number of messages in the input queue.
OutQ depth	Number of messages in the output queue.
Sent	Total number of transmitted messages.
Rcvd	Total number of received messages.
Opens	Number of open messages sent and received.
Notifications	Number of notification (error) messages sent and received.
Updates	Number of update messages sent and received.
Keepalives	Number of keepalive messages sent and received.
Route Refresh	Number of route refresh request messages sent and received.
Total	Total number of messages sent and received.
Default minimum time between advertisement runs	Time, in seconds, between advertisement transmissions.
For address family	Address family for which the following fields refer.
Session	IP address and number assigned to the TCP session.

Field	Description
BGP table version	Internal version number of the table. This is the primary routing table with which the neighbor has been updated. The number increments when the table changes.
neighbor version	Number used by the software to track prefixes that have been sent and those that need to be sent.
Topology identifier	Number that is associated with an MTR topology.
Connections established	Number of times a TCP and BGP connection has been successfully established.
dropped	Number of times that a valid session has failed or been taken down.
Last reset	Time since this peering session was last reset. The reason for the reset is displayed on this line.
External BGP neighbor may be... (not shown in the display)	Indicates that the BGP TTL security check is enabled. The maximum number hops that can separate the local and remote peer is displayed on this line.
Connection state	Connection status of the BGP peer.
Minimum incoming TTL, Outgoing TTL	Number of expected incoming or outgoing TTL packets.
Local host, Local port	IP address of the local BGP speaker and BGP port number.
Foreign host, Foreign port	Neighbor address and BGP destination port number.

**Related Commands**

Command	Description
<b>topology (BGP)</b>	Configures a BGP routing process to route IP for a specified MTR topology instance.

## show ip eigrp topology

To display Enhanced Interior Gateway Routing Protocol (EIGRP) topology table entries, use the **show ip eigrp topology** command in user EXEC or privileged EXEC mode.

**show ip eigrp topology**[*vrf vrf-name*| *autonomous-system-number*| *network* [*mask*]| *prefix*| **active**| **all-links**| **detail-links**| **frr**| **name**| **pending**| **summary**| **zero-successors**]

### Syntax Description

<i>vrf vrf-name</i>	(Optional) Displays information about the specified virtual routing and forwarding (VRF) instance.
<i>autonomous-system-number</i>	(Optional) Autonomous system number.
<i>network</i>	(Optional) Network address.
<i>mask</i>	(Optional) Network mask.
<i>prefix</i>	(Optional) Network prefix in the format <network>/<length>; for example, 192.168.0.0/16.
<b>active</b>	(Optional) Displays all topology entries that are in the active state.
<b>all-links</b>	(Optional) Displays all entries in the EIGRP topology table (including nonfeasible-successor sources).
<b>detail-links</b>	(Optional) Displays all topology entries with additional details.
<b>frr</b>	(Optional) Displays information about Fast Reroute (FRR) loop-free alternates (LFAs).
<b>name</b>	(Optional) Displays the IPv4 topology table name. This name is the topology identifier and shows topology-related information for Multitopology Routing (MTR).
<b>pending</b>	(Optional) Displays all entries in the EIGRP topology table that are either waiting for an update from a neighbor or waiting to reply to a neighbor.
<b>summary</b>	(Optional) Displays a summary of the EIGRP topology table.
<b>zero-successors</b>	(Optional) Displays available routes that have zero successors.

**Command Default**

If this command is used without any of the optional keywords, only topology entries with feasible successors are displayed and only feasible paths are shown.

**Command Modes**

User EXEC (>)  
Privileged EXEC (#)

**Command History**

Release	Modification
10.0	This command was introduced.
12.3(8)T	This command was modified. The output of this command was enhanced to display internal and external EIGRP routes.
12.2(33)SRA	This command was integrated into Cisco IOS Release 12.2(33)SRA.
12.2(33)SRB	This command was modified. The <b>name</b> keyword was added to support MTR.
12.2(33)SXH	This command was integrated into Cisco IOS Release 12.2(33)SXH.
15.0(1)M	This command was modified. The <b>vrf vrf-name</b> keyword-argument pair was added.
12.2(33)SRE	This command was modified. The <b>vrf vrf-name</b> keyword-argument pair was added. The <b>name</b> keyword was removed.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.
15.1(3)S	This command was integrated into Cisco IOS Release 15.1(3)S. The output of the command was enhanced to display information about wide metrics.
Cisco IOS XE Release 3.4S	This command was modified. The output of the command was enhanced to display information about wide metrics.
Cisco IOS XE Release 3.5S	This command was modified. Information about the Equal Cost Multipath (ECMP) mode was included in the command output.
15.2(1)S	This command was modified. Information about the ECMP mode was included in the command output.

Release	Modification
15.2(2)S	This command was modified. The output of the command was enhanced to display route tag values in dotted-decimal format.
Cisco IOS XE Release 3.6S	This command was modified. The output of the command was enhanced to display route tag values in dotted-decimal format.
15.2(3)T	This command was modified. Information about the ECMP mode was included in the command output.
15.2(4)S	This command was modified. The <b>frr</b> keyword was added.
Cisco IOS XE Release 3.7S	This command was modified. The <b>frr</b> keyword was added.
15.1(1)SY	This command was integrated into Cisco IOS Release 15.1(1)SY. The output of the command was enhanced to display information about wide metrics.

### Usage Guidelines

Use the **show ip eigrp topology** command to display topology entries, feasible and nonfeasible paths, metrics, and states. This command can be used without any arguments or keywords to display only topology entries with feasible successors and feasible paths. The **all-links** keyword displays all paths, whether feasible or not, and the **detail-links** keyword displays additional details about these paths.

Use this command to display information about EIGRP named and EIGRP autonomous system configurations. This command displays the same information as the **show eigrp address-family topology** command. We recommend using the **show eigrp address-family topology** command.

### Examples

The following is sample output from the **show ip eigrp topology** command:

```
Device# show ip eigrp topology

EIGRP-IPv4 Topology Table for AS(1)/ID(10.0.0.1)
Codes: P - Passive, A - Active, U - Update, Q - Query, R - Reply,
       r - Reply status, s - sia status
P 10.0.0.0/8, 1 successors, FD is 409600
   via 192.0.2.1 (409600/128256), Ethernet0/0
P 172.16.1.0/24, 1 successors, FD is 409600
   via 192.0.2.1 (409600/128256), Ethernet0/0
P 10.0.0.0/8, 1 successors, FD is 281600
   via Summary (281600/0), Null0
P 10.0.1.0/24, 1 successors, FD is 281600
   via Connected, Ethernet0/0
```

The following sample output from the **show ip eigrp topology prefix** command displays detailed information about a single prefix. The prefix shown is an EIGRP internal route.

```
Device# show ip eigrp topology 10.0.0.0/8

EIGRP-IPv4 VR(vr1) Topology Entry for AS(1)/ID(10.1.1.2) for 10.0.0.0/8
  State is Passive, Query origin flag is 1, 1 Successor(s), FD is 82329600, RIB is 643200
```

```

Descriptor Blocks:
10.1.1.1 (Ethernet2/0), from 10.1.1.1, Send flag is 0x0
  Composite metric is (82329600/163840), route is Internal
  Vector metric:
    Minimum bandwidth is 16000 Kbit
    Total delay is 631250000 picoseconds
    Reliability is 255/255
    Load is 1/255
    Minimum MTU is 1500
    Hop count is 1
    Originating router is 10.1.1.1

```

The following sample output from the **show ip eigrp topology prefix** command displays detailed information about a single prefix. The prefix shown is an EIGRP external route.

```

Device# show ip eigrp topology 172.16.1.0/24

EIGRP-IPv4 Topology Entry for AS(1)/ID(10.0.0.1) for 172.16.1.0/24
State is Passive, Query origin flag is 1, 1 Successor(s), FD is 409600, RIB is 643200
Descriptor Blocks:
  172.16.1.0/24 (Ethernet0/0), from 10.0.1.2, Send flag is 0x0
    Composite metric is (409600/128256), route is External
    Vector metric:
      Minimum bandwidth is 10000 Kbit
      Total delay is 6000 picoseconds
      Reliability is 255/255
      Load is 1/255
      Minimum MTU is 1500
      Hop count is 1
      Originating router is 172.16.1.0/24
    External data:
      AS number of route is 0
      External protocol is Connected, external metric is 0
      Administrator tag is 0 (0x00000000)

```

The following sample output from the **show ip eigrp topology prefix** command displays ECMP mode information when the **no ip next-hop-self** command is configured without the **no-ecmp-mode** keyword in an EIGRP topology. The ECMP mode provides information about the path that is being advertised. If there is more than one successor, the top most path will be advertised as the default path over all interfaces, and “ECMP Mode: Advertise by default” will be displayed in the output. If any path other than the default path is advertised, “ECMP Mode: Advertise out <Interface name>” will be displayed.

```

Device# show ip eigrp topology 192.168.10.0/24

EIGRP-IPv4 Topology Entry for AS(1)/ID(10.10.100.100) for 192.168.10.0/24
State is Passive, Query origin flag is 1, 2 Successor(s), FD is 284160
Descriptor Blocks:
  10.100.1.0 (Tunnel0), from 10.100.0.1, Send flag is 0x0
    Composite metric is (284160/281600), route is Internal
    Vector metric:
      Minimum bandwidth is 10000 Kbit
      Total delay is 1100 microseconds
      Reliability is 255/255
      Load is 1/255
      Minimum MTU is 1400
      Hop count is 1
      Originating router is 10.10.1.1
      ECMP Mode: Advertise by default
  10.100.0.2 (Tunnel1), from 10.100.0.2, Send flag is 0x0
    Composite metric is (284160/281600), route is Internal
    Vector metric:
      Minimum bandwidth is 10000 Kbit
      Total delay is 1100 microseconds
      Reliability is 255/255
      Load is 1/255
      Minimum MTU is 1400
      Hop count is 1
      Originating router is 10.10.2.2
      ECMP Mode: Advertise out Tunnel1

```

The following sample output from the **show ip eigrp topology all-links** command displays all paths, even those that are not feasible:

```
Device# show ip eigrp topology all-links

EIGRP-IPv4 Topology Table for AS(1)/ID(10.0.0.1)
Codes: P - Passive, A - Active, U - Update, Q - Query, R - Reply,
       r - reply Status, s - sia Status
P 172.16.1.0/24, 1 successors, FD is 409600, serno 14
   via 10.10.1.2 (409600/128256), Ethernet0/0
   via 10.1.4.3 (2586111744/2585599744), Serial3/0, serno 18
```

The following sample output from the **show ip eigrp topology detail-links** command displays additional details about routes:

```
Device# show ip eigrp topology detail-links

EIGRP-IPv4 Topology Table for AS(1)/ID(10.0.0.1)
Codes: P - Passive, A - Active, U - Update, Q - Query, R - Reply,
       r - reply Status, s - sia Status
P 10.0.0.0/8, 1 successors, FD is 409600, serno 6
   via 10.10.1.2 (409600/128256), Ethernet0/0
P 172.16.1.0/24, 1 successors, FD is 409600, serno 14
   via 10.10.1.2 (409600/128256), Ethernet0/0
P 10.0.0.0/8, 1 successors, FD is 281600, serno 3
   via Summary (281600/0), Null0
P 10.1.1.0/24, 1 successors, FD is 281600, serno 1
   via Connected, Ethernet0/0
```

The following sample output from the **show ip eigrp topology frr** command displays details about the LFAs in the EIGRP topology:

```
Device# show ip eigrp topology frr

EIGRP-IPv4 VR(test) Topology Table for AS(1)/ID(10.1.1.1)
Codes: P - Passive, A - Active, U - Update, Q - Query, R - Reply,
       r - reply Status, s - sia Status

P 192.168.2.0/24, 1 successors, FD is 131153920
   via 10.1.1.2 (131153920/163840), Ethernet0/0
   via 10.3.3.3 (137625600/6635520), Ethernet0/1, [LFA]
P 192.168.1.0/24, 1 successors, FD is 131153920
   via 10.1.1.2 (131153920/163840), Ethernet0/0
   via 10.4.4.4 (137625600/6635520), Ethernet0/2, [LFA]
   via 10.3.3.3 (137625600/6635520), Ethernet0/1
P 192.168.4.0/32, 1 successors, FD is 131727360
   via 10.4.4.4 (131727360/7208960), Ethernet0/2
P 192.168.3.0/24, 1 successors, FD is 131072000
   via Connected, Ethernet0/1
P 192.168.5.0/24, 1 successors, FD is 131072000
   via Connected, Ethernet0/0
P 10.10.10.0/24, 1 successors, FD is 262144000
   via 10.1.1.2 (262144000/196608000), Ethernet0/0
   via 10.4.4.4 (131727360/7208960), Ethernet0/2, [LFA]
```

The table below describes the significant fields shown in the displays.

**Table 5: show ip eigrp topology Field Descriptions**

Field	Description
Codes	<p>State of this topology table entry. Passive and Active refer to the EIGRP state with respect to the destination. Update, Query, and Reply refer to the type of packet that is being sent.</p> <ul style="list-style-type: none"> <li>• P - Passive—Indicates that no EIGRP computations are being performed for this route.</li> <li>• A - Active—Indicates that EIGRP computations are being performed for this route.</li> <li>• U - Update—Indicates that a pending update packet is waiting to be sent for this route.</li> <li>• Q - Query—Indicates that a pending query packet is waiting to be sent for this route.</li> <li>• R - Reply—Indicates that a pending reply packet is waiting to be sent for this route.</li> <li>• r - Reply status—Indicates that EIGRP has sent a query for the route and is waiting for a reply from the specified path.</li> <li>• s - sia status—Indicates that the EIGRP query packet is in stuck-in-active (SIA) status.</li> </ul>
successors	Number of successors. This number corresponds to the number of next hops in the IP routing table. If “successors” is capitalized, then the route or the next hop is in a transition state.
serno	Serial number.
FD	Feasible distance. The feasible distance is the best metric to reach the destination or the best metric that was known when the route became active. This value is used in the feasibility condition check. If the reported distance of the device is less than the feasible distance, the feasibility condition is met and that route becomes a feasible successor. After the software determines that it has a feasible successor, the software need not send a query for that destination.
via	Next-hop address that advertises the passive route.

**Related Commands**

Command	Description
<b>show eigrp address-family topology</b>	Displays entries in the EIGRP address-family topology table.

## show ip interface (MTR)

To display the usability status of interfaces configured for IP or to display IP traffic statistics for all interfaces or for a particular interface, use the **show ip interface** command in user EXEC or privileged EXEC mode.

**show ip interface** [*type number*] [**topology** {*name*| **all**| **base**}] [**stats**]

### Syntax Description

<i>type</i>	(Optional) Interface type.
<i>number</i>	(Optional) Interface number.
<b>topology</b>	(Optional) Displays IP traffic statistics related to a particular topology.
<i>name</i>	(Optional) The topology instance.
<b>all</b>	(Optional) Displays statistics for all topologies.
<b>base</b>	(Optional) Displays base topology statistics.
<b>stats</b>	(Optional) Displays IP traffic statistics without topology awareness, that is, an aggregate of all topologies is displayed.

### Command Default

The Cisco IOS software automatically enters a directly connected route in the routing table if the interface is usable. A usable interface is defined as one that can send and receive packets. If an interface is not usable, the directly connected routing entry is removed from the routing table. Removing the entry allows the software to use dynamic routing protocols to determine backup routes to the network, if any.

If the interface can provide two-way communication, the line protocol is marked *up*. If the interface hardware is usable, the interface is marked *up*.

If you specify an optional interface type and number, you see information for that specific interface.

If you specify no optional arguments, you see information on all the interfaces.

### Command Modes

User EXEC (>)

Privileged EXEC (#)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

### Usage Guidelines

Use the **show ip interface** command to display IP traffic statistics. When the **stats** keyword is used by itself, this command displays IP traffic statistics without topology awareness (an aggregate of all topologies). When the **topology name** keyword and argument are used, the statistics are limited to the IP traffic for that specific topology. The topology **base** keyword is reserved for IPv4 unicast base topology. Use the **all** keyword to display all topologies.

There are no statistics collected for the interface by default. Statistics collection for Multitopology Routing (MTR) is enabled by using the **ip topology-accounting** command in interface configuration mode.

### Examples

The following is sample output from the **show ip interface** command:

```
Device# show ip interface FastEthernet 1/10 stats
```

```
FastEthernet1/10
 5 minutes input rate 0 bits/sec, 0 packet/sec,
 5 minutes output rate 0 bits/sec, 0 packet/sec,
 201 packets input, 16038 bytes
 588 packets output, 25976 bytes
```

The table below describes the significant fields shown in the display.

**Table 6: show ip interface Field Descriptions**

Field	Description
5 minutes input rate 0 bits/sec, 0 packets/sec,	The rate at which packets and bits are being sent into an interface.
5 minutes output rate 0/bits/sec, 0 packets/sec,	The rate at which packets and bits are being sent out of an interface.
201 packets input, 16038 bytes	The total number of packets and bytes sent into an interface.
588 packets output, 25976 bytes	The total number of packets and bytes sent out of an interface.

### Related Commands

Command	Description
<b>ip topology-accounting</b>	Enables topology accounting for all IPv4 unicast topologies in the VRF associated with a particular interface.

# show ip ospf interface

To display interface information related to Open Shortest Path First (OSPF), use the **show ip ospf interface** command in user EXEC or privileged EXEC mode.

**show ip [ospf] [ *process-id* ] interface [ *type number* ] [brief] [multicast] [topology {*topology-name*| base}]**

## Syntax Description

<i>process-id</i>	(Optional) Process ID number. If this argument is included, only information for the specified routing process is included. The range is 1 to 65535.
<i>type</i>	(Optional) Interface type. If the <i>type</i> argument is included, only information for the specified interface type is included.
<i>number</i>	(Optional) Interface number. If the <i>number</i> argument is included, only information for the specified interface number is included.
<b>brief</b>	(Optional) Displays brief overview information for OSPF interfaces, states, addresses and masks, and areas on the device.
<b>multicast</b>	(Optional) Displays multicast information.
<b>topology</b> <i>topology-name</i>	(Optional) Displays OSPF-related information about the named topology instance.
<b>topology base</b>	(Optional) Displays OSPF-related information about the base topology.

## Command Modes

User EXEC (>)  
Privileged EXEC (#)

## Command History

Release	Modification
10.0	This command was introduced.
12.0(25)S	This command was modified. The <b>brief</b> keyword was added.
12.2(15)T	This command was modified. The <b>brief</b> keyword was added.
12.2(33)SRA	This command was integrated into Cisco IOS Release 12.2(33)SRA.

Release	Modification
12.2(33)SRB	The <b>multicast</b> , <b>topology</b> , <b>base</b> , and <i>topology-name</i> keywords and argument were added.
12.2SX	This command is supported in the Cisco IOS Release 12.2SX train. Support in a specific 12.2SX release of this train depends on your feature set, platform, and platform hardware.
12.2(33)SRC	Support for the OSPF TTL Security Check feature was added.
15.0(1)M	This command was integrated into Cisco IOS Release 15.0(1)M.
15.1(3)S	This command was modified to display output when loop-free alternate (LFA) Fast Reroute (FRR) is enabled on an interface and whether it can be a protected or a protecting interface.

## Examples

The following is sample output from the **show ip ospf interface** command when Ethernet interface 0/0 is specified. It shows that LFA and FRR is enabled on the interface and that it can be both a protected and a protecting interface.

```
Device# show ip ospf interface ethernet 0/0
```

```
Ethernet0/0 is up, line protocol is up
  Internet Address 192.168.254.202/24, Area 0
  Process ID 1, Router ID 192.168.99.1, Network Type BROADCAST, Cost: 10
  Topology-MTID      Cost      Disabled      Shutdown      Topology Name
    0                 10         no            no            Base
  Transmit Delay is 1 sec, State DR, Priority 1
  Designated Router (ID) 192.168.99.1, Interface address 192.168.254.202
  Backup Designated router (ID) 192.168.254.10, Interface address 192.168.254.10
  Timer intervals configured, Hello 10, Dead 40, Wait 40, Retransmit 5
    oob-resync timeout 40
    Hello due in 00:00:05
  Supports Link-local Signaling (LLS)
  Cisco NSF helper support enabled
  IETF NSF helper support enabled
  Can be protected by per-prefix Loop-free FastReroute
  Can be used for per-prefix Loop-free FastReroute repair paths
  Index 1/1, flood queue length 0
  Next 0x0(0)/0x0(0)
  Last flood scan length is 1, maximum is 1
  Last flood scan time is 0 msec, maximum is 0 msec
  Neighbor Count is 1, Adjacent neighbor count is 1
    Adjacent with neighbor 192.168.254.10 (Backup Designated Router)
  Suppress hello for 0 neighbor(s)
```

In Cisco IOS Release 12.2(33)SRB, the following sample output from the **show ip ospf interface brief topology VOICE** command shows a summary of information, including a confirmation that the Multitopology Routing (MTR) VOICE topology is configured in the interface configuration:

```
Device# show ip ospf interface brief topology VOICE
```

```
VOICE Topology (MTID 10)
Interface  PID  Area      IP Address/Mask  Cost  State Nbrs F/C
Lo0        1    0         10.0.0.2/32      1     LOOP  0/0
Se2/0      1    0         10.1.0.2/30      10    P2P   1/1
```

The following sample output from the **show ip ospf interface brief topology VOICE** command displays details of the MTR VOICE topology for the interface. When the command is entered without the **brief** keyword, more information is displayed.

Device# **show ip ospf interface topology VOICE**

```

                VOICE Topology (MTID 10)
Loopback0 is up, line protocol is up
  Internet Address 10.0.0.2/32, Area 0
  Process ID 1, Router ID 10.0.0.2, Network Type LOOPBACK
  Topology-MTID    Cost    Disabled    Shutdown    Topology Name
    10             1      no         no         VOICE
  Loopback interface is treated as a stub Host Serial2/0 is up, line protocol is up
  Internet Address 10.1.0.2/30, Area 0
  Process ID 1, Router ID 10.0.0.2, Network Type POINT_TO_POINT
  Topology-MTID    Cost    Disabled    Shutdown    Topology Name
    10             10     no         no         VOICE
  Transmit Delay is 1 sec, State POINT_TO_POINT
  Timer intervals configured, Hello 10, Dead 40, Wait 40, Retransmit 5
    oob-resync timeout 40
    Hello due in 00:00:03
  Supports Link-local Signaling (LLS)
  Cisco NSF helper support enabled
  IETF NSF helper support enabled
  Index 1/1, flood queue length 0
  Next 0x0(0)/0x0(0)
  Last flood scan length is 1, maximum is 1
  Last flood scan time is 0 msec, maximum is 0 msec
  Neighbor Count is 1, Adjacent neighbor count is 1
    Adjacent with neighbor 10.0.0.1
  Suppress hello for 0 neighbor(s)

```

In Cisco IOS Release 12.2(33)SRC, the following sample output from the **show ip ospf interface** command displays details about the configured Time-to-Live (TTL) limits:

```

Device# show ip ospf interface ethernet 0
.
.
.
Strict TTL checking enabled
! or a message similar to the following is displayed
Strict TTL checking enabled, up to 4 hops allowed
.
.
.

```

The table below describes the significant fields shown in the displays.

**Table 7: show ip ospf interface Field Descriptions**

Field	Description
Ethernet	Status of the physical link and operational status of the protocol.
Process ID	OSPF process ID.
Area	OSPF area.
Cost	Administrative cost assigned to the interface.
State	Operational state of the interface.
Nbrs F/C	OSPF neighbor count.

Field	Description
Internet Address	Interface IP address, subnet mask, and area address.
Topology-MTID	MTR topology Multitopology Identifier (MTID). A number assigned so that the protocol can identify the topology associated with information that it sends to its peers.
Transmit Delay	Transmit delay in seconds, interface state, and device priority.
Designated Router	Designated router ID and respective interface IP address.
Backup Designated router	Backup designated router ID and respective interface IP address.
Timer intervals configured	Configuration of timer intervals.
Hello	Number of seconds until the next hello packet is sent out this interface.
Strict TTL checking enabled	Only one hop is allowed.
Strict TTL checking enabled, up to 4 hops allowed	A set number of hops has been explicitly configured.
Neighbor Count	Count of network neighbors and list of adjacent neighbors.

# show ip ospf topology-info

To display Open Shortest Path First (OSPF) details about the topologies configured under the OSPF protocol instance, use the **show ip ospf topology-info** command in privileged EXEC mode.

**show ip ospf** [*process-id*] **topology-info** [**multicast**] [**topology** {*topology-name*| **base**}]

## Syntax Description

<i>process-id</i>	(Optional) Process ID. If this argument is included, only information for the specified routing process is included.
<b>multicast</b>	(Optional) Displays information about multicast topologies.
<b>topology</b> <i>topology-name</i>	(Optional) Displays information about the named topology.
<b>topology base</b>	(Optional) Displays OSPF-related information about the base topology.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.

## Examples

The following example shows information about an OSPF routing process under the VOICE topology:

```
Device# show ip ospf topology-info topology VOICE
          OSPF Router with ID (10.0.0.2) (Process ID 1)
            VOICE Topology (MTID 10)
Topology priority is 120
Number of areas transit capable is 0
Initial SPF schedule delay 10 msec
Minimum hold time between two consecutive SPF's 20 msec
Maximum wait time between two consecutive SPF's 20000 msec
  Area BACKBONE(0)
    SPF algorithm last executed 15:05:41.808 ago
    SPF algorithm executed 9 times
    Area ranges are
```

The table below describes the significant fields shown in the display.

**Table 8: show ip ospf topology-info Field Descriptions**

Field	Description
OSPF Router	Router ID and OSPF process ID.
VOICE Topology	Name of the OSPF topology and its MTR Topology ID (MTID).
Topology Priority	The priority that an OSPF process assigns to a topology instance for SPF calculations.
Number of areas transit capable	Number of OSPF areas that are transit-capable.
SPF algorithm last executed	Shows the last time an SPF calculation was performed in response to topology change event records.
SPF algorithm executed	Shows the number of times an SPF calculation was performed in response to topology change event records.

# show ip protocols topology

To display the configuration and state of active routing protocol processes under a topology instance, use the **show ip protocols topology** command in user EXEC or privileged EXEC mode.

**show ip protocols topology** *topology-name* [**summary**]

## Syntax Description

<i>topology-name</i>	Name of the topology.
<b>summary</b>	(Optional) Displays summary information.

## Command Modes

User EXEC (>)  
Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

The **show ip protocols topology** command is used to display general routing information and routing protocol status under a topology instance. The topology name must be specified when entering this command.

## Examples

The following example shows information about an OSPF routing process under the DATA topology:

```
Device# show ip protocols topology DATA

*** IP Routing is NSF aware ***
Routing Protocol is "ospf 1"
  Outgoing update filter list for all interfaces is not set
  Incoming update filter list for all interfaces is not set
  Router ID 10.1.1.253
  It is an autonomous system boundary router
  Redistributing External Routes from,
  Number of areas in this router is 3. 3 normal 0 stub 0 nssa
  Maximum path: 4
  Routing for Networks:
  Routing Information Sources:
    Gateway         Distance      Last Update
  Distance: (default is 110)
```

The table below describes the significant fields shown in the display.

**Table 9: show ip protocols topology Field Descriptions**

Field	Description
Routing Protocol is...	Name and autonomous system or process number of currently running routing protocols.
Outgoing update filter list for all interfaces...	Indicates whether a filter for outgoing routing updates has been specified with the <b>distribute-list out</b> command.
Incoming update filter list for all interfaces...	Indicates whether a filter for incoming routing updates has been specified with the <b>distribute-list in</b> command.
Router ID	Displays the default or locally configured router ID.
Redistributing...	Indicates whether route redistribution has been enabled.
Automatic network summarization...	Indicates whether route summarization is enabled by default or with the <b>auto-summary</b> command. (Not shown in the example.)
Number of areas...	Indicates the number of locally configured areas on the device.
Maximum path	Displays the maximum number of multipaths that the routing process will support. This field displays the default or the number configured with the <b>maximum-paths</b> command.
Routing for Networks	Networks for which the routing process is currently injecting routes.
Routing Information Sources	Lists all the routing sources that the Cisco IOS software is using to build its routing table. The following is displayed for each source: <ul style="list-style-type: none"> <li>• IP address</li> <li>• Administrative distance</li> <li>• Time the last update was received from this source</li> </ul>
Distance	Number of internal and/or external distance metrics configured for the protocol.

The following example displays summary information about the topology DATA:

```
Device# show ip protocols topology DATA summary
```

```
Index Process Name
0      connected
1      static
2      ospf 1
*** IP Routing is NSF aware ***
```

The table below describes the significant fields shown in the display.

**Table 10: show ip protocols topology summary Field Descriptions**

Field	Description
Index Process Name	Displays route source type and number of associated routes.
IP Routing is NSF aware	Indicates that the Cisco IOS software image is NSF aware.

#### Related Commands

Command	Description
<b>clear ip route topology</b>	Clears entries from the routing table of a topology.
<b>ip route topology</b>	Configures static routing under a topology instance.
<b>ping topology</b>	Diagnoses basic network connectivity through a topology instance.
<b>show ip route topology</b>	Displays entries in a topology routing table.
<b>show topology</b>	Displays status and configuration information for topologies configured with MTR.

# show ip route multicast

To display multicast routes in the routing table, use the **show ip route multicast** command in user EXEC or privileged EXEC mode.

**show ip route multicast** [*vrf vrf-name*][*host-name* |*ip-address* [*mask*] [**longer-prefixes**]] [**connected**|*protocol*|**static**| **summary**| **supernets-only**| **track-table**]

## Syntax Description

<b>vrf</b> <i>vrf-name</i>	(Optional) Specifies a VPN routing and forwarding (VRF) instance name.
<i>hostname ip-address</i>	(Optional) Host name or IP address for a specific routing table entry.
<i>mask</i>	(Optional) Network mask.
<b>longer-prefixes</b>	(Optional) Specifies that only routes that match the <i>hostname mask</i> are displayed.
<b>connected</b>	(Optional) Specifies that only connected routes are displayed.
<i>protocol</i>	(Optional) Specifies that routes for the specified routing protocol are displayed. Enter the routing protocol as it displayed in the CLI help string.
<b>static</b>	(Optional) Specifies that only static routes are displayed.
<b>summary</b>	(Optional) Specifies that only summary routes are displayed.
<b>supernets-only</b>	(Optional) Specifies that only supernets are displayed.
<b>track-table</b>	(Optional) Displays backup static routes that are installed in the routing table via object tracking configuration.

## Command Modes

User EXEC (>)

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.

Release	Modification
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
15.0(1)M	This command was integrated into Cisco IOS Release 15.0(1)M.
15.0(1)SY	This command was integrated into Cisco IOS Release 15.0(1)SY.

### Usage Guidelines

Use the **show ip route multicast** command to display multicast routes in the routing table.

### Examples

The following example shows how to display a summary of multicast routes:

```
Device# show ip route multicast summary
```

```
IP routing table name is multicast (0x8000)
IP routing table maximum-paths is 32
Route Source      Networks      Subnets      Replicates      Overhead      Memory (bytes)
connected         0             0             0               0             0
static            0             0             0               0             0
internal          0             0             0               0             20
Total             0             0             0               0             20
```

The table below describes the significant fields shown in the display.

**Table 11: show ip route multicast summary Field Descriptions**

Field	Description
IP routing table name	Name of the routing table.
IP routing table maximum paths	Maximum paths displayed in the routing table.
Route source	The source of the route.
Replicates	Number of routes replicated from one topology to another.

# show ip route topology

To display entries in a topology routing table, use the **show ip route topology** command in user EXEC or privileged EXEC mode.

**show ip route topology** *topology-name* [*hostname*|*ip-address* [*mask* ] [**longer-prefixes**]] [**connected**|*protocol*] [**static**|**summary**|**supernets-only**|**track-table**]

## Syntax Description

<i>topology-name</i>	Name of a topology instance.
<i>hostname ip-address</i>	(Optional) Hostname or IP address for a specific routing table entry.
<i>mask</i>	(Optional) Network mask.
<b>longer-prefixes</b>	(Optional) Specifies that only routes that match the <i>ip-address mask</i> pair are displayed.
<b>connected</b>	(Optional) Specifies that only connected routes are displayed.
<i>protocol</i>	(Optional) Routes for the specified routing protocol are displayed. Enter the routing protocol as it displayed in the CLI help string.
<b>static</b>	(Optional) Specifies that only static routes are displayed.
<b>summary</b>	(Optional) Specifies that only summary routes are displayed.
<b>supernets-only</b>	(Optional) Specifies that only supernets are displayed.
<b>track-table</b>	(Optional) Displays backup static routes that are installed in the routing table via object tracking configuration.

## Command Default

No default behavior or values

## Command Modes

User EXEC (>)

Privileged EXEC (#)

**Command History**

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines**

The **show ip route topology** command is used to display routes installed in a topology routing table. The topology name must be specified when you enter this command.

**Examples**

The following example displays information for the 10.2.1.1 route under the DATA topology:

```
Device# show ip route topology DATA 10.2.1.1
Routing entry for 10.2.1.1/32
  Known via "connected", distance 0, metric 0 (connected)
  Routing Descriptor Blocks:
    * directly connected, via Ethernet1/0
      Route metric is 0, traffic share count is 1
```

The table below describes the significant fields shown in the display.

**Table 12: show ip route topology with Address Field Descriptions**

Field	Description
Routing entry for...	Network number and mask if configured.
Known via...	Indicates how the route was derived.
Routing Descriptor Blocks	Displays the next hop IP address followed by the information source.
Route metric	This value is the best metric for this routing descriptor block.
traffic share count	Number of uses for this routing descriptor block.

The following examples show the routing table of the DATA topology:

```
Device# show ip route topology DATA
Routing Table: DATA
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, + - replicated route
Gateway of last resort is not set
10.3.0.0/8 is variably subnetted, 2 subnets, 2 masks
```

```

C      10.3.2.0/24 is directly connected, Ethernet2/0
L      10.3.2.1/32 is directly connected, Ethernet2/0
      10.0.0.0/8 is variably subnetted, 6 subnets, 2 masks
C      10.1.1.0/25 is directly connected, Ethernet0/0
L      10.1.1.1/32 is directly connected, Ethernet0/0
C      10.1.1.128/25 is directly connected, Loopback0
L      10.1.1.253/32 is directly connected, Loopback0
C      10.2.1.0/25 is directly connected, Ethernet1/0
L      10.2.1.1/32 is directly connected, Ethernet1/0

```

The table below describes the significant fields shown in the display.

**Table 13: show ip route topology Field Descriptions**

Field	Description
Routing Table	Name of the routing table.
Codes	Indicates the protocol that derived the route. The status codes are defined in the output.
10.3.2.2	Address of the remote network.
Ethernet...	Interface through which the specified network can be reached.
via...	Specifies the address of the next device to the remote network. (Not shown in the display.)
0:01:00	Specifies the last time the route was updated (in hours:minutes:seconds). (Not shown in the display.)

#### Related Commands

Command	Description
<b>clear ip route topology</b>	Clears entries from the routing table of a topology.
<b>ip route topology</b>	Configures static routing under a topology instance.
<b>ping (MTR)</b>	Pings a destination within a specific topology.
<b>show ip route topology</b>	Displays the current state of a topology routing table.
<b>show topology</b>	Displays status and configuration information for topologies configured with MTR.

## show ip static route

To display the static process local Routing Information Base (RIB) information, use the **show ip static route** command in user EXEC or privileged EXEC mode.

**show ip static route** [**bfd**] [**vrf** *vrf-name*] [**topology** *topology-name*] [*ip-address* [ *mask* ]] [**multicast**] [**summary**]

### Syntax Description

<b>bfd</b>	(Optional) Displays IPv4 static Bidirectional Forwarding Detection (BFD) neighbor information.
<b>vrf</b> <i>vrf-name</i>	(Optional) Name of the VRF by which static routing information should be displayed.
<b>topology</b> <i>topology-name</i>	(Optional) Static route information for the specified topology.
<i>ip-address</i>	(Optional) Address by which static routing information should be displayed.
<i>mask</i>	(Optional) Subnet mask.
<b>multicast</b>	(Optional) Displays IPv4 multicast information.
<b>summary</b>	(Optional) Displays summary information.

### Command Modes

User EXEC (>)  
Privileged EXEC (#)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRC	The command output was enhanced to include BFD neighbor information.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
15.1(2)SNG	This command was implemented on the Cisco ASR 901 Series Aggregation Services Routers.

## Examples

The following is sample output from the **show ip static route** command:

```
Device# show ip static route
```

```
Codes: M - Manual static, A - AAA download, N - IP NAT, D - DHCP,
       G - GPRS, V - Crypto VPN, C - CASA, P - Channel interface processor,
       B - BootP, S - Service selection gateway
       DN - Default Network, T - Tracking object
       L - TL1, E - OER
```

```
Codes in []: A - active, N - non-active, P - permanent
```

In Cisco IOS Release 12.2(33)SRC, the following is sample output for the **show ip static route** command:

```
Device# show ip static route
```

```
Codes: M - Manual static, A - AAA download, N - IP NAT, D - DHCP,
       G - GPRS, V - Crypto VPN, C - CASA, P - Channel interface processor,
       B - BootP, S - Service selection gateway
       DN - Default Network, T - Tracking object
       L - TL1, E - OER
```

```
Codes in []: A - active, N - non-active, B - BFD-tracked, P - permanent
```

```
Static local RIB for default
```

```
M 10.2.2.2/32 [1/0] via Serial2/0 192.168.201.2 [N B]
```

```
M 10.0.0.0/8 [1/0] via Serial2/0 192.168.202.2 [N B]
```

```
M 10.2.0.0/8 [1/0] via Loopback0 [A]
```

The table below describes the significant fields shown in the display.

**Table 14: show ip static route Descriptions**

Field	Description
Codes	Indicates the protocol that derived the route. The status codes are defined in the output.
Static local RIB for default	Default static local RIB information.
M 10.2.2.2/32 [1/0] via Serial2/0 192.168.201.2 [N B]	Specifies the manually configured static route and the address of the next device to the remote network.

## show ip static route bfd

To display information about the IPv4 static Bidirectional Forwarding Detection (BFD) configuration from specific configured BFD groups and nongroup entries, use the **show ip static route bfd** command in user EXEC or privileged EXEC mode.

**show ip static route bfd** [*interface-type interface-number* [*destination-ip-address*]] [**group** [*group-name*]] [**vrf** *destination-vrf-name*] [*destination-ip-address* [**vrf** *source-vrf-name*] [*source-ip-address*]]

### Syntax Description

<i>interface-type interface-number</i>	(Optional) Interface type and interface number for which BFD is configured.
<i>destination-ip-address</i>	(Optional) Multihop BFD destination IP address or the gateway IP address.
<b>group</b> <i>group-name</i>	(Optional) Specifies a BFD group and group name.
<b>vrf</b>	(Optional) Specifies the Virtual Routing and Forwarding (VRF) instance.
<i>destination-vrf-name</i>	(Optional) Destination VRF name.
<i>source-vrf-name</i>	(Optional) Source VRF name.
<i>source-ip-address</i>	(Optional) Multihop BFD source IP address.

### Command Modes

User EXEC (>)  
Privileged EXEC (#)

### Command History

Release	Modification
15.1(2)S	This command was introduced.
15.1(1)SG	This command was integrated into Cisco IOS Release 15.1(1)SG.
15.1(1)SY	This command was integrated into Cisco IOS Release 15.1(1)SY.
15.2(3)S	This command was modified. The <b>vrf</b> keyword, and <i>interface-type</i> , <i>interface-number</i> , <i>destination-ip-address</i> , <i>source-ip-address</i> , <i>destination-vrf-name</i> , and <i>source-vrf-name</i> arguments were added.

### Usage Guidelines

You can specify a BFD group for a set of BFD-tracked static routes. Nongroup entries are BFD-tracked static routes for which a BFD group is not specified. Use the **ip route static bfd** command to configure static route BFD neighbors.

Use the **show ip static route bfd** command to display information about the IPv4 static BFD configuration from specific configured BFD groups and nongroup entries. The **group group-name** keyword and argument specifies a BFD group and BFD group name.

Example:

The following is sample output from the **show ip static route bfd group** command:

```
Device# show ip static route bfd group group1
```

```
Codes in []: R - Reachable, U - Unreachable, L - Loop, D - Not Tracked
GigabitEthernet1/1 10.1.1.1 [U] [group1, Active]
GigabitEthernet1/2 10.2.2.2 [U] [group1, Passive]
```

The following table describes the significant fields shown in the display.

**Table 15: show ip static route bfd group Field Descriptions**

Field	Description
GigabitEthernet1/1	Interface for which the BFD session is initiated.
10.1.1.1	Next-hop IP address.
group1	BFD group name.
Active	Active member of the group.
GigabitEthernet1/2	Interface for which the BFD session is initiated.
10.2.2.2	Next-hop IP address.
Passive	Passive member of the group.

### Related Commands

Command	Description
<b>ip route static bfd</b>	Specifies static route BFD neighbors.
<b>show ip static route</b>	Displays static route database information.

# show ip static route summary

To display a global summary of the static process local Routing Information Base (RIB), use the **show ip static route summary** command in user EXEC or privileged EXEC configuration mode.

**show ip static route summary**

**Syntax Description** This command has no arguments or keywords.

**Command Modes** User EXEC (>)  
Privileged EXEC (#)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Examples** The following example shows a global summary of the static routes:

```
Device# show ip static route summary
```

```
Allow inter-vrf: yes
Number of download routes: 0
Number of static routes: 20
Number of per user routes: 5
Download route version: 0
```

The table below describes the significant fields shown in the display.

**Table 16: show ip static route summary Descriptions**

Field	Description
Allow inter-vrf:	Routes across VRFs or confined to separate VRFs.
Number of download routes:	Number of routes downloaded.
Number of static routes:	The total number of static routes.
Number of per user routes:	The total number of routes per static route owner.
Download route version:	Version of the downloaded route.

# show ip traffic (MTR)

To display statistics about IP traffic, use the **show ip traffic** command in privileged EXEC mode.

**show ip traffic** [*topology {name| all| base}*]

## Syntax Description

<b>topology</b>	(Optional) Displays IP traffic statistics for a particular topology.
<i>name</i>	(Optional) Topology name.
<b>all</b>	(Optional) Displays statistics for all topologies.
<b>base</b>	(Optional) Displays base topology statistics.

## Command Default

Statistics for all topologies are displayed.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Usage Guidelines

Use the **show ip traffic** command to display global IP traffic statistics (an aggregation of all the topologies when Multitopology Routing [MTR] is enabled) or statistics related to a particular topology. The **base** keyword is reserved for the IPv4 unicast base topology. The **all** keyword displays all topologies.

## Examples

The following is sample output from the **show ip traffic** command for the VOICE topology:

```
Device# show ip traffic topology VOICE
Topology: VOICE
 5 minute input rate 0 bits/sec, 0 packet/sec,
 5 minute output rate 0 bits/sec, 0 packet/sec,
100 packets input, 6038 bytes,
 88 packets output, 5976 bytes.
```

The table below describes the significant fields shown in the display.

**Table 17: show ip traffic Field Descriptions**

Field	Description
5 minute input rate 0 bits/sec, 0 packets/sec,	The rate at which the system is processing incoming IP packets for the VOICE topology.
5 minute output rate 0/bits/sec, 0 packets/sec,	The rate at which the system is processing outgoing IP packets for the VOICE topology.
100 packets input, 6038 bytes	The total number of incoming packets and bytes processed for the VOICE topology.
88 packets output, 5976 bytes	The total number of outgoing packets and bytes processed for the VOICE topology.

# show isis neighbors

To display information about Intermediate System-to-Intermediate System (IS-IS) neighbors, use the **show isis neighbors** command in privileged EXEC mode.

**show isis neighbors [detail]**

## Syntax Description

<b>detail</b>	(Optional) Displays more detailed information for IS-IS neighbors.
---------------	--

## Command Default

Brief information for IS-IS neighbors is displayed.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(18)S	This command was introduced.
12.3	This command was integrated into Cisco IOS Release 12.3.
12.0(29)S	This command was integrated into Cisco IOS Release 12.0(29)S.
12.2(28)SB	This command was integrated into Cisco IOS Release 12.2(28)SB.
12.2(33)SRA	This command was integrated into Cisco IOS Release 12.2(33)SRA.
12.2(33)SRB	The command output was modified to support the Multitopology Routing (MTR) feature.
12.2SX	This command is supported in the Cisco IOS Release 12.2SX train. Support in a specific 12.2SX release of this train depends on your feature set, platform, and platform hardware.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

## Usage Guidelines

The **show isis neighbors** command is used to display brief information about connected IS-IS devices. Enter the **detail** keyword to display more detailed information.

## Examples

In Release 12.0(29)S, the **show isis neighbors** command is entered to display information about the IS-IS neighbor Device1.

```
Device5# show isis neighbors
```

```
System Id      Type Interface IP Address      State Holdtime Circuit Id
0000.0000.0002 L1   Et0/0    192.168.128.2   UP    21      R5.02
0000.0000.0002 L2   Et0/0    192.168.128.2   UP    28      R5.02
```

The **show isis neighbors detail** command is entered to display more detailed information about the IS-IS neighbor Device1.

```
Device5# show isis neighbors detail
```

```
System Id      Type Interface IP Address      State Holdtime Circuit Id
0000.0000.0002 L1   Et0/0    192.168.128.2   UP    21      R5.02
  Area Address(es): 49.0001
  SNPA: aabb.cc00.1f00
  State Changed: 00:00:52
  LAN Priority: 64
  Format: Phase V
0000.0000.0002 L2   Et0/0    192.168.128.2   UP    22      R5.02
  Area Address(es): 49.0001
  SNPA: aabb.cc00.1f00
  State Changed: 00:00:52
  LAN Priority: 64
  Format: Phase V
```

In Release 12.2(33)SRB, the **show isis neighbors detail** command is entered to verify the status of the IS-IS neighbor Device1 for a network that has MTR configured. For each of the topologies - unicast, DATA and VOICE, the interface information is displayed.

```
Device5# show isis neighbors detail
```

```
System Id      Type Interface IP Address      State Holdtime Circuit Id
0000.0000.0005 L2   Et0/0    192.168.128.2   UP    28      R5.01
  Area Address(es): 33
  SNPA: aabb.cc00.1f00
  State Changed: 00:07:05
  LAN Priority: 64
  Format: Phase V
  Remote TID: 100, 200
  Local TID: 100, 200
```

The table below describes the significant fields shown in the display.

**Table 18: show isis neighbors Field Descriptions**

Field	Description
System Id	Six-byte value that identifies a system in an area.
Type	Level type. Indicates whether the IS-IS neighbor is a Level 1, Level-1-2, or Level 2 device.
Interface	Interface from which the system was learned.
IP Address	IP address of the neighbor device.
State	Indicates whether the state of the IS-IS neighbor is up or down.

Field	Description
Holdtime	Link-state packet (LSP) holdtime. Amount of time that the LSP remains valid (in seconds).
Circuit Id	Port location for the IS-IS neighbor device that indicates how it is connected to the local device.
Area Address(es)	Reachable area addresses from the device. For Level 1 LSPs, these are the area addresses configured manually on the originating device. For Level 2 LSPs, these are all the area addresses for the area to which this device belongs.
SNPA	Subnetwork point of attachment. This is the data-link address.
State Changed	State change.
LAN Priority	Priority of the LAN.
Remote TID	Neighbor device topology IDs.
Local TID	Local device topology IDs.

# show mtm table

To display information about the classifier values and the differentiated services code point (DSCP) values assigned to each topology, use the **show mtm table** command in user EXEC or privileged EXEC mode.

**show mtm table**

**Syntax Description** This command has no arguments or keywords.

**Command Modes** User EXEC (>)  
Privileged EXEC (#)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines** The **show mtm table** command shows the DSCP bits and classifier values that are mapped to the topologies for Multitopology Routing (MTR). The DSCP bits are used to mark the packet and assign traffic to a topology.

**Examples** The following example displays the classifier and DSCP values for the VOICE and VIDEO topologies:

```
Device# show mtm table

MTM Table for VRF: default, ID:0
Topology          Address Family  Associated VRF  Topo-ID
base              ipv4            default         0
VOICE             ipv4            default         2051
Classifier: ClassID:3
DSCP: cs1
DSCP: 9
VIDEO             ipv4            default         2054
Classifier: ClassID:4
DSCP: af11
```

The table below describes the significant fields shown in the display.

**Table 19: show mtm table Field Descriptions**

Field	Description
MTM table	Displays the MTR translation manager table.
Topology	Name of the topology.
Classifier: ClassID:	Displays the class identifier.

Field	Description
DSCP:	DSCP code used to mark the packet. A subset of DSCP bits is used to encode classification values in the IP packet header.
Topo-ID	Topology identifier (TID). Each topology is configured with a unique TID.

# show policy-map type class-routing ipv4 unicast

To display class-routing policy map information for Multitopology Routing (MTR), use the **show policy-map type class-routing ipv4 unicast** command in privileged EXEC mode.

**show policy-map type class-routing ipv4 unicast** [**interface** [*interface-type interface-number*]]

## Syntax Description

<b>interface</b>	(Optional) Displays statistics on all interfaces under the global space.
<i>interface-type interface-number</i>	(Optional) Displays statistics on a specific interface.

## Command Modes

Privileged EXEC (#)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

## Examples

The following example shows that the policy map MTR is attached to the voice and video topologies:

```
Device# show policy-map type class-routing ipv4 unicast
```

```
Policy Map type class-routing ipv4 unicast MTR
  Class VOICE-CLASS
    select-topology voice
  Class VIDEO-CLASS
    select-topology video
```

The following example shows statistics about the policy map named MTR and the voice and video topologies. The number of packets and total bytes on a per-class and per-interface basis are shown. There is also further granularity in the display output by showing per match statement statistics:

```
Device# show policy-map type class-routing ipv4 unicast interface ethernet 0/0
```

```
Service-policy: MTR
  Class-map: VOICE-CLASS (match-any)
    10 packets, 600 bytes
    5 minute offered rate 0 bps, drop rate 0 bps
    Match: dscp cs1 (8)
      10 packets, 600 bytes
      5 minute rate 0 bps
      select-topology voice
  Class-map: VIDEO-CLASS (match-any)
    15 packets, 900 bytes
    5 minute offered rate 0 bps, drop rate 0 bps
    Match: dscp af43
      15 packets, 900 bytes
```

```

5 minute rate 0 bps
select-topology video

```

The table below describes the significant fields shown in the display.

**Table 20: show policy-map type class-routing ipv4 unicast Field Descriptions**

Field	Description
Service-policy:	Name of the service policy.
Class	Name of the class.
Class-map:	Class map to be used for matching packets to a specified class. Match any is the required behavior for MTR.
10 packets, 600 bytes	Number of packets and bytes per class and interface.
Match:	Identifies the DSCP value as a match criteria. Statistics are further refined to show statistics for packets with the specified DSCP value in the IP header.
select-topology	Name of the topology.

## show snmp context mapping

To display information about Simple Network Management Protocol (SNMP) context mappings for Multitopology Routing (MTR), use the **show snmp context mapping** command in privileged EXEC mode.

**show snmp context mapping**

**Syntax Description** This command has no arguments or keywords.

**Command Default** No default behavior or values.

**Command Modes** Privileged EXEC (#)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.

**Usage Guidelines** The SNMP agent software component on the device can be configured to pass a context string to existing MIB access functions by using the **snmp context** command. Network management applications can provide these context strings in SNMP transactions to direct those transactions to a specific virtual private network (VPN) routing and forwarding (VRF) instance, a specific topology, and/or routing protocol instance. The **show snmp context mapping** command displays information about the mapping of the context to the VRF, address family, topology, and protocol.

**Examples** The following example displays the mapping of the context to the topology and protocol instance:

```
Device# show snmp context mapping

Context: ospf-voice
  VRF Name:
  Address Family Name: ipv4
  Topology Name: voice
  Protocol Instance: OSPF-3 Router
Context: context-ospf
  VRF Name:
  Address Family Name:
  Topology Name:
  Protocol Instance: OSPF-3 Router
Context: context-vrfA
  VRF Name: vrfA
  Address Family Name:
  Topology Name:
  Protocol Instance:
Context: context-voice
  VRF Name:
  Address Family Name: ipv4
  Topology Name: voice
  Protocol Instance:
```

The table below describes the significant fields shown in the display.

**Table 21: show snmp context mapping Field Descriptions**

Field	Description
Context:	The context string that is associated with the VRF, data topology, or protocol instance.
VRF Name:	VRF name.
Address Family Name:	Address family name. Currently, only the IPv4 address family (multicast and unicast) is supported.
Topology Name:	Name of the topology.
Protocol Instance:	Routing protocol that is associated with the context string.

#### Related Commands

Command	Description
<b>snmp context</b>	Creates an SNMP context for MTR.

# show topology

To display status and configuration information for topologies configured with Multitopology Routing (MTR), use the **show topology** command in privileged EXEC mode.

## show topology

[**cache** [*topology-id*] | **ha** [**detail** | **interface** | **lock** | **router**] [**all** | **ipv4** | **ipv6** | **vrf** *vpn-instance*]]

### Syntax Description

<b>cache</b>	(Optional) Displays cache topology information.
<i>topology-id</i>	(Optional) A topology ID in hexadecimal format.
<b>ha</b>	(Optional) Displays routing table high availability information.
<b>detail</b>	(Optional) Displays detailed routing topology instance information.
<b>interface</b>	(Optional) Displays the status of interfaces that are associated with a topology.
<b>lock</b>	(Optional) Displays topology lock information.
<b>router</b>	(Optional) Displays the status of topologies on a device.
<b>all</b>	(Optional) Displays all topologies.
<b>ipv4</b>	(Optional) Displays IPv4 topologies.
<b>ipv6</b>	(Optional) Displays IPv6 topologies.
<b>vrf</b> <i>vpn-instance</i>	(Optional) Displays topologies associated with a VPN.

### Command Default

Information about all topologies is displayed.

### Command Modes

Privileged EXEC (#)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines**

The **show topology** command is used to display configuration information for MTR. The output displays global mode, interface mode, and device mode configurations. The output can be filtered to display information for only specific address families and subaddress families or specific topologies.

**Examples**

The following example shows the topology name and status of base and class-specific topologies:

```
Device# show topology
```

```
Topology          Address Family  Associated VRF  State
base              ipv4           default        UP
VOICE             ipv4           default        UP
base              default        UP
```

The table below describes the significant fields shown in the display.

**Table 22: show topology Field Descriptions**

Field	Description
Topology:	The topology name. This field will display base and class-specific topologies.
Address family	The address family and subaddress family.
Associated VRF	The VPN or VRF name is displayed if configured. VRF instances are shown as separate base topologies. The word “default” is displayed if no VRF is configured.
State	Status of the topology. The state will be displayed as UP or DOWN.

The following example shows detailed information about base and class-specific topologies:

```
Device# show topology detail
```

```
Topology: base
  Address-family: ipv4
  Associated VPN VRF is default
  Topology state is UP
  Associated interfaces:
    Ethernet0/0, operation state: UP
    Ethernet1/0, operation state: DOWN
    Serial2/0, operation state: DOWN
    Serial3/0, operation state: UP
Topology: VOICE
  Address-family: ipv4
  Associated VPN VRF is default
  Topology state is UP
  Associated interfaces:
    Ethernet0/0, operation state: UP
Topology: base
  Address-family:
  Associated VPN VRF is default
  Topology state is UP
```

```

Route Replication Enabled:
  from unicast all
Associated interfaces:
  Ethernet0/0, operation state: UP

```

The table below describes the significant fields shown in the display.

**Table 23: show topology detail Field Descriptions**

Field	Description
Topology	The topology name. This field will display base and class-specific topologies.
Address-family	The address family and subaddress family.
Associated VPN VRF is	The VPN or VRF name is displayed if configured. VRF instances are shown as separate base topologies. The word “default” is displayed if no VRF is configured.
Topology state is	Status of the topology. The state will be displayed as UP or DOWN.
Topology fallback is enabled (not shown)	This field is displayed when incremental forwarding mode is enabled when the <b>forward-base</b> command is configured under the global topology configuration.
Topology is enabled on all interfaces (not shown)	This field is displayed when a topology is configured to use all interfaces when the <b>all-interfaces</b> command is configured under the global topology configuration.
Route Replication Enabled:	This field is displayed when route replication is configured to be enabled.
Associated interfaces:	Lists all interfaces that are associated with a given topology. The list displays interfaces that are configured globally or individually.
operation state:	Status of the operation. The state will be displayed as UP or DOWN.

The following example shows information about the status of topologies on a route. The additional fields here show which IP routing protocols are configured for each topology.

```

Device# show topology router

Topology: base
  Address-family: ipv4
  Associated VPN VRF is default
  OSPF 2 Area 0
  IS-IS [name] Level-1
Topology: VOICE
  Address-family: ipv4
  Associated VPN VRF is default

```

```

    OSPF 2 Area 0
    IS-IS [name] Level-1
Topology: base
  Address-family: IPv4 multicast
  Associated VPN VRF is default
  OSPF 2 Area 0
  IS-IS [name] Level-1

```

The following example shows information about the status of each interface that is associated with a topology:

```

Device# show topology interface

Topology: base
  Address-family: ipv4
  Associated VPN VRF is default
  Topology state is UP
  Associated interfaces:
    Ethernet0/0, operation state: UP
    OSPF 2 metric: 10 state: UP
    IS-IS [name] metric (10,10) state: UP
Topology: VOICE
  Address-family: ipv4
  Associated VPN VRF is default
  Topology state is UP
  Associated interfaces:
    Ethernet0/0, operation state: UP
    OSPF 2 metric: 10 state: UP
    IS-IS [name] metric (10,10) state: UP
Topology: base
  Address-family: IPv4 multicast
  Associated VPN VRF is default
  Topology state is UP
  Associated interfaces:
    Ethernet0/0, operation state: UP
    OSPF 2 metric: 10 state: UP
    IS-IS [name] metric (10,10) state: UP

```

## Related Commands

Command	Description
<b>clear ip route topology</b>	Clears entries from the routing table of a topology.
<b>ip route topology</b>	Configures static routing under a topology instance.
<b>ping topology</b>	Diagnoses basic network connectivity through a topology instance.
<b>show ip protocols topology</b>	Displays the configuration and state of active routing protocol processes under a topology instance.
<b>show ip route topology</b>	Displays the current state of a topology routing table.

## shutdown (MTR)

To temporarily disable a topology instance without removing the topology configuration, use the **shutdown** command in address family topology configuration mode. To restart the topology instance, use the **no** form of this command.

**shutdown**

**no shutdown**

**Syntax Description** This command has no arguments or keywords.

**Command Default** The default state is enabled.

**Command Modes** Address family topology configuration (config-af-topology)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines** The **shutdown** (MTR) command is used to temporarily disable a topology without removing the topology configuration from the device. This command is useful for initial topology configuration. The topology can be placed in a shutdown state until the configuration is complete and the topology is ready to be deployed.

A topology is operationally disabled when it is shut down. No routing or forwarding occurs, and routing and forwarding tables are either empty or nonexistent when a topology is in a shutdown state.



**Note** A topology cannot be placed in the shutdown state if referenced by any active policy map.

**Examples** The following example configures the device to temporarily place the VOICE topology in a shutdown state:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# all-interfaces
Device(config-af-topology)# forward-base
Device(config-af-topology)# shutdown
Device(config-af-topology)# end
```

**Related Commands**

Command	Description
<b>all-interfaces</b>	Configures a topology instance to use all interfaces on a device.
<b>exit-topo</b>	Exits address family topology configuration mode, and enters global address family configuration mode.
<b>forward-base</b>	Configures the forwarding mode under a topology instance.
<b>maximum routes (MTR)</b>	Sets the maximum number of routes that a topology instance will accept and install into the RIB.
<b>topology (global)</b>	Configures a topology instance.

## snmp context

To create a Simple Network Management Protocol (SNMP) context for Multitopology Routing (MTR) for virtual networking, use the **snmp context** command in the appropriate command mode. To delete an SNMP context, use the **no** form of this command.

### For SNMPv1 or v2c

**snmp context** *context-name* [**community** *community-name* [**ro**| **rw**]]

### For SNMPv3

**snmp context** *context-name* [**user** *username* [**credential**] [**encrypted**] [**auth** {**md5** *password*| **sha** *password*}] [**access** {*access-list-number*| *access-list-name*| **ipv6** *access-list-name*}]]]

**no snmp context** *context-name*

### Syntax Description

<i>context-name</i>	Name of the SNMP context being created.
<b>community</b> <i>community-name</i>	(Optional) In SNMPv2c, specifies an SNMP community string.
<b>ro</b>	(Optional) In SNMPv2c, specifies read-only access.
<b>rw</b>	(Optional) In SNMPv2c, specifies read/write access.
<b>user</b> <i>username</i>	(Optional) In SNMPv3, specifies an SNMP user.
<b>credential</b>	(Optional) In SNMPv3, specifies if a user password is already configured and saved.
<b>encrypted</b>	(Optional) In SNMPv3, specifies that passwords are Message Digest5 (MD5) or Secure Hash Algorithm (SHA) digests.
<b>auth</b>	(Optional) In SNMPv3, specifies authentication parameters for a user.
<b>md5</b> <i>password</i>	(Optional) In SNMPv3, uses an Hash-based Message Authentication Code (HMAC) MD5 algorithm for authentication.
<b>sha</b> <i>password</i>	(Optional) In SNMPv3, uses an HMAC SHA algorithm for authentication.
<b>access</b>	(Optional) In SNMPv3, specifies an access list associated with a group.

<i>access-list-number</i>	(Optional) In SNMPv3, a standard access list number in the range of 1 to 99.
<i>access-list-name</i>	(Optional) In SNMPv3, an access list name.
<b>ipv6</b> <i>access-list-name</i>	(Optional) In SNMPv3, specifies an IPv6 access list name.

**Command Default**

No SNMP contexts are configured.

**Command Modes**

Address family configuration (config-router-af)  
 Router address family topology configuration (config-router-af-topology)  
 Router configuration (config-router)  
 VRF address family configuration (config-vrf-af)  
 VRF configuration (config-vrf)

**Command History**

Release	Modification
12.2(33)SRB	This command was introduced.
Cisco IOS XE Release 3.1S	This command integrated into Cisco IOS XE Release 3.1S.
Cisco IOS XE Release 3.2S	This command was modified. All of the keywords were added, and all of the arguments except for <i>context-name</i> were added.
15.0(1)SY	This command was integrated into Cisco IOS Release 15.0(1)SY.
15.1(1)SG	This command was integrated into Cisco IOS Release 15.1(1)SG.
Cisco IOS XE Release 3.3SG	This command was integrated into Cisco IOS XE Release 3.3SG.
15.3(2)T	This command was integrated into Cisco IOS Release 15.3(2)T.

**Usage Guidelines**

When you use the **no snmp context** command, all SNMP instances in that context are deleted.

**Examples**

The following example shows how to create an SNMP context to be associated with VPN companyA:

```
Device(config)# ip vrf companyA
Device(config-vrf)# snmp context contextA
```

The following example shows how to create an SNMP context in VRF address family configuration mode to be associated with VPN companyA:

```
Device(config)# vrf definition companyA
Device(config-vrf)# address-family ipv4
Device(config-vrf-af)# snmp context contextA
```

#### Related Commands

Command	Description
<b>address-family</b> (VRF)	Selects an address family type for a VRF table and enters VRF address family configuration mode.
<b>ip vrf</b>	Configures a VRF routing table.
<b>show snmp context mapping</b>	Displays information about SNMP context mappings for MTR.
<b>vrf definition</b>	Configures a VRF routing table instance and enters VRF configuration mode.

# topology (BGP)

To configure a Border Gateway Protocol (BGP) routing process to route IP traffic for the specified topology instance and to enter router scope address family topology configuration mode, use the **topology** command in router scope address family configuration mode. To disassociate the BGP routing process from the topology instance, use the **no** form of this command.

**topology** {*topology-name*| **base**}

**no topology** {*topology-name*| **base**}

## Syntax Description

<i>topology-name</i>	Name of a class-specific topology. The argument is case-sensitive.
<b>base</b>	Specifies the base topology.

## Command Default

No default behavior or values

## Command Modes

Router scope address family configuration (config-router-scope-af)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

## Usage Guidelines

The **topology** (BGP) command is used in a Multitopology Routing (MTR) configuration to enable a specific topology inside a BGP address family session. Command configurations after the **topology** command is entered apply only to the topology instance. The topology must first be defined globally using the **global-address-family** command in global configuration mode before the topology can be configured under the BGP routing session. The **topology** (BGP) command is entered under a BGP router scope hierarchy that includes an address family configuration.

## Examples

The following example configures a BGP peering session with the 192.168.3.2 neighbor under the VOICE topology:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# all-interfaces
Device(config-af-topology)# exit
Device(config-af)# exit
Device(config)# router bgp 45000
```

```

Device(config-router)# scope global
Device(config-router-scope)# bgp default ipv4-unicast
Device(config-router-scope)# neighbor 192.168.3.2 remote-as 50000
Device(config-router-scope)# address-family ipv4 unicast
Device(config-router-scope-af)# topology VOICE
Device(config-router-scope-af-topo)# bgp tid 100
Device(config-router-scope-af-topo)# neighbor 192.168.3.2 activate
Device(config-router-scope-af-topo)# end

```

### Related Commands

Command	Description
<b>bgp tid</b>	Configures BGP to accept routes with a specified topology ID.
<b>global-address-family</b>	Configures the BGP to accept routes with a specified topology ID.
<b>scope</b>	Defines the scope for a BGP routing session and enters router scope configuration mode.
<b>show ip bgp topology</b>	Displays topology instance information from the BGP table.

## topology (EIGRP)

To configure an Enhanced Interior Gateway Routing Protocol (EIGRP) process to route IP traffic under the specified topology instance and to enter address-family topology configuration mode, use the **topology** command in address-family configuration mode. To disassociate the EIGRP routing process from the topology instance, use the **no** form of this command.

**topology** {**base**| *topology-name* **tid** *number*}

**no topology** *topology-name*

### Syntax Description

<b>base</b>	Specifies the base topology.
<i>topology-name</i>	Topology name. The <i>topology-name</i> argument is case-sensitive.
<b>tid</b> <i>number</i>	Specifies the topology ID number. The range is 1 to 65535.

### Command Default

EIGRP routing processes are not configured to route IP traffic under a topology instance.

### Command Modes

Address-family configuration (config-router-af)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
15.0(1)M	This command was integrated into Cisco IOS Release 15.0(1)M.
12.2(33)XNE	This command was integrated into Cisco IOS Release 12.2(33)XNE.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5.

### Usage Guidelines

The **topology** command is used in a Multitopology Routing (MTR) configuration to enable an EIGRP process under the specified topology. The **topology** command is entered under address-family configuration mode. Command configurations are applied only to the topology instance. The topology must be defined globally with the **global-address-family** command in global address-family configuration mode before the topology can be configured under the EIGRP process.

The **tid** keyword associates an ID with the topology instance. Each topology must be configured with a unique topology ID. The topology ID is used to identify and group Network Layer Reachability Information (NLRI) for each topology in EIGRP updates.

The topology ID must be consistent across devices so that EIGRP can correctly associate topologies.

### Examples

The following example configures EIGRP process 1 to route traffic for the 192.168.0.0/16 network under the VOICE topology instance:

```
Device(config)# router eigrp 1
Device(config-router)# address-family ipv4 unicast autonomous-system 3
Device(config-router-af)# topology VOICE tid 100
Device(config-router-af-topology)# no auto-summary
Device(config-router-af-topology)# network 192.168.0.0 0.0.255.255
Device(config-router-af-topology)# end
```

### Related Commands

Command	Description
<b>clear ip eigrp</b>	Resets EIGRP process and neighbor session information.
<b>global-address-family ipv4</b>	Enters global address family configuration mode to configure MTR.
<b>topology (interface)</b>	Configures an MTR topology instance on an interface.

## topology (global)

To configure a global topology instance and enter routing topology configuration mode, use the **topology** command in global address family configuration mode. To disable the topology instance and remove from the device configuration, use the **no** form of this command.

**topology** {**base**| *topology-name*}

**no topology** {**base**| *topology-name*}

### Syntax Description

<b>base</b>	Configures the topology instance to import the base topology. This keyword can only be accepted in IPv4 multicast families.
<i>topology-name</i>	Name of the topology instance. The <i>topology-name</i> argument is case-sensitive; VOICE and voice specify different topologies.

### Command Default

No global topology instances are configured.

### Command Modes

Global address family configuration (config-af)

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
15.2(3)T	This command was integrated into Cisco IOS Release 15.2(3)T.

### Usage Guidelines

Use the **topology** (global) command to configure a topology instance and enter routing topology configuration mode. Up to 32 unicast and a single multicast topology can be configured on a device. In routing topology configuration mode, the following global topology configuration parameters are applied:

- Global interface configuration—The topology is configured on all interfaces by entering the **all-interfaces** command. All interfaces are removed from the topology by entering the **no** form of this command, which is the default.
- Forwarding mode—The method that the device uses to look up forwarding entries in the FIB is configured by entering the **forward-base** command. Entering this command enables “incremental” forwarding mode. Entering the **no** form enables “strict” forwarding mode, which is the default. In strict mode, the device looks for a forwarding entry only within the class-specific topology FIB. If an entry is not found,

the packet is dropped. In incremental mode, the device first looks in the class-specific topology FIB. If a covering forwarding entry is not found, the device then looks in the base topology FIB.

- **Maximum route limit**—A limit for the number of routes that are permitted in the topology and installed to the topology RIB is configured by entering the **maximum routes** (MTR) command. This functionality is similar to routing and VPN maximum route features. No limit is the default.

**Note**

Per-interface topology configuration parameters override configurations applied in global address family topology configuration and routing topology configuration mode.

**Examples**

The following example creates a topology instance named VOICE. The device is configured to use incremental forwarding mode and to generate warning messages when 1000 routes have been accepted/installed in the VOICE topology RIB:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology VOICE
Device(config-af-topology)# forward-base
Device(config-af-topology)# maximum routes 1000 warn-only
```

**Related Commands**

Command	Description
<b>all-interfaces</b>	Configures a topology instance to use all interfaces on a device.
<b>exit-topo</b>	Exits address family topology mode and enters global address family configuration mode.
<b>forward-base</b>	Configures the forwarding mode under a topology instance.
<b>global-address-family</b>	Enters global address family configuration mode to configure MTR.
<b>maximum routes</b> (MTR)	Sets the maximum number of routes that a topology instance will accept and install into the RIB.
<b>shutdown</b>	Temporarily disables a topology instance without removing the topology configuration.
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

# topology (interface)

To configure a Multitopology routing (MTR) topology instance on an interface, use the **topology** command in interface configuration mode. To disable the topology interface configuration and configure the device to use global defaults, use the **no** form of this command.

**topology ipv4** [**multicast**| **unicast**] {*topology-name* [**disable**]| **base**}

**no topology ipv4** [**multicast**| **unicast**] {*topology-name* [**disable**]| **base**}

## Syntax Description

<b>ipv4</b>	Specifies the IPv4 address family.
<b>multicast</b>	(Optional) Specifies the multicast subaddress family.
<b>unicast</b>	(Optional) Specifies the unicast address family.
<i>topology-name</i>	Specifies the name of the topology instance.
<b>disable</b>	(Optional) Disables the specified topology instance on the interface. Entering the <b>no</b> form of this command with this keyword enables the interface.
<b>base</b>	Specifies the base topology.

## Command Default

Unicast subaddress family configuration mode is entered when no subaddress family is specified.

No interfaces are included in class-specific topologies unless explicitly configured.

Configuration applied with the **all-interfaces** command in routing topology configuration does not override individual interface configuration applied in interface topology configuration mode.

## Command Modes

Interface configuration (config-if)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
15.2(3)T	This command was integrated into Cisco IOS Release 15.2(3)T.

## Usage Guidelines

The **topology** command is used to apply specific topology configuration at the interface level. The address family must be specified when this command is entered. The subaddress family can be optionally specified.

Entering this command in Interface configuration mode places the device in interface topology configuration mode. In this mode, Enhanced Interior Gateway Routing Protocol (EIGRP), Intermediate System-to-Intermediate System, and Open Shortest Path First (OSPF) interface-specific configuration can be applied.

### Disabling a Topology Under an Interface

An interface topology configuration can be disabled or an interface can be excluded from global topology configuration by entering this command with the **disable** keyword. Entering the **disable** keyword for a base topology removes only specific base topology configuration that applies to a class-specific topology.

### Examples

The following example applies an OSPF cost of 10 to routes learned through the topology VOICE. This configuration also disables the multicast topology VIDEO.

```
Device(config)# interface Ethernet 0/0
Device(config-if)# topology ipv4 VOICE
Device(config-if-topology)# ip ospf cost 10
Device(config-if-topology)# exit
Device(config-if)# topology ipv4 multicast VIDEO disable
Device (config-if)#
end
```

### Related Commands

Command	Description
<b>exit-if-topology</b>	Exits interface topology configuration mode.
<b>ip ospf cost (MTR)</b>	Configures the OSPF interface cost under a topology instance.
<b>ip ospf topology disable</b>	Disables an OSPF process under a topology interface configuration.

# topology (IS-IS)

To configure Intermediate System-to-Intermediate System (IS-IS) Multitopology Routing (MTR) support for a non-base topology or to enter a configuration sub-mode specific to an IPv4 multicast base topology, use the **topology** command in router address family configuration mode.

## MTR Unicast for IPv4 or IPv6

**topology** *topology-name* **tid** *number*

## MTR Multicast for IPv4

**topology** **base**

### Syntax Description

<b>base</b>	(Required) Specifies the base topology and enters a configuration sub-mode specific to the IPv4 multicast base topology. This keyword is available only for MTR multicast for IPv4.
<i>topology-name</i>	(Required) Topology name. This argument is case-sensitive and is available only for MTR unicast for IPv4 and Ipv6.
<b>tid</b> <i>number</i>	(Required) Specifies the topology ID number. The range is 1 to 65535. This keyword and argument are available only for MTR unicast for IPv4 and IPv6.

### Command Default

No default behavior or values

### Command Modes

Router address family configuration

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
Cisco IOS XE Release 2.5	This command was integrated into Cisco IOS XE Release 2.5

### Usage Guidelines

The **topology** command is used in an MT configuration to enable an IS-IS instance under the base topology for IPv4 multicast, or to configure IS-IS support for a non-base topology. The **topology** command is entered under an address family configuration. Command configurations are applied to only the topology instance.

The topology must be defined globally with the **global-address-family** command in global configuration mode before the topology can be configured under the IS-IS instance.

The **tid** keyword associates an ID with the topology instance. Each topology must be configured with a unique topology ID. The topology ID is used to identify and group Network Layer Reachability Information (NLRI) for each topology in IS-IS updates.

### Examples

The following example configures the IS-IS DATA topology with a TID value of 200 for IPv4 unicast:

```
router isis
 net 33.3333.3333.3333.00
 metric-style wide
 address-family ipv4 unicast
 topology DATA tid 200
 end
```

The **topology** command is entered with the **base** keyword to specify the base topology for IPv4 multicast base topology:

```
router isis
 net 33.3333.3333.3333.00
 metric-style wide
 address-family ipv4 multicast
 topology base
```

### Related Commands

Command	Description
<b>address-family</b> (IS-IS)	Configures the exchange of address family and subaddress family prefixes.
<b>topology</b> (interface)	Configures an MTR topology instance on an interface.

## topology (OSPF)

To configure an Open Shortest Path First (OSPF) process to route IP traffic under the specified topology instance, use the **topology** command in address family configuration mode. To remove the OSPF routing process from the topology instance, use the **no** form of this command.

**topology** {**base**| *topology-name* **tid number**}

**no topology** {**base**| *topology-name* **tid number**}

### Syntax Description

<b>base</b>	Specifies the base topology.
<i>topology-name</i>	Topology name. This argument is case-sensitive; VOICE and voice specify different topologies.
<b>tid number</b>	Specifies a topology ID number. The range is 5 to 4095.  <b>Note</b> The topology ID must be entered during initial configuration. This keyword and argument is optional for subsequent configuration of the same topology instance.

### Command Default

OSPF assigns the ID number 0 to the base unicast topology and the number 1 to the base multicast topology.

### Command Modes

Address family configuration

### Command History

Release	Modification
12.2(33)SRB	This command was introduced.

### Usage Guidelines

The **topology** command is used in Multitopology Routing (MTR) configuration to enable an OSPF process under the specified topology. The **topology** command is entered under router address family configuration. Entering the **topology** command places the device in router address family topology configuration mode. Subsequent commands that are configured are applied to only the specified topology instance. The topology must be defined globally with the **global-address-family** command in global configuration mode before the topology can be configured under the OSPF process.

#### Multicast Base Topology

The **base** keyword is used to enter the base topology when a multicast subaddress family configuration is created. Entering the **no** form of this command for a multicast configuration does not remove the base topology, only the command configurations that were entered in this mode.

**Note**

The base keyword is accepted for only IPv4 multicast. The **tid** keyword is accepted for only IPv4 and IPv6 unicast.

**Topology ID**

The topology ID must be specified with the **tid** keyword when this command is first entered. This keyword is optional for subsequent configuration. The topology ID cannot be changed after a topology instance is configured. You must first remove the topology instance from the device configuration and then reconfigure the topology instance with a new topology ID.

**Examples**

The following example creates the VOICE topology instance and configures the topology ID 100:

```
Device(config)# router ospf 1  
Device(config-router)# address-family ipv4  
Device(config-router-af)# topology VOICE tid 100  
Device(config-router-af-topology)# end
```

**Related Commands**

Command	Description
<b>address-family</b> (OSPF)	Configures address family and subaddress family IP prefix exchange.

# topology-accounting

To enable topology accounting on all of the interfaces in the global address family for the default VRF instance, use the **topology-accounting** command in global address family configuration mode. To disable statistics collection from all interfaces that are part of default VRF, use the **no** form of this command.

**topology-accounting**

**no topology-accounting**

**Syntax Description** This command has no arguments or keywords.

**Command Default** No topology accounting statistics are collected.

**Command Modes** Global address family configuration (config-af)

Command History	Release	Modification
	12.2(33)SRB	This command was introduced.
	12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.

**Usage Guidelines** Use this command to enable topology accounting on all of the interfaces in the global address family for all IPv4 unicast topologies in the default VRF instance. Enabling this command does not impact interfaces in other VRF instances. Statistic collection is enabled and information is collected and accumulated from interfaces that belong in the default VRF and are participating in one or more IPv4 topologies.

The **no** form of this command disables statistics collection from all interfaces that are part of the default VRF instance. The **no** form of this command does not disable statistics collection from interfaces on which the **ip topology-accounting** command has been configured.

**Examples** The following example shows how to enable topology accounting on all interfaces in the global address family for all IPv4 unicast topologies in the default VRF instance:

```
Device(config)# global-address-family ipv4
Device(config-af)# topology-accounting
```

## Related Commands

Command	Description
<b>ip topology-accounting</b>	Enables topology accounting for all IPv4 unicast topologies in the VRF associated with a particular interface.



# traceroute

To discover the routes that packets will actually take when traveling to their destination address, use the **traceroute** command in user EXEC or privileged EXEC mode.

**traceroute** [**vrf** *vrf-name*] **topology** *topology-name*] [*protocol*] *destination*

## Syntax Description

<b>vrf</b> <i>vrf-name</i>	(Optional) Specifies the name of a VPN virtual routing and forwarding (VRF) instance table in which to find the destination address. The only keyword that you can select for the <i>protocol</i> argument when you use the <b>vrf</b> <i>vrf-name</i> keyword-argument pair is the <b>ip</b> keyword.
<b>topology</b> <i>topology-name</i>	(Optional) Specifies the name of the topology instance. The <i>topology-name</i> argument is case-sensitive; “VOICE” and “voice” specify different topologies.
<i>protocol</i>	(Optional) Protocol keyword, either <b>appletalk</b> , <b>clns</b> , <b>ip</b> , <b>ipv6</b> , <b>ipx</b> , <b>oldvines</b> , or <b>vines</b> . When not specified, the <i>protocol</i> argument is based on an examination by the software of the format of the <i>destination</i> argument. The default protocol is IP.
<i>destination</i>	(Optional in privileged EXEC mode; required in user EXEC mode) The Destination address or hostname you want to trace of the route. The software determines the default parameters for the appropriate protocol and the tracing action begins.

## Command Default

When not specified, the *protocol* argument is determined by the software examining the format of the *destination* argument. For example, if the software finds a *destination* argument in IP format, the protocol value defaults to IP.

## Command Modes

User EXEC (>)

Privileged EXEC (#)

## Command History

Release	Modification
10.0	This command was introduced.
12.0(5)T	The <b>vrf</b> <i>vrf-name</i> keyword and argument were added.

Release	Modification
12.2(2)T	This command was modified, support for IPv6 was added.
12.0(21)ST	This command was modified, support for IPv6 was added.
12.0(22)S	This command was modified, support for IPv6 was added.
12.2(11)T	The <b>traceroute</b> command test characters for IPv6 were updated. A new error message was added.
12.2(14)S	This command was integrated into Cisco IOS Release 12.2(14)S.
12.3(5)	This command was modified, a line was added to the interactive <b>traceroute vrf</b> command, so that you can resolve the autonomous system number through the use of the global table or a VRF table, or you can choose not to resolve the autonomous system.
12.0(26)S1	This command was integrated into Cisco IOS Release 12.0(26)S1.
12.2(20)S	This command was integrated into Cisco IOS Release 12.2(20)S.
12.2(28)SB	This command was integrated into Cisco IOS Release 12.2(28)SB.
12.2(25)SG	This command was integrated into Cisco IOS Release 12.2(25)SG.
12.2(33)SRA	This command was integrated into Cisco IOS Release 12.2(33)SRA.
12.2(33)SRB	The <b>topology</b> <i>topology-name</i> keyword-argument pair was added to support Multitopology Routing (MTR).
12.2(33)SXH	This command was integrated into Cisco IOS Release 12.2(33)SXH.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
Cisco IOS XE Release 3.2S	This command was modified. When the <b>vrf</b> keyword is used, the output displays the incoming VRF name/tag and the outgoing VRF name/tag.
15.0(1)SY	This command was modified. When the <b>vrf</b> keyword is used, the output displays the incoming VRF name/tag and the outgoing VRF name/tag.
15. 2 (2)SNI	This command was implemented on the Cisco ASR 901 Series Aggregation Services Routers.

### Usage Guidelines

The **traceroute** command works by taking advantage of the error messages generated by devices when a datagram exceeds its hop limit value.

The **traceroute** command starts by sending probe datagrams with a hop limit of 1. Including a hop limit of 1 with a probe datagram causes the neighboring devices to discard the probe datagram and send back an error

message. The **traceroute** command sends several probes with increasing hop limits and displays the round-trip time for each.

The **traceroute** command sends out one probe at a time. Each outgoing packet might result in one or more error messages. A time-exceeded error message indicates that an intermediate device has seen and discarded the probe. A destination unreachable error message indicates that the destination node has received and discarded the probe because the hop limit of the packet reached a value of 0. If the timer goes off before a response comes in, the **traceroute** command prints an asterisk (\*).

The **traceroute** command terminates when the destination responds, when the hop limit is exceeded, or when the user interrupts the trace with the escape sequence. By default, to invoke the escape sequence, simultaneously press and release the Ctrl, Shift, and 6 keys, and then pressing the X key.

To use nondefault parameters and invoke an extended **traceroute** test, enter the command without a *protocol* or *destination* argument in privileged EXEC mode then follow a series of steps to select the desired parameters. Extended **traceroute** tests are not supported in user EXEC mode. The user-level traceroute feature provides a basic trace facility for users who do not have system privileges. The *destination* argument is required in user EXEC mode.

If the system cannot map an address for a hostname, it returns a "%No valid source address for destination" message.

If the **vrf** *vrf-name* keyword-argument pair is used, the **topology** option is not displayed because only the default VRF instance is supported. The **topology** *topology-name* keyword-argument pair and the DiffServ Code Point (DSCP) option in the extended traceroute system dialog are displayed only if a topology is configured on the device.

In Cisco IOS XE Release 3.2S, output of the **traceroute** command with the **vrf** keyword was enhanced to make troubleshooting easier by displaying the incoming VRF name/tag and the outgoing VRF name/tag.

## Examples

After you enter the **traceroute** command in privileged EXEC mode, the system prompts you for a protocol. The default protocol is IP.

If you enter a hostname or address on the same line as the **traceroute** command, the default action is taken as appropriate for the protocol type of that name or address.

The following example is sample output from the **traceroute** command using default values in privileged EXEC mode. The specific output varies somewhat from protocol to protocol.

```
Device# traceroute
Protocol [ip]:
Target IP address:
Source address:
DSCP Value [0]: ! Only displayed if a topology is configured on the device.
Numeric display [n]:
Timeout in seconds [3]:
Probe count [3]:
Minimum Time to Live [1]:
Maximum Time to Live [30]:
Port Number [33434]:
Loose, Strict, Record, Timestamp, Verbose [none]:
```

The following example displays output available in Cisco IOS XE Release 3.2S and later. Output of the **traceroute** command with the **vrf** keyword includes the incoming VRF name/tag and the outgoing VRF name/tag.

```
Device# traceroute vrf red 10.0.10.12
Type escape sequence to abort.
Tracing the route to 10.0.10.12
VRF info: (vrf in name/id, vrf out name/id)
 1 10.1.13.15 (red/13,red/13) 0 msec
```

```
10.1.16.16 (red/13,red/13) 0 msec
10.1.13.15 (red/13,red/13) 1 msec
2 10.1.8.13 (red/13,red/13) 0 msec
10.1.7.13 (red/13,red/13) 0 msec
10.1.8.13 (red/13,red/13) 0 msec
3 10.1.2.11 (red/13,blue/10) 1 msec 0 msec 0 msec
4 * * *
```

**Related Commands**

Command	Description
<b>ping</b> (MTR)	Pings a destination within a specific topology for MTR.

# use-topology

To configure a multicast topology to perform Reverse Path Forwarding (RPF) computations using a unicast topology Routing Information Base (RIB), use the **use-topology** command in address family topology configuration mode. To disable RPF computations using a unicast topology RIB, use the **no** form of this command.

**use-topology unicast** {**base**| *topology-name*}

**no use-topology unicast** {**base**| *topology-name*}

## Syntax Description

<b>unicast</b>	Specifies a unicast sub-address family.
<b>base</b>	Specifies a base topology.
<i>topology-name</i>	A class-specific unicast topology.

## Command Default

No default behavior or values.

## Command Modes

Address family topology configuration (config-af-topology)

## Command History

Release	Modification
12.2(33)SRB	This command was introduced.
12.2(33)SRE	This command was integrated into Cisco IOS Release 12.2(33)SRE.
15.0(1)M	This command was integrated into Cisco IOS Release 15.0(1)M.
15.0(1)SY	This command was integrated into Cisco IOS Release 15.0(1)SY.

## Usage Guidelines

When this command is configured, the multicast topology uses routes in the specified unicast topology table to build multicast distribution trees.

This multicast RIB is not used when this command is enabled, even if the multicast RIB is populated and supported by a routing protocol.

## Examples

The following example shows how to configure a multicast topology to perform RPF computations using a unicast topology RIB:

```
Device(config)# ip multicast-routing
Device(config)# ip multicast rpf multitopology
```

```
Device(config)# global-address-family ipv4 multicast  
Device(config-af)# topology base  
Device(config-af-topology)# use-topology unicast base
```

