



Cisco IP Solution Center Infrastructure Reference, 4.1

Corporate Headquarters

Cisco Systems, Inc.
170 West Tasman Drive
San Jose, CA 95134-1706
USA
<http://www.cisco.com>
Tel: 408 526-4000
800 553-NETS (6387)
Fax: 408 526-4100

Text Part Number: OL-7642-01



THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

CCSP, CCVP, the Cisco Square Bridge logo, Follow Me Browsing, and StackWise are trademarks of Cisco Systems, Inc.; Changing the Way We Work, Live, Play, and Learn, and iQuick Study are service marks of Cisco Systems, Inc.; and Access Registrar, Aironet, ASIST, BPX, Catalyst, CCDA, CCDP, CCIE, CCIP, CCNA, CCNP, Cisco, the Cisco Certified Internetwork Expert logo, Cisco IOS, Cisco Press, Cisco Systems, Cisco Systems Capital, the Cisco Systems logo, Cisco Unity, Empowering the Internet Generation, Enterprise/Solver, EtherChannel, EtherFast, EtherSwitch, Fast Step, FormShare, GigaDrive, GigaStack, HomeLink, Internet Quotient, IOS, IP/TV, iQ Expertise, the iQ logo, iQ Net Readiness Scorecard, LightStream, Linksys, MeetingPlace, MGX, the Networkers logo, Networking Academy, Network Registrar, *Packet*, PIX, Post-Routing, Pre-Routing, ProConnect, RateMUX, ScriptShare, SlideCast, SMARTnet, StrataView Plus, TeleRouter, The Fastest Way to Increase Your Internet Quotient, and TransPath are registered trademarks of Cisco Systems, Inc. and/or its affiliates in the United States and certain other countries.

All other trademarks mentioned in this document or Website are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (0502R)

Cisco IP Solution Center Infrastructure Reference, 4.1

Copyright © 2005, Cisco Systems, Inc.

All rights reserved.



About This Guide	xxix
Objective	xxix
Related Documentation	xxix
Audience	xxx
How This Book Is Organized	xxx
Document Conventions	xxxi
Obtaining Documentation	xxxii
Cisco.com	xxxii
Product Documentation DVD	xxxiii
Ordering Documentation	xxxiii
Documentation Feedback	xxxiii
Cisco Product Security Overview	xxxiii
Reporting Security Problems in Cisco Products	xxxiv
Obtaining Technical Assistance	xxxiv
Cisco Technical Support & Documentation Website	xxxv
Submitting a Service Request	xxxv
Definitions of Service Request Severity	xxxv
Obtaining Additional Publications and Information	xxxvi

CHAPTER 1

Getting Started	1-1
System Recommendations	1-1
Introduction	1-1
Structural Overview	1-2
Product Category Tabs	1-3
Links	1-3
Home	1-3
Shortcuts	1-3
Account	1-5
Index	1-5
Help	1-5
About	1-6
Logout	1-6
Customer	1-6

Common GUI Components	1-6
Filters	1-7
Header Row Check Box	1-7
Rows per Page	1-7
Go To Page	1-7
Auto Refresh	1-8
Color Coding	1-8
Icons	1-10
Service Inventory	1-10
Service Design	1-12
Monitoring	1-13
Diagnostics	1-14
Administration	1-15

CHAPTER 2

WatchDog Commands 2-1

startdb Command	2-1
Description	2-1
Syntax	2-2
startns Command	2-2
Description	2-2
Syntax	2-2
startwd Command	2-2
Description	2-2
Syntax	2-3
stopall Command	2-3
Description	2-3
Syntax	2-3
stopdb Command	2-3
Description	2-3
Syntax	2-4
stopns Command	2-4
Description	2-4
Syntax	2-4
stopwd Command	2-4
Description	2-4
Syntax	2-5
wdclient Command	2-5
wdclient disk Subcommand	2-6

Description	2-6
Syntax	2-6
wdclient group <i><group_name></i> Subcommand	2-6
Description	2-6
Syntax	2-6
wdclient groups Subcommand	2-6
Description	2-7
Syntax	2-7
wdclient health Subcommand	2-7
Description	2-7
Syntax	2-7
wdclient hosts Subcommand	2-7
Description	2-7
Syntax	2-7
wdclient restart Subcommand	2-8
Description	2-8
Syntax	2-8
wdclient start Subcommand	2-8
Description	2-8
Syntax	2-9
wdclient status Subcommand	2-9
Description	2-9
Syntax	2-9
Information Produced: Name Column	2-9
Information Produced: State Column	2-10
Information Produced: Gen Column	2-11
Information Produced: Exec Time Column	2-11
Information Produced: PID Column	2-11
Information Produced: Success Column	2-11
Information Produced: Missed Column	2-11
wdclient stop Subcommand	2-11
Description	2-11
Syntax	2-12
wdclient syshealth Subcommand	2-12
Description	2-12
Syntax	2-12

Traffic Engineering Management	3-5
Inventory Manager	3-5
Accessing the Inventory Manager Window	3-5
Importing Devices	3-6
Opening and Editing Devices	3-7
General Attributes Devices	3-9
Password Attributes Devices	3-10
SNMP Attributes Devices	3-11
CNS Attributes Devices	3-12
Platform Attributes Devices	3-13
Interfaces Devices	3-13
Opening and Editing PEs	3-15
General Attributes Provider	3-17
Password Attributes Provider	3-18
SNMP Attributes Provider	3-19
CNS Attributes Provider	3-20
Platform Attributes Provider	3-21
PE Attributes Provider	3-22
Interfaces Provider	3-23
Opening and Editing CEs	3-24
General Attributes Customer	3-27
Password Attributes Customer	3-28
SNMP Attributes Customer	3-29
CNS Attributes Customer	3-30
Platform Attributes Customer	3-30
CPE Attributes Customer	3-31
Interfaces Customer	3-32
Assigning Devices	3-33
Topology Tool	3-36
Introduction	3-37
Launching Topology Tool	3-37
Conventions	3-39
Accessing the Topology Tool for ISC-VPN Topology	3-41
Types of Views	3-43
VPN View	3-44
Logical View	3-49
Physical View	3-52
Viewing Device and Link Properties	3-53
Device Properties	3-54
Link Properties	3-57

Filtering and Searching	3-60
Filtering	3-60
Searching	3-63
Using Maps	3-64
Loading a map	3-65
Layers	3-66
Map data	3-67
Node locations	3-67
Adding new maps	3-68
Devices	3-68
Configuring SSH	3-69
Configuring SSH on Cisco IOS Routers	3-69
Setting Up SNMP	3-70
Setting Up SNMPv1/v2c on Cisco IOS Routers	3-71
Setting SNMPv3 Parameters on Cisco IOS Routers	3-71
Manually Enabling RTR Responder on Cisco IOS Routers	3-72
Accessing the Devices Window	3-72
Creating a Device	3-74
Creating a Catalyst Switch	3-75
Creating a Cisco Device	3-80
Creating a Terminal Server	3-86
Creating a Cisco CNS IE2100	3-91
Editing a Device	3-92
Deleting Devices	3-95
Editing a Device Configuration	3-96
E-mailing a Device's Owner	3-98
Copying a Device	3-99
Device Groups	3-100
Accessing the Device Groups Window	3-101
Creating a Device Group	3-101
Editing a Device Group	3-104
Deleting Device Groups	3-104
E-mailing a Device Group	3-105
Customers	3-106
Accessing the Customers Window	3-106
Creating a Customer	3-107
Editing a Customer	3-108
Deleting Customers	3-109
Creating Customer Sites	3-110

CPE Devices	3-111
Create CPE Device	3-113
Edit CPE Device	3-113
Delete CPE Device	3-114
Providers	3-114
Accessing the Providers Window	3-115
Creating a Provider	3-115
Editing a Provider	3-116
Deleting Providers	3-117
Creating Provider Regions	3-118
Creating PE Devices	3-120
Creating Access Domains	3-121
Resource Pools	3-122
Accessing the Resource Pools Window	3-123
Creating an IP Address Pool	3-124
Creating a Multicast Pool	3-125
Creating a Route Distinguisher and Route Target Pool	3-126
Creating a Site of Origin Pool	3-128
Creating a VC ID Pool	3-130
Creating a VLAN Pool	3-130
Deleting Resource Pools	3-132
CE Routing Communities	3-132
Accessing the CE Routing Communities Window	3-133
Creating CE Routing Communities	3-134
Deleting CE Routing Communities	3-135
VPNs	3-136
Accessing the VPNs Window	3-136
Creating a VPN	3-137
Deleting VPNs	3-140
AAA Servers	3-140
Named Physical Circuits	3-140
Accessing the Named Physical Circuits Window	3-141
Creating a Named Physical Circuit	3-142
Deleting Named Physical Circuits	3-145
Creating NPC Rings	3-146
Editing NPC Rings	3-149
Deleting NPC Rings	3-150

CHAPTER 4**Service Inventory—Discovery 4-1**

Overview of ISC Discovery	4-1
Technical Notes for ISC Discovery	4-3
General Notes	4-4
Using the Discovery Log Files	4-4
Using ISC Discovery with Cisco IP Solution Center MPLS VPN Management	4-5
Using ISC Discovery With Cisco IP Solution Center L2VPN Management	4-5
Using ISC Discovery With Cisco IP Solution Center MPLS Diagnostics Expert	4-5
Using ISC Discovery With Cisco IP Solution Center Traffic Engineering Management	4-6
Summary of Tasks for Discovery (Cisco ISC MPLS VPN Management and L2VPN Management)	4-6
Summary of ISC Discovery Steps for MPLS Diagnostics Expert	4-10
Step 1: Perform Preliminary Steps	4-13
Review System Requirements	4-14
Ensure the Repository Is Empty	4-15
Copying an Empty Repository	4-15
Install Licenses	4-15
(CDP Discovery Only) Verify That a Unique TIBCO Port Is Defined	4-16
(CDP Discovery Only) Verify That CDP Is Running on Devices To Be Discovered	4-16
Code XML Files Required for Discovery	4-17
Sample XML Files	4-17
Coding the inventory.xml File	4-17
Coding the policy.xml File	4-20
Coding the device.xml File	4-22
Coding the topology.xml File	4-24
Step 2: Perform Device Discovery	4-26
Starting Device Discovery	4-27
Editing Device Configurations	4-31
Setting Password Attributes (Required Step)	4-32
Setting General Device Attributes	4-34
Setting Cisco CNS Attributes	4-35
Saving the Device Configuration	4-36
Step 3: Perform Configuration Collection	4-36
Step 4: Perform Role Assignment	4-36
Initiating Device Role Assignment	4-37
Changing the Device Assignment Display	4-38
Changing Device Assignments	4-39
Assigning Devices Individually or in Bulk	4-39
Determine Device Roles	4-40
Assigning the PE Role	4-40

Editing the PE Role	4-42
Assigning the CE Role	4-43
Editing the CE Role	4-45
Saving the Role Assignment Information	4-48
Step 5: Perform NPC Discovery	4-49
Preliminary Steps Before Completing NPC Discovery for Metro Ethernet Networks with an Ethernet Core	4-49
Create Access Domains	4-50
Create Resource Pools	4-50
Edit Inter-N-PE Interfaces	4-50
Starting NPC Assignment	4-51
Adding a Device for an NPC	4-53
Adding a Ring	4-54
Inserting a Device	4-55
Inserting a Ring	4-55
Deleting a Device or a Ring	4-55
Saving the NPC Configuration	4-55
Step 6: Perform MPLS VPN Service Discovery (Optional)	4-56
Filtering the MPLS VPN View	4-58
Splitting a VPN	4-58
Creating a VPN	4-61
Viewing VPN Link Details	4-63
Saving the MPLS VPNs and Initiating MPLS VPN Service Creation	4-64
Step 7: Perform L2VPN (Metro Ethernet) Service Discovery (Optional)	4-65
Viewing Discovered Layer 2 Services Grouped by VPN	4-66
Editing Discovered Layer 2 Services Grouped by VPN	4-68
Deleting Discovered Layer 2 Services Grouped by VPN	4-69
Viewing Discovered Layer 2 End to End Wires	4-69
Editing the VPN Associated with an End-to-End Wire	4-71
Splitting Layer 2 Service End to End Wires	4-72
Joining Layer 2 Service End to End Wires	4-73
Deleting Layer 2 Service End to End Wires	4-73
Viewing Discovered Layer 2 VPLS Links	4-73
Editing Discovered Layer 2 VPLS Links	4-75
Deleting Discovered Layer 2 VPLS Links	4-76
Saving the L2VPN Metro Ethernet Policy and Initiating Service Creation	4-77
Step 8: Create and Run a Collect Config Task for the Discovered Devices	4-77
Step 9: View and Edit Services	4-78

CHAPTER 5**Service Inventory—Device Console 5-1**

- Device Console 5-1
 - Download Commands 5-2
 - Download Template 5-3
 - Device Configuration Manager 5-7
 - EXEC Commands 5-9
 - Reload 5-13

CHAPTER 6**Service Design 6-1**

- Policies 6-1
- Templates 6-2
 - View Templates Tree and Data Pane 6-3
 - Create Folders and Subfolders 6-4
 - Copying Folders or Subfolders 6-5
 - Create Template 6-5
 - Copying Templates 6-14
 - Create Data File 6-14
 - Edit 6-19
 - Delete 6-20
 - Template Examples 6-21
 - Summary of Repository Variables 6-23
 - Link QoS 6-37

CHAPTER 7**Monitoring 7-1**

- Task Manager 7-1
 - Tasks 7-2
 - Starting Task Manager 7-2
 - Create 7-3
 - Audit 7-5
 - Details 7-6
 - Schedules 7-6
 - Logs 7-7
 - Delete 7-7
 - Task Logs 7-7
- Ping 7-8
- SLA 7-11
 - Setup Prior to Using SLA 7-12
 - Probes 7-12
 - Create Common Parameters 7-13

Create From Any SA Agent Device(s)	7-15
Create from MPLS CPE	7-17
Create From MPLS PE or MVRP-CE	7-22
Protocols	7-24
Details	7-30
Delete	7-31
Enable Probes	7-32
Enable Traps	7-33
Disable Probes	7-34
Disable Traps	7-35
Reports	7-35
Summary Report	7-36
HTTP Report	7-39
Jitter Report	7-39
Summary CoS Report	7-39
HTTP CoS Report	7-40
Jitter CoS Report	7-41
TEM Performance Report	7-41
Reports	7-41
Introducing Reports	7-42
Accessing Reports	7-42
Using Reports GUI	7-42
Layout	7-43
Filters	7-43
Output Fields	7-43
Sorting	7-43
Running Reports	7-43
Using the Output from Reports	7-44
Exporting Reports	7-45
Printing Reports	7-45
E-mailing Reports	7-46
Invoking Help	7-46
Creating Custom Reports	7-46

CHAPTER 8

Diagnostics 8-1

CHAPTER 9

Administration 9-1

Security 9-1

Users 9-2

Details	9-3
Create	9-3
Copy	9-5
Edit	9-6
Delete	9-6
User Groups	9-7
Create	9-8
Edit	9-8
Delete	9-9
User Roles	9-9
Create	9-11
Copy	9-15
Edit	9-15
Delete	9-16
Object Groups	9-16
Create	9-17
Edit	9-19
Delete	9-19
User Roles Design Example	9-20
Example	9-20
Illustration of Setup	9-20
Steps to Set Up Example	9-22
Control Center	9-23
Hosts	9-23
Details	9-24
Config	9-25
Servers	9-26
Watchdog	9-27
Install	9-28
Uninstall	9-29
Logs	9-29
Collection Zones	9-30
Licensing	9-32
Active Users	9-34
User Access Log	9-35
Manage TIBCO Rendezvous	9-37

APPENDIX A

ISC XML Reference A-1

APPENDIX B

Cisco CNS IE2100 Appliances B-1

Creating a Cisco CNS IE2100 Appliance **B-1**

Creating a Cisco IOS Device Using the Cisco CNS Device Access Protocol **B-3**

Using Plug-and-Play **B-7**

APPENDIX C

Property Settings C-1

INDEX



FIGURES

Figure 1-1	Home Window	1-2
Figure 1-2	ISC Shortcuts	1-4
Figure 1-3	New ISC Shortcut	1-4
Figure 1-4	Index of all Choices	1-5
Figure 1-5	Customer Context	1-6
Figure 1-6	Example of Filtering, Header Row Check Box, Rows per Page, and Changing Pages	1-8
Figure 1-7	Example of Auto Refresh	1-8
Figure 1-8	Colors as Identifiers	1-9
Figure 1-9	Devices—Icons	1-10
Figure 1-10	Service Inventory Selections	1-11
Figure 1-11	Inventory and Connection Manager Selections	1-12
Figure 1-12	Service Design Selections	1-13
Figure 1-13	Templates Selections	1-13
Figure 1-14	Monitoring Selections	1-14
Figure 1-15	Diagnostics Selections	1-14
Figure 1-16	Administration Selections	1-15
Figure 1-17	Security Selections	1-16
Figure 1-18	Control Center Selections	1-16
Figure 3-1	Service Inventory Selections Window	3-1
Figure 3-2	Inventory and Connection Manager Selections Window	3-2
Figure 3-3	Service Request States Transition Diagram	3-4
Figure 3-4	Inventory Manager Window	3-5
Figure 3-5	Import Devices from Configuration Files Window	3-6
Figure 3-6	Select Device Configuration File Dialog	3-6
Figure 3-7	Select Devices Window	3-7
Figure 3-8	General Attributes Devices Window	3-8
Figure 3-9	Attributes Options Window	3-8
Figure 3-10	General Attributes Devices Window	3-9
Figure 3-11	Password Attributes Devices Window	3-10
Figure 3-12	SNMP Attributes Devices Window	3-11
Figure 3-13	CNS Attributes Devices Window	3-12

Figure 3-14	Platform Attributes Devices Window	3-13
Figure 3-15	Interfaces Devices Window	3-14
Figure 3-16	Select Provider Window	3-15
Figure 3-17	General Attributes Provider Window	3-16
Figure 3-18	Attributes Options Window	3-16
Figure 3-19	General Attributes Provider Window	3-17
Figure 3-20	Password Attributes Provider Window	3-18
Figure 3-21	SNMP Attributes Provider Window	3-19
Figure 3-22	CNS Attributes Provider Window	3-20
Figure 3-23	Platform Attributes Provider Window	3-21
Figure 3-24	PE Attributes Provider Window	3-22
Figure 3-25	Interfaces Provider Window	3-23
Figure 3-26	Select Customer Window	3-25
Figure 3-27	General Attributes Customer Window	3-25
Figure 3-28	Attributes Options Window	3-26
Figure 3-29	General Attributes Customer Window	3-27
Figure 3-30	Password Attributes Provider Window	3-28
Figure 3-31	SNMP Attributes Customer Window	3-29
Figure 3-32	CNS Attributes Customer Window	3-30
Figure 3-33	Platform Attributes Customer Window	3-31
Figure 3-34	CPE Attributes Customer Window	3-31
Figure 3-35	Interfaces Customer Window	3-32
Figure 3-36	Open Options Window	3-34
Figure 3-37	Select Devices Window	3-34
Figure 3-38	General Attributes Devices Window	3-35
Figure 3-39	Select Provider Window	3-35
Figure 3-40	Topology Launch Window	3-37
Figure 3-41	Security Warning Window	3-38
Figure 3-42	Topology Desktop Integration Window	3-38
Figure 3-43	Log On to ISC Window	3-38
Figure 3-44	Topology Application Window	3-42
Figure 3-45	The File Menu	3-43
Figure 3-46	The View Menu	3-44
Figure 3-47	Folder View Window	3-45
Figure 3-48	Aggregate View	3-46

Figure 3-49	Virtual Circuit with IP Core	3-47
Figure 3-50	Attachment Circuit View	3-48
Figure 3-51	Emulated Circuit View	3-49
Figure 3-52	Logical View	3-50
Figure 3-53	Device Properties	3-50
Figure 3-54	Interface Properties Window	3-51
Figure 3-55	Detailed Connection View	3-52
Figure 3-56	Physical View	3-53
Figure 3-57	Device Properties	3-54
Figure 3-58	Logical Device Properties Window	3-54
Figure 3-59	Physical Device Properties Window	3-55
Figure 3-60	Device Interface Properties Window	3-56
Figure 3-61	Service Request Properties Window	3-57
Figure 3-62	Link Properties	3-57
Figure 3-63	Expand Link Window	3-58
Figure 3-64	Link Service Request Properties Window	3-59
Figure 3-65	Link MPLS VPN Properties Window	3-60
Figure 3-66	Physical View with Dimmed Nodes	3-61
Figure 3-67	Advanced Filter Dialog	3-62
Figure 3-68	Find Dialog Box	3-63
Figure 3-69	The Map Menu	3-64
Figure 3-70	Load Map Window	3-65
Figure 3-71	Map Layers	3-66
Figure 3-72	Physical View with a Map of Japan	3-67
Figure 3-73	Devices List Window	3-73
Figure 3-74	Create Options Window	3-74
Figure 3-75	Create Catalyst Device Window	3-75
Figure 3-76	Catalyst Device Additional Properties Window	3-78
Figure 3-77	Create Cisco Device Window	3-81
Figure 3-78	Cisco Device Properties Window	3-84
Figure 3-79	Create Terminal Server Window	3-87
Figure 3-80	Terminal Server Device Properties Window	3-90
Figure 3-81	Create IE2100 Device Window	3-92
Figure 3-82	Devices List Window	3-93
Figure 3-83	Editing a Device Window	3-94

Figure 3-84	Devices List Window	3-95
Figure 3-85	Confirm Delete Window	3-95
Figure 3-86	Devices List Window	3-96
Figure 3-87	Device Configurations Window	3-97
Figure 3-88	Device Configuration Window	3-97
Figure 3-89	Devices List Window	3-98
Figure 3-90	Send Mail to Device Owners Window	3-99
Figure 3-91	Devices List Window	3-100
Figure 3-92	Device Groups Window	3-101
Figure 3-93	Create Device Group Window	3-102
Figure 3-94	Select Group Members Window	3-103
Figure 3-95	Create Device Group Window	3-103
Figure 3-96	Edit Device Group Window	3-104
Figure 3-97	Confirm Delete Window	3-105
Figure 3-98	Send Mail to Device Owners of Selected Groups Window	3-106
Figure 3-99	Customers Window	3-107
Figure 3-100	Create Customer Window	3-108
Figure 3-101	Edit Customer Window	3-109
Figure 3-102	Confirm Delete Window	3-110
Figure 3-103	Customer Sites Window	3-110
Figure 3-104	CPE Devices Window	3-112
Figure 3-105	Create CPE Device Window	3-113
Figure 3-106	Edit CPE Device Window	3-114
Figure 3-107	Providers Window	3-115
Figure 3-108	Create Provider Window	3-116
Figure 3-109	Edit Provider Window	3-117
Figure 3-110	Confirm Delete Window	3-118
Figure 3-111	Provider Regions Window	3-119
Figure 3-112	PE Devices Window	3-120
Figure 3-113	Access Domains Window	3-121
Figure 3-114	Resource Pools Window	3-123
Figure 3-115	Create IP Address Pool Window	3-124
Figure 3-116	Create Multicast Pool Window	3-125
Figure 3-117	Create Route Distinguisher Pool Window	3-126
Figure 3-118	Provider for New Resource Pool Window	3-127

Figure 3-119	Create Route Target Pool Window	3-127
Figure 3-120	Provider for New Resource Pool Window	3-128
Figure 3-121	Create Site of Origin Pool Window	3-129
Figure 3-122	Provider for New Resource Pool Window	3-129
Figure 3-123	Create VC ID Pool Window	3-130
Figure 3-124	Create VLAN Pool Window	3-131
Figure 3-125	Access Domain for new VLAN Pool Window	3-131
Figure 3-126	Confirm Delete Window	3-132
Figure 3-127	CE Routing Communities Window	3-133
Figure 3-128	Create CE Routing Community Window	3-135
Figure 3-129	VPNs Window	3-137
Figure 3-130	Create VPN Window	3-138
Figure 3-131	Named Physical Circuits Window	3-141
Figure 3-132	Create a Named Physical Circuit Window	3-142
Figure 3-133	Select Device Window	3-143
Figure 3-134	Create Named Physical Circuit Window	3-143
Figure 3-135	Select Outgoing Interface Window	3-144
Figure 3-136	Select Incoming Interface Window	3-144
Figure 3-137	Select NPC Ring Window	3-145
Figure 3-138	NPC Rings Window	3-146
Figure 3-139	Create Ring Window	3-146
Figure 3-140	Select Source Device — CPE/PE Window	3-147
Figure 3-141	Select Source Interface Window	3-147
Figure 3-142	Select Destination Device — CPE/PE Window	3-148
Figure 3-143	Select Destination Interface Window	3-148
Figure 3-144	NPC Rings Window	3-149
Figure 3-145	NPC Rings Window	3-150
Figure 3-146	Delete Rings Window	3-151
Figure 4-1	ISC Discovery Steps	4-2
Figure 4-2	Basic Workflow for Discovery with Cisco ISC MPLS VPN Management or Cisco ISC L2VPN Management	4-7
Figure 4-3	Detailed Diagram of Discovery Steps (Cisco ISC MPLS VPN Management and Cisco ISC L2VPN Management)	4-10
Figure 4-4	Discovery Workflow for the MPLS Diagnostics Expert Application	4-11
Figure 4-5	Summary of Preliminary Steps for Discovery	4-14
Figure 4-6	Choose TIBCO Port	4-16
Figure 4-7	Service Inventory Window	4-27

Figure 4-8	Discovery Window	4-27
Figure 4-9	Discovery Window with Device/Topology Fields	4-28
Figure 4-10	Discovery Workflow Window	4-30
Figure 4-11	Discovery Workflow Window with Device Input Pending	4-30
Figure 4-12	The General Attributes-Devices Window	4-31
Figure 4-13	Password Attributes Window	4-33
Figure 4-14	Edit Attributes Window for Password Attributes	4-34
Figure 4-15	CNS Attributes Window	4-35
Figure 4-16	Discovery Workflow with Role Collection Pending Input	4-36
Figure 4-17	Role Assignment - Un-assigned Devices Window	4-37
Figure 4-18	Role Assignment - CEs Window	4-39
Figure 4-19	Assign as PE Window	4-41
Figure 4-20	PE Region Name Window	4-41
Figure 4-21	Role Assignment - PEs Window	4-42
Figure 4-22	Assign as CE Window	4-44
Figure 4-23	Customer Name Window	4-44
Figure 4-24	Role Assignment - CEs Window	4-46
Figure 4-25	Site Name Window	4-48
Figure 4-26	Discovery Workflow with NPC Discovery Pending Input	4-49
Figure 4-27	Named Physical Circuits Window	4-51
Figure 4-28	Create Physical Circuits Window.	4-52
Figure 4-29	Select a Device Window	4-52
Figure 4-30	Create a Named Physical Circuit Window with Initial Device Added	4-53
Figure 4-31	Select Device Interface Window	4-54
Figure 4-32	NPC Complete Window	4-56
Figure 4-33	Discovery Workflow Window with MPLS VPN Discovery Pending Input	4-56
Figure 4-34	MPLS VPNs Window with Invalid MPLS VPN	4-57
Figure 4-35	Split VPN Window (Left Portion)	4-59
Figure 4-36	Split VPN Window (Right Portion)	4-59
Figure 4-37	Split VPNs Window After Creation of a Valid CERC Topology	4-60
Figure 4-38	Create VPN Window	4-61
Figure 4-39	MPLS VPNs Window with Valid VPN and Invalid VPN	4-62
Figure 4-40	Edit VPN Window	4-63
Figure 4-41	MPLS VPN Links Window	4-64
Figure 4-42	Discovery Workflow Window with MPLS Ethernet Discovery Pending Input	4-65

Figure 4-43	L2VPN Discovery (Ethernet Services) Window	4-66
Figure 4-44	L2 VPNs Window	4-67
Figure 4-45	Link Details Window	4-67
Figure 4-46	Edit Link Policy Window	4-68
Figure 4-47	Metro Ethernet End- to-End Wires Window	4-69
Figure 4-48	Link Details Window	4-70
Figure 4-49	Interface Detail Window	4-71
Figure 4-50	Edit VPN Window for L2VPN VPNs	4-72
Figure 4-51	VPLS Links Window	4-74
Figure 4-52	Link Details Window	4-75
Figure 4-53	Edit Link Policy Window	4-76
Figure 4-54	Discovery Workflow Window with L2 VPN Service Discovery Completed	4-77
Figure 4-55	Inventory and Connection Manager Window	4-79
Figure 4-56	Service Requests Window	4-79
Figure 5-1	Service Inventory Selections	5-1
Figure 5-2	Example of Device Console Selections	5-2
Figure 5-3	Device Console—Download Commands: Select Devices	5-3
Figure 5-4	Device Console—Download Template: Select Devices	5-4
Figure 5-5	Device Selection	5-4
Figure 5-6	Device Group Selection	5-5
Figure 5-7	Group Association	5-5
Figure 5-8	Select Download Template	5-6
Figure 5-9	Add/Remove Templates	5-6
Figure 5-10	Download Template Summary	5-7
Figure 5-11	Device Configuration Manager	5-8
Figure 5-12	Device Selection	5-8
Figure 5-13	Device Console—EXEC Commands: Select Devices	5-10
Figure 5-14	Device Selection	5-10
Figure 5-15	Device Group Selection	5-11
Figure 5-16	Group Association	5-11
Figure 5-17	Operation Commands	5-12
Figure 5-18	EXEC Commands Summary	5-12
Figure 5-19	Device Console—Reload: Select Devices	5-13
Figure 5-20	Device Selection	5-14
Figure 5-21	Device Group Selection	5-14

Figure 5-22	Group Association	5-15
Figure 5-23	Reload Summary	5-15
Figure 6-1	Service Design Selections	6-1
Figure 6-2	Templates	6-2
Figure 6-3	Tree and Data Pane Structure	6-4
Figure 6-4	Folder Naming	6-5
Figure 6-5	Folder with Existing Templates	6-6
Figure 6-6	Template Editor	6-6
Figure 6-7	Example Template	6-7
Figure 6-8	Template Variables	6-8
Figure 6-9	Variable Definition—Type String	6-8
Figure 6-10	Variable Definition—Type Integer	6-10
Figure 6-11	Variable Definition—Type Float	6-11
Figure 6-12	Variable Definition—Type IPv4	6-12
Figure 6-13	Variable Definition—Type Sub-Template	6-13
Figure 6-14	Variable Definition—Type Dynamic Java Class	6-13
Figure 6-15	Variable Definition—Type Dynamic URL	6-14
Figure 6-16	Choose Existing Template > Create Data File	6-15
Figure 6-17	Choose Existing Template > Create Data File	6-15
Figure 6-18	Template Data File Editor	6-16
Figure 6-19	Template Data File Editor	6-16
Figure 6-20	Editing a One-Dimensional Array	6-17
Figure 6-21	Adding a Variable	6-17
Figure 6-22	Editing a Two-Dimensional Array	6-18
Figure 6-23	Enter Row Information	6-18
Figure 6-24	Enter Column Information	6-18
Figure 6-25	Two-Dimensional Array Results	6-19
Figure 6-26	Choose Existing Template > Edit	6-20
Figure 6-27	Choose Existing Data File > Edit	6-20
Figure 6-28	Choose Existing Template > Delete	6-21
Figure 6-29	Choose Existing Data File > Delete	6-21
Figure 7-1	Monitoring Selections	7-1
Figure 7-2	Tasks	7-2
Figure 7-3	Create Tasks	7-3
Figure 7-4	Task Devices	7-4

Figure 7-5	Service Deployment Task	7-4
Figure 7-6	Task Schedule Details	7-5
Figure 7-7	Task Scheduling	7-6
Figure 7-8	Tasks	7-7
Figure 7-9	Task Logs	7-7
Figure 7-10	Task Log	7-8
Figure 7-11	Services	7-9
Figure 7-12	MPLS Parameters	7-9
Figure 7-13	MPLS CE Selection	7-10
Figure 7-14	MPLS Ping Test Results	7-10
Figure 7-15	SLA Probes	7-12
Figure 7-16	SLA Common Parameters	7-13
Figure 7-17	SLA Source Devices	7-15
Figure 7-18	SLA Devices > Add	7-16
Figure 7-19	SLA Destination Devices	7-17
Figure 7-20	SLA CPE Parameters	7-18
Figure 7-21	Select VPN	7-18
Figure 7-22	Select CPE	7-18
Figure 7-23	Interfaces	7-19
Figure 7-24	Connected PE Interface	7-20
Figure 7-25	CPEs	7-21
Figure 7-26	Select CPE Associated with the Specified VPN	7-21
Figure 7-27	SLA Source and Destination Devices	7-22
Figure 7-28	Select VPN	7-22
Figure 7-29	Select PE	7-23
Figure 7-30	Select CPE	7-23
Figure 7-31	Select PEs	7-24
Figure 7-32	Select CPEs	7-24
Figure 7-33	Protocols	7-25
Figure 7-34	Protocol ICMP Echo	7-25
Figure 7-35	Protocol TCP Connect	7-26
Figure 7-36	Protocol UDP Echo	7-26
Figure 7-37	Protocol Jitter	7-27
Figure 7-38	Protocol FTP	7-27
Figure 7-39	Protocol DNS	7-28

Figure 7-40	Protocol HTTP	7-28
Figure 7-41	Protocol DHCP	7-29
Figure 7-42	SLA Probes > Details	7-30
Figure 7-43	SLA Probes Details	7-30
Figure 7-44	SLA Probes > Delete	7-31
Figure 7-45	Confirm Delete Probes	7-31
Figure 7-46	SLA Probes > Enable > Probes	7-32
Figure 7-47	Confirm Enable Probes	7-32
Figure 7-48	SLA Probes > Enable > Traps	7-33
Figure 7-49	Confirm Enable Traps	7-33
Figure 7-50	SLA Probes > Disable > Probes	7-34
Figure 7-51	Confirm Disable Probes	7-34
Figure 7-52	SLA Probes > Disable > Traps	7-35
Figure 7-53	Confirm Disable Traps	7-35
Figure 7-54	SLA Reports	7-36
Figure 7-55	Parameters of Summary Report	7-37
Figure 7-56	Parameters of CoS Summary Report	7-40
Figure 7-57	Inventory > SAMPLE - Template Report - Report Window	7-41
Figure 7-58	Report Output	7-44
Figure 7-59	Report Output Icons	7-45
Figure 7-60	Exporting Report Window	7-45
Figure 7-61	Print Report	7-45
Figure 7-62	E-mail Report	7-46
Figure 8-1	Diagnostics Selection	8-1
Figure 9-1	Administration Selections	9-1
Figure 9-2	Security Window	9-2
Figure 9-3	Users Window	9-3
Figure 9-4	Create/Copy/Edit Users Window	9-4
Figure 9-5	Users Confirm Delete	9-7
Figure 9-6	User Groups Window	9-7
Figure 9-7	Create/Edit User Groups Window	9-8
Figure 9-8	User Groups Confirm Delete	9-9
Figure 9-9	User Roles Window	9-11
Figure 9-10	Create/Copy/Edit User Roles Window (Top)	9-12
Figure 9-11	Create/Copy/Edit User Roles Window (Bottom)	9-13

Figure 9-12	User Roles Confirm Delete	9-16
Figure 9-13	Object Groups Window	9-17
Figure 9-14	Create/Edit Object Group Window	9-18
Figure 9-15	Delete Object Groups Confirm Delete	9-19
Figure 9-16	Contents in Example	9-21
Figure 9-17	Control Center > Hosts	9-23
Figure 9-18	Host Details	9-24
Figure 9-19	Properties	9-25
Figure 9-20	Properties Detail Example	9-26
Figure 9-21	Servers	9-27
Figure 9-22	WatchDog Logs	9-27
Figure 9-23	Install ISC Host	9-28
Figure 9-24	Remote Uninstall	9-29
Figure 9-25	Choose Control Center > Collection Zones	9-30
Figure 9-26	Create Collection Zone	9-31
Figure 9-27	Collection Zone Devices	9-32
Figure 9-28	Choose Control Center > Licensing	9-33
Figure 9-29	Installed Licenses	9-33
Figure 9-30	Enter License Key	9-34
Figure 9-31	Active Users	9-34
Figure 9-32	User Access Log Viewer with Simple Filter	9-35
Figure 9-33	User Access Log Viewer with Advanced Filter	9-36
Figure 9-34	TIBCO Rendezvous	9-37
Figure 9-35	Connection Configuration	9-38
Figure B-1	Devices Window	B-2
Figure B-2	Create IE2100 Device Window	B-2
Figure B-3	Create Cisco Device Window	B-4
Figure B-4	Cisco Device Additional Properties	B-5



TABLES

<i>Table 2-1</i>	Servers and Their Functions	2-10
<i>Table 2-2</i>	Valid States	2-10
<i>Table 3-1</i>	Summary of Cisco IP Solution Center Service Request States	3-3
<i>Table 3-2</i>	Device Role Shapes	3-39
<i>Table 3-3</i>	Link Type Color Scheme	3-41
<i>Table 3-4</i>	Link State Pattern Scheme	3-41
<i>Table 3-5</i>	SNMP Security Models and Levels	3-70
<i>Table 3-6</i>	Create Catalyst Device Interfaces Fields	3-76
<i>Table 3-7</i>	Create Cisco Device Interface Fields	3-82
<i>Table 3-8</i>	Create Terminal Server Device Interfaces Fields	3-88
<i>Table 4-1</i>	Steps in the Discovery Process	4-3
<i>Table 4-2</i>	Description of Discovery Steps for M PLS VPN Management and L2VPN Management	4-8
<i>Table 4-3</i>	Description of Discovery Steps for M PLS Diagnostics Expert	4-12
<i>Table 4-4</i>	XML Files Used with ISC Discovery	4-17
<i>Table 4-5</i>	XML Tags Used in the inventory.xml File	4-19
<i>Table 4-6</i>	XML Tags and Attributes Used in the policy.xml File	4-21
<i>Table 4-7</i>	XML Tags Used in the device.xml File	4-23
<i>Table 4-8</i>	XML tags and Attributes Used in the topology.xml File	4-25
<i>Table 4-9</i>	Discovery Settings	4-28
<i>Table 6-1</i>	Template Examples and Their Descriptions	6-22
<i>Table 6-2</i>	L2VPN Repository Variables	6-23
<i>Table 6-3</i>	MPLS Repository Variables	6-26
<i>Table 6-4</i>	QoS Repository Variables	6-33
<i>Table 6-5</i>	VPLS Repository Variables	6-35
<i>Table 7-1</i>	Meanings of Precedence Values	7-14
<i>Table A-1</i>	ISC XML Rules, Tags, and Attributes	A-1
<i>Table C-1</i>	DCPL Properties	C-1



About This Guide

This preface defines the following:

- [Objective, page xxix](#)
- [Related Documentation, page xxix](#)
- [Audience, page xxx](#)
- [How This Book Is Organized, page xxx](#)
- [Document Conventions, page xxxi](#)
- [Obtaining Documentation, page xxxii](#)
- [Documentation Feedback, page xxxiii](#)
- [Cisco Product Security Overview, page xxxiii](#)
- [Obtaining Technical Assistance, page xxxiv](#)
- [Obtaining Additional Publications and Information, page xxxvi](#)

Objective

This guide provides details about the WatchDog commands and the Graphical User Interface (GUI) for the Cisco IP Solution Center (ISC) product. Detailed explanations are given for common components across all applications.

Related Documentation

The entire documentation set for Cisco IP Solution Center, 4.1 can be accessed at:

http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1

The following documents comprise the ISC 4.1 documentation set.

General documentation (in suggested reading order):

- *Cisco IP Solution Center Getting Started and Documentation Guide, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/docguide/index.htm
- *Release Notes for Cisco IP Solution Center, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/relnotes/index.htm

- *Cisco IP Solution Center Installation Guide, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/install/index.htm
- *Cisco IP Solution Center Infrastructure Reference, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/infrastr/index.htm
- *Cisco IP Solution Center System Error Messages, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/mess/index.htm

Application and technology documentation (listed alphabetically):

- *Cisco IP Solution Center L2VPN User Guide, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/l2vpn/index.htm
- *Cisco IP Solution Center MPLS VPN User Guide, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/mppls/index.htm
- *Cisco IP Solution Center Quality of Service User Guide, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/qos/index.htm
- *Cisco IP Solution Center Traffic Engineering Management User Guide, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/tem/index.htm
- *Cisco MPLS Diagnostics Expert 1.0 User Guide on ISC 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/trble/index.htm

API Documentation:

- *Cisco IP Solution Center API Programmer Guide, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/api_set/api_gd/index.htm
- Index: *Cisco IP Solution Center API Programmer Reference, 4.1*
http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/api_set/api_ref/index.htm



Note

All documentation *might* be upgraded over time. All upgraded documentation will be available at the same URLs specified in this document.

Audience

This guide is written as a resource for experienced users and administrators who use ISC. It provides details about how to implement the infrastructure functionality of ISC that is common to all applications.

It is assumed that you have a basic understanding of network design, operation, and terminology, and that you are familiar with your own network configurations.

How This Book Is Organized

This guide is organized as follows:

- **Chapter 1, “Getting Started,”** provides a reference to the system recommendations, provides an overview of the ISC product, provides an overview of the GUI structure, and explains the common GUI components.

- [Chapter 2, “WatchDog Commands,”](#) provides the description, syntax, and arguments for the commands for WatchDog, a background daemon process that is automatically installed as part of the installation procedure for ISC.
- [Chapter 3, “Service Inventory — Inventory and Connection Manager,”](#) explains the navigation path from the **Service Inventory** tab to **Inventory and Connection Manager** and how to use the topics found there.
- [Chapter 4, “Service Inventory—Discovery,”](#) explains the navigation path from the **Service Inventory** tab to **Discovery** and how to discover devices, connections, and services.
- [Chapter 5, “Service Inventory—Device Console,”](#) explains the navigation path from the **Service Inventory** tab to **Device Console** and how to use the topics found there.
- [Chapter 6, “Service Design,”](#) explains the **Service Design** tab and how to use the topics found there.
- [Chapter 7, “Monitoring,”](#) explains the **Monitoring** tab and how to use the topics found there.
- [Chapter 8, “Diagnostics,”](#) explains the **Diagnostics** tab and where to navigate for a full explanation.
- [Chapter 9, “Administration,”](#) explains the **Administration** tab and how to use the topics found there.
- [Appendix A, “ISC XML Reference,”](#) explains XML files for Discovery.
- [Appendix B, “Cisco CNS IE2100 Appliances,”](#) explains how to use the Cisco CNS IE2100 functionality on ISC.
- [Appendix C, “Property Settings,”](#) explains the Dynamic Component Properties Library (DCPL) properties, their defaults, and ranges and rules.
- [Glossary](#) explains terminology used in the ISC product.

Document Conventions

This section discusses conventions and terminology used throughout this manual.

- *pointer*—indicates where the mouse action is to occur
- *select*—to push and hold down the left mouse button
- *release*—to let up on a mouse button to initiate an action
- *click*—to select and release a mouse button without moving the pointer
- *double-click*—to click a mouse button twice quickly without moving the pointer
- *drag*—to move the pointer by sliding the mouse with one or more buttons selected

This manual uses this terminology throughout (even though it is possible for individual users to customize their devices to use the buttons in an alternative manner).

In situations that allow more than one item to be selected from a list simultaneously, the following actions are supported:

- To select a single item in a list, click the entry. Clicking a second time on a previously selected entry deselects it.
- To select a contiguous block of items, click the first entry; then, without releasing the mouse button, drag to the last desired entry and release. (A subsequent click anywhere on the window deselects all previous selections.)

- To extend a currently selected block, hold the **Shift** key down and click the entry at the end of the group to be added
- To add a noncontiguous entry to the selection group, press the **Ctrl** (Control) key and click the entry to be added.

Names of on-window elements that you click or select (menu names, commands, and controls such as buttons, drop-down lists, and so on) are printed in **bold** font.

Bold font is also used for keywords, names of commands, and names of keys on the keyboard.

Text displayed as on-window examples is printed in `courier` font.

When set off from the main text, words and characters you should enter by the keyboard are printed in **bold** font. When the word or character string is enclosed in angle brackets (< and >), you should substitute your own character string for the example presented in the text.

For example, when you see:

login: **root**

you should specify the string **root** at the **login** prompt. However, when you see:

password: *<rootpassword>*

you should specify your own password in place of the character string *<rootpassword>*.

The *italic style* is used to emphasize words, to introduce new terms, and for titles of printed publications (however, not titles of CD-ROMs or floppy disks).



Note

Means *reader take note*. Notes contain helpful suggestions or references to materials not contained in this manual.



Caution

Means *reader be careful*. In this situation, you might do something that could result in equipment damage or loss of data.

Obtaining Documentation

Cisco documentation and additional literature are available on Cisco.com. Cisco also provides several ways to obtain technical assistance and other technical resources. These sections explain how to obtain technical information from Cisco Systems.

Cisco.com

You can access the most current Cisco documentation at this URL:

<http://www.cisco.com/techsupport>

You can access the Cisco website at this URL:

<http://www.cisco.com>

You can access international Cisco websites at this URL:

http://www.cisco.com/public/countries_languages.shtml

Product Documentation DVD

Cisco documentation and additional literature are available in the Product Documentation DVD package, which may have shipped with your product. The Product Documentation DVD is updated regularly and may be more current than printed documentation.

The Product Documentation DVD is a comprehensive library of technical product documentation on portable media. The DVD enables you to access multiple versions of hardware and software installation, configuration, and command guides for Cisco products and to view technical documentation in HTML. With the DVD, you have access to the same documentation that is found on the Cisco website without being connected to the Internet. Certain products also have .pdf versions of the documentation available.

The Product Documentation DVD is available as a single unit or as a subscription. Registered Cisco.com users (Cisco direct customers) can order a Product Documentation DVD (product number DOC-DOCDVD=) from Cisco Marketplace at this URL:

<http://www.cisco.com/go/marketplace/>

Ordering Documentation

Beginning June 30, 2005, registered Cisco.com users may order Cisco documentation at the Product Documentation Store in the Cisco Marketplace at this URL:

<http://www.cisco.com/go/marketplace/>

Nonregistered Cisco.com users can order technical documentation from 8:00 a.m. to 5:00 p.m. (0800 to 1700) PDT by calling 1 866 463-3487 in the United States and Canada, or elsewhere by calling 011 408 519-5055. You can also order documentation by e-mail at tech-doc-store-mkpl@external.cisco.com or by fax at 1 408 519-5001 in the United States and Canada, or elsewhere at 011 408 519-5001.

Documentation Feedback

You can rate and provide feedback about Cisco technical documents by completing the online feedback form that appears with the technical documents on Cisco.com.

You can send comments about Cisco documentation to bug-doc@cisco.com.

You can submit comments by using the response card (if present) behind the front cover of your document or by writing to the following address:

Cisco Systems
Attn: Customer Document Ordering
170 West Tasman Drive
San Jose, CA 95134-9883

We appreciate your comments.

Cisco Product Security Overview

Cisco provides a free online Security Vulnerability Policy portal at this URL:

http://www.cisco.com/en/US/products/products_security_vulnerability_policy.html

From this site, you can perform these tasks:

- Report security vulnerabilities in Cisco products.
- Obtain assistance with security incidents that involve Cisco products.
- Register to receive security information from Cisco.

A current list of security advisories and notices for Cisco products is available at this URL:

<http://www.cisco.com/go/psirt>

If you prefer to see advisories and notices as they are updated in real time, you can access a Product Security Incident Response Team Really Simple Syndication (PSIRT RSS) feed from this URL:

http://www.cisco.com/en/US/products/products_psirt_rss_feed.html

Reporting Security Problems in Cisco Products

Cisco is committed to delivering secure products. We test our products internally before we release them, and we strive to correct all vulnerabilities quickly. If you think that you might have identified a vulnerability in a Cisco product, contact PSIRT:

- Emergencies—security-alert@cisco.com

An emergency is either a condition in which a system is under active attack or a condition for which a severe and urgent security vulnerability should be reported. All other conditions are considered nonemergencies.

- Nonemergencies—psirt@cisco.com

In an emergency, you can also reach PSIRT by telephone:

- 1 877 228-7302
- 1 408 525-6532



Tip

We encourage you to use Pretty Good Privacy (PGP) or a compatible product to encrypt any sensitive information that you send to Cisco. PSIRT can work from encrypted information that is compatible with PGP versions 2.x through 8.x.

Never use a revoked or an expired encryption key. The correct public key to use in your correspondence with PSIRT is the one linked in the Contact Summary section of the Security Vulnerability Policy page at this URL:

http://www.cisco.com/en/US/products/products_security_vulnerability_policy.html

The link on this page has the current PGP key ID in use.

Obtaining Technical Assistance

Cisco Technical Support provides 24-hour-a-day award-winning technical assistance. The Cisco Technical Support & Documentation website on Cisco.com features extensive online support resources. In addition, if you have a valid Cisco service contract, Cisco Technical Assistance Center (TAC) engineers provide telephone support. If you do not have a valid Cisco service contract, contact your reseller.

Cisco Technical Support & Documentation Website

The Cisco Technical Support & Documentation website provides online documents and tools for troubleshooting and resolving technical issues with Cisco products and technologies. The website is available 24 hours a day, at this URL:

<http://www.cisco.com/techsupport>

Access to all tools on the Cisco Technical Support & Documentation website requires a Cisco.com user ID and password. If you have a valid service contract but do not have a user ID or password, you can register at this URL:

<http://tools.cisco.com/RPF/register/register.do>



Note

Use the Cisco Product Identification (CPI) tool to locate your product serial number before submitting a web or phone request for service. You can access the CPI tool from the Cisco Technical Support & Documentation website by clicking the **Tools & Resources** link under Documentation & Tools. Choose **Cisco Product Identification Tool** from the Alphabetical Index drop-down list, or click the **Cisco Product Identification Tool** link under Alerts & RMAs. The CPI tool offers three search options: by product ID or model name; by tree view; or for certain products, by copying and pasting **show** command output. Search results show an illustration of your product with the serial number label location highlighted. Locate the serial number label on your product and record the information before placing a service call.

Submitting a Service Request

Using the online TAC Service Request Tool is the fastest way to open S3 and S4 service requests. (S3 and S4 service requests are those in which your network is minimally impaired or for which you require product information.) After you describe your situation, the TAC Service Request Tool provides recommended solutions. If your issue is not resolved using the recommended resources, your service request is assigned to a Cisco engineer. The TAC Service Request Tool is located at this URL:

<http://www.cisco.com/techsupport/servicerequest>

For S1 or S2 service requests or if you do not have Internet access, contact the Cisco TAC by telephone. (S1 or S2 service requests are those in which your production network is down or severely degraded.) Cisco engineers are assigned immediately to S1 and S2 service requests to help keep your business operations running smoothly.

To open a service request by telephone, use one of the following numbers:

Asia-Pacific: +61 2 8446 7411 (Australia: 1 800 805 227)

EMEA: +32 2 704 55 55

USA: 1 800 553-2447

For a complete list of Cisco TAC contacts, go to this URL:

<http://www.cisco.com/techsupport/contacts>

Definitions of Service Request Severity

To ensure that all service requests are reported in a standard format, Cisco has established severity definitions.

Severity 1 (S1)—Your network is “down,” or there is a critical impact to your business operations. You and Cisco will commit all necessary resources around the clock to resolve the situation.

Severity 2 (S2)—Operation of an existing network is severely degraded, or significant aspects of your business operation are negatively affected by inadequate performance of Cisco products. You and Cisco will commit full-time resources during normal business hours to resolve the situation.

Severity 3 (S3)—Operational performance of your network is impaired, but most business operations remain functional. You and Cisco will commit resources during normal business hours to restore service to satisfactory levels.

Severity 4 (S4)—You require information or assistance with Cisco product capabilities, installation, or configuration. There is little or no effect on your business operations.

Obtaining Additional Publications and Information

Information about Cisco products, technologies, and network solutions is available from various online and printed sources.

- Cisco Marketplace provides a variety of Cisco books, reference guides, documentation, and logo merchandise. Visit Cisco Marketplace, the company store, at this URL:
<http://www.cisco.com/go/marketplace/>
- *Cisco Press* publishes a wide range of general networking, training and certification titles. Both new and experienced users will benefit from these publications. For current Cisco Press titles and other information, go to Cisco Press at this URL:

<http://www.ciscopress.com>

- *Packet* magazine is the Cisco Systems technical user magazine for maximizing Internet and networking investments. Each quarter, Packet delivers coverage of the latest industry trends, technology breakthroughs, and Cisco products and solutions, as well as network deployment and troubleshooting tips, configuration examples, customer case studies, certification and training information, and links to scores of in-depth online resources. You can access Packet magazine at this URL:
<http://www.cisco.com/packet>
- *iQ Magazine* is the quarterly publication from Cisco Systems designed to help growing companies learn how they can use technology to increase revenue, streamline their business, and expand services. The publication identifies the challenges facing these companies and the technologies to help solve them, using real-world case studies and business strategies to help readers make sound technology investment decisions. You can access iQ Magazine at this URL:

<http://www.cisco.com/go/iqmagazine>

or view the digital edition at this URL:

<http://ciscoiq.texterity.com/ciscoiq/sample/>

- *Internet Protocol Journal* is a quarterly journal published by Cisco Systems for engineering professionals involved in designing, developing, and operating public and private internets and intranets. You can access the Internet Protocol Journal at this URL:

<http://www.cisco.com/ipj>

- Networking products offered by Cisco Systems, as well as customer support services, can be obtained at this URL:

<http://www.cisco.com/en/US/products/index.html>

- Networking Professionals Connection is an interactive website for networking professionals to share questions, suggestions, and information about networking products and technologies with Cisco experts and other networking professionals. Join a discussion at this URL:

<http://www.cisco.com/discuss/networking>

- World-class networking training is available from Cisco. You can view current offerings at this URL:

<http://www.cisco.com/en/US/learning/index.html>



Getting Started

This chapter provides information about how to get started to use Cisco IP Solution Center (ISC) and gives a structural overview of this manual. It contains the following sections:

- [System Recommendations, page 1-1](#)
- [Introduction, page 1-1](#)
- [Structural Overview, page 1-2](#)
- [Service Inventory, page 1-10](#)
- [Service Design, page 1-12](#)
- [Monitoring, page 1-13](#)
- [Diagnostics, page 1-14](#)
- [Administration, page 1-15](#)

System Recommendations

The system recommendations and requirements are listed in Chapter 1, “System Recommendations” of [Cisco IP Solution Center Installation Guide, 4.1](#). The recommendation is to thoroughly review this list before even planning your installation, to be sure that you have all the hardware and software you must successfully install.



Note

There is no direct way to upgrade from ISC 3.0 or ISC 3.1 to ISC 4.1. To upgrade from ISC 3.0 or ISC 3.1 to ISC 4.1, you *must* contact ISC Marketing, e-mail: isc-mktg@cisco.com.

Introduction

Cisco IP Solution Center, 4.1 (ISC 4.1) is a follow-on release to Cisco IP Solution Center, 4.0 (ISC 4.0), with the exceptions listed in [Release Notes for Cisco IP Solution Center, 4.1](#).

This manual lists many features that are common among multiple applications, which are sold and licensed separately. The applications and their respective *User Guides* reference this document for setup steps necessary before creating a policy and then a service request specific to the application and for other common features.

Before explaining the tabs in the Graphical User Interface (GUI), see the “[Structural Overview](#)” section on [page 1-2](#). It explains elements common to many windows in ISC.

The GUI is separated into the following large sections (tabs):


- “[Service Inventory](#)” section on [page 1-10](#)
- “[Service Design](#)” section on [page 1-12](#)
- “[Monitoring](#)” section on [page 1-13](#)
- “[Diagnostics](#)” section on [page 1-14](#)
- “[Administration](#)” section on [page 1-15](#)

The remaining sections in this chapter explain the sections and subsections of this manual that explain the functionality available from these tabs.

Structural Overview

After you log into Cisco IP Solution Center (ISC), the first window to appear is the Home window, as shown in [Figure 1-1](#), “[Home Window](#).”

Figure 1-1 Home Window



Note

The tabs and the choices navigating within the tabs that appear depend on the user permission, explained in [Chapter 9](#), “[Administration](#)” (**Administration** > **Security** > **User Roles**). The choices shown in this manual are for all permissions (**admin**).

This overview includes the following sections:

- [Product Category Tabs](#), [page 1-3](#)
- [Links](#), [page 1-3](#)
- [Common GUI Components](#), [page 1-6](#)

Product Category Tabs

The organization of this manual is based on the tabs shown in [Figure 1-1](#), “Home Window.” Click either the specific tab or the name in the data pane:

- **Service Inventory** An overview is given in the “Service Inventory” section on page 1-10 and detailed information is given in [Chapter 3](#), “Service Inventory — Inventory and Connection Manager,” [Chapter 4](#), “Service Inventory—Discovery,” and [Chapter 5](#), “Service Inventory—Device Console.”
- **Service Design** An overview is given in the “Service Design” section on page 1-12 and detailed information is given in [Chapter 6](#), “Service Design.”
- **Monitoring** An overview is given in the “Monitoring” section on page 1-13 and detailed information is given in [Chapter 7](#), “Monitoring.”
- **Diagnostics** An overview is given in the “Diagnostics” section on page 1-14 and a pointer to detailed information is given in [Chapter 8](#), “Diagnostics.”
- **Administration** An overview is given in the “Administration” section on page 1-15 and detailed information is given in [Chapter 9](#), “Administration.”

Links

In the upper right-hand corner of the Home window ([Figure 1-1](#)), additional links appear that function as follows:

- [Home](#), page 1-3
- [Shortcuts](#), page 1-3
- [Account](#), page 1-5
- [Index](#), page 1-5
- [Help](#), page 1-5
- [About](#), page 1-6
- [Logout](#), page 1-6

On the far right of the **You are Here:** line on the Home window ([Figure 1-1](#)), is the name of a Customer Context, which is explained in the “Customer” section on page 1-6.

Home

When you click **Home**, you always return to the first window to appear, as shown in [Figure 1-1](#), “Home Window.”

Shortcuts

When you click **Shortcuts**, you can define shortcuts to help quickly navigate to day to day operations. In addition, by grouping these shortcuts together into folders, you can create work flows specific to your operating environment. To get more information about shortcuts, follow these steps:

-
- Step 1** After you click **Shortcuts**, you receive a window as shown in [Figure 1-2](#), “ISC Shortcuts.”

Figure 1-2 *ISC Shortcuts*

Showing 1 - 5 of 5 records

#	<input type="checkbox"/>	Folder Name	Shortcut Name	Description
1.	<input type="checkbox"/>		test1	
2.	<input type="checkbox"/>		test2	
3.	<input type="checkbox"/>		test3	
4.	<input checked="" type="checkbox"/>	testfolder1	testf1	
5.	<input type="checkbox"/>	testfolder1	test4	

Rows per page: All Go to page: 1 of 1 Go

Go Create Edit Delete Close

116231

Step 2 To create a shortcut, click the **Create** button in [Figure 1-2](#) and you receive a window as shown in [Figure 1-3](#), “New ISC Shortcut.”

Figure 1-3 *New ISC Shortcut*

Name :

URL :

Type or paste the desired URL into the field above. If the URL is external to ISC, it must begin with "http://". Or, select an internal URL from the list below and click "Set":

Choose...

Description:

Folder:

Folder Shortcut Ordering:

- test1
- test2
- test3

116232

Step 3 Fill in the required **Name** and **URL** (you can type in the URL, in which case if it is external to ISC, you must start the URL name with **http://**, or you can click the drop-down list and choose a path internal to ISC and then click the **Set** button) and optionally the **Description**, **Folder**, and **Folder Shortcut Ordering**. Then click **Save**.

- Step 4** You return to [Figure 1-2](#) and can repeat [Step 2](#) and [Step 3](#) to **Create** more shortcuts or you can select a shortcut to proceed to **Go**, select a shortcut to **Edit**, select one or more shortcuts to **Delete**, or select **Close**.
- Step 5** Any time you want to go directly to a URL, you can click **Shortcuts** on the **Home** page and from [Figure 1-2](#) select the shortcut of your choice and click **Go**.


Account

When you click **Account**, you can change your password without the SysAdmin or UserAdmin privileges. This allows you to edit the user profile, including changing the password.

Index

When you click **Index**, you receive an overall picture of all choices from which you can click and jump to, as shown in [Figure 1-4](#), “[Index of all Choices](#).”

Figure 1-4 *Index of all Choices*



Help

When you click **Help**, you receive a pointer to the documentation set.

About

When you click **About**, you receive the product name and version.

Logout

When you click **Logout**, you log out of the product.

Customer

On the far right of the **You are Here** line of the Home page is **Customer:** followed by **None** (default) or a customer name. This is referred to as Customer Context. The advantage of Customer Context is to focus only on information for a specified customer. To set the Customer Context, follow these steps:

- Step 1** Click on the name after **Customer:** on the far right of the line that starts with **You are Here**. The default is **None**. The window shown in [Figure 1-5](#), “**Customer Context**,” appears.

Figure 1-5 Customer Context

- Step 2** Click the **Select** button and you receive a list of all the currently created customers.
- Step 3** Click the radio button for the customer for which you want information and click **Select**.
- Step 4** [Figure 1-5](#), “**Customer Context**,” reappears with the name of the selected customer. Click **Save** or highlight the customer name and click **Clear** to reset the customer for which you want information.
- Step 5** The customer you chose now appears after **Customer:** on the Home window and it is the only customer for which information appears.
- Step 6** You can reset the Customer Context by clearing and reselecting.

Common GUI Components

GUI components that are common on many windows are as follows:

- [Filters](#), page 1-7
- [Header Row Check Box](#), page 1-7
- [Rows per Page](#), page 1-7
- [Go To Page](#), page 1-7
- [Auto Refresh](#), page 1-8

- [Color Coding, page 1-8](#)
- [Icons, page 1-10](#)

Filters

At the top of many windows you can filter information that appears in the window. As shown in [Figure 1-6, “Example of Filtering, Header Row Check Box, Rows per Page, and Changing Pages,”](#) you can click the drop-down list for categories, then in the **matching** field enter the search criteria, using * if you want to indicate anything is a match (you can enter only * or you can place * before other characters, in the middle of other characters, at the end of other characters, or in multiple locations), and click **Find**. In some cases you might also have a field after the **matching** field from which you can select or enter more specifics for your **Find**.

Header Row Check Box

Many windows have a check box in the header row, where the column names exist, as shown in [Figure 1-6, Example of Filtering, Header Row Check Box, Rows per Page, and Changing Pages](#). If you select this check box, then all check boxes in the window are chosen.

Rows per Page

In the bottom left corner of many windows, as shown in [Figure 1-6, “Example of Filtering, Header Row Check Box, Rows per Page, and Changing Pages,”](#) you can change the number of rows shown on this window in **Rows per page**. Click the drop-down list and you can select **5, 10, 20, 30, 40, 50, 100, 500, 1000, or 2500**.

Go To Page

Near the bottom in the right corner of many windows, as shown in [Figure 1-6, “Example of Filtering, Header Row Check Box, Rows per Page, and Changing Pages,”](#) there is **Go to page** *field of y*. In the *field*, you can enter the page to which you want to navigate and then click the **Go** button to get there. The *y* indicates the last page for this topic. Another way to navigate to a specific page is to use the arrows. You can click the > arrow to navigate to the next page or the furthest arrow to the right >| to navigate to the last page. You can click the < arrow to navigate to the previous page or the furthest arrow to the left |< to navigate to the first page.

Figure 1-6 Example of Filtering, Header Row Check Box, Rows per Page, and Changing Pages

Devices

ShowDevices with matching

Showing 1 - 8 of 8 records

#	<input type="checkbox"/>	Device Name	Management IP Address	Type	Parent Device Name
1.	<input type="checkbox"/>	pe1		Cisco IOS Device	
2.	<input type="checkbox"/>	pe3		Cisco IOS Device	
3.	<input type="checkbox"/>	sw2		Cisco IOS Device	
4.	<input type="checkbox"/>	sw3		Cisco IOS Device	
5.	<input type="checkbox"/>	sw4		Cisco IOS Device	
6.	<input type="checkbox"/>	ce3		Cisco IOS Device	
7.	<input type="checkbox"/>	ce8		Cisco IOS Device	
8.	<input type="checkbox"/>	ce13		Cisco IOS Device	

Rows per page: Go to page: of 1

129048

Auto Refresh

At the bottom left corner of several windows, there is a check box used to enable or disable the **Auto Refresh** feature, as shown in [Figure 1-7](#), “Example of Auto Refresh.” Selecting this check box causes the window and its data to refresh every **n** milliseconds. The amount of time between refresh cycles can be set in the DCPL property: GUI.srRefreshRate. By default, the **Auto Refresh** feature is enabled to 30000 milliseconds.

Figure 1-7 Example of Auto Refresh

Services

ShowServices with matching of Type

Showing 1 - 2 of 2 records

#	<input type="checkbox"/>	Job ID	State	Type	Operation Type	Creator	Customer Name	Policy Name	Last Modified	Description
1.	<input type="checkbox"/>	1	REQUESTED	MPLS	ADD	admin	Customer1	MPLSPolicy_PECE	10/27/05 5:25 PM	
2.	<input type="checkbox"/>	2	REQUESTED	MPLS	ADD	admin	Customer1	MPLSPolicyNO_CE	10/27/05 5:25 PM	

Rows per page: Go to page: of 1

Auto Refresh: ☒

129049

Color Coding

In the Service Request table, the Task table, and the Device table, the colors you see indicate the state of the items, as shown in [Figure 1-8](#), “Colors as Identifiers.”

In the **Service Request** table, the states have the following colors:

- BROKEN is bright yellow

- CLOSED is no color
- DEPLOYED is bright green
- FAILED AUDIT is bright yellow
- FAILED DEPLOY is bright red
- FUNCTIONAL is bright green
- INVALID is bright red
- LOST is bright yellow
- PENDING is bright green
- REQUESTED is cream
- WAIT DEPLOYED is cream











In the **Task** table, the states have the following colors:

- ABORTED is orange
- RUNNING is bright green
- WAITING_TO_RUN is cream
- errors is bright red
- successfully is bright green
- warnings is cyan

In the **devices** table, the states have the following colors:

- device returns anything else is bright red
- device returns success is bright green
- no result from device is dark blue

Figure 1-8 Colors as Identifiers

Service Requests									
Show Services with <input type="text" value="Job ID"/> matching <input type="text" value="*"/> of Type <input type="text" value="All"/> <input type="button" value="Find"/>									
Showing 1 - 10 of 11 records									
#	<input type="checkbox"/>	Job ID	State	Type	Operation Type	Creator	Customer Name	Policy Name	Last Modified
1.	<input type="checkbox"/>	3	 PENDING	L2VPN	MODIFY	admin	Customer1	L2VpnPolicy1	9/15/05 2:23 PM
2.	<input type="checkbox"/>	4	 PENDING	QoS	ADD	admin	Customer1	3550-DSCP	9/15/05 2:23 PM
3.	<input type="checkbox"/>	6	 PENDING	VPLS	ADD	admin	Customer2	VPLSPolicy1	9/15/05 2:23 PM
4.	<input type="checkbox"/>	13	 DEPLOYED	L2VPN	ADD	admin	Customer1	L2vpnErsCe	9/15/05 2:15 PM
5.	<input type="checkbox"/>	17	 INVALID	L2VPN	ADD	admin	Customer1	L2vpnEwsCe	9/15/05 2:51 PM
6.	<input type="checkbox"/>	18	 DEPLOYED	L2VPN	ADD	admin	Customer3	L2vpnErsNoCe	9/15/05 3:02 PM
7.	<input type="checkbox"/>	19	 REQUESTED	L2VPN	ADD	admin	Customer1	L2vpnEwsNoCe	9/14/05 11:38 AM
8.	<input type="checkbox"/>	22	 REQUESTED	L2VPN	ADD	admin	Customer1	L2tpv3AtmCe	9/14/05 3:32 PM
9.	<input type="checkbox"/>	25	 REQUESTED	L2VPN	ADD	admin	Customer2	L2tpv3AtmNoCe	9/14/05 3:58 PM
10.	<input type="checkbox"/>	26	 REQUESTED	VPLS	ADD	admin	Customer1	VplsMplsErsCe	9/15/05 10:57 AM
Rows per page: <input type="text" value="10"/> <input type="button" value="Go to page: 1 of 2"/> <input type="button" value="Go"/> <input type="button" value="Previous"/> <input type="button" value="Next"/>									
Auto Refresh: <input checked="" type="checkbox"/> <input type="button" value="Create"/> <input type="button" value="Details"/> <input type="button" value="Status"/> <input type="button" value="Edit"/> <input type="button" value="Deploy"/> <input type="button" value="Decommission"/> <input type="button" value="Purge"/>									

138470

Icons

In some windows with tables of information, icons appear to show the type of device, as shown in [Figure 1-9, “Devices—Icons.”](#)



Note

A list of possible icons can be found in [Table 3-2](#) in the [Topology Tool](#) section of [Chapter 3, “Service Inventory — Inventory and Connection Manager.”](#)

Figure 1-9 **Devices—Icons**

#		Device Name	Management IP Address	Type	Parent Device Name
1.	<input type="checkbox"/>	pe1		Cisco IOS Device	
2.	<input type="checkbox"/>	pe3		Cisco IOS Device	
3.	<input type="checkbox"/>	sw2		Cisco IOS Device	
4.	<input type="checkbox"/>	sw3		Cisco IOS Device	
5.	<input type="checkbox"/>	sw4		Cisco IOS Device	
6.	<input type="checkbox"/>	ce3		Cisco IOS Device	
7.	<input type="checkbox"/>	ce8		Cisco IOS Device	
8.	<input type="checkbox"/>	ce13		Cisco IOS Device	

Service Inventory

Service Inventory contains tools to manage inventory elements, service requests, and devices. This is explained in [Chapter 3, “Service Inventory — Inventory and Connection Manager,”](#) [Chapter 4, “Service Inventory—Discovery,”](#) and [Chapter 5, “Service Inventory—Device Console.”](#)

From the Home window you receive upon logging in, click the **Service Inventory** tab and you receive a window as shown in [Figure 1-10, “Service Inventory Selections.”](#)

Figure 1-10 **Service Inventory Selections**

The selections are as follows:

- **Inventory and Connection Manager** (explained in detail in [Chapter 3, “Service Inventory — Inventory and Connection Manager”](#))

The functions within **Inventory and Connection Manager** are shown in [Figure 1-11, “Inventory and Connection Manager Selections,”](#) and are as follows:

- **Service Requests** Create, deploy, and manage service requests (SRs). Details are explained in *User Guides*.
- **Traffic Engineering Management** Create, deploy, and manage elements of Traffic Engineering Management (explained in detail in [Cisco IP Solution Center Traffic Engineering Management User Guide, 4.1](#)).
- **Inventory Manager** Bulk-manage inventory elements.
- **Topology Tool** View topology maps.
- **Devices** Create and manage devices.
- **Device Groups** Create and manage device groups.
- **Customers** Create and manage customers.
- **Providers** Create and manage Providers.
- **Resource Pools** Create and manage pools for IP address, multicast address, route distinguisher, route target, site of origin, VC ID, and VLAN.
- **CE Routing Communities** Create and manage CE Routing Communities.
- **VPNs** Create and manage VPNs.
- **AAA Servers** Create and manage AAA Servers.
- **Named Physical Circuits** Create and manage Named Physical Circuits (NPCs).

Figure 1-11 *Inventory and Connection Manager Selections*

- **Discovery** Discover devices, connections, and services (explained in detail in [Chapter 4, “Service Inventory—Discovery”](#)).
- **Device Console** Download commands and configlets to devices and view device configuration (explained in detail in [Chapter 5, “Service Inventory—Device Console”](#)).

The functions with Device Console are as follows:

- **Download Commands**
- **Download Template**
- **Device Configuration Manager**
- **EXEC Commands**
- **Reload**

Service Design

Service Design contains management tools for creating and managing policies, templates, and Link QoS. This is explained in [Chapter 6, “Service Design.”](#)

From the Home window you receive upon logging in, click the **Service Design** tab and you receive a window as shown in [Figure 1-12, “Service Design Selections.”](#)


Figure 1-12 Service Design Selections



The selections are as follows:

- **Policies** Create and manage policies for licensed services. Details are explained in *User Guides*.
- **Templates** Create and manage templates and associated data. The available choices are shown in the left column of Figure 1-13, “*Templates Selections*.”

Figure 1-13 Templates Selections



- **Link QoS** Create and manage IP Link QoS and Ethernet Link QoS settings. Details are explained in *Cisco IP Solution Center Quality of Service User Guide, 4.1*.

Monitoring

Monitoring contains tools to manage tasks, ping parameters, Service Level Agreement (SLA) probes, Traffic Engineering performance reports, and other reports. This is explained in Chapter 7, “*Monitoring*.”

From the Home window you receive upon logging in, click the **Monitoring** tab and you receive a window as shown in [Figure 1-14](#), “Monitoring Selections.”

Figure 1-14 Monitoring Selections



The selections are as follows:


- **Task Manager** Create and schedule tasks and monitor task run details.
- **Ping** Perform Ping connectivity tests.
- **SLA** Manage probes and view reports.
- **TE Performance Report** TE Performance report.
- **Reports** Create and schedule reports.

Diagnostics

Diagnostics contains automated troubleshooting and diagnostics for MPLS VPNs. This is explained in [Cisco MPLS Diagnostics Expert 1.0 User Guide on ISC 4.1](#).

From the Home window you receive upon logging in, click the **Diagnostics** tab and you receive a window as shown in [Figure 1-15](#), “Diagnostics Selections.”

Figure 1-15 Diagnostics Selections




Administration

Administration contains tools to manage users, ISC configuration, servers, remote installation, and licensing, to view users and the user access log, and to specify attributes for some messages. This is explained in detail in [Chapter 9, “Administration.”](#)


From the Home window you receive upon logging in, click the **Administration** tab and you receive a window as shown in [Figure 1-16, “Administration Selections.”](#)

Figure 1-16 Administration Selections



The selections are as follows:

- **Security** Create and manage Users, User Groups, User Roles, and Object Groups. The following choices are shown in [Figure 1-17, “Security Selections”](#):
 - **Users** Create and manage Users to also access Inventory Manager, Topology, and Northbound API.
 - **User Groups** Create and manage User Groups. A Group is used to combine the privileges of all the roles contained within it.
 - **User Roles** Create and manage User Roles, which define a set of permissions.
 - **Object Groups** Create and manage a group of objects, such as devices, interfaces, and named physical circuits.

Figure 1-17 Security Selections


- **Control Center** Manage ISC configuration, servers, remote installation, and licensing. The following choices are shown in the left column of [Figure 1-18](#), “**Control Center Selections**”:

- **Hosts**

**Note**

From **Hosts**, you can choose **Install**. You can remotely install a Processing Server, Collection Server, or Interface Server. In this Remote Install, you *must* accept the default values, similar to the **express** install. If you want to do a **custom** install, this is only available through the Installation procedure explained in [Cisco IP Solution Center Installation Guide, 4.1](#).

- **Collection Zones**
- **Licensing**

Figure 1-18 Control Center Selections

- **Active Users** View users currently connected to ISC. Disconnect users.
- **User Access Log** View the user access log.
- **Manage TIBCO Rendezvous** Specify attributes for proper messaging among all Java™ Web Start distributed applications.



WatchDog Commands

The WatchDog is responsible for bootstrapping Cisco IP Solution Center (ISC) and starting the necessary set of server processes. In addition, the WatchDog monitors the health and performance of each server to ensure it is functioning properly. In the event of a software error that causes a server to fail, the WatchDog automatically restarts the errant server.

The WatchDog is a background daemon process that is automatically installed as part of the installation procedure for ISC. After the installation procedure has completed, WatchDog is started automatically. You can execute the **startwd** command to run the WatchDog after the installation. The WatchDog can be configured to automatically start any time the machine is rebooted.

In addition to the commands that are specified in this chapter, you can navigate in the product to **Admin > Control Center > Servers** and from there you can start, stop, restart, and view log files for the individual ISC servers.

This chapter provides the description, syntax, and arguments (listed alphabetically) for the following WatchDog commands:

- [startdb Command, page 2-1](#)
- [startns Command, page 2-2](#)
- [startwd Command, page 2-2](#)
- [stopall Command, page 2-3](#)
- [stopdb Command, page 2-3](#)
- [stopns Command, page 2-4](#)
- [stopwd Command, page 2-4](#)
- [wdclient Command, page 2-5](#)

startdb Command

This section provides the description and syntax for the **startdb** command.

Description

The **startdb** command starts the database.

Syntax

startdb

The **startdb** command has no arguments and starts the database.

The location of **startdb** is: *<ISC Directory>/bin*.



Note

Do *not* run **startdb** in the background. Do *not* enter **startdb &**.

startns Command

This section provides the description and syntax for the **startns** command.

Description

The **startns** command starts the name server. The **orbd** process provides the name server functionality. **orbd** (from JDK) is required, but **startwd** starts it if it is not already running. The **startns** and **stopns** commands deal with **orbd**.

Syntax

startns

The **startns** command has no arguments and starts the name server.

The location of **startns** is: *<ISC Directory>/bin*.

startwd Command

This section provides the description and syntax for the **startwd** command.

Description

The **startwd** command starts the WatchDog and all ISC processes. The **startwd** command includes the functionality of **startdb** (see the [“startdb Command” section on page 2-1](#)) and **startns** (see the [“startns Command” section on page 2-2](#)). Executing this command is a necessary procedure and occurs automatically as part of the installation. Use this **startwd** command after issuing a **stopwd** command to restart the WatchDog. The master ISC host *must* be started first. Other ISC hosts can be started any time after the master ISC host, but all hosts *must* be started before starting to use ISC.

If for some reason the master ISC host is stopped, either inadvertently or by issuing the **stopwd** command, this master ISC host can be restarted by using the **startwd** command.

Syntax

startwd

The **startwd** command has no arguments and starts the WatchDog only for the machine where it is executed.

The location of **startwd** is: *<ISC Directory>/bin*.



Note

Do *not* run **startwd** in the background. Do *not* enter **startwd &**.

stopall Command

This section provides the description and syntax for the **stopall** command.

Description

The **stopall** command stops the database, name server, and WatchDog on the machine on which it is run. The **stopall** command includes the functionality of **stopdb -y** (see the “[stopdb Command](#)” section on page 2-3), **stopns -y** (see the “[stopns Command](#)” section on page 2-4), and **stopwd -y** (see the “[stopwd Command](#)” section on page 2-4). Normally this is only necessary before installing a new version of ISC.

Syntax

stopall



Caution

There is no **-y** parameter. Therefore, everything stops without the ability to cancel.

The location of **stopall** is: *<ISC Directory>/bin*.

stopdb Command

This section provides the description and syntax for the **stopdb** command.

Description

The **stopdb** command stops the database.

Syntax

stopdb [-y]

where:

-y indicates not to prompt before shutdown. If **-y** is not specified, you are prompted with the following message: “Are you absolutely sure you want to stop the database?” You are then prompted to reply **yes** or **no**.

The location of **stopdb** is: *<ISC Directory>/bin*.

stopns Command

This section provides the description and syntax for the **stopns** command.

Description

The **stopns** command stops the name server. The **startns** and **stopns** commands deal with **orbd**.

Syntax

stopns [-y]

where:

-y indicates not to prompt before shutdown. If **-y** is not specified, you are prompted with the following message: “Are you absolutely sure you want to stop the nameserver?” You are then prompted to reply **yes** or **no**.

The location of **stopns** is: *<ISC Directory>/bin*.

stopwd Command

This section provides the description and syntax for the **stopwd** command.

Description

The **stopwd** command stops the WatchDog and all ISC processes other than the name server and the database.

Syntax

stopwd [-y] [-all]

where:

-y indicates not to prompt before shutdown. If **-y** is not specified, you are prompted with the following message: “Are you absolutely sure you want to stop the watchdog and all of its servers? Other users may be using this system as well. No activity (for example: collections, performance monitoring, provisioning) occurs until the system is restarted.” You are then prompted to reply **yes** or **no**.

-all indicates to stop all the hosts. This argument is only available to the master host.

The location of **stopwd** is: *<ISC Directory>/bin*.

wdclient Command

This section provides the description, syntax, and options (listed alphabetically) for the **wdclient** subcommands. These subcommands are diagnostic tools. This section also describes the column format of the output of each of the subcommands.



Note

The location of **wdclient** is: *<ISC Directory>/bin*.

The following are the **wdclient** subcommands:

- [wdclient disk Subcommand, page 2-6](#)
- [wdclient group <group_name> Subcommand, page 2-6](#)
- [wdclient groups Subcommand, page 2-6](#)
- [wdclient health Subcommand, page 2-7](#)
- [wdclient hosts Subcommand, page 2-7](#)
- [wdclient restart Subcommand, page 2-8](#)
- [wdclient start Subcommand, page 2-8](#)
- [wdclient status Subcommand, page 2-9](#)
 - [Information Produced: Name Column, page 2-9](#)
 - [Information Produced: State Column, page 2-10](#)
 - [Information Produced: Gen Column, page 2-11](#)
 - [Information Produced: Exec Time Column, page 2-11](#)
 - [Information Produced: Success Column, page 2-11](#)
 - [Information Produced: Missed Column, page 2-11](#)
- [wdclient stop Subcommand, page 2-11](#)
- [wdclient syshealth Subcommand, page 2-12](#)



Note

If you enter **wdclient -help**, you receive a listing of all the **wdclient** subcommands.

If you enter **wdclient -master -help**, you receive a listing of all the **wdclient -master** subcommands.

wdclient disk Subcommand

This section provides the description and syntax for the **wdclient disk** subcommand.

Description

The **wdclient disk** subcommand gives the disk space statistics for the directories where ISC is installed.

Syntax

wdclient [-master [-host <hostname>]] disk

where:

-master is an optional parameter that indicates to give the WatchDog information for the master ISC host. If **-master** is not specified, only local information about the current host is given.

-host <hostname> is an optional parameter. **<hostname>** is the fully-qualified name of the remote host on which the WatchDog is running. If this optional parameter is not specified, information from all the hosts is returned.

wdclient group <group_name> Subcommand

This section provides the description and syntax for the **wdclient group <group_name>** subcommand.

Description

The **wdclient group <group_name>** subcommand lists the servers in the specified server group. Server groups provide a convenient way to start or stop a group of servers with a single command.

Syntax

wdclient [-master [-host <hostname>]] group <group_name>

where:

-master is an optional parameter that indicates to give the WatchDog information for the master ISC host. If **-master** is not specified, only local information about the current host is given.

-host <hostname> is an optional parameter. **<hostname>** is the fully-qualified name of the remote host on which the WatchDog is running. If this optional parameter is not specified, information from all the hosts is returned.

<group_name> is the name of a server group chosen from the list displayed by the **wdclient groups** command.

wdclient groups Subcommand

This section provides the description and syntax for the **wdclient groups** subcommand.

Description

The **wdclient groups** subcommand lists all the active server groups.

Syntax

```
wdclient [-master [-host <hostname>]] groups
```

where:

-master is an optional parameter that indicates to give the information for the master ISC host. If

-master is not specified, only local information about the current host is given.

-host <hostname> is an optional parameter. *<hostname>* is the fully-qualified name of the remote host on which the WatchDog is running. If this optional parameter is not specified, information from all the hosts is returned.

wdclient health Subcommand

This section provides the description and syntax for the **wdclient health** subcommand.

Description

The **wdclient health** subcommand indicates whether all the servers are stable on the master ISC host.

Syntax

```
wdclient health
```

wdclient hosts Subcommand

This section provides the description and syntax for the **wdclient hosts** subcommand.

Description

The **wdclient hosts** subcommand returns the status of all the hosts including the master.

Syntax

```
wdclient -master [-poll <seconds>] hosts
```

where:

-master is a required parameter that indicates to get the information from the master ISC host.

-poll <seconds> is an optional parameter. *<seconds>* is the number of seconds. A number other than zero indicates that when new status data is available it is displayed every *<seconds>* seconds, where *<seconds>* is the specified number of seconds. The default **-poll** value is zero (0), which shows the status just once.

wdclient restart Subcommand

This section provides the description and syntax for the **wdclient restart** subcommand.

Description

The **wdclient restart** subcommand restarts one or more servers. Any dependent servers are also restarted.



Note

It is not necessary to restart servers in a properly functioning system. The **wdclient restart** command should only be run under the direction of Cisco Support.

Syntax

```
wdclient [-master [-host <hostname>]] restart [all | <server_name> | group <group_name>]
```

where:

-master is an optional parameter that indicates the restart operation should be performed on the master ISC host. If **-master** is not specified, the restart operation is performed only on the local machine.

-host <hostname> is an optional parameter. <hostname> is the fully-qualified name of the remote host on which the WatchDog is running. If this optional parameter is not specified, information from all the hosts is returned.

You can choose one of the following arguments. If none are chosen, the default is **all**:

all is all servers. This is the default if no argument is specified.

<server_name> is the name of a server chosen from the list displayed by the **wdclient status** command. See [Table 2-1, “Servers and Their Functions,”](#) for server descriptions.

group <group_name> is the term **group** followed by the name of a server group chosen from the list displayed by the **wdclient groups** command.

wdclient start Subcommand

This section provides the description and syntax for the **wdclient start** subcommand.

Description

The **wdclient start** subcommand starts one or more servers. Other servers that depend on the specified server(s) might also start.



Note

It is not necessary to stop and start servers in a properly functioning system. The **wdclient start** command should only be run under the direction of Cisco Support.

Syntax

```
wdclient [-master [-host <hostname>]] start [all | <server_name> | group <group_name>]
```

where:

-master is an optional parameter that indicates the start operation should be performed on the master ISC host. If **-master** is not specified, the start operation is performed only on the local machine.

-host <hostname> is an optional parameter. <hostname> is the fully-qualified name of the remote host on which the WatchDog is running. If this optional parameter is not specified, information from all the hosts is returned.

You can choose one of the following arguments. If none are chosen, the default is **all**:

all is all servers. This is the default if no argument is specified.

<server_name> is the name of a server chosen from the list displayed by the **wdclient status** command. See [Table 2-1, “Servers and Their Functions,”](#) for server descriptions.

group <group_name> is the name of a server group chosen from the list displayed by the **wdclient groups** command.

wdclient status Subcommand

This section provides the description, syntax, and information produced for the **wdclient status** subcommand.

Description

The **wdclient status** subcommand lists all the servers and their states. See [Table 2-1 on page 2-10, “Servers and Their Functions,”](#) for server descriptions. See [Table 2-2 on page 2-10, “Valid States,”](#) for the list of all the states.

Syntax

```
wdclient [-master [-host <hostname>]] [-poll <seconds>]] status
```

where:

-master is an optional parameter that indicates to give the information for the master ISC host. If **-master** is not specified, only local information about the current host is given.

-host <hostname> is an optional parameter. <hostname> is the fully-qualified name of the remote host on which the WatchDog is running. If this optional parameter is not specified, information from all the hosts is returned.

-poll <seconds> is an optional parameter. <seconds> is the number of seconds. A number other than zero indicates that when new status data is available it is displayed every <seconds> seconds, where <seconds> is the specified number of seconds. The default **-poll** value is zero (0), which shows the status just once.

Information Produced: Name Column

The **Name** column provides the name of each of the servers. [Table 2-1](#) provides a list of the servers and a description of the function that each server provides.

Table 2-1 Servers and Their Functions

Server	Function
cnsserver	Handles TIBCO messages from Cisco CNS IE2100 appliances and takes appropriate actions.
cornerstonebridge	Used for peer-to-peer communication with client applications invoking auto-discovery commands.
dbpoller	Monitors database server.
dispatcher	Manages workers. Distributes work to other hosts (if any).
httpd	Web server.
lockmanager	Handles device locking so a router's configuration is not modified by multiple service requests at the same time.
nspoller	Monitors name service.
scheduler	Enables you to schedule tasks immediately or later in time, for one-time or repeated execution.
worker	Executes various ISC tasks/jobs such as Provisioning.

Information Produced: State Column

The **State** column provides the current state of the server. [Table 2-2](#) provides a description of each of the states in normal progression order.

Table 2-2 Valid States

State	Description
start_depends	This server has been asked to start, but is waiting for servers it depends on to start. After all dependent servers have started, this server transitions to the state of starting.
starting	This server is currently starting. After a successful heartbeat occurs, this server transitions to the state of started.
started	This server is currently started and running.
stop_depends	This server is supposed to be stopped, but it is waiting for servers it depends on to be stopped first.
stopping_gently	This server is in the process of stopping in a gentle fashion. That is, it was notified that it is to stop.
stopping_hard	This server is in the process of being killed because either it did not have a way to stop gently or because the gentle stop took too long.
stopped	This server is stopped. The WatchDog either starts it again or disables it if it has been frequently dying.
disabled_dependent	This server is disabled because one or more servers it depends on are disabled. If all servers it depends on are started, this server automatically starts.

Table 2-2 **Valid States (continued)**

State	Description
disabled	This server is disabled and must be manually restarted.
restart_delay	This server is delaying before restarting. There is a short delay after a server stops and before it is restarted again.

Information Produced: Gen Column

The **Gen** column provides the generation of the server. Each time the server is started, the generation is incremented by 1.

Information Produced: Exec Time Column

The **Exec Time** column provides the date and time the server was last started.

Information Produced: PID Column

The **PID** column provides the UNIX process identifier for each server, except for dbpoller and nspoller.

Information Produced: Success Column

The **Success** column provides the number of successful heartbeats since the server was last started. Heartbeats are used to verify that servers are functioning correctly.

Information Produced: Missed Column

The **Missed** column provides the number of missed heartbeats since the server was last started.

A few missed heartbeats could simply indicate the system was busy. However, more than a couple of missed heartbeats per day could indicate a problem. See the logs to diagnose the reason.

Three missed heartbeats in a row is the default for restarting the server.

wdclient stop Subcommand

This section provides the description and syntax for the **wdclient stop** subcommand.

Description

The **wdclient stop** subcommand stops one or more servers. Other servers that depend on the specified servers also stop.

**Note**

It is not necessary to stop servers in a properly functioning system. The **wdclient stop** command should *only* be run under the direction of Cisco Support.

Syntax

wdclient [-master [-host <hostname>]] **stop** [all | <server_name> | **group** <group_name>]

where:

-master is an optional parameter that indicates to perform the operation on the master ISC host.

-host <hostname> is an optional parameter. <hostname> is the fully-qualified name of the remote host on which the WatchDog is running. If this optional parameter is not specified, information from all the hosts is returned.

You can choose one of the following arguments. If none are chosen, the default is **all**.

all is all servers. This is the default if no argument is specified.

<server_name> is the name of a server chosen from the list displayed by the **wdclient status** command. See Table 2-1, “Servers and Their Functions,” for server descriptions.

group <group_name> is the name of a server group chosen from the list displayed by the **wdclient groups** command.

wdclient syshealth Subcommand

This section provides the description and syntax for the **wdclient syshealth** subcommand.

Description

The **wdclient syshealth** subcommand gives the system health information about the entire system, including the master and the hosts. Their health is listed either as **good**, which means, running, or **not good**, which means, not running.

Syntax

wdclient -master [-host <hostname>] syshealth

where:

-master is a required parameter that indicates to get the information from the master ISC host.


-host <hostname> is an optional parameter. <hostname> is the fully-qualified name of the remote host on which the WatchDog is running. If this optional parameter is not specified, information from all the hosts is returned.




Service Inventory — Inventory and Connection Manager

From the Home window of Cisco IP Solution Center (ISC), which appears upon logging in, click the **Service Inventory** tab and a window as shown in [Figure 3-1](#), “[Service Inventory Selections Window](#),” appears.

Figure 3-1 *Service Inventory Selections Window*



Click on **Inventory and Connection Manager** and a window as shown in [Figure 3-2](#), “[Inventory and Connection Manager Selections Window](#),” appears.

Figure 3-2 *Inventory and Connection Manager Selections Window*

From **Inventory and Connection Manager** window, you can navigate to any of the following functions:

- **Service Requests, page 3-3** Create, deploy, and manage Service Requests (SRs).
- **Traffic Engineering Management, page 3-5** Create, deploy, and manage elements of Traffic Engineering Management.
- **Inventory Manager, page 3-5** Bulk-manage inventory elements.
- **Topology Tool, page 3-36** View topology maps.
- **Devices, page 3-68** Create and manage Devices.
- **Device Groups, page 3-100** Create and manage Device Groups.
- **Customers, page 3-106** Create and manage Customers.
- **Providers, page 3-114** Create and manage Providers.
- **Resource Pools, page 3-122** Create and manage pools for IP address, Multicast address, Route Distinguisher, Route Target, Site of Origin, VC ID, and VLAN.
- **CE Routing Communities, page 3-132** Create and manage CE Routing Communities.
- **VPNs, page 3-136** Create and manage VPNs.
- **AAA Servers, page 3-140** Create and manage AAA Servers.
- **Named Physical Circuits, page 3-140** Create and manage Named Physical Circuits (NPCs).

Service Requests

Service Requests are explained in each of the *User Guides* for each of the licensed services.

Table 3-1, “Summary of Cisco IP Solution Center Service Request States,” describes each ISC service request state. The states are listed in alphabetical order.


Figure 3-3, “Service Request States Transition Diagram,” shows the transitions of states.

Table 3-1 Summary of Cisco IP Solution Center Service Request States

Service Request Type	Description
Broken (valid only for L2TPv3 and MPLS services)	The router is correctly configured but the service is unavailable (due to a broken cable or Layer 2 problem, for example). An MPLS service request moves to Broken if the auditor finds the routing and forwarding tables for this service, but they do not match the service intent.
Closed	A service request moves to Closed if the service request should no longer be used during the provisioning or auditing process. A service request moves to the Closed state only upon successful audit of a decommission service request. ISC does not remove a service request from the database to allow for extended auditing. Only a specific administrator purge action results in service requests being removed.
Deployed	A service request moves to Deployed if the intention of the service request is found in the router configuration file. Deployed indicates that the configuration file has been downloaded to the router, and the intent of the request has been verified at the configuration level. That is, ISC downloaded the configlets to the routers and the service request passed the audit process.
Failed Audit	This state indicates that ISC downloaded the configlet to the router successfully, but the service request did not pass the audit. Therefore, the service did not move to the Deployed state. The Failed Audit state is initiated from the Pending state. After a service request is deployed successfully, it cannot re-enter the Failed Audit state (except if the service request is redeployed).
Failed Deploy	The cause for a Failed Deploy status is that DCS reports that either the upload of the initial configuration file from the routers failed or the download of the configuration update to the routers failed (due to lost connection, faulty password, and so on).
Functional (valid only for L2TPv3 and MPLS services)	An MPLS service request moves to Functional when the auditor finds the VPN routing and forwarding tables (VRF) for this service and they match with the service intent. This state requires that both the configuration file audit and the routing audit are successful.
Invalid	Invalid indicates that the service request information is incorrect in some way. A service request moves to Invalid if the request was either internally inconsistent or not consistent with the rest of the existing network/router configurations (for example, no more interfaces were available on the router). The Provisioning Driver cannot generate configuration updates to service this request.

Table 3-1 Summary of Cisco IP Solution Center Service Request States (continued)

Service Request Type	Description
Lost	A service request moves to Lost when the Auditor cannot find a configuration-level verification of intent in the router configuration files. The service request was in the Deployed state, but now some or all router configuration information is missing. A service request can move to the Lost state <i>only</i> when the service request had been Deployed .
Pending	A service request moves to Pending when the Provisioning Driver determines that the request looks consistent and was able to generate the required configuration updates for this request. Pending indicates that the service request has generated the configuration updates and the configuration updates are successfully downloaded to the routers. The Auditor regards pending service requests as new requests and begins the audit. If the service has been freshly provisioned and not yet audited, it is not an error (pending audit). However, if an audit is performed and the service is still pending, it is in an error state.
Requested	If the service is newly entered and not yet deployed, it is not an error. However, if a Deploy is done and it remains Requested , the service is in an error state.
Wait Deploy	This service request state pertains only when downloading configlets to a Cisco CNS-CE server, such as a Cisco CNS IE2100 appliance. Wait Deploy indicates that the configlet has been generated, but it has not been downloaded to the Cisco CNS-CE server because the device is not currently online. The configlet is staged in the repository until such time as the Cisco CNS-CE server notifies ISC that it is up. Configlets in the Wait Deploy state are then downloaded to the Cisco CNS-CE server.

Figure 3-3 Service Request States Transition Diagram

Traffic Engineering Management

Traffic Engineering Management allows you to create, deploy, and manage elements of Traffic Engineering Management. This is explained in detail in *Cisco IP Solution Center Traffic Engineering Management User Guide, 4.1*.

Inventory Manager

Inventory Manager provides a method of managing mass changes to inventory and service model data in the ISC provisioning process. In this process, Inventory Manager enables an operator to import network specific data into the ISC Repository (Repository) in bulk mode.

Inventory Manager performs three primary functions:

- Imports devices from configuration files and configures CPEs and PEs by associating devices with a Customer or Provider.
- Edits devices, CPEs or PEs stored in the ISC repository.
- Assigns a device to a provider or customer.

Accessing the Inventory Manager Window

To access the Inventory Manager, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Inventory Manager** to access the Inventory Manager window shown in [Figure 3-4](#).

Figure 3-4 Inventory Manager Window



From the Inventory Manager window you can import devices or open a list of devices, providers or customers.

Importing Devices

To import a device, it must be in an existing directory on the same server that is running ISC. After a device is imported into the ISC repository, you can assign it to a customer or provider if desired.


To import devices with configuration files, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Inventory Manager**.

Step 2 Click the **Import Devices** button.

The Import Devices from Configuration Files window appears, as shown in [Figure 3-5](#).


Figure 3-5 Import Devices from Configuration Files Window



Step 3 Click the **Select** button.

The Select Device Configuration File dialog box appears, as shown in [Figure 3-6](#).

Figure 3-6 Select Device Configuration File Dialog



Step 4 At the **Select Device Configuration File** dialog box, enter the directory on the ISC server where the configuration files reside.

Step 5 The **Import Devices from Configuration Files** window appears.

Step 6 Select as many of the configuration files as you want to import by selecting the box to the left of the Configuration File name.

Step 7 If you want to import devices from more than one directory, you can repeat Steps 3 through 6.


- Step 8** Click **Import**.
The **General Attributes** window appears.
- Step 9** Click **Save**.

Opening and Editing Devices

To open device configuration files to bulk edit, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Inventory Manager**.
- Step 2** Click the **Open** button.
The **Open** drop-down list appears. The **Open** options include the following:
- **Devices**—Every network element that ISC manages.
 - **Provider**—PEs belonging to a specific provider.
 - **Customer**—CEs belonging to a specific customer.
- Step 3** Select **Devices**.
The Select Device window appears, as shown in [Figure 3-7](#).

Figure 3-7 Select Devices Window



- Step 4** Select a device to open by selecting the check box to the left of the Device Name. You can select more than one device to open.
- Step 5** Click the **Select** button.
The General Attributes window appears containing information on the selected devices, as shown in [Figure 3-8](#).

Figure 3-8 General Attributes Devices Window

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1.	pe1	Cisco IOS Device				Default	Default	Device-Group-1
2.	pe3	Cisco IOS Device				Default	Default	Device-Group-2
3.	sw2	Cisco IOS Device				Default	Default	

Rows per page: 10 Go to page: 1 of 1

Attributes Assign CE/PE Edit Save

Step 6 To view specific attributes click the **Attributes** button.

The Attributes options appear, as shown in Figure 3-9.

Figure 3-9 Attributes Options Window

Selection

- Service Requests
- Traffic Engineering Management
- Inventory Manager**
- Topology Tool
- Devices
- Device Groups
- Customers
- Customer Sites
- CPE Devices
- Providers
- Provider Regions
- PE Devices
- Access Domains
- Resource Pools
- CE Routing Communities
- VPNs
- AAA Servers
- Named Physical Circuits
- NPS Devices

General Attributes - Devices

Show entries with Host matching * Find

Showing 1 - 3 of 3 records

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1.	pe1	Cisco IOS Device				Default	Default	Device-Group-1
2.	pe3	Cisco IOS Device				Default	Default	Device-Group-2
3.	sw2	Cisco IOS Device				Default	Default	

Rows per page: 10 Go to page: 1 of 1

Attributes Assign CE/PE Edit Save

General Attributes Password Attributes SNMP Attributes CNS Attributes Platform Attributes Interfaces

Step 7 Select the type of attribute to display.

See the following sections for descriptions of these attribute fields.

- [General Attributes Devices, page 3-9](#)
- [Password Attributes Devices, page 3-10](#)
- [SNMP Attributes Devices, page 3-11](#)

- [CNS Attributes Devices, page 3-12](#)
- [Platform Attributes Devices, page 3-13](#)
- [Interfaces Devices, page 3-13](#)

- Step 8** To bulk edit an attribute, do the following:
- Select the one or more boxes to the left of the Device Name.
 - Select the check box above the attribute name column.
 - Click the **Edit** button.

Step 9 Enter the changes you want to make.

Step 10 Click **Save**.

The changes are saved.

General Attributes Devices

The General Attributes Devices window appears, as shown in [Figure 3-10](#).

Figure 3-10 General Attributes Devices Window

Inventory Manager

General Attributes - Devices

Show entries with Host matching

Showing 1 - 3 of 3 records

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1. <input type="checkbox"/>	pe1	Cisco IOS Device				Default	Default	Device-Group-1
2. <input type="checkbox"/>	pe3	Cisco IOS Device				Default	Default	Device-Group-2
3. <input type="checkbox"/>	sw2	Cisco IOS Device				Default	Default	

Rows per page:

Go to page: of 1

The General Attributes Devices window contains the following:

- **Host**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Device Type**—The device type includes the following devices:
 - Cisco Router
 - Catalyst OS device
 - Terminal server
 - IE2100 (Cisco CNS appliance)

149463

- **Description**—Can contain any pertinent information about the device, such as the type of device, its location, or other information that might be helpful to service provider operators. Limited to 80 characters.
- **Management IP Address**—Valid IP address of the device that ISC uses to configure the target router device. This IP address must be reachable from the ISC host.
- **Device Domain Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. The name must match the domain name on the target router device.
- **Terminal Session Protocol**—Configures the method of communication between ISC and the device. Choices include: Telnet, Secure Shell (SSH), CNS, and RSH. Default: Telnet.
- **Config Access Protocol**—Administers the access protocol for config upload and download. Choices include: Terminal, TFTP, FTP, and RCP. Default: Terminal
- **Device Groups**—Lists the names of the Device Groups. You can add and modify Device Groups in this column.

Password Attributes Devices

The Password Attributes Devices window appears, as shown in [Figure 3-11](#).

Figure 3-11 Password Attributes Devices Window

The screenshot shows the 'Password Attributes - Devices' window. It features a search bar at the top with the text 'Show entries with Host matching' and a 'Find' button. Below the search bar, it indicates 'Showing 1 - 3 of 3 records'. The main area contains a table with the following columns: #, Device Name, Login User, Login Password, Enable User, Enable Password, Community String RO, and Community String RW. The table lists three devices: pe1, pe3, and sw2. The Login Password column is masked with asterisks. At the bottom, there is a 'Rows per page' dropdown set to 10, a 'Go to page' field set to 1 of 1, and buttons for 'Attributes', 'Assign CE/PE', 'Edit', and 'Save'.

#	Device Name	Login User	Login Password	Enable User	Enable Password	Community String RO	Community String RW
1.	pe1		*****		*****	public	private
2.	pe3		*****		*****	public	private
3.	sw2		*****		*****	public	private

The Password Attributes Devices window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Login User**—Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password, as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Login Password**—Displayed as stars (*). Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password, as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.

- **Enable User**—Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Enable Password**—Displayed as stars (*). Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Community String RO**—Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.
- **Community String RW**—Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.

SNMP Attributes Devices

The SNMP Attributes Devices window appears, as shown in [Figure 3-12](#).

Figure 3-12 *SNMP Attributes Devices Window*

#	Device Name	SNMP Version	Security Level	Authentication User Name	Authentication Password	Authentication Algorithm	Encryption Password	Encryption Algorithm
1.	pe1	Default	Default			None		None
2.	pe3	Default	Default			None		None
3.	sw2	Default	Default			None		None

The SNMP Attributes Devices window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **SNMP Version**—Choices include: SNMP v1/v2c, and SNMP v3.
- **Security Level**—Choices include: No Authentication/No Encryption, Authentication/No Encryption, and Authentication/Encryption. Default: No Authentication/No Encryption.
- **Authentication User Name**—User name configured on the specified device router. User must have permission to the object identification numbers (OIDs) specified in the security request (that is, write permission for a set request, and read permission for a get request). Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Limited to 80 characters.
- **Authentication Password**—Displayed as stars (*). Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Should match what is configured on the target router device. Limited to 80 characters.

- **Authentication Algorithm**—Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Choices include: None, MD5, and SHA. Default: None.
- **Encryption Password**—Displayed as stars (*). In previous versions, this field was called Privacy Password. Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Limited to 80 characters.
- **Encryption Algorithm**—In previous versions, this field was called Privacy Protocol. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Choices include: None and DES 56. Default: None.

CNS Attributes Devices

The CNS Attributes Devices window appears, as shown in [Figure 3-13](#).

Figure 3-13 CNS Attributes Devices Window

#	Device Name	IE2100 Name	Device State	Event Identification	CNS Identification
1.	pe1	None	Active	Host Name	
2.	pe3	None	Active	Host Name	
3.	sw2	None	Active	Host Name	

Rows per page: 10 Go to page: 1 of 1

Attributes Assign CE/PE Edit Save

The CNS Attributes Devices window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **IE2100 Name**—Disabled unless the Device-State field is Inactive or the Terminal Session Protocol field is CNS. A valid Cisco CNS IE2100 appliance must be selected if the Terminal Session Protocol is CNS. Choices include: None and the list of existing Cisco CNS IE2100 appliance names. Default: None.
- **Device State**—Choices include: Active and Inactive. Active indicates that the router has been plugged on the network and can be part of ISC tasks such as collect config and provisioning. Inactive indicates the router has not been plugged-in. Default: Active.
- **Event Identification**—Indicates whether the CNS Identification field contains a HOST NAME or CNS ID. Default: HOST NAME.
- **CNS Identification**—Required if the Event Identification field is set to CNS ID. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash.

Platform Attributes Devices

The Platform Attributes Devices window appears, as shown in [Figure 3-14](#).

Figure 3-14 Platform Attributes Devices Window

Platform Attributes

Platform Attributes - Devices

Show entries with Host matching *

Showing 1 - 3 of 3 records

#	Device Name	Platform	Software Version	Image Name	Serial Number
1.	pe1	7204VXR	12.2(16.6)S	16.6/c7200-p-mz.122-16.6.S	
2.	pe3	7204VXR	12.2(16.6)S	16.6/c7200-p-mz.122-16.6.S	
3.	sw2	WS-C3550-24	12.1(14)EA1	C3550-I9Q3L2-M:c3550-i9q3l2-mz.121-11.EA1/c3550-i9q3l2-mz.121-11.EA1.bin	

Rows per page: 10

The Platform Attributes Devices window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Platform**—Should match what is configured on the target router device. Limited to 80 characters.
- **Software Version**—Should match what is configured on the target router device. Limited to 80 characters.
- **Image Name**—Should match what is configured on the target router device. Limited to 80 characters.
- **Serial Number**—Should match what is configured on the target router device. Limited to 80 characters.

Interfaces Devices

The Interfaces Devices window appears, as shown in [Figure 3-15](#).

Figure 3-15 Interfaces Devices Window

Interface Attributes

Interfaces - Devices								
Show entries with Host matching						<input type="text" value="*"/>	<input type="button" value="Find"/>	
Showing 1 - 10 of 39 records								
#	<input type="checkbox"/>	Host	Interface Name	Interface Type	Interface Description	<input type="checkbox"/> Interface IP Address	<input type="checkbox"/> Encapsulation	<input type="checkbox"/> Port Type
1.	<input type="checkbox"/>	pe1	ATM2/0	atm				None
2.	<input type="checkbox"/>	pe1	Ethernet4/0	ethernet		172.29.146.21/26		None
3.	<input type="checkbox"/>	pe1	Ethernet4/1	ethernet				None
4.	<input type="checkbox"/>	pe1	Ethernet4/2	ethernet				None
5.	<input type="checkbox"/>	pe1	Ethernet4/3	ethernet				None
6.	<input type="checkbox"/>	pe1	FastEthernet0/0	fastethernet	L4: Link To sw3			None
7.	<input type="checkbox"/>	pe1	FastEthernet0/1	fastethernet				None
8.	<input type="checkbox"/>	pe1	Loopback0	loopback	For BGP neighbor, do not remove	10.8.0.101/32		None
9.	<input type="checkbox"/>	pe1	Serial3/0	serial		10.8.0.2/30		None
10.	<input type="checkbox"/>	pe1	Serial3/1	serial				None
Rows per page:		<input type="text" value="10"/>		<input type="button" value="Go to page: 1 of 4 Go"/>				
<div>AttributesAssign CE/PEEditSave</div>								

149445

The Interfaces Devices window contains the following:

- **Host**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Interface Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required. Limited to 256 characters.
- **Interface Type**—Specifies the type of interface. It is a display-only field.
- **Interface Description**—Description of the interface. This field is display-only. Field is populated by importing a configuration file.
- **Interface IP Address**—IP address associated with this interface.
- **Encapsulation**—The Layer 2 Encapsulation for this device. It is a display-only field. Choices include:
 - DEFAULT
 - DOT1Q
 - ETHERNET
 - ISL
 - FRAME_RELAY
 - FRAME_RELAY_IETF
 - HDLC
 - PPP
 - ATM
 - AAL5SNAP

- AAL0
 - AAL5
 - AAL5MUX
 - AAL5NLPID
 - AAL2
 - ENCAP_QinQ
 - GRE
- **Port Type**—Choices include: Access, Trunk, Routed, and None.

Opening and Editing PEs

To open PE files to bulk edit, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Inventory Manager**.

Step 2 Click the **Open** button.


The **Open** drop-down list appears. The **Open** options include the following:

- **Devices**—Every network element that ISC manages.
- **Provider**—PEs belonging to a specific provider.
- **Customer**—CEs belonging to a specific customer.

Step 3 Select **Provider**.

The Select Provider window appears, as shown in [Figure 3-16](#).

Figure 3-16 Select Provider Window



Step 4 Select a provider by clicking the radio button to the left of the Provider Name.

Step 5 Click the **Select** button.

The General Attributes window appears showing the PEs assigned to the selected provider, as shown in [Figure 3-17](#).

Figure 3-17 General Attributes Provider Window

Inventory Manager

General Attributes - PEs for Provider Provider1

Show entries with Host matching

Showing 1 - 5 of 5 records

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1.	<input type="checkbox"/> pe1	Cisco IOS Device				Default	Default	Device-Group-1
2.	<input type="checkbox"/> pe3	Cisco IOS Device				Default	Default	Device-Group-2
3.	<input type="checkbox"/> sw2	Cisco IOS Device				Default	Default	
4.	<input type="checkbox"/> sw3	Cisco IOS Device				Default	Default	Device-Group-1
5.	<input type="checkbox"/> sw4	Cisco IOS Device				Default	Default	Device-Group-2

Rows per page: Go to page: of 1

- Step 6** To view specific attributes click the **Attributes** button.
- The Attributes options appear, as shown in Figure 3-18.

Figure 3-18 Attributes Options Window

CISCO SYSTEMS **IP Solution Center** Home | Shortcuts | Account | Index | Help | About | Logout

Service Inventory **Service Design** **Monitoring** **Diagnostics** **Administration** User: admin

Inventory and Connection Manager > Discovery > Device Console > Inventory Manager Customer: None

You Are Here: Service Inventory > Inventory and Connection Manager > Inventory Manager

Inventory Manager

General Attributes - PEs for Provider Provider1

Show entries with Host matching

Showing 1 - 5 of 5 records

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1.	<input type="checkbox"/> pe1	Cisco IOS Device				Default	Default	Device-Group-1
2.	<input type="checkbox"/> pe3	Cisco IOS Device				Default	Default	Device-Group-2
3.	<input type="checkbox"/> sw2	Cisco IOS Device						
4.	<input type="checkbox"/> sw3	Cisco IOS Device						Device-Group-1
5.	<input type="checkbox"/> sw4	Cisco IOS Device						Device-Group-2

Rows per page: Go to page: of 1

Attributes

Selection

- Service Requests
- Traffic Engineering Management
- Inventory Manager**
- Topology Tool
- Devices
- Device Groups
- Customers
 - Customer Sites
 - CPE Devices
- Providers
 - Provider Regions
 - PE Devices
 - Access Domains
- Resource Pools
- CE Routing Communities
- VPNs
- AAA Servers
- Named Physical Circuits
- NPC Rings

General Attributes

- General Attributes
- Password Attributes
- SNMP Attributes
- CNS Attributes
- Platform Attributes
- PE Attributes
- Interfaces

- Step 7** Select the type of attribute to display.
- See the following sections for descriptions of these attribute fields.
- [General Attributes Provider, page 3-17](#)

- Password Attributes Provider, page 3-18
- SNMP Attributes Provider, page 3-19
- CNS Attributes Provider, page 3-20
- Platform Attributes Provider, page 3-21
- PE Attributes Provider, page 3-22
- Interfaces Provider, page 3-23

- Step 8** To bulk edit an attribute, do the following:
- Select the one or more boxes to the left of the Host or Device Name.
 - Select the check box above the attribute name column.
 - Click the **Edit** button.
- Step 9** Enter the changes you want to make.
- Step 10** Click **Save**.
- The changes are saved.

General Attributes Provider

The General Attributes Provider window appears, as shown in [Figure 3-19](#).

Figure 3-19 General Attributes Provider Window

Inventory Manager

General Attributes - PEs for Provider Provider1

Show entries with Host matching **Find**

Showing 1 - 5 of 5 records

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1.	<input type="checkbox"/> pe1	Cisco IOS Device				Default	Default	Device-Group-1
2.	<input type="checkbox"/> pe3	Cisco IOS Device				Default	Default	Device-Group-2
3.	<input type="checkbox"/> sw2	Cisco IOS Device				Default	Default	
4.	<input type="checkbox"/> sw3	Cisco IOS Device				Default	Default	Device-Group-1
5.	<input type="checkbox"/> sw4	Cisco IOS Device				Default	Default	Device-Group-2

Rows per page: 10 Go to page: 1 of 1 **Go**

Attributes **Edit** **Save**

The General Attributes Provider window contains the following:

- **Host** —Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.

- **Device Type**—The device type includes the following devices:
 - Cisco Router
 - Catalyst OS device
 - Terminal server
 - IE2100 (Cisco CNS appliance)
- **Description**—Can contain any pertinent information about the device, such as the type of device, its location, or other information that might be helpful to service provider operators. Limited to 80 characters.
- **Management IP Address**—Valid IP address of the device that ISC uses to configure the target router device. This IP address must be reachable from the ISC host.
- **Device Domain Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. The name must match the domain name on the target router device.
- **Terminal Session Protocol**—Configures the method of communication between ISC and the device. Choices include: Telnet, Secure Shell (SSH), CNS, and RSH. Default: Telnet.
- **Config Access Protocol**—Administers the access protocol for config upload and download. Choices include: Terminal, TFTP, FTP, and RCP. Default: Terminal
- **Device Groups**—Lists the names of the Device Groups. You can add and modify Device Groups in this column.

Password Attributes Provider

The Password Attributes Provider window appears, as shown in [Figure 3-20](#).

Figure 3-20 Password Attributes Provider Window

The screenshot shows the 'Password Attributes' window. At the top, it says 'Password Attributes - PEs for Provider Provider1'. Below this is a search bar with the text 'Show entries with Host matching' and a 'Find' button. A status bar indicates 'Showing 1 - 5 of 5 records'. The main table has the following columns: #, Device Name, Login User, Login Password, Enable User, Enable Password, Community String RO, and Community String RW. The table contains five rows of data, each with a checkbox in the first column. At the bottom, there is a 'Rows per page' dropdown set to 10, a 'Go to page' field set to 1 of 1, and buttons for 'Attributes', 'Edit', and 'Save'.

#	Device Name	Login User	Login Password	Enable User	Enable Password	Community String RO	Community String RW
1.	<input type="checkbox"/> pe1		*****		*****	public	private
2.	<input type="checkbox"/> pe3		*****		*****	public	private
3.	<input type="checkbox"/> sw2		*****		*****	public	private
4.	<input type="checkbox"/> sw3		*****		*****	public	private
5.	<input type="checkbox"/> sw4		*****		*****	public	private

The Password Attributes Provider window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.

- **Login User**—Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password, as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Login Password**—Displayed as stars (*). Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password, as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Enable User**—Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Enable Password**—Displayed as stars (*). Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Community String RO**—Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.
- **Community String RW**—Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.

SNMP Attributes Provider

The SNMP Attributes Provider window appears, as shown in [Figure 3-21](#).

Figure 3-21 *SNMP Attributes Provider Window*

The screenshot shows the 'SNMP Attributes' window. At the top, it says 'SNMP Attributes - PEs for Provider Provider1'. Below this is a search bar with the text 'Show entries with Host matching' and a 'Find' button. A status bar indicates 'Showing 1 - 5 of 5 records'. The main table has columns: #, Device Name, SNMP Version, Security Level, Authentication User Name, Authentication Password, Authentication Algorithm, Encryption Password, and Encryption Algorithm. The table contains five rows of data for devices pe1, pe3, sw2, sw3, and sw4. At the bottom, there is a 'Rows per page' dropdown set to 10, a 'Go to page' field set to 1 of 1, and buttons for 'Attributes', 'Edit', and 'Save'.

#	Device Name	SNMP Version	Security Level	Authentication User Name	Authentication Password	Authentication Algorithm	Encryption Password	Encryption Algorithm
1.	pe1	Default	Default			None		None
2.	pe3	Default	Default			None		None
3.	sw2	Default	Default			None		None
4.	sw3	Default	Default			None		None
5.	sw4	Default	Default			None		None

The SNMP Attributes Provider window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **SNMP Version**—Choices include: SNMP v1/v2c, and SNMP v3.
- **Security Level**—Choices include: No Authentication/No Encryption, Authentication/No Encryption, and Authentication/Encryption. Default: No Authentication/No Encryption.

- **Authentication User Name**—User name configured on the specified device router. User must have permission to the object identification numbers (OIDs) specified in the security request (that is, write permission for a set request, and read permission for a get request). Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Limited to 80 characters.
- **Authentication Password**—Displayed as stars (*). Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Should match what is configured on the target router device. Limited to 80 characters.
- **Authentication Algorithm**—Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Choices include: None, MD5, and SHA. Default: None.
- **Encryption Password**—Displayed as stars (*). In previous versions, this field was called Privacy Password. Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Limited to 80 characters.
- **Encryption Algorithm**—In previous versions, this field was called Privacy Protocol. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Choices include: None and DES 56. Default: None.

CNS Attributes Provider

The CNS Attributes Provider window appears, as shown in [Figure 3-22](#).

Figure 3-22 CNS Attributes Provider Window

The screenshot shows the 'CNS Attributes' window. At the top, it says 'CNS Attributes - PEs for Provider Provider1'. Below this is a search bar with the text 'Show entries with Host matching' and a 'Find' button. A status bar indicates 'Showing 1 - 5 of 5 records'. The main area contains a table with the following columns: #, Device Name, IE2100 Name, Device State, Event Identification, and CNS Identification. The table lists five entries: pe1, pe3, sw2, sw3, and sw4. Each entry has a checkbox in the first column. The 'Device State' column shows 'Active' for all entries. The 'Event Identification' column shows 'Host Name' for all entries. The 'CNS Identification' column is empty. At the bottom, there is a 'Rows per page' dropdown set to 10, a 'Go to page' field set to 1 of 1, and buttons for 'Attributes', 'Edit', and 'Save'.

#	Device Name	IE2100 Name	Device State	Event Identification	CNS Identification
1. <input type="checkbox"/>	pe1	None	Active	Host Name	
2. <input type="checkbox"/>	pe3	None	Active	Host Name	
3. <input type="checkbox"/>	sw2	None	Active	Host Name	
4. <input type="checkbox"/>	sw3	None	Active	Host Name	
5. <input type="checkbox"/>	sw4	None	Active	Host Name	

The CNS Attributes Provider window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **IE2100 Name**—Disabled unless the Device-State field is Inactive or the Terminal Session Protocol field is CNS. A valid Cisco CNS IE2100 appliance must be selected if the Terminal Session Protocol is CNS. Choices include: None and the list of existing Cisco CNS IE2100 appliance names. Default: None.

- **Device State**—Choices include: Active and Inactive. Active indicates that the router has been plugged on the network and can be part of ISC tasks such as collect config and provisioning. Inactive indicates the router has not been plugged-in. Default: Active.
- **Event Identification**—Indicates whether the CNS Identification field contains a HOST NAME or CNS ID. Default: HOST NAME.
- **CNS Identification**—Required if the Event Identification field is set to CNS ID. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash.

Platform Attributes Provider

The Platform Attributes Provider window appears, as shown in [Figure 3-23](#).

Figure 3-23 Platform Attributes Provider Window

The screenshot shows the 'PE Attributes' window for 'Provider1'. It contains a table with 7 columns: #, Device Name, Provider, Region*, Role, Loopback Interface, and Managed. There are 5 rows of data. Below the table is a pagination bar with 'Rows per page: 10' and 'Go to page: 1 of 1'. At the bottom right are buttons for 'Attributes', 'Edit', and 'Save'. A note at the bottom left states 'Note: * - Required Field'.

#	Device Name	Provider	Region*	Role	Loopback Interface	Managed
1.	pe1	Provider1	region_1	N_PE	10.8.0.101	Yes
2.	pe3	Provider1	region_1	N_PE	10.8.0.103	Yes
3.	sw2	Provider1	region_1	U_PE		Yes
4.	sw3	Provider1	region_1	U_PE		Yes
5.	sw4	Provider1	region_1	U_PE		Yes

Rows per page: 10 Go to page: 1 of 1

Note: * - Required Field

The Platform Provider window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Platform**—Should match what is configured on the target router device. Limited to 80 characters.
- **Software Version**—Should match what is configured on the target router device. Limited to 80 characters.
- **Image Name**—Should match what is configured on the target router device. Limited to 80 characters.
- **Serial Number**—Should match what is configured on the target router device. Limited to 80 characters.

PE Attributes Provider

The PE Attributes Provider window appears, as shown in [Figure 3-24](#).

Figure 3-24 PE Attributes Provider Window

The screenshot shows the 'PE Attributes' window for 'Provider1'. It includes a search bar for host matching, a table with 5 records, and pagination controls. The table columns are: #, Device Name, Provider, Region*, Role, Loopback Interface, and Managed. The records are for devices pe1, pe3, sw2, sw3, and sw4, all associated with Provider1 and region_1. The roles are N-PE for pe1 and pe3, and U-PE for sw2, sw3, and sw4. The Managed column is set to Yes for all devices. The pagination shows 10 rows per page and 1 of 1 page.

#	Device Name	Provider	Region*	Role	Loopback Interface	Managed
1.	pe1	Provider1	region_1	N-PE	10.8.0.101	Yes
2.	pe3	Provider1	region_1	N-PE	10.8.0.103	Yes
3.	sw2	Provider1	region_1	U-PE		Yes
4.	sw3	Provider1	region_1	U-PE		Yes
5.	sw4	Provider1	region_1	U-PE		Yes

Note: * - Required Field

The PE Attributes Provider window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Provider**—Lists the names of providers. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by provider name.
- **Region**—Lists the names of regions. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by region name.
- **Role**—Choices include: N-PE, U-PE, P, PE_AGG.
- **Loopback Interface**—Loopback address is the IP address of any loopback interface on the device. You can select one of the loopback interfaces for this field and use the IP address on that loopback interface.
- **Managed**—Provisioned by ISC. Select the check box for yes. Default is no.

Interfaces Provider

The Interfaces Provider window appears, as shown in [Figure 3-25](#).

Figure 3-25 Interfaces Provider Window

Interface Attributes

Interfaces - PEs for Provider Provider1								
						Show entries with Host matching <input type="text"/> <input type="button" value="Find"/>		
Showing 1 - 10 of 67 records								
#	<input type="checkbox"/>	Host	Interface Name	Interface Type	Interface Description	<input type="checkbox"/> Interface IP Address	<input type="checkbox"/> Encapsulation	<input type="checkbox"/> Port Type
1.	<input type="checkbox"/>	pe1	ATM2/0	atm				None
2.	<input type="checkbox"/>	pe1	Ethernet4/0	ethernet		172.29.146.21/26		None
3.	<input type="checkbox"/>	pe1	Ethernet4/1	ethernet				None
4.	<input type="checkbox"/>	pe1	Ethernet4/2	ethernet				None
5.	<input type="checkbox"/>	pe1	Ethernet4/3	ethernet				None
6.	<input type="checkbox"/>	pe1	FastEthernet0/0	fastethernet	L4: Link To sw3			None
7.	<input type="checkbox"/>	pe1	FastEthernet0/1	fastethernet				None
8.	<input type="checkbox"/>	pe1	Loopback0	loopback	For BGP neighbor, do not remove	10.8.0.101/32		None
9.	<input type="checkbox"/>	pe1	Serial3/0	serial		10.8.0.2/30		None
10.	<input type="checkbox"/>	pe1	Serial3/1	serial				None
Rows per page: <input type="text" value="10"/>						Go to page: <input type="text" value="1"/> of 7 <input type="button" value="Go"/>		
						<input type="button" value="Attributes"/> <input type="button" value="Edit"/> <input type="button" value="Save"/>		

149455

The Interfaces Provider window contains the following:

- **Host**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Interface Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required. Limited to 256 characters.
- **Interface Type**—Specifies the type of interface. It is a display-only field.
- **Interface Description**—Description of the interface. This field is display-only. Field is populated by importing a configuration file.
- **Interface IP Address**—IP address associated with this interface.
- **Encapsulation**—The Layer 2 Encapsulation for this device. It is a display-only field. Choices include:
 - DEFAULT
 - DOT1Q
 - ETHERNET
 - ISL
 - FRAME_RELAY

- FRAME_RELAY_IETF
 - HDLC
 - PPP
 - ATM
 - AAL5SNAP
 - AAL0
 - AAL5
 - AAL5MUX
 - AAL5NLPID
 - AAL2
 - ENCAP_QinQ
 - GRE
- **Port Type**—Choices include: Access, Trunk, Routed, and None.

Opening and Editing CEs

To open CE files to bulk edit, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Inventory Manager**.

Step 2 Click the **Open** button.

The **Open** drop-down list appears. The **Open** options include the following:

- **Devices**—Every network element that ISC manages.
- **Provider**—PEs belonging to a specific provider.
- **Customer**—CEs belonging to a specific customer.

Step 3 Select **Customer**.

The Select Customer window appears, as shown in [Figure 3-26](#).

Figure 3-26 Select Customer Window

Select Customer - Cisco Systems, Inc.

Show Customers with Customer Name matching * Find

Showing 1 - 2 of 2 records

#	Customer Name
1.	Customer1
2.	Customer2

Rows per page: 10 Go to page: 1 of 1 Go

Select Cancel

Step 4 Select a customer by clicking the radio button to the left of the Customer Name.

Step 5 Click the **Select** button.

The General Attributes window appears showing the CEs assigned to the selected customer, as shown in Figure 3-27.

Figure 3-27 General Attributes Customer Window

Inventory Manager

General Attributes - CEs for Customer Customer 1

Show entries with Host matching * Find

Showing 1 - 3 of 3 records

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1.	ce3	Cisco IOS Device				Default	Default	
2.	ce8	Cisco IOS Device				Default	Default	Device-Group-1
3.	ce13	Cisco IOS Device				Default	Default	Device-Group-2


Rows per page: 10 Go to page: 1 of 1 Go

Attributes Edit Save

Step 6 To view specific attributes click the **Attributes** button.

The Attributes options appear, as shown in Figure 3-28.

Figure 3-28 Attributes Options Window



Step 7 Select the type of attribute to display.

See the following sections for descriptions of these attribute fields.

- [General Attributes Customer, page 3-27](#)
- [Password Attributes Customer, page 3-28](#)
- [SNMP Attributes Customer, page 3-29](#)
- [CNS Attributes Customer, page 3-30](#)
- [Platform Attributes Customer, page 3-30](#)
- [CPE Attributes Customer, page 3-31](#)
- [Interfaces Customer, page 3-32](#)

Step 8 To bulk edit an attribute, do the following:

- a. Select the one or more boxes to the left of the Host or Device Name.
- b. Select the check box above the attribute name column.
- c. Click the **Edit** button.

Step 9 Enter the changes you want to make.

Step 10 Click **Save**.

The changes are saved.

General Attributes Customer

The General Attributes Customer window appears, as shown in [Figure 3-29](#).

Figure 3-29 General Attributes Customer Window

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1.	ce3	Cisco IOS Device				Default	Default	
2.	ce8	Cisco IOS Device				Default	Default	Device-Group-1
3.	ce13	Cisco IOS Device				Default	Default	Device-Group-2

The General Attributes Customer window contains the following:

- **Host**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Device Type**—The device type includes the following devices:
 - Cisco Router
 - Catalyst OS device
 - Terminal server
 - IE2100 (Cisco CNS appliance)
- **Description**—Can contain any pertinent information about the device, such as the type of device, its location, or other information that might be helpful to service provider operators. Limited to 80 characters.
- **Management IP Address**—Valid IP address of the device that ISC uses to configure the target router device. This IP address must be reachable from the ISC host.
- **Device Domain Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. The name must match the domain name on the target router device.
- **Terminal Session Protocol**—Configures the method of communication between ISC and the device. Choices include: Telnet, Secure Shell (SSH), CNS, and RSH. Default: Telnet.
- **Config Access Protocol**—Administers the access protocol for config upload and download. Choices include: Terminal, TFTP, FTP, and RCP. Default: Terminal
- **Device Groups**—Lists the names of the Device Groups. You can add and modify Device Groups in this column.

Password Attributes Customer

The Password Attributes Customer window appears, as shown in [Figure 3-30](#).

Figure 3-30 Password Attributes Provider Window

The screenshot shows the 'Password Attributes' window for 'Customer 1'. It features a table with columns: #, Device Name, Login User, Login Password, Enable User, Enable Password, Community String RO, and Community String RW. There are three records listed. Below the table, there are controls for 'Rows per page' (set to 10) and 'Go to page' (set to 1 of 1). At the bottom right, there are buttons for 'Attributes', 'Edit', and 'Save'. A vertical label '149327' is on the far right.

#	Device Name	Login User	Login Password	Enable User	Enable Password	Community String RO	Community String RW
1.	ce3		*****		*****	public	private
2.	ce8		*****		*****	public	private
3.	ce13		*****		*****	public	private

The Password Attributes Customer window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Login User**—Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password, as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Login Password**—Displayed as stars (*). Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password, as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Enable User**—Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Enable Password**—Displayed as stars (*). Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Community String RO**—Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.
- **Community String RW**—Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.

SNMP Attributes Customer

The SNMP Attributes Customer window appears, as shown in [Figure 3-31](#).

Figure 3-31 SNMP Attributes Customer Window

SNMP Attributes - CEs for Customer Customer1

Show entries with Host matching

Showing 1 - 3 of 3 records

#	Device Name	SNMP Version	Security Level	Authentication User Name	Authentication Password	Authentication Algorithm	Encryption Password	Encryption Algorithm
1.	<input type="checkbox"/> ce3	Default	Default			None		None
2.	<input type="checkbox"/> ce8	Default	Default			None		None
3.	<input type="checkbox"/> ce13	Default	Default			None		None

Rows per page: 10 Go to page: 1 of 1

The SNMP Attributes Customer window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **SNMP Version**—Choices include: SNMP v1/v2c, and SNMP v3.
- **Security Level**—Choices include: No Authentication/No Encryption, Authentication/No Encryption, and Authentication/Encryption. Default: No Authentication/No Encryption.
- **Authentication User Name**—User name configured on the specified device router. User must have permission to the object identification numbers (OIDs) specified in the security request (that is, write permission for a set request, and read permission for a get request). Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Limited to 80 characters.
- **Authentication Password**—Displayed as stars (*). Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Should match what is configured on the target router device. Limited to 80 characters.
- **Authentication Algorithm**—Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Choices include: None, MD5, and SHA. Default: None.
- **Encryption Password**—Displayed as stars (*). In previous versions, this field was called Privacy Password. Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Limited to 80 characters.
- **Encryption Algorithm**—In previous versions, this field was called Privacy Protocol. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Choices include: None and DES 56. Default: None.

CNS Attributes Customer

The CNS Attributes Customer window appears, as shown in [Figure 3-32](#).

Figure 3-32 CNS Attributes Customer Window

The screenshot shows the 'CNS Attributes' window titled 'CNS Attributes - CEs for Customer Customer1'. It features a search bar with the text 'Show entries with Host matching' and a 'Find' button. Below the search bar, it indicates 'Showing 1 - 3 of 3 records'. The main content is a table with the following columns: #, Device Name, IE2100 Name, Device State, Event Identification, and CNS Identification. The table contains three rows of data. At the bottom, there is a 'Rows per page' dropdown set to 10, a 'Go to page' field set to 1 of 1, and buttons for 'Attributes', 'Edit', and 'Save'.

#	Device Name	IE2100 Name	Device State	Event Identification	CNS Identification
1.	ce3	None	Active	Host Name	
2.	ce8	None	Active	Host Name	
3.	ce13	None	Active	Host Name	

The CNS Attributes Customer window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **IE2100 Name**—Disabled unless the Device-State field is Inactive or the Terminal Session Protocol field is CNS. A valid Cisco CNS IE2100 appliance must be selected if the Terminal Session Protocol is CNS. Choices include: None and the list of existing Cisco CNS IE2100 appliance names. Default: None.
- **Device State**—Choices include: Active and Inactive. Active indicates that the router has been plugged on the network and can be part of ISC tasks such as collect config and provisioning. Inactive indicates the router has not been plugged-in. Default: Active.
- **Event Identification**—Indicates whether the CNS Identification field contains a HOST NAME or CNS ID. Default: HOST NAME.
- **CNS Identification**—Required if the Event Identification field is set to CNS ID. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash.

Platform Attributes Customer

The Platform Attributes Customer window appears, as shown in [Figure 3-33](#).

Figure 3-33 Platform Attributes Customer Window

Platform Attributes

Platform Attributes - CEs for Customer Customer1

Show entries with Host matching

Showing 1 - 3 of 3 records

#	<input type="checkbox"/>	Device Name	Platform	Software Version	Image Name	Serial Number
1.	<input type="checkbox"/>	ce3	2621	12.2(5d)	C2600-JS-M:c2600-js-mz.122-16.6	
2.	<input type="checkbox"/>	ce8	2621	12.2(5d)	C2600-JS-M:c2600-js-mz.122-16.6	
3.	<input type="checkbox"/>	ce13	2621	12.2(5d)	C2600-JS-M:c2600-js-mz.122-16.6	

Rows per page: 10

149331

The Platform Customer window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Platform**—Should match what is configured on the target router device. Limited to 80 characters.
- **Software Version**—Should match what is configured on the target router device. Limited to 80 characters.
- **Image Name**—Should match what is configured on the target router device. Limited to 80 characters.
- **Serial Number**—Should match what is configured on the target router device. Limited to 80 characters.

CPE Attributes Customer

The CPE Attributes Customer window appears, as shown in [Figure 3-34](#).

Figure 3-34 CPE Attributes Customer Window

CPE Attributes

CPE Attributes for Customer Customer1

Show entries with Host matching

Showing 1 - 3 of 3 records

#	<input type="checkbox"/>	Device Name	Customer	<input type="checkbox"/> Site*	<input type="checkbox"/> Management Type
1.	<input type="checkbox"/>	ce3	Customer1	east	Managed
2.	<input type="checkbox"/>	ce8	Customer1	east	Managed
3.	<input type="checkbox"/>	ce13	Customer1	east	Managed

Rows per page: 10

Note: * - Required Field

149316

The CPE Attributes Customer window contains the following:

- **Device Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Customer**—Lists the names of customers. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by customer name.
- **Site**—Lists the names of sites. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by site name.
- **Management Type**—Choices include: Managed, Unmanaged, Managed - Management LAN, Unmanaged - Management LAN, Directly Connected, Directly Connected Management Host, Multi-VRF, and Unmanaged Multi-VRF.

Interfaces Customer

The Interfaces Customer window appears, as shown in [Figure 3-35](#).

Figure 3-35 Interfaces Customer Window

Interface Attributes

Interfaces - CEs for Customer Customer1

Show entries with Host matching Find

Showing 1 - 10 of 12 records

#	<input type="checkbox"/>	Host	Interface Name	Interface Type	Interface Description	<input type="checkbox"/> Interface IP Address	<input type="checkbox"/> Encapsulation	<input type="checkbox"/> Port Type
1.	<input type="checkbox"/>	ce3	Ethernet0/0	ethernet		172.29.146.26/26		None
2.	<input type="checkbox"/>	ce3	Ethernet0/1	ethernet				None
3.	<input type="checkbox"/>	ce3	Ethernet0/2	ethernet				None
4.	<input type="checkbox"/>	ce3	Ethernet0/3	ethernet				None
5.	<input type="checkbox"/>	ce3	Serial1/0	serial				None
6.	<input type="checkbox"/>	ce3	Serial1/1	serial				None
7.	<input type="checkbox"/>	ce3	Serial1/2	serial				None
8.	<input type="checkbox"/>	ce3	Serial1/3	serial				None
9.	<input type="checkbox"/>	ce8	FastEthernet0/0	fastethernet		172.29.146.31/26		None
10.	<input type="checkbox"/>	ce8	FastEthernet0/1	fastethernet	L7: Link To sw3			None

Rows per page: 10

Go to page: 1 of 2

Attributes Edit Save

The Interfaces Customer window contains the following:

- **Host**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Interface Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required. Limited to 256 characters.
- **Interface Type**—Specifies the type of interface. It is a display-only field.


- **Interface Description**—Description of the interface. This field is display-only. Field is populated by importing a configuration file.
- **Interface IP Address**—IP address associated with this interface.
- **Encapsulation**—The Layer 2 Encapsulation for this device. It is a display-only field. Choices include:
 - DEFAULT
 - DOT1Q
 - ETHERNET
 - ISL
 - FRAME_RELAY
 - FRAME_RELAY_IETF
 - HDLC
 - PPP
 - ATM
 - AAL5SNAP
 - AAL0
 - AAL5
 - AAL5MUX
 - AAL5NLPID
 - AAL2
 - ENCAP_QinQ
 - GRE
- **Port Type**—Choices include: Access, Trunk, Routed, and None.

Assigning Devices

To assign a device to a provider or customer, follow these steps:


-
- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Inventory Manager**.
- Step 2** Click the **Open** button.
- The **Open** drop-down list appears, as shown in [Figure 3-37](#).

Figure 3-36 Open Options Window

**Step 3** Select Devices.

The Select Device window appears, as shown in Figure 3-37.

Figure 3-37 Select Devices Window

**Step 4** Select a device to open by selecting the box to the left of the Device Name. You can select more than one device to open.

Step 5 Click the **Select** button.

The General Attributes window appears containing information on the selected devices, as shown in [Figure 3-38](#).

Figure 3-38 General Attributes Devices Window

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol	Device Groups
1.	pe1	Cisco IOS Device				Default	Default	Device-Group-1
2.	pe3	Cisco IOS Device				Default	Default	Device-Group-2
3.	sw2	Cisco IOS Device				Default	Default	

Rows per page: 10 Go to page: 1 of 1

Buttons: Attributes, Assign CE/PE, Edit, Save

Step 6 Click the **Assign CE/PE** button.

Step 7 Select **Customer** or **Provider**.

The corresponding **Select Customer** or **Select Provider** window appears, as shown in [Figure 3-39](#).

Figure 3-39 Select Provider Window

#	Provider Name
1.	Provider1

Rows per page: 10 Go to page: 1 of 1

Buttons: Select, Cancel

Step 8 Select the customer or provider to which you want to assign the device by selecting the box to the left of the Customer or Provider Name.

Step 9 Click the **Select** button.

If you assigned the device to a provider, the PE Attributes window appears. If you assigned the device to a customer, the CPE Attributes window appears.

Step 10 In order to save the assigned devices to the ISC repository, you must specify the Site in the CPE Attributes window or the Region in the PE Attributes window. Do the following:

- a. Select the one or more boxes to the left of the Device Name.

- b. Select the check box above the **Site** column.
- c. Click the **Edit** button. The **Edit Attributes** window appears.
- d. Click **Select**. The **Select Site** window appears.
- e. Select a site by selecting the box to the left of the Site Name.
- f. Click Save.

Step 11 You can choose to edit attributes as desired. Enter any changes you want to make.

Step 12 Click **Save**.

The PE or CPE is saved to the ISC repository.

Topology Tool

The topology tool provides a graphical view of networks set up through the ISC web client. It gives a graphical representation of the various physical and logical parts of the network, both devices and links.

- [Introduction, page 3-37](#)
- [Launching Topology Tool, page 3-37](#)
- [Conventions, page 3-39](#)
- [Accessing the Topology Tool for ISC-VPN Topology, page 3-41](#)
- [Types of Views, page 3-43](#)
 - [VPN View, page 3-44](#)
 - [Logical View, page 3-49](#)
 - [Physical View, page 3-52](#)
- [Viewing Device and Link Properties, page 3-53](#)
- [Filtering and Searching, page 3-60](#)
 - [Filtering, page 3-60](#)
 - [Searching, page 3-63](#)
- [Using Maps, page 3-64](#)
 - [Loading a map, page 3-65](#)
 - [Layers, page 3-66](#)
 - [Map data, page 3-67](#)
 - [Node locations, page 3-67](#)
 - [Adding new maps, page 3-68](#)
- [Devices, page 3-68.](#)

Introduction

The topology tool includes three types of views:

- VPN view—shows connectivity between customer devices. The VPN view also gives an aggregate view of all services and individual logical and physical views of each of the services.
- Logical view—shows logical connections set up in a selected provider region
- Physical view—displays connectivity of named physical circuits in a provider region.

In addition, this chapter describes the following features:

- Filtering and Searching—filter out unnecessary detail in large graphs or jump straight to a particular device using the search tool
- Using Maps—associate maps with the individual views.

Please note that some details, such as window decorations, are system specific and might appear differently in different environments. However, the functionality should remain consistent.

Launching Topology Tool


To launch the Topology Tool, follow these steps:


- Step 1** Log into ISC.
- Step 2** Navigate **Service Inventory > Inventory and Connection Manager > Topology Tool** and a window appears, as shown in [Figure 3-40](#), “Topology Launch Window.” If you do not have the proper Java Runtime Environment (JRE) as specified at the bottom of the window, click the corresponding link for your system, follow that path, then quit the browser, log in again, and navigate back to the Topology Tool page.

Figure 3-40 *Topology Launch Window*

Topology Tool

View topology maps.


ISC-VPN Topology
 Launches a Java™ Web Start application that presents graphical views of VPNs, Regions, and Access Domains.


ISC-TEM Topology Interface Applet
 Launches the ISC-TEM Topology Interface Applet.

Java Runtime Environment (JRE) and Java Webstart must be installed to run Inventory Manager. If you are having trouble getting them to function properly or need to update your local JRE please download and install one appropriate for your operating system.

JRE Description	Platform	Version	Supported
Windows (all languages, including English)	Windows	1.4.2_04	Yes
Solaris SPARC 32-bit self-extracting file	Solaris SPARC	1.4.2_04	Yes
Linux self-extracting file	Linux	1.4.2_04	No

101966

- Step 3** Click **ISC-VPN Topology** in Figure 3-40, “Topology Launch Window” to launch the Topology Tool application on the web client. This starts up the Java Web Start application.

**Note**

Name resolution is required. The ISC HTTP server host must be in the Domain Name System (DNS) that the web client is using or the name and address of the ISC server must be in the client host file.


- Step 4** The first time Inventory Manager is activated, the Security Warning window in Figure 3-41 appears. Click **Start** to proceed or **Details** to verify the security certificate.

Figure 3-41 Security Warning Window




- Step 5** The Desktop Integration window in Figure 3-42 appears. Click **Yes** to integrate into your desktop environment, click **No** to decline, click **Ask Later** to be prompted the next time VPN Topology is invoked, or click **Configure ...** to customize the desktop integration.

Figure 3-42 Topology Desktop Integration Window



The Login window in Figure 3-43, “Log On to ISC Window.” appears whether or not a selection has been made in the Desktop Integration window.

Figure 3-43 Log On to ISC Window



- Step 6** Enter your **User Name** and **Password** and click **OK**. The Topology Tool launches and connects to the Master ISC server.

Conventions

Topology software uses several conventions to visually communicate information about displayed objects. The shape and color of a node representing a device depends on the role of the device, as shown in [Table 3-2](#).

Table 3-2 *Device Role Shapes*













Shape	Description
	<p>Green icon for a CAT OS customer device followed by the following information:</p> <ul style="list-style-type: none"> - Device name - Customer Name - Site Name - Management IP Address - Description - Role (SPOKE or HUB of a VPN)
	<p>Green icon for a router customer device followed by the following information:</p> <ul style="list-style-type: none"> - Device name - Customer Name - Site Name - Management IP Address - Description - Role (SPOKE or HUB of a VPN)
	<p>Green icon for a VPN 3000 customer device (This feature is not supported in this device) followed by the following information:</p> <ul style="list-style-type: none"> - Device name - Customer Name - Site Name - Management IP Address - Description - Role (SPOKE or HUB of a VPN)
	<p>Green icon for an interface followed by the following information:</p> <ul style="list-style-type: none"> - Interface name - Management IP Address - Encapsulation Type - Interface Type

Table 3-2 **Device Role Shapes (continued)**

Shape	Description
 <p>device-1.domain.com</p> <p>Provider Name Region 1 Name 177.0.0.1 Description of device-1 N-PE</p> <p>111687</p>	<p>Blue icon for a CAT OS provider device followed by the following information:</p> <ul style="list-style-type: none"> - Device name - Provider Name - Region Name - Management IP Address - Description - Role
 <p>device-0.domain.com</p> <p>Provider Name Region 1 Name 177.0.0.0 Description of device-0 N-PE</p> <p>111688</p>	<p>Blue icon for a router provider device followed by the following information:</p> <ul style="list-style-type: none"> - Device name - Provider Name - Region Name - Management IP Address - Description - Role
 <p>Region 1 Name</p> <p>Provider Name</p> <p>111689</p>	<p>Blue icon for a region followed by the following information:</p> <ul style="list-style-type: none"> - Region name - Provider Name
 <p>Site C Name</p> <p>Customer Name HUB</p> <p>111690</p>	<p>Green icon for a site followed by the following information:</p> <ul style="list-style-type: none"> - Site name - Customer Name - Role in which Site's device joined VPN (HUB, SPOKE, or combination of HUB and SPOKE)
 <p>Site A Name</p> <p>Customer Name SPOKE</p> <p>111691</p>	<p>Green icon for a site followed by the following information:</p> <ul style="list-style-type: none"> - Site name - Customer Name - Role in which Site's device joined VPN (HUB, SPOKE, or combination of HUB and SPOKE)





A distinct color scheme is used to highlight the link type as shown in [Table 3-3](#):

Table 3-3 *Link Type Color Scheme*

Color	Connection Type
 (green)	End-to-end wire
 (purple)	Attachment circuit
 (brown)	MPLS VPN link

Finally, the four patterns shown in [Table 3-4](#) are used to indicate the service request state:

Table 3-4 *Link State Pattern Scheme*


Pattern	Service Request State
	Deployed, functional, pending
	Failed audit, invalid, broken, lost
	Wait deploy, requested, failed deploy
	Closed

Accessing the Topology Tool for ISC-VPN Topology

Launch the Topology Tool as explained in [Figure 3-40](#), “Topology Launch Window,” in the “[Launching Topology Tool](#)” section on [page 3-37](#) and then use the following steps to access the **ISC-VPN Topology** tool.

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Topology Tool > ISC-VPN Topology**.

The Topology window shown in [Figure 3-44](#) appears.

Figure 3-44 **Topology Application Window**


The application window is divided into four areas, as shown in [Figure 3-44](#):

- area (1)—The top left corner shows the Overview area. The colored rectangular panel, called the panner, corresponds to the area currently visible in the main area. Moving the panner around changes the part of the graph showing in the main area. This is particularly useful for large graphs.
- area (2)—The bottom left area shows the Tree View of the graph. When no graph is shown, a single node called **Unnamed** is displayed. When a graph is shown, a tree depicting devices and their possible interfaces and connections is displayed. The tree can be used to quickly locate a device or a connection.
- area (3)—The main area (Main View) of the window shows a graph representing connections between devices. The name of the displayed network is shown at the bottom. When no view is present, the name defaults to **Unnamed**.
- area (4)—Above the main window is the Filter area. It allows you to filter nodes by entering a pattern. Nodes whose name contains the entered pattern maintain the normal level of brightness. All other nodes and edges become dimmed, as shown in [Figure 3-66](#) and the “[Filtering](#)” section on [page 3-60](#).



Note The bottom bar below all the areas, is a Status bar.

Views are loaded, saved, and closed using the **File** menu, as shown in [Figure 3-45](#).

Figure 3-45 *The File Menu*

The **File** menu contains the following menu items:

- **Open**—Opens a view.
- **Save**—Saves the open and active view with the existing file name, if any.
- **Export...**—Exports the active view in either Scalable Vector Graphics (SVG), Joint Photographic Experts Group (JPG), or Portable Network Graphics (PNG) format.
- **Save All**—Saves all open views.
- **Close**—Closes the open and active view.
- **Close All**—Closes all open views.
- **Print...**—Prints the open and active view.
- **Exit**—Exits the Topology tool.


Types of Views

There are three view panes in the topology application and they are described in the following sections:

- **VPN View**, page 3-44, shows connectivity between devices in a VPN
- **Logical View**, page 3-49, shows connectivity between PEs and CPEs in a region
- **Physical View**, page 3-52, shows physical devices and links for PEs in a region.

The view attributes can be changed using the **View** menu, as shown in Figure 3-46.

Figure 3-46 The View Menu



The **View** menu contains the following menu items:

- **Anti-Aliasing**—When drawing a view, this creates smoother lines and a more pleasant appearance at the expense of performance.
- **Grid**—Activates a magnetic grid. The grid has a 10 by 10 spacing and can be used to help align nodes in a view.
- **Auto-Layout**—Generates an automatic layout of nodes in a view. If selected, the program tries to find the most presentable arrangement of nodes.
- **Zoom**—Opens a dialog where the desired magnification level can be specified.
- **Zoom In**—Increases the magnification level.
- **Zoom Out**—Decreases the magnification level.
- **Refresh**—Regenerates the view. This is especially useful if the data in the repository changes. To see an updated view, select **Refresh** or click the Refresh toolbar button.

VPN View


The VPN view shows connectivity between devices forming a given VPN. To activate the VPN view, follow these steps:

Step 1 In the menu bar, select **File > Open**.

or

click the **Open** button in the tool bar.

The Folder View window in Figure 3-47 appears displaying a directory tree with available VPNs.


Figure 3-47 Folder View Window

- Step 2** Navigate to the desired VPN's folder, select the folder, and click **Open**. This opens the desired folder to display any logical and physical views associated with that VPN.
- Step 3** Click a logical or a physical view item in the folder tree. The logical view minimizes the amount of detail and shows connectivity between customer devices. The physical view reveals more about the physical structure of the VPN. For example, for MPLS it shows connectivity between customer and provider devices and the core of the provider.

Aggregate View


The Aggregate View, as shown in [Figure 3-48](#), “[Aggregate View](#),” shows connectivity between all customer devices, regardless of the type of technology used to connect them.

A single view might show a combination of MPLS, Layer 2, and VPLS. For MPLS, only the Customer Premises Equipment devices (CPEs) are shown.

Figure 3-48 Aggregate View

The Layer 2 VPN might in addition to CPEs show connectivity between Customer Location Edge devices (CLEs) or Provider Edge devices (PE). For VPLS, you see connectivity between CPEs. For missing CPEs, you see connectivity to PEs.


In MPLS Layer 2 VPN, the topology displays Virtual Circuit (VC) with MPLS core (as MPLS string) but with L2TPv3, the topology will display Virtual Circuit (VC) with IP core (as IP string) as shown in [Figure 3-49](#).

Figure 3-49 Virtual Circuit with IP Core


VPLS Topology

In the case of a VPLS topology, you can access an Attachment Circuit View or an Emulated Circuit View. The Attachment Circuit View corresponds to a logical view in other types of VPNs. It shows customer devices connected to a virtual private LAN, as shown in Figure 3-50, “Attachment Circuit View.”

Figure 3-50 Attachment Circuit View



The Emulated Circuit View shows the physical connectivity details omitted in the Attachment Circuit View. Connectivity between provider devices and customer devices connected to provider devices, as shown in [Figure 3-51, “Emulated Circuit View.”](#)

Figure 3-51 Emulated Circuit View


Logical View

The logical view shows connectivity, created through service requests, between PEs and CPEs of a given region.

To activate the logical view, follow these steps:


- Step 1** In the menu bar, select **File > Open**.
or
click the **Open** button in the tool bar.
The Folder View window, as shown in [Figure 3-47](#), appears.
 - Step 2** Navigate to the desired VPN's folder and double-click on the desired folder. Any logical and physical views associated with that VPN are displayed.
 - Step 3** To open the logical view for the selected VPN, do one of the following:
Single-click the **Logical View** icon and click **Open**
or
Double-click the **Logical View** icon.
- This creates a logical view for the chosen VPN, as shown in [Figure 3-52](#).

Figure 3-52 Logical View




In a created view, the node, usually located in the center of the graph, is the node representing a given region of a provider. The node is annotated with the name of the region and the name of the provider. Each node directly connected to the regional node represents a PE. The icon of a node depends on the type and the role of the device it represents (see the “Conventions” section on page 3-39). Each PE is annotated with the fully-qualified device name, provider name, region name, management IP address, description, and role. A right-click on a node displays the details of the logical and physical device, interfaces, and service requests (SR) associated with the node, as shown in Figure 3-53. For the regional node, details are shown in a tabulated form.

Figure 3-53 Device Properties



The various node and link properties are described in detail in Viewing Device and Link Properties, page 3-53. Likewise, you can right-click on a link to learn about its link properties. For example, when selecting **Interfaces...** for a sample serial link, a Properties window like the one in Figure 3-54 appears.

Figure 3-54 **Interface Properties Window**


Each PE can be logically connected to one or more CPEs. Such connections are created by either MPLS VPN links or Layer 2 Logical Links. Each such connection is represented by an edge linking the given PE to a CPE. If there are more connections between a particular PE and CPE, all of them are shown. Depending on the state of a connection, the edge is drawn using a solid line (for functioning connections), dotted line (for broken connections), or dashed line (for connections yet to be established).

Depending on the connection type, the connection is drawn as described in [Table 3-3](#) and [Table 3-4](#). Each connection is annotated with the PE Interface Name (IP address), VLAN ID number, CPE Interface Name (IP address).

In the Overview area, a direct connection is drawn between a CPE and a PE, even if a number of devices are forming such a connection.

For more about viewing device properties, see [Viewing Device and Link Properties](#), page 3-53.

To view the details of a connection, right-click on it and select the **Expand** option from a pop-up menu. The expanded view, displayed in a new tab, shows all devices and interfaces making a given PE to CPE connection, as shown in [Figure 3-55](#).

Figure 3-55 Detailed Connection View

Physical View

A physical view shows all named physical circuits defined for PEs in a given region. Each named physical circuit is represented as a sequence of connections leading from a PE through its interfaces to interfaces of CLEs or CPEs. All physical links between PEs of a given region and their CLEs or CPEs are shown. Since physical links are assumed to be in a perfect operational order, edges are always drawn with solid lines.

To activate the physical view, follow these steps:

- Step 1** In the menu bar, select **File > Open**.
or
click the **Open** button in the tool bar.
The Folder View window, as shown in [Figure 3-47](#), appears.
- Step 2** Navigate to the desired VPN's folder and double-click on the desired folder. Any logical and physical views associated with that VPN are displayed.

Step 3 To open the physical view for the selected VPN, do one of the following:


Single-click the **Physical View** icon and click **Open**

or

Double-click the **Physical View** icon.

This creates a physical view for the chosen VPN, as shown in Figure 3-56.

Figure 3-56 Physical View



In this view, each device is connected with a thin line to the interfaces it owns. Interfaces are connected to other interfaces with thick lines. If there is more than one connection between two interfaces, they are spaced to show all of them.

The tree shows devices and connections. Each device can be a folder, holding all interfaces connected to it.

Viewing Device and Link Properties

In the logical view, you can view the properties of both devices and links. In the physical view, only properties of physical devices are accessible.

Thus, device properties can be viewed in both the logical and physical views.

Device Properties

To view the properties of a device, right-click the device. The Device Properties menu in [Figure 3-57](#) appears.

Figure 3-57 *Device Properties*




The following properties are available:

- Logical Device...**—View the logical properties of the device.
- Physical Device...**—View the physical properties of the device.
- Interfaces...**—View interface properties of the device.
- Service Requests...**—View service request properties associated with the device.

Logical Device

When right-clicking a device and selecting **Logical Device...**, the logical device properties window in [Figure 3-58](#) appears.

Figure 3-58 *Logical Device Properties Window*




The logical properties window displays the following information:

- Device Name**—Name of the device.
- Provider Name**—Name of the provider whom the device is serving.
- Region Name**—Name of the provider region.
- Loopback Address**—IP address of the loopback address.
- Role Type**—Role assigned to the device.

Physical Device

When right-clicking a device and selecting **Physical Device...**, the physical device properties window in [Figure 3-59](#) appears.

Figure 3-59 *Physical Device Properties Window*



The physical properties window displays the following information:

Name—Name of the device.

Description—User-defined description of the device.

Collection Zone—Collection zone for device data.

IP Address—IP address of the interface used in the topology.

User ID—User ID for the interface.

Enable User—Password for the interface.

Device Access Protocol—Protocol used to communicate with the device.

Config Upload/Download—Upload/download method for the configuration file.

SNMP Version—Simple Network Management Protocol (SNMP) version on the device.

Community String RO—**public** or **private**

Community String RW—**public** or **private**

SNMP Security Level—Simple Network Management Protocol (SNMP) security level.

Authentication User Name—User name for performing authentication on the device.

Authentication Algorithm—Algorithm used to perform authentication.

Encryption Algorithm—Encryption algorithm used for secure communication.

Terminal Server—Name of the terminal server.

Terminal Server Port—Port number used by the terminal server.

Platform—Hardware platform.

Software—IOS version or other management software on the device.


Image Name—Boot image for device initialization.

Serial Number—Serial number of the device.

Interfaces

When right-clicking a device and selecting **Interfaces...**, the interface properties window in [Figure 3-60](#) appears.

Figure 3-60 *Device Interface Properties Window*



The interface properties window displays the following information:

Name—Name of the device.

IP Address—IP address of the device.

IP Address Type—STATIC or DYNAMIC.


Encapsulation—Encapsulation used on the interface traffic.

Description—Description assigned to the interface, if any.

Select (link)—If a connection is attached to the interface, a drop-down list at the bottom of the window allows you to choose between the interfaces available on the device.

Service Requests

When right-clicking a device and selecting **Service Requests...**, the service request (SR) properties window in [Figure 3-61](#) appears.

Figure 3-61 Service Request Properties Window

The service request properties window displays the following information:

Job ID—SR identifier.

Type—Protocol type used in the SR.

State—SR state.

Operation Type—Encapsulation used on the interface traffic.

Creator—Description assigned to the interface, if any.

Creation Time—Date and time when the SR was created.

Customer Name—Name of customer associated with the SR.


Last Modified—Date and time when the SR was last modified.

Description—User-defined description of the SR.

Select (SR)—If more than one SR is associated with the interface, the drop-down list at the bottom of the window allows you to choose between these SRs.

Link Properties

To view the properties of a given link, right-click the link. The Link Properties menu in [Figure 3-62](#) appears.

Figure 3-62 Link Properties

The following options are available:

Expand...—View link details, including devices local to the link not shown in the general topology.


Service Request...—View service request properties associated with the link.

MPLS VPN...—View the MPLS VPN properties of the link. Other link protocol properties than MPLS VPN are currently not available.

Expand

When right-clicking a link and selecting **Expand...**, the Topology Display will display any devices and connections local to that link. An Expand Link window similar to the one in [Figure 3-63](#) will appear.


Figure 3-63 *Expand Link Window*



Properties information for devices and links can only be obtained in the master view as described earlier in this section.

Service Request

When right-clicking a link and selecting **Service Requests...**, the service request (SR) properties window in [Figure 3-64](#) appears.

Figure 3-64 Link Service Request Properties Window

The service request properties window displays the following information:

Job ID—SR identifier.

Type—Protocol type used in the SR.

State—SR state.

Operation Type—Encapsulation used on the interface traffic.

Creator—Description assigned to the interface, if any.

Creation Time—Date and time when the SR was created.

Customer Name—Name of customer associated with the SR.


Last Modified—Date and time when the SR was last modified.

Description—User-defined description of the SR.

Select (SR)—If more than one SR is associated with the interface, the drop-down list at the bottom of the window allows you to choose between these SRs.

MPLS VPN

When right-clicking a link that is configured for MPLS VPN and selecting **MPLS VPN...**, the MPLS VPN properties window in [Figure 3-65](#) appears.

Figure 3-65 Link MPLS VPN Properties Window

The service request properties window displays the following information:

Status—Status of the MPLS VPN link.

Status Message—Displays any error or warning messages.

Operation Type—MPLS operation type.

Policy Type—The policy type applied to the link.

Data MTD Threshold—Memory Technology Driver (MTD) data threshold.

Default MTD Address—Default MTD IP address.

Data MTD Subnet—Data MTD subnet.

Data MTD Size—Data MTD size.

SOO Enabled—Yes or No.

Manual Config—Yes or No.

Filtering and Searching

On large graphs, the amount of detail can be overwhelming. In such cases, filtering might help eliminate unnecessary details, while searching can lead to a prompt location of a device you want to examine further.

Both advanced filtering and searching use the same dialog to enter conditions on nodes to be either filtered or located. The filtering area also allows you to quickly filter viewed objects by name.

Filtering

The topology view can be filtered in two ways, simple and advanced.

Simple Filtering


To perform simple filtering of the view, follow these steps:

-
- Step 1** Enter a string in area (4) of the main window, as shown in [Figure 3-44 on page 3-42](#).

Step 2 Press **Enter** to dim all objects whose name does not contain the specified string.

For example, to locate nodes that contain string **router** in their name you would enter **router** in area (4) and click **Enter**. All objects whose name does not contain the entered string are dimmed, as shown in Figure 3-66.

Figure 3-66 Physical View with Dimmed Nodes



Note

Regular expressions are supported but only in the advanced dialog (click **Advanced...** button). For example, by entering `^foo.*a`, you only request nodes that have names starting with "foo" followed by arbitrary characters and containing the letter 'a' somewhere in the name. The regular expressions must follow the rules defined for Java regular expressions.

Advanced Filtering

To perform advanced filtering, follow these steps:


- Step 1** Open the advanced filtering dialog by clicking the **Advanced...** button. The Advanced Filter dialog appears, as shown in Figure 3-67.
- Step 2** Make the desired filtering elections.

The dialog allows you to enter one or more conditions on filtered nodes. The first drop-down list allows you to specify the attribute by which the filtering is performed. The second allows you to decide how the matching between the value of the attribute and text entered in the third column is performed.

The following matching modes are supported from the drop-down list:

- **contains**—The attribute value is fetched from the device and it is selected if it contains the string given by you. The string can be located at the start, end, or middle of the attribute for the match to succeed. For example, if the pattern is **cle** the following values match it in the **contains** mode: **clean**, **nucleus**, **circle**.
- **starts with**—The value of the attribute must start with the string given by you. For example, if the pattern is **foot**, **footwork** matches, but **afoot** does not.
- **ends with**—This is the reverse of the **starts with** case, when a given attribute matches only if the specified pattern is at the end of the attribute value. In this mode, for example, the pattern **foot** matches **afoot** but not **footwork**.
- **doesn't contain**—In this mode, only those strings that do not contain the given pattern match. The results are opposite to that of the **contains** mode. For example, if you specify **cle** in this mode, **clean**, **nucleus**, and **circle** are rejected, but **foot** is deemed to match, because it does not contain **cle**.
- **matches**—This is the most generic mode, in which you can specify a full or partial expression that defines which nodes you are interested in.

Figure 3-67 *Advanced Filter Dialog*



By clicking one of the two radio buttons, **Match any conditions** or **Match all conditions**, you can request that any or all of the conditions are matched. In the first case, you can look for devices where, for example, the name contains **cisco** and the management IP address ends with **204**. When all conditions must be met, it is possible to look for devices that, for example, have a given name and platform.

Click **More** or **Fewer** to add more rows of conditions or remove existing rows of conditions.

By default, all matches are performed without regard for upper or lower case. However, in some cases it is beneficial to have a more exact matching that takes the case into account. To do so, select the **Match case** check box.

Step 3 Click **OK** to start the filtering process. Click **Cancel** to hide the dialog without any changes to the state of the filters.

The **Clear** button allows you to clear all conditions. Clicking **Clear** followed by **OK** effectively removes all filtering, restoring all nodes to their default brightness level. If filtering is active, the same can be achieved by clicking **Clear** in area (4) of the main window, as shown in [Figure 3-44 on page 3-42](#).

Searching

Searching can be conducted by using the menus or the tool bar. To perform a search, follow these steps:

Step 1 Select **Find** in the **Edit** menu


or

Click the **Find** icon in the main toolbar.

Both approaches bring up the same dialog box, as shown in [Figure 3-68](#).

Again, you can enter one or more conditions to locate the node.

Figure 3-68 Find Dialog Box



Step 2 Make the desired filtering selections. Match modes, case check box, and the radio button are used as described under [Advanced Filtering, page 3-61](#), as shown in [Figure 3-67](#).

Step 3 Click **OK** to start searching for the first node that matches the given criteria. If found, the node is highlighted and the view is shifted to make it appear in the currently viewed area of the main window.


Step 4 After the first search, press **F3** or click the **Find Again** button to repeat the search. If more than one node matches the condition the **Find Again** function highlights each one of them. If no nodes match the entered criteria, the **Object Not Found** dialog box appears.

Using Maps

You can associate a map with each view. Currently, the topology viewer only supports maps in the Environmental Systems Research Institute, Inc. (ESRI) shape format. The following sections describe how to load maps and selectively view map layers and data associated with each map.

The map features are accessed from the **Map** menu shown in Figure 3-69.

Figure 3-69 The Map Menu



The **Map** menu contains the following menu items:

- **Open Map...** Loads a map into the application
- **Clear Map** Clears the active map from the current view
- **View** Allows you to select which layers in the map should be displayed (for example, country, state, city).

Loading a map

You might want to set a background map showing the physical locations of the displayed devices. To load a map, follow these steps:


Step 1 In the menu bar, select **Map > Open Map....**

or

Press **Ctrl-M**

Providing the web map server is running and operational, the Load Map window appears, as shown in Figure 3-70.

Figure 3-70 Load Map Window



Step 2 Make your selections in the Load Map window.

The right-hand side of the window contains a small control panel, which allows you to select the projection in which a map is shown. A map projection is a projection that maps a sphere onto a plane. Typical projections are Mercator, Lambert, and Stereographic.

For more information on projections, consult the Map Projections section of Eric Weisstein's World of Mathematics at:

<http://mathworld.wolfram.com/topics/MapProjections.html>

For each projection, you can also select the region of the map to be shown. In most cases, the predefined values should be sufficient. The top level the file hierarchy should contain folders for all major regions, such as Europe, North America, Oceania, and so on.

If desired, make changes to the settings in the **Longitude Range** and **Latitude Range** fields.

Step 3 Navigate to the desired folder.

Each folder can contain either complete maps or folders for countries. Each map is clearly distinguished with the **Map** icon.


Step 4 Select a map file and click **Open** to load the map.

Selecting the map file and clicking the **Open** button starts loading it. Maps can consist of several components and thus a progress dialog is shown informing you which part of the map file is loaded.

Layers

Each map can contain several layers. For example most country maps have country, region, and city layers, as shown in [Figure 3-71](#).

Figure 3-71 Map Layers



After a map is loaded, the **View** submenu of the **Map** menu is automatically populated for you. A name of each available layer is shown together with the check box indicating visibility of the layer. If a given map shows too many details, you can turn off some or all layers by deselecting the corresponding check box(es). The same submenu can be used to restore visibility of layers.

If an incorrect map is loaded or the performance of the topology tool is unsatisfactory with the map loaded, you can clear the map entirely. To do this, select **Clear Map** from the **Map** menu. Maps are automatically cleared if another map is loaded.

Consequently if you want just to load another map, there is no need to clear the existing map. The act of loading a new map does this.

Map data


If map data files are successfully loaded with the map, the right field of the Status bar shows the longitude and latitude location of the cursor on the map. If map objects, such as cities, lakes, and so on, have data associated with them, their names are displayed after the longitude and latitude coordinates.

Node locations

After a map is successfully loaded, the view area is adjusted to fully accommodate it, as shown in Figure 3-72. If nodes shown on the window had longitude and latitude information associated with them, they are moved to locations on the map corresponding to their geographical location. If not, their positions remain unchanged.

However, you can manually move them to the desired location and save the positions for future reference. The next time the image of a given network is loaded, node positions are restored and the map file is loaded.

Figure 3-72 Physical View with a Map of Japan



Adding new maps

You might want to add your own maps to the selection of maps available to the topology application. This is done by placing a map file in the desired directory within the ISC installation. To make this example more accessible, assume that you want to add a map of Toowong, a suburb of Brisbane, the capital of Queensland. The first step to do so is to obtain maps from a map vendor. All maps must be in the ESRI shape file format (as explained at the web site: <http://www.esri.com>). In addition, a data file might accompany each shape file. Data files contain information about objects whose shapes are contained within the shape file. Let us assume that the vendor provided four files:

- toowong_city.shp
- toowong_city.dbf
- toowong_street.shp
- toowong_street.dbf

We must create a map file that informs the topology application about layers of the map. In this case we have two layers: a city and a street layer. The map file, say, Toowong.map, would thus have the following contents:

```
toowong_city
toowong_street
```

It lists all layers that create a map of Toowong. The order is important, as the first file forms the background layer, with other layers placed on top of the preceding layers.

Having obtained shape and data files and having written the map file, decide on its location. As mentioned, Toowong is a suburb of Brisbane, located in Queensland, Australia. All map files must be located in or under the **\$ISC_HOME/resources/webserver/tomcat/webapps/ipsc-maps/data** directory. Since by default this directory contains a directory called **Oceania** intended for all maps from that region, simply create a path **Australia/Queensland/Brisbane** under the directory **Oceania**. Next, place all five files in this location. After this is done, the map is automatically accessible to the topology viewer.

Devices

Every network element that ISC manages must be defined as a device in the system. An element is any device from which ISC can collect information. In most cases, devices are Cisco IOS routers that function as Provider Edge Routers (PEs) or Customer Edge Routers (CEs) in the MPLS VPN.



Note

To provision services with ISC, you must have IPv4 connectivity.

This section describes how to configure SSH, set up SNMP, manually enable an RTR responder, and create, edit, delete, and configure various types of supported devices. This section includes the following:

- [Configuring SSH, page 3-69](#)
- [Setting Up SNMP, page 3-70](#)
- [Manually Enabling RTR Responder on Cisco IOS Routers, page 3-72](#)
- [Accessing the Devices Window, page 3-72](#)
- [Creating a Device, page 3-74](#)

- [Editing a Device, page 3-92](#)
- [Deleting Devices, page 3-95](#)
- [Editing a Device Configuration, page 3-96](#)
- [E-mailing a Device's Owner, page 3-98](#)
- [Copying a Device, page 3-99](#)

Configuring SSH

ISC needs a mechanism to securely access and deploy configuration files on devices, which include routers and switches. And, to securely download a configlet and upload a configuration file from a device, SSH must be enabled.

The following sections describe how to configure SSH on a device.

Configuring SSH on Cisco IOS Routers

This Cisco IOS router configuration procedure assumes that the router's authentication database is stored locally on the router and not on a TACACS or RADIUS server.

The procedure for configuring SSH on a Cisco IOS router is as follows:.

	Command	Description
Step 1	Router# configure terminal	Enters global configuration mode.
Step 2	Router(config)# ip domain-name <i><domain_name></i>	Specifies the IP domain name.
Step 3	Router(config)# username <i><username></i> password <i><password></i>	Configures the user ID and password. Enter your ISC username and password. For example: username admin password iscpwd
Step 4	Router(config)# crypto key generate rsa	Generates keys for the SSH session.
Step 5	You will see the following prompt: Choose the size of the key modulus in the range of 360 to 2048 for your general purpose keys. How many bits in the modulus (nnn): Press Enter to accept the default number of bits.	Sets the number of bits.
Step 6	Router(config)# line vty 0 4	Enables SSH as part of the vty login transport.
Step 7	Router(config-line)# login local	The login local command indicates that the router stores the authentication information locally.
Step 8	Router(config-line)# transport input telnet ssh	Enables SSH transport.
Step 9	Router(config-line)# Ctrl+Z	Returns to Privileged Exec mode.
Step 10	Router# copy running startup	Saves the configuration changes to NVRAM.

Setting Up SNMP

To work with ISC, SNMP must be configured on each CPE device in the customer network. In ISC, SNMP is used to:

- collect from the Interface MIB
- provision and collect SLA data.

Two security models are available: SNMPv1/v2c and SNMPv3. [Table 3-5](#) identifies the combinations of security models and levels.

Table 3-5 *SNMP Security Models and Levels*

Model	Level	Authentication	Encryption	Description
v1/v2c	No Authentication/ No Encryption	Community String	No	Uses a community string match for authentication.
v3	No Authentication/ No Encryption	Username	No	Uses a username match for authentication.
v3	Authentication/ No Encryption	MD5 or SHA	No	Provides authentication based on the HMAC-MD5 or HMAC-SHA algorithms.
v3	Authentication/ Encryption	MD5 or SHA	DES	Provides authentication based on the HMAC-MD5 or HMAC-SHA algorithms, and provides DES 56-bit encryption in addition to authentication based on the CBC-DES (DES-56) standard.

SNMPv3 provides for both security models and security levels. A *security model* is an authentication strategy that is set up for a user and the group in which the user resides. A *security level* is the permitted level of security within a security model. A combination of a security model and a security level determines which security mechanism is employed when handling an SNMP packet.

The security features provided in SNMPv3 are as follows:

- Message integrity—Ensures that a packet has not been tampered with in-transit.
- Authentication—Determines the message is from a valid source.
- Encryption—Encoding the contents of a packet to prevent it from being read by an unauthorized source.

SNMPv3 objects have the following characteristics:

- Each user belongs to a group.
- The group defines the access policy for a set of users and determines the list of notifications its users can receive. The group also defines the security model and security level for its users.
- The access policy defines which SNMP objects can be accessed for reading, writing, or creation.

Setting Up SNMPv1/v2c on Cisco IOS Routers

To determine whether SNMP is enabled, and to set the SNMP community strings on a Cisco IOS router, perform the following steps for each router:

	Command	Description
Step 1	Router> enable Router> <enable_password>	Enters enable mode, and then enters the enable password.
Step 2	Router# show snmp	Check the output of the show snmp command to see whether the following statement is present: “SNMP agent not enabled.” If SNMP is not enabled, complete the steps in this procedure.
Step 3	Router# configure terminal	Enters global configuration mode.
Step 4	Router(config)# snmp-server community <userstring> RO	Sets the community read-only string.
Step 5	Router(config)# snmp-server community <userstring> RW	Sets the community read-write string.
Step 6	Router(config)# Ctrl+Z	Returns to Privileged Exec mode.
Step 7	Router# copy running startup	Saves the configuration changes to NVRAM.



Tip

The SNMP community strings defined in ISC for each target device must be identical to those configured on the device.

Setting SNMPv3 Parameters on Cisco IOS Routers

This section describes how to set the SNMPv3 parameters on Cisco IOS routers. SNMPv3 is only supported on IOS crypto images. For Authentication/Encryption, the IOS image must have DES56.



Tip

The SNMP users defined in ISC for each target device must be identical to those configured on the device.

To check the existing SNMP configuration, use these commands in the router terminal session:

- show snmp group
- show snmp user

To set the SNMPv3 server group and user parameters on a Cisco IOS router, perform the following steps.



Note

The group must be created first and then the user.

	Command	Description
Step 1	Router> enable Router> <i><enable_password></i>	Enters enable mode, then enter the enable password.
Step 2	Router# configure terminal	Enters global configuration mode.

	Command	Description
Step 3	Router(config)# snmp-server group [<i><groupname></i>] {v1 v2c v3 {auth noauth priv}}] [read <i><readview></i>] [write <i><writeview></i>] [notify <i><notifyview></i>] [access <i><access-list></i>]	The snmp-server group command configures a new SNMP group or a table that maps SNMP users to SNMP views. Each group belongs to a specific security level. Example: snmp-server group v3auth v3 auth read v1default write v1default
Step 4	Router(config)# snmp-server user <i><username></i> [<i><groupname></i>] remote <i><ip-address></i> [udp-port <i><port></i>] {v1 v2c v3 [encrypted] [auth {md5 sha} <i><auth-password></i>] [priv des56 <i><priv-password></i>]} [access <i><access-list></i>]	The snmp-server user command configures a new user to an SNMP group. Example: snmp-server user user1 v3auth v3 auth md5 user1Pass
Step 5	Router(config)# Ctrl+Z	Returns to Privileged Exec mode.
Step 6	Router# copy running startup	Saves the configuration changes to NVRAM.

Manually Enabling RTR Responder on Cisco IOS Routers



Note

SNMP must be configured on the router.

To manually enable an RTR Responder on a Cisco IOS router, execute the following steps:

	Command	Description
Step 1	Router> enable Router> <i><enable_password></i>	Enters enable mode, and then enters the enable password.
Step 2	Router# configure terminal	Enters the global configuration mode.
Step 3	Router(config)# rtr responder	Enables the SA responder on the target router of SA Agent operations.
Step 4	Router(config)# Ctrl+Z	Returns to Privileged Exec mode.
Step 5	Router# copy running startup	Saves the configuration changes to NVRAM.


Accessing the Devices Window

The Devices feature is used to create, edit, delete, and configure devices, and e-mail the device owner.

To access the Devices window, follow these steps:

- Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Devices** to access the Devices window shown in [Figure 3-73](#).

Figure 3-73 Devices List Window



The Devices window contains the following:

- **Device Name** Lists the fully qualified host and domain name of the device. You can sort the list of devices by device name.
- **Management IP Address** Lists the management IP address or the IE2100 address. You can sort the list of devices by this field.
- **Type** Lists the type of the device. Types include: Cisco IOS Device, CatOs Device, Terminal Server, and IE2100.
- **Parent Device Name**

In the Devices window, you can create, edit, delete, or configure devices or e-mail the device owner using the following buttons:

- **Create** Click to create new devices. Enabled only if no devices are selected.
- **Edit** Click to edit selected device (select device by clicking the corresponding box). Enabled only if a single device is selected.
- **Delete** Click to delete selected device (select device by clicking the corresponding box). Enabled only if one or more devices are selected.
- **Config** Click to change the selected device configuration (select device by clicking the corresponding box). Enabled only if a single device is selected.
- **E-mail** Click to send e-mail to the owner of selected device (select device by clicking the corresponding box). Enabled only if one or more devices are selected.
- **Copy**

Creating a Device

From the Create window, you can define different types of devices.


To create a device, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Devices**.

Step 2 Click the **Create** button.

The Create options window appears, as shown in [Figure 3-74](#).

Figure 3-74 Create Options Window



The **Create** options include the following:

- **Catalyst Switch** A Catalyst device running the Catalyst Operating System.
- **Cisco Device** Any router that runs the Cisco IOS. This includes Catalyst devices running Cisco IOS.
- **Terminal Server** A device that represents the workstation that can be used to provision edge routers.
- **IE2100** Any Cisco Intelligence Engine (IE) 2100 series network device.

Step 3 See the following sections for instructions on creating each type of device.

- [Creating a Catalyst Switch, page 3-75](#)
- [Creating a Cisco Device, page 3-80](#)
- [Creating a Terminal Server, page 3-86](#)
- [Creating a Cisco CNS IE2100, page 3-91](#)

Creating a Catalyst Switch

To create a Catalyst switch, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Devices**.
- Step 2** Click the **Create** button.
- Step 3** Select **Catalyst Switch**.

The Create Catalyst Device window appears, as shown in [Figure 3-75](#).

Figure 3-75 Create Catalyst Device Window

Create Catalyst Device

General

Device Host Name * :

Device Domain Name:

Description:

Collection Zone:

Management IP Address:

Interfaces:

Associated Groups

Operating System: ☒ Catalyst OS ☐ Cisco IOS

Login and Password Information

Login User:

Login Password:

Verify Login Password:

Enable User:

Enable Password:

Verify Enable Password:

Device and Configuration Access Information

Terminal Session Protocol:

Config Access Protocol:

OS:

SNMP Version:

SNMP v1v2c

Community String RO:

Community String RW:

Additional Properties:

Note: * - Required Field

149462

The General section of the Create Catalyst Device window contains the following fields:

- **Device Host Name** (required) Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field must match the name configured on the target router device. Limited to 256 characters.
- **Device Domain Name** (optional) Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. The name must match the domain name on the target router device.
- **Description** (optional) Limited to 80 characters. Can contain any pertinent information about the device such as the type of device, its location, or other information that might be helpful to service provider operators.
- **Collection Zone** (optional) Drop-down list of all collection zones within the ISC. Choices include: None and all collection zones within the ISC. Default: None.
- **Management IP Address** (optional) Valid IP address of the device that ISC uses to configure the target router device.
- **Interfaces** (optional) Click the **Edit** button to view, add, edit, and delete all interfaces associated with the device. See [Table 3-6](#) for a description of the Interfaces fields.

Table 3-6 Create Catalyst Device Interfaces Fields

Field	Description	Additional
Name	Name of this interface.	List can be sorted by this field. Limited to 80 characters.
Encapsulation	The Layer 2 Encapsulation for this device.	DEFAULT DOT1Q ETHERNET ISL FRAME_RELAY FRAME_RELAY_IETF HDLC PPP ATM AAL5SNAP AAL0 AAL5 AAL5MUX AAL5NLPID AAL2 ENCAP_QinQ GRE
IP Address	IP address associated with this interface.	

Table 3-6 Create Catalyst Device Interfaces Fields (continued)

Field	Description	Additional
Port Type		NONE ACCESS TRUNK ROUTED
VLAN ID	The VLAN ID to assign to this interface.	

- **Associated Groups** (optional) Click the **Edit** button to view, add, and remove all Device Group associations.
- **Operating System** (optional) Click the radio button for the operating system currently running on the CAT switch. Choices include: CatOs or IOS. Default: CatOs. When you choose the IOS operating system, VPNSM is available under the heading Catalyst Properties.

The Login and Password Information section of the Create Catalyst Device window contains the following fields:

- **Login User** (optional) Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Login Password** (optional) Displayed as stars (*). Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Login Password** (optional) Displayed as stars (*). Must match the Login Password field. Limited to 80 characters.
- **Enable User** (optional) Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Enable Password** (optional) Displayed as stars (*). Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Enable Password** (optional) Displayed as stars (*). Must match the Enable Password field. Limited to 80 characters.

The Device and Configuration Access Information section of the Create Catalyst Device window contains the following fields:

- **Terminal Session Protocol** (optional) Configures the method of communication between ISC and the device. Choices include: Telnet, Secure Shell (SSH), and CNS. In previous versions of ISC, this field was called the Transport field. Default: The default set in the DCPL properties.
- **Config Access Protocol** (optional) Administers the access protocol for config upload and download. Choices include: Terminal, TFTP, and FTP. Default: The default set in the DCPL properties.
- **SNMP Version** (optional) Configures the version of SNMP to use when communicating with the device. Choices include: SNMP v1/v2c and SNMP v3. Default: The default set in the DCPL properties.

The SNMP v1/v2c section of the Create Catalyst Device window contains the following fields:

- **Community String RO** (optional) SNMP Read-Only Community String. Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.
- **Community String RW** (optional) SNMP Read-Write Community String. Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.

Step 4 Enter the desired information for the Catalyst device you are creating.

Step 5 To access the Additional Properties section of the **Create Catalyst Device**, click **Show**.

The Additional Properties window appears, as shown in [Figure 3-76](#).

Figure 3-76 Catalyst Device Additional Properties Window

The SNMP v3 section of the Catalyst Device Properties window contains the following fields:

- **SNMP Security Level** (optional) Choices include: Default (*<default_set_in_DCPL>*), Authentication/No Encryption, and Authentication/Encryption. Default: Default (*<default_set_in_DCPL>*). Note: When you change the DCPL property, the *<default_set_in_DCPL>* variable changes.
- **Authentication User Name** (optional) User name configured on the specified device router. User must have permission to the object identification numbers (OIDs) specified in the security request (that is, write permission for a set request, and read permission for a get request). Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Limited to 80 characters.

- **Authentication Password** (optional) Displayed as stars (*). Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Authentication Password** (optional) Displayed as stars (*). Must match the Encryption Password field. Limited to 80 characters.
- **Authentication Algorithm** (optional) Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Choices include: None, MD5, and SHA. Default: None.
- **Encryption Password** (optional) Displayed as stars (*). In previous versions of ISC, this field was called Privacy Password. Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Limited to 80 characters.
- **Verify Encryption Password** (optional) Displayed as stars (*). Must match the Encryption Password field. Limited to 80 characters.
- **Encryption Algorithm** (optional) In previous versions of ISC, this field was called Privacy Protocol. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Choices include: None and DES 56. Default: None.

The Terminal Server and CNS Options section of the Catalyst Device Properties window contains the following fields:

- **Terminal Server** (optional) Choices include: None and the list of existing Terminal Server names. Default: None.
- **Port** (optional) Disabled until a Terminal Server is selected. Range: 0-65535. Default: 0.
- **Fully Managed** (optional) If the Fully Managed check box is selected, the device becomes a fully managed device. ISC performs additional management actions only for fully managed devices. These actions include e-mail notifications upon receipt of device configuration changes originated outside ISC and the scheduling of enforcement audit tasks upon detection of possible intrusion. Default: Not selected and therefore not selected.
- **Device State** (optional) Choices include: ACTIVE and INACTIVE. ACTIVE indicates that the router has been plugged on the network and can be part of ISC tasks such as collect config and provisioning. INACTIVE indicates the router has not been plugged-in. Default: ACTIVE.
- **CNS Identification** Required if the Device Event Identification field is set to CNS_ID. Only valid characters that Cisco IOS allows are alphanumeric characters and (.) (-) (_).
- **Device Event Identification** (optional) Indicates whether the CNS Identification field contains a HOST_NAME or CNS_ID. Default: HOST_NAME.
- **Most Recent CNS event** (optional) Choices include: None, CONNECT, and DISCONNECT. Changing from the default of None is not recommended. Note: The last connect or disconnect CNS TIBCO event received by ISC for each CNS-enabled IOS device is automatically recorded.
- **IE2100** (optional) Disabled unless the Device State field is INACTIVE or the Terminal Session Protocol field is CNS. A valid IE2100 must be selected if the Terminal Session Protocol is CNS. Choices include: None and the list of existing IE2100 names. Default: None.
- **CNS Software Version** (optional) Choices include: 1.3, 1.3.1, 1.3.2, 1.4, and 1.5. This is the release version of Cisco CNS Configuration Engine that manages the IOS device. Default: 1.4.
- **CNS Device Transport** (optional) Choices include: HTTP and HTTPS. This field determines what will be the transport mechanism used by ISC to create, delete, or edit devices in the IE2100 repository. If HTTPS is used, the Cisco CNS Configuration Engine must be running in secure mode. Default: HTTP.

The Device Platform Information section of the Catalyst Device Properties window contains the following fields:

- **Platform** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Software Version** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Image Name** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Serial Number** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Device Owner's Email Address** (optional) Used in the To: field when the Email button is selected from the device list. Limited to 80 characters and must be valid Email format.

Step 6 Enter any desired Additional Properties information for the Catalyst device you are creating.

Step 7 Click **Save**.

The Devices window reappears with the new Catalyst device listed.

Creating a Cisco Device

To create a Cisco device, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Devices**.

Step 2 Click the **Create** button.

Step 3 Select **Cisco Device**.

The Create Cisco Device window appears, as shown in [Figure 3-77](#).

Figure 3-77 Create Cisco Device Window

Create Cisco Device

General	
Device Host Name *	<input type="text"/>
Device Domain Name:	<input type="text"/>
Description:	<input type="text"/>
Collection Zone:	None ▾
Management IP Address:	<input type="text"/>
Interfaces:	<input type="button" value="Edit"/>
Associated Groups	<input type="button" value="Edit"/>
Login and Password Information	
Login User:	<input type="text"/>
Login Password:	<input type="password"/>
Verify Login Password:	<input type="password"/>
Enable User:	<input type="text"/>
Enable Password:	<input type="password"/>
Verify Enable Password:	<input type="password"/>
Device and Configuration Access Information	
Terminal Session Protocol:	Default (Telnet) ▾
Config Access Protocol:	Default (Terminal) ▾
OS:	IOS ▾
SNMP Version:	Default (SNMP v1/v2c) ▾
SNMP v1/v2c	
Community String RO:	<input type="text"/>
Community String RW:	<input type="text"/>
Additional Properties:	<input type="button" value="Show"/>
<input type="button" value="Save"/> <input type="button" value="Cancel"/>	

Note: * - Required Field

149136

The General section of the Create Cisco IOS Device window contains the following fields:

- **Device Host Name** Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Device Domain Name** (optional) Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. The name must match the domain name on the target router device.
- **Description** (optional) Limited to 80 characters. Can contain any pertinent information about the device such as the type of device, its location, or other information that might be helpful to service provider operators.
- **Collection Zone** (optional) Drop-down list of all collection zones within the ISC. Choices include: None and all collection zones within the ISC. Default: None.
- **Management IP Address** (optional) Valid IP address of the device that ISC uses to configure the target router device.
- **Interfaces** (optional) Click the Edit button to view, add, edit, and delete all interfaces associated with the device. See [Table 3-7](#) for a description of the Interface fields.

Table 3-7 Create Cisco Device Interface Fields

Field	Description	Additional
Name	Name of this interface.	List can be sorted by this field. Limited to 80 characters.
Encapsulation	The Layer 2 Encapsulation for this device.	DEFAULT DOT1Q ETHERNET ISL FRAME_RELAY FRAME_RELAY_IETF HDLC PPP ATM AAL5SNAP AAL0 AAL5 AAL5MUX AAL5NLPID AAL2 ENCAP_QinQ GRE
IP Address	IP address associated with this interface.	

- **Associated Groups** (optional) Click the **Edit** button to view, add, and remove all Device Group associations.

The Login and Password Information section of the Create Cisco IOS Device window contains the following fields:

- **Login User** (optional) Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Login Password** (optional) Displayed as stars (*). Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Login Password** (optional) Displayed as stars (*). Must match the Login Password field. Limited to 80 characters.
- **Enable User** (optional) Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Enable Password** (optional) Displayed as stars (*). Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Enable Password** (optional) Displayed as stars (*). Must match the Enable Password field. Limited to 80 characters.

The Device and Configuration Access Information section of the Create Cisco IOS Device window contains the following fields:

- **Terminal Session Protocol** (optional) Configures the method of communication between ISC and the device. Choices include: Telnet, Secure Shell (SSH), and CNS. In previous versions of ISC this
- **Config Access Protocol** (optional) Administers the access protocol for config upload and download. Choices include: Terminal, TFTP, and FTP. Default: The default set in the DCPL properties.
- **SNMP Version** (optional) Configures the version of SNMP to use when communicating with the device. Choices include: SNMP v1/v2c and SNMP v3. Default: The default set in the DCPL properties.

The SNMP v1/v2c section of the Create Cisco IOS Device window contains the following fields:

- **Community String RO** (optional) SNMP Read-Only Community String. Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.
- **Community String RW** (optional) SNMP Read-Write Community String. Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.

Step 4 Enter the desired information for the Cisco IOS device you are creating.

Step 5 To access the Additional Properties section of the **Create Cisco Device**, click **Show**.

The Additional Properties window appears, as shown in [Figure 3-78](#).

Figure 3-78 Cisco Device Properties Window

Additional Properties:		Hide
SNMP v3		
SNMP Security Level:	Default (No Authentication/No Encryption) ▾	
Authentication User Name:	<input type="text"/>	
Authentication Password:	<input type="text"/>	
Verify Authentication Password:	<input type="text"/>	
Authentication Algorithm:	None ▾	
Encryption Password:	<input type="text"/>	
Verify Encryption Password:	<input type="text"/>	
Encryption Algorithm:	None ▾	
Terminal Server and CNS Options		
Terminal Server:	None ▾	
Port:	<input type="text"/>	
Fully Managed:	<input type="checkbox"/>	
Device State:	ACTIVE ▾	
CNS Identification:	<input type="text"/>	
Device Event Identification:	CNS_ID ▾	
Most recent CNS event:	None ▾	
IE2100:	None ▾	
CNS Software Version:	1.4 ▾	
CNS Device Transport:	HTTP ▾	
Device Platform Information		
Platform:	<input type="text"/>	
Software Version:	<input type="text"/>	
Image Name:	<input type="text"/>	
Serial Number:	<input type="text"/>	
Device Owner's Email Address:	<input type="text"/>	
		Save Cancel
Note: * - Required Field		

149133

The SNMP v3 section of the Cisco IOS Device Properties window contains the following fields:

- **SNMP Security Level** (optional) Choices include: Default (<default_set_in_DCPL>), Authentication/No Encryption, and Authentication/Encryption. Default: Default (<default_set_in_DCPL>). Note: When you change the DCPL property, the <default_set_in_DCPL> variable changes.
- **Authentication User Name** (optional) User name configured on the specified device router. User must have permission to the object identification numbers (OIDs) specified in the security request (that is, write permission for a set request, and read permission for a get request). Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Limited to 80 characters.

- **Authentication Password** (optional) Displayed as stars (*). Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Authentication Password** (optional) Displayed as stars (*). Must match the Encryption Password field. Limited to 80 characters.
- **Authentication Algorithm** (optional) Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Choices include: None, MD5, and SHA. Default: None.
- **Encryption Password** (optional) Displayed as stars (*). In previous versions of ISC, this field was called Privacy Password. Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Limited to 80 characters.
- **Verify Encryption Password** (optional) Displayed as stars (*). Must match the Encryption Password field. Limited to 80 characters.
- **Encryption Algorithm** (optional) In previous versions of ISC, this field was called Privacy Protocol. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Choices include: None and DES 56. Default: None.

The Terminal Server and CNS Options section of the Cisco IOS Device Properties window contains the following fields:

- **Terminal Server** (optional) Choices include: None and the list of existing Terminal Server names. Default: None.
- **Port** (optional) Disabled until a Terminal Server is selected. Range: 0-65535. Default: 0.
- **Fully Managed** (optional) If the Fully Managed check box is selected, the device becomes a fully managed device. ISC performs additional management actions only for fully managed devices. These actions include e-mail notifications upon receipt of device configuration changes originated outside ISC and the scheduling of enforcement audit tasks upon detection of possible intrusion. Default: Not selected and therefore not selected.
- **Device State** (optional) Choices include: ACTIVE and INACTIVE. ACTIVE indicates that the router has been plugged on the network and can be part of ISC tasks such as collect config and provisioning. INACTIVE indicates the router has not been plugged-in. Default: ACTIVE.
- **CNS Identification** Required if the Device Event Identification field is set to CNS_ID. Only valid characters that Cisco IOS allows are alphanumeric characters and (.) (-) (_).
- **Device Event Identification** (optional) Indicates whether the CNS Identification field contains a HOST_NAME or CNS_ID. Default: HOST_NAME.
- **Most Recent CNS event** (optional) Choices include: None, CONNECT, and DISCONNECT. Changing from the default of None is not recommended. Note: The last connect or disconnect CNS TIBCO event received by ISC for each CNS-enabled IOS device is automatically recorded.
- **IE2100** (optional) Disabled unless the Device State field is INACTIVE or the Terminal Session Protocol field is CNS. A valid IE2100 must be selected if the Terminal Session Protocol is CNS. Choices include: None and the list of existing IE2100 names. Default: None.
- **CNS Software Version** (optional) Choices include: 1.3, 1.3.1, 1.3.2, 1.4, and 1.5. This is the release version of Cisco CNS Configuration Engine that manages the IOS device. Default: 1.4.
- **CNS Device Transport** (optional) Choices include: HTTP and HTTPS. This field determines what will be the transport mechanism used by ISC to create, delete, or edit devices in the IE2100 repository. If HTTPS is used, the Cisco CNS Configuration Engine must be running in secure mode. Default: HTTP.

The Device Platform Information section of the Cisco IOS Device Properties window contains the following fields:

- **Platform** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Software Version** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Image Name** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Serial Number** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Device Owner's Email Address** (optional) Used in the To: field when the Email button is selected from the device list. Limited to 80 characters and must be valid Email format.

Step 6 Enter any desired Additional Properties information for the Cisco IOS device you are creating.

Step 7 Click **Save**.

The Devices window reappears with the new Cisco IOS device listed.

Creating a Terminal Server

To create a Terminal Server device, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Devices**.

Step 2 Click the **Create** button.

Step 3 Select **Terminal Server**.

The Create Terminal Server window appears, as shown in [Figure 3-79](#).

Figure 3-79 Create Terminal Server Window

Create Terminal Server

General

Device Host Name*:

Device Domain Name:

Description:

Collection Zone:

Management IP Address:

Interfaces:

Associated Groups:

Login and Password Information

Login User:

Login Password:

Verify Login Password:

Enable User:

Enable Password:

Verify Enable Password:

Device and Configuration Access Information

Terminal Session Protocol:

Config Access Protocol:

OS:

SNMP Version:

SNMP v1/v2c

Community String RO:

Community String RW:

Additional Properties:

Note: * - Required Field

149153

The General section of the Create Terminal Server window contains the following fields:

- **Device Host Name** (required) Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field must match the name configured on the target router device. Limited to 256 characters.
- **Device Domain Name** (optional) Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. The name must match the domain name on the target router device.
- **Description** (optional) Limited to 80 characters. Can contain any pertinent information about the device such as the type of device, its location, or other information that might be helpful to service provider operators.
- **Collection Zone** (optional) Drop-down list of all collection zones within the ISC. Choices include: None and all collection zones within the ISC. Default: None.

- **Management IP Address** (optional) Valid IP address of the device that ISC uses to configure the target router device.
- **Interfaces** (optional) Click the **Edit** button to view, add, edit, and delete all interfaces associated with the device. See [Table 3-8](#) for a description of the Interfaces fields.

Table 3-8 Create Terminal Server Device Interfaces Fields

Field	Description	Additional
Name	Name of this interface.	List can be sorted by this field. Limited to 80 characters.
Encapsulation	The Layer 2 Encapsulation for this device.	DEFAULT DOT1Q ETHERNET ISL FRAME_RELAY FRAME_RELAY_IETF HDLC PPP ATM AAL5SNAP AAL0 AAL5 AAL5MUX AAL5NLPID AAL2 ENCAP_QinQ GRE
IP Address	IP address associated with this interface.	

- **Associated Groups** (optional) Click the **Edit** button to view, add, and remove all Device Group associations.

The Login and Password Information section of the Create Terminal Server window contains the following fields:

- **Login User** (optional) Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Login Password** (optional) Displayed as stars (*). Not required by ISC. However, collection and upload/download will not function without the Login User and Login Password as ISC will not be able to access the device. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Login Password** (optional) Displayed as stars (*). Must match the Login Password field. Limited to 80 characters.

- **Enable User** (optional) Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Enable Password** (optional) Displayed as stars (*). Not required by ISC. However, collection and upload/download only function if the Login User has sufficient privileges to configure the router in EXEC mode. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Enable Password** (optional) Displayed as stars (*). Must match the Enable Password field. Limited to 80 characters.

The Device and Configuration Access Information section of the Create Terminal Server window contains the following fields:

- **Terminal Session Protocol** (optional) Configures the method of communication between ISC and the device. Choices include: Telnet, Secure Shell (SSH), CNS, and RSH. In previous versions of ISC, this field was called the Transport field. Default: The default set in the DCPL properties.
- **Config Access Protocol** (optional) Administers the access protocol for config upload and download. Choices include: Terminal, TFTP, FTP, and RCP. Default: The default set in the DCPL properties.
- **SNMP Version** (optional) Configures the version of SNMP to use when communicating with the device. Choices include: SNMP v1/v2c and SNMP v3. Default: The default set in the DCPL properties.

The SNMP v1/v2c section of the Create Terminal Server window contains the following fields:

- **Community String RO** (optional) SNMP Read-Only Community String. Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.
- **Community String RW** (optional) SNMP Read-Write Community String. Many tasks use SNMP to access the device. This field must match what is configured on the target router device. Limited to 80 characters.

Step 4 Enter the desired information for the Terminal Server you are creating.

Step 5 To access the Additional Properties section of the **Create Terminal Server**, click **Show**.

The Additional Properties window appears, as shown in [Figure 3-80](#).

Figure 3-80 Terminal Server Device Properties Window

The SNMP v3 section of the Terminal Server Device Properties window contains the following fields:

- **SNMP Security Level** (optional) Choices include: Default (<default_set_in_DCPL>), Authentication/No Encryption, and Authentication/Encryption. Default: Default (<default_set_in_DCPL>). Note: When you change the DCPL property, the <default_set_in_DCPL> variable changes.
- **Authentication User Name** (optional) User name configured on the specified device router. User must have permission to the object identification numbers (OIDs) specified in the security request (that is, write permission for a set request, and read permission for a get request). Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Limited to 80 characters.
- **Authentication Password** (optional) Displayed as stars (*). Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Should match what is configured on the target router device. Limited to 80 characters.
- **Verify Authentication Password** (optional) Displayed as stars (*). Must match the Encryption Password field. Limited to 80 characters.
- **Authentication Algorithm** (optional) Should be provisioned if the SNMP Security Level is Authentication/No Encryption or Authentication/Encryption. Choices include: None, MD5, and SHA. Default: None.
- **Encryption Password** (optional) Displayed as stars (*). In previous versions of ISC, this field was called Privacy Password. Should match what is configured on the target router device. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Limited to 80 characters.

- **Verify Encryption Password** (optional) Displayed as stars (*). Must match the Encryption Password field. Limited to 80 characters.
- **Encryption Algorithm** (optional) In previous versions of ISC, this field was called Privacy Protocol. Should be provisioned if the SNMP Security Level is Authentication/Encryption. Choices include: None and DES 56. Default: None.

The Device Platform Information section of the Terminal Server Device Properties window contains the following fields:

- **Platform** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Software Version** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Image Name** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Serial Number** (optional) Should match what is configured on the target router device. Limited to 80 characters.
- **Device Owner's Email Address** (optional) Used in the To: field when the Email button is selected from the device list. Limited to 80 characters and must be valid Email format.

Step 6 Enter any desired Additional Properties information for the Terminal Server device you are creating.

Step 7 Click **Save**.

The Devices window reappears with the new Terminal Server device listed.

Creating a Cisco CNS IE2100



Note

To use the Cisco CNS IE2100 functionality on ISC, you must first set up the Cisco CNS IE2100 appliance and the ISC workstation as explained in Appendix B, “Setting Up Cisco CNS IE2100 Appliances with ISC” in *Cisco IP Solution Center Installation Guide*. You must also create a Cisco IOS device to communicate with the Cisco CNS IE2100 appliance. See Appendix A, “Setting Up Oracle for ISC,” in *Cisco IP Solution Center Installation Guide*.

To create a Cisco CNS IE2100 appliance, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Devices**.

Step 2 Click the **Create** button.

Step 3 Select **IE2100**.

The Create IE2100 Device window appears, as shown in [Figure 3-81](#).

Figure 3-81 Create IE2100 Device Window

The screenshot shows a window titled 'Create IE2100 Device Window' with a 'General' tab. It contains four text input fields: 'Device Host Name *', 'Device Domain Name', 'Description', and 'IP Address'. The 'Device Host Name' field has a small asterisk next to it. At the bottom right are 'Save' and 'Cancel' buttons. At the bottom left, a note reads 'Note: * - Required Field'. A vertical text '95322' is on the right side of the window.

The General section of the Create IE2100 Device window contains the following fields:

- **Device Host Name** (required) Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field must match the name configured on the target router device. Limited to 256 characters.
- **Device Domain Name** (optional) Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. The name must match the domain name on the target router device.
- **Description** (optional) Limited to 80 characters. Can contain any pertinent information about the device such as the type of device, its location, or other information that might be helpful to service provider operators.
- **IP Address** (optional) Valid IP address of the Cisco CNS IE2100 device that ISC uses to configure the target router device.

Step 4 Enter the desired information for the Cisco CNS IE2100 device you are creating.

Step 5 Click **Save**.

The Devices window reappears with the new Cisco CNS IE2100 device listed.

Editing a Device

From the Edit window, you can modify the fields that have been specified for a particular device.

To access the Edit window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Devices** to access the Devices window shown in [Figure 3-82](#).

Figure 3-82 Devices List Window

IP Solution Center

Home | Shortcuts | Account | Index | Help | About | Logout

Service Inventory | Service Design | Monitoring | Diagnostics | Administration

User: admin

Inventory and Connection Manager | Discovery | Device Console

You Are Here: Service Inventory > Inventory and Connection Manager > Devices Customer: None

Selection

- Service Requests
- Traffic Engineering Management
- Inventory Manager
- Topology Tool
- Devices**
 - Device Groups
 - Customers
 - Customer Sites
 - CPE Devices
 - Providers
 - Provider Regions
 - PE Devices
 - Access Domains
 - Resource Pools
 - CE Routing Communities
 - VPNs
 - AAA Servers
 - Named Physical Circuits
 - NPC Rings

Devices

Show Devices with Device Name matching Find

Showing 1 - 8 of 8 records

#		Device Name	Management IP Address	Type	Parent Device Name
1.	<input type="checkbox"/>	pe1		Cisco IOS Device	
2.	<input type="checkbox"/>	pe3		Cisco IOS Device	
3.	<input type="checkbox"/>	sw2		Cisco IOS Device	
4.	<input type="checkbox"/>	sw3		Cisco IOS Device	
5.	<input type="checkbox"/>	sw4		Cisco IOS Device	
6.	<input type="checkbox"/>	ce3		Cisco IOS Device	
7.	<input type="checkbox"/>	ce8		Cisco IOS Device	
8.	<input type="checkbox"/>	ce13		Cisco IOS Device	

Rows per page: 10 Go to page: 1 of 1 Go

Create Edit Delete Config E-mail Copy

Step 2 Select a single device to edit by selecting the box to the left of the Device Name. You can also select a device to edit by clicking on the hyperlink of the device name.

Step 3 Click the **Edit** button. This button is only enabled if a device is selected.

The Edit window appropriate to the type of device selected appears. For example, if you selected a Cisco IOS device the Edit Cisco IOS Device window appears, as shown in [Figure 3-83](#).

Figure 3-83 *Editing a Device Window*

Edit Cisco Device

General

Device Host Name * :

Device Domain Name:

Description:

Collection Zone:

None

Management IP Address:

Interfaces:

192.168.30.3, 192.168.30.4

Edit

Associated Groups

Edit

Login and Password Information

Login User:

Login Password:

Verify Login Password:

Enable User:

Enable Password:

Verify Enable Password:

Device and Configuration Access Information

Terminal Session Protocol:

Default (Telnet)

Config Access Protocol:

Default (Terminal)

OS:

IOS

SNMP Version:

Default (SNMP v1/v2c)

SNMP v1/v2c

Community String RO:

Community String RW:

Additional Properties:

Show

Save

Cancel

Note: * - Required Field

149144

Step 4 Enter the changes you want to make to the selected device.

Step 5 Click **Save**.

The changes are saved and the Devices window reappears.


Deleting Devices

From the Delete window, you can remove selected devices from the database.

To access the Delete window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Devices** to access the Devices window shown in [Figure 3-84](#).

Figure 3-84 *Devices List Window*




- Step 2** Select one or more devices to delete by selecting the check box(es) to the left of the Device Name(s).

- Step 3** Click the **Delete** button. This button is only enabled if one or more devices are selected.

The Confirm Delete window appears, as shown in [Figure 3-85](#).

Figure 3-85 *Confirm Delete Window*



- Step 4** Click the **Delete** button to confirm that you want to delete the device(s) listed.
The Devices window reappears with the specified device(s) deleted.

Editing a Device Configuration

From the Config window, you can edit the configuration for a specified device.
To access the Config window, follow these steps:


- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Devices** to access the Devices window shown in [Figure 3-86](#).

Figure 3-86 *Devices List Window*

The screenshot shows the Cisco IP Solution Center interface. The top navigation bar includes links for Home, Shortcuts, Account, Index, Help, About, and Logout. The user is logged in as 'admin'. The main navigation pane on the left shows a tree structure with 'Devices' selected. The main content area is titled 'Devices' and displays a table of 8 devices. The table has columns for #, Device Name, Management IP Address, Type, and Parent Device Name. The devices listed are pe1, pe3, sw2, sw3, sw4, ce3, ce8, and ce13, all of which are Cisco IOS Devices. Below the table, there are controls for 'Rows per page' (set to 10) and 'Go to page' (set to 1 of 1). At the bottom, there are buttons for 'Create', 'Edit', 'Delete', 'Config', 'E-mail', and 'Copy'.


#	Device Name	Management IP Address	Type	Parent Device Name
1.	pe1		Cisco IOS Device	
2.	pe3		Cisco IOS Device	
3.	sw2		Cisco IOS Device	
4.	sw3		Cisco IOS Device	
5.	sw4		Cisco IOS Device	
6.	ce3		Cisco IOS Device	
7.	ce8		Cisco IOS Device	
8.	ce13		Cisco IOS Device	

- Step 2** Select a single device to modify by selecting the check box to the left of the Device Name.
Step 3 Click the **Config** button.
The Device Configurations window for the selected device appears, as shown in [Figure 3-87](#).

Figure 3-87 Device Configurations Window

- Step 4** Select the box to the left of the Date for the configuration that you want to modify and click the **Edit** button. This button is only enabled if a device is selected.

The Device Configuration window for the selected device appears, as shown in [Figure 3-88](#).

Figure 3-88 Device Configuration Window

- Step 5** Enter the changes you want to make to the selected device configuration.

- Step 6** Click **Save**.

The changes are saved and the Device Configurations window reappears.

- Step 7** Click **OK** to return to the Devices window.

E-mailing a Device's Owner

From the E-mail window, you can send a device report via e-mail to the owners of specified devices.

To access the E-mail window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Devices** to access the Devices window shown in [Figure 3-89](#).

Figure 3-89 *Devices List Window*

The screenshot shows the Cisco IP Solution Center interface. The top navigation bar includes 'Service Inventory', 'Service Design', 'Monitoring', 'Diagnostics', and 'Administration'. The 'Inventory and Connection Manager' section is active, showing a breadcrumb trail: 'You Are Here: Service Inventory > Inventory and Connection Manager > Devices'. The left sidebar contains a 'Selection' menu with various options, including 'Devices'. The main content area, titled 'Devices', displays a table of 8 devices. The table has columns for '#', 'Device Name', 'Management IP Address', 'Type', and 'Parent Device Name'. The devices listed are pe1, pe3, sw2, sw3, sw4, ce3, ce8, and ce13, all identified as 'Cisco IOS Device'. Below the table, there is a 'Rows per page' dropdown set to 10, a 'Go to page' field set to 1 of 1, and a row of action buttons: 'Create', 'Edit', 'Delete', 'Config', 'E-mail', and 'Copy'. The 'E-mail' button is highlighted, indicating it is the active or selected action.

#	Device Name	Management IP Address	Type	Parent Device Name
1.	pe1		Cisco IOS Device	
2.	pe3		Cisco IOS Device	
3.	sw2		Cisco IOS Device	
4.	sw3		Cisco IOS Device	
5.	sw4		Cisco IOS Device	
6.	ce3		Cisco IOS Device	
7.	ce8		Cisco IOS Device	
8.	ce13		Cisco IOS Device	

- Step 2** Select the devices for which you want to send a device report by selecting the check box(es) to the left of the Device Name(s).

- Step 3** Click the **E-mail** button. This button is only enabled if one or more devices are selected.

The Send Mail to Device Owners window appears, as shown in [Figure 3-90](#).

Figure 3-90 *Send Mail to Device Owners Window*

Send Mail to Device owners

Please separate E-mail addresses using comma.

To:

CC:

Subject: Device Report

Message:

93789

Step 4 Compose the e-mail that you want to send to the selected device owners.

Step 5 Click **Send**.


The e-mail is sent and the Devices window reappears.

Copying a Device

From the Copy window, you receive a copy of the chosen device and can name it and change values.

To access the Copy window, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Devices** to access the Devices window shown in [Figure 3-91](#).

Figure 3-91 **Devices List Window**

Step 2 Select a single device to copy by selecting the check box to the left of the Device Name.

Step 3 Click the **Copy** button. This button is only enabled if a device is selected.

A window appropriate to the type of device selected to copy appears. You receive an exact copy of the selected device but the Name, Management IP Address, all Interfaces, and VPNSM blades for a Catalyst Switch running Cisco IOS are blanked out and you must fill in the required information and save this new device. See the [“Creating a Device”](#) section on page 3-74 for specifics.

Device Groups

Every network element that ISC manages must be defined as a device in the system. After you have defined your network elements as devices, you can organize the devices into groups for collection and management purposes.

This section describes how to create, edit, and delete device groups and e-mail device group owners. This section includes the following:

- [Accessing the Device Groups Window, page 3-101](#)
- [Creating a Device Group, page 3-101](#)
- [Editing a Device Group, page 3-104](#)
- [Deleting Device Groups, page 3-104](#)
- [E-mailing a Device Group, page 3-105](#)

Accessing the Device Groups Window

The Device Groups feature is used to create, edit, and delete device groups and e-mail device group owners.

To access the Device Groups window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Device Groups** to access the Device Groups window shown in [Figure 3-92](#).

Figure 3-92 Device Groups Window

The screenshot shows the 'Device Groups' window. At the top, there is a search bar with the text 'Show Device Groups with' followed by a dropdown menu set to 'Device Group Name', the word 'matching', and a text input field with an asterisk. A 'Find' button is to the right. Below the search bar, it says 'Showing 1-4 of 4 records'. The main area contains a table with two columns: '# Device Group Name' and 'Description'. The table has four rows, each with a checkbox and a device group name: 1. group1, 2. Device Group 1, 3. Device Group B, and 4. DeviceC. Below the table, there is a 'Rows per page' dropdown set to '10'. At the bottom right, there are four buttons: 'Create', 'Edit', 'Delete', and 'Email'.

The Device Groups window contains the following:

- **Device Group Name** Lists the name of the device group. You can sort the list by device group name.
- **Description** Lists the description of the device group.

From the Device Groups window, you can create, edit, or delete device groups or e-mail device group owners using the following buttons:

- **Create** Click to create new device groups. Enabled only if no device group is selected.
- **Edit** Click to edit a selected device group (select device group by clicking the corresponding box). Enabled only if a single device group is selected.
- **Delete** Click to delete selected device group(s) (select device group by clicking the corresponding box). Enabled only if one or more device groups are selected.
- **E-mail** Click to send e-mail to the owner of a selected device group (select device group by clicking the corresponding box). Enabled only if one or more device groups are selected.

Creating a Device Group

From the Create Device Group window, you can create different device groups.

To create a device group, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Device Groups**.

Step 2 Click the **Create** button.

The Create Device Group window appears, as shown in [Figure 3-93](#).

Figure 3-93 Create Device Group Window

Create Device Group

Name *

Description:

Devices:

#	Name	Description
Rows per page: 10 <input type="button" value="Go to page: 1 of 1"/> <input type="button" value="Go"/>		

Note: * - Required Field

117443

The Create Device Group window contains the following fields:

- **Name** (required) Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. Limited to 80 characters.
- **Description** (optional) Any pertinent information about the device group that could be helpful to service provider operators. Limited to 512 characters.

Step 3 Enter the name and the description of the Device Group that you are creating.

Step 4 Click **Edit**.

The Select Group Members window appears, as shown in [Figure 3-94](#).

Figure 3-94 **Select Group Members Window**

Select Group Members

Members of the Device Group <>>

Show with matching

Showing 1-10 of 26 records

#	<input type="checkbox"/>	Name	Type
1.	<input type="checkbox"/>	ipsec-cpe-london.cisco.com	Cisco IOS Device
2.	<input type="checkbox"/>	ipsec-cpe-paris.cisco.com	Cisco IOS Device
3.	<input type="checkbox"/>	ence11	Cisco IOS Device
4.	<input type="checkbox"/>	ence132	Cisco IOS Device
5.	<input type="checkbox"/>	ence21	Cisco IOS Device
6.	<input type="checkbox"/>	ence51	Cisco IOS Device
7.	<input type="checkbox"/>	ence61	Cisco IOS Device
8.	<input type="checkbox"/>	ipsec-cpe-london	Cisco IOS Device
9.	<input type="checkbox"/>	ipsec-cpe-ny	Cisco IOS Device
10.	<input type="checkbox"/>	barnes.cisco.com	Cisco IOS Device

Rows per page: Page 1 of 3 | 2 | 3 | Go to page

Step 5 Select the devices that you want to be group members by selecting the check box to the left of the device name.

Step 6 Click **OK**.

The Create Device Group window appears listing the selected devices, as shown in [Figure 3-95](#).

Figure 3-95 **Create Device Group Window**

Create Device Group

Name:

Description:

Devices:

#	Name	Description
1.	a2100	
2.	ats-18.cisco.com	

Rows per page: Go to page: of 1

Note: * - Required Field

Step 7 Click **Save**.

The Device Groups window reappears with the new device group listed.

Editing a Device Group

From the Edit Device Group window, you can modify the fields that have been specified for a particular device group.

To access the Edit Device Group window, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Device Groups**.

Step 2 Select a single device group to modify by selecting the check box to the left of the Device Group Name.

Step 3 Click the **Edit** button. This button is only enabled if a device group is selected.

The Edit Device Group window appears, as shown in [Figure 3-96](#).

Figure 3-96 Edit Device Group Window

Edit Device Group

Name : group2

Description:

Devices:

#	Name	Description
Rows per page: 10 Go to page: 1 of 1 Go		

Save Cancel

Note: * - Required Field

117445

Step 4 Enter the changes you want to make to the selected device group.

Step 5 Click **Save**.

The changes are saved and the Device Groups window reappears.

Deleting Device Groups

From the Delete window, you can remove selected device groups from the database.

To access the Delete window, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Device Groups**.

- Step 2** Select one or more device groups to delete by selecting the check box(es) to the left of the Device Group Names.
- Step 3** Click the **Delete** button. This button is only enabled if one or more device groups are selected. The Confirm Delete window appears, as shown in [Figure 3-97](#).

Figure 3-97 Confirm Delete Window

The screenshot shows a window titled "Confirm Delete". Inside, there is a table with the following data:

#	Name	Description	Associated Devices
1.	San Jose	Devices located in San Jose.	ence51, ence61

Below the table, it says "Showing 1-1 of 1 records". There is a "Rows per page:" dropdown menu set to "10". At the bottom right, there are two buttons: "Delete" and "Cancel".

- Step 4** Click the **Delete** button to confirm that you want to delete the device group(s) listed. The Device Groups window reappears with the specified device group(s) deleted.

E-mailing a Device Group

From the E-mail window, you can send a device report via e-mail to the owners of specified device groups.

To access the E-mail window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Device Groups**.
- Step 2** Select the device groups for which you want to send a device report by selecting the check box to the left of the Device Group Name.
- Step 3** Click the **E-mail** button. This button is only enabled if one or more device groups are selected. The Send Mail to Device owners of selected groups window appears, as shown in [Figure 3-98](#).

Figure 3-98 *Send Mail to Device Owners of Selected Groups Window*

Step 4 Compose the e-mail that you want to send to the selected device group owners.

Step 5 Click **Send**.

The e-mail is sent and the Device Groups window reappears.

Customers

A customer site is a set of IP systems with mutual IP connectivity between them without the use of a VPN. Each customer site belongs to exactly one customer. A customer site can contain one or more (for load balancing) edge device routers. This section describes how to create, edit, and delete customers. This section includes the following:

- [Accessing the Customers Window, page 3-106](#)
- [Creating a Customer, page 3-107](#)
- [Editing a Customer, page 3-108](#)
- [Deleting Customers, page 3-109](#)
- [Creating Customer Sites, page 3-110](#)
- [CPE Devices, page 3-111](#)

Accessing the Customers Window

The Customers feature is used to create, edit, and delete customers.

To access the Customers window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Customers** to access the Customers window shown in [Figure 3-99](#).

Figure 3-99 Customers Window

The screenshot shows the 'Customers' window. At the top, there is a search bar with the text 'Show Customers with Customer Name matching' followed by an asterisk and a text input field. To the right of the input field is a 'Find' button. Below the search bar, it says 'Showing 1-3 of 3 records'. The main area contains a table with three columns: '#', a checkbox, and 'Customer Name'. The table has three rows of data: 1. [checkbox] Customer01, 2. [checkbox] Customer1, and 3. [checkbox] Customer2. Below the table, there is a 'Rows per page:' label with a dropdown menu set to '10'. At the bottom right, there are three buttons: 'Create', 'Edit', and 'Delete'. A vertical text '95238' is visible on the right side of the window.

The Customers window contains the following:

- **Customer Name** Lists the names of customers. You can sort the list by customer name.

From the Customers window, you can create, edit, or delete customers using the following buttons:

- **Create** Click to create new customers.
- **Edit** Click to edit selected customer (select by clicking the corresponding box). Enabled only if a single customer is selected.
- **Delete** Click to delete selected customer (select customer by clicking the corresponding box). Enabled only if one or more customers are selected.

Creating a Customer

From the Create Customer window, you can create different customers.

To create a customer, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Customers**.

- Step 2** Click the **Create** button.

The Create Customer window appears, as shown in [Figure 3-100](#).

Figure 3-100 Create Customer Window

The Create Customer window contains the following fields:

- **Name** (required) Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters.
- **Customer Abbreviation** This field is used only for L2VPN and L2TPv3 Frame Relay service requests. The entry in this field is used to construct a connect name. When this field is left blank, DLCI switching is the transport mode used. Limited to 10 characters.
- **Customer Information** (optional) Any pertinent information about the customer that could be helpful to service provider operators. Limited to 5256 characters.
- **Site of Origin Enabled** (optional) This check box appears only when you have MPLS permissions. Select this check box to enable the site of origin.

Step 3 Enter the name and information for the Customer that you are creating. Select the **Site of Origin Enabled** check box if you want this enabled.

Step 4 Click **Save**.

The Customers window reappears with the new customer listed.

Editing a Customer

From the Edit Customer window, you can modify the fields that have been specified for a particular customer.

To access the Edit Customer window, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Customers**.

Step 2 Select a single customer to modify by selecting the check box to the left of the Customer Name.

Step 3 Click the **Edit** button. This button is only enabled if a customer is selected.

The Edit Customer window appears, as shown in [Figure 3-101](#).

Figure 3-101 *Edit Customer Window*

Edit Customer

Name * : Customer1

Customer Abbreviation: CUST1

Contact Information:

Enable Site of Origin: ☐

Save Cancel

Note: * - Required Field

129012

Step 4 Enter the changes you want to make to the selected customer.

Step 5 Click **Save**.

The changes are saved and the Customers window reappears.

Deleting Customers

From the Delete window, you can remove selected customers from the database.


To access the Delete window, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Customers**.

Step 2 Select one or more customers to delete by selecting the check box to the left of the Customer Name.

Step 3 Click the **Delete** button. This button is only enabled if one or more customers are selected.

The Confirm Delete window appears, as shown in [Figure 3-102](#).

Figure 3-102 Confirm Delete Window


Delete Customer

Confirm Delete

Showing 1-1 of 1 records

#	Name
1.	Customer2

Rows per page: 10


95241

- Step 4** Click the **Delete** button to confirm that you want to delete the customer(s) listed. The Customers window reappears with the specified customer(s) deleted.

Creating Customer Sites

To access the Customer Sites window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager**.
- Step 2** Click on **Customer Sites** listed in the Inventory and Connection Manager tree in the left column as shown in [Figure 3-103](#). The Customer Sites window appears.

Figure 3-103 Customer Sites Window


Cisco Systems IP Solution Center

Home | Shortcuts | Account | Index | Help | About | Logout

User: admin

Service Inventory | Service Design | Monitoring | Diagnostics | Administration

Inventory and Connection Manager | Discovery | Device Console

You Are Here: Service Inventory > Inventory and Connection Manager > Customers > Customer Sites Customer: None

Customer Sites

Show Sites with Site Name matching * Find

Showing 1 - 1 of 1 record

#	Site Name	Customer Name
1.	east	Customer1

Rows per page: 10

Go to page: 1 of 1

149140

The Customer Sites window contains the following:

- **Site Name** Lists the names of sites. The first character must be a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limit: 80 characters. You can sort the list by site name.
- **Customer Name** Lists the names of customer. The first character must be a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limit: 80 characters. You can sort the list by customer name.

From the Customer Sites window, you can create, edit, or delete customer sites using the following buttons:

- **Create** Click to create new customer sites. Enabled only if no customer site is selected.
 - **Edit** Click to edit selected customer sites (select by clicking the corresponding box). Enabled only if a single customer site is selected.
 - **Delete** Click to delete selected customer site(s) (select by clicking the corresponding box). Enabled only if one or more customer sites are selected.
-


CPE Devices

The CPE feature provides a list of CPEs that have been associated with a site through the CPE editor or Inventory Manager. To access the CPE Devices window, follow these steps:

-
- Step 1** Navigate **Service Inventory > Inventory and Connection Manager**.
- Step 2** Click on **CPE Devices** listed in the Inventory and Connection Manager tree in the left column, as shown in [Figure 3-104](#).

The CPE Devices window appears.

Figure 3-104 CPE Devices Window



The CPE Devices window contains the following:

- **Device Name** Lists the names of devices. The first character must be a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limit: 80 characters. You can sort the list by device name.
- **Customer Name** Lists the names of customer. The first character must be a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limit: 80 characters. You can sort the list by customer name.
- **Site Name** Lists the names of sites. The first character must be a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limit: 80 characters. You can sort the list by site name.
- **Management Type** When associating a CE with a customer site, you can select Managed or Unmanaged. Other choices are available (see below), but they should not be confused with this primary choice.
 - **Managed**—A managed CE can be provisioned directly by the provider using ISC. The CE must be reachable from an ISC server.
 - **Unmanaged** —An unmanaged CE cannot be provisioned directly by the provider. If Unmanaged is selected, the provider can use ISC to generate a configuration, and then send the configuration to the customer for placement on the CE.
 - **Managed - Management LAN** —A managed Management LAN or Management CE (MCE) is configured like a managed CE router, but it resides in the provider space. Normally, an MCE acts as the network operations center (NOC) gateway router.
 - **Unmanaged - Management LAN** —An unmanaged Management LAN or MCE is configured like an unmanaged CE router, but it resides in the provider space. Normally, an MCE acts as the network operations center (NOC) gateway router.
 - **Directly Connected** —In most cases, the CE is connected to a PE router. In this case, the CE is connected to a workstation or other device.

- Directly Connected Management Host —In most cases, the CE is connected to a PE router. In this case, the CE is connected to a workstation or other device, on which ISC resides.
- Multi-VRF —A multi-VRF CE (MVRFCE) is owned by the customer, but resides in the provider space. It is used to off load traffic from the PE.
- Unmanaged Multi-VRF—An unmanaged multi-VRF CE is provisioned like an unmanaged CE (configurations are not uploaded or downloaded to the device by the provider). It is owned by the customer and resides in the provider space.

Create CPE Device

Click **Create** to create new CPE devices. Enabled only if no customer site is selected. The resulting window is shown in [Figure 3-105](#), “Create CPE Device Window.”

Figure 3-105 Create CPE Device Window

Create CPE Device

Device Name *		Select
Site Name *		Select
Management Type:	Managed	

Save Cancel

Note: * - Required Field

116250

Edit CPE Device

Click **Edit** to edit a single CPE device selected in [Figure 3-104](#). The result is a window as shown in the example in [Figure 3-106](#), “Edit CPE Device Window.”

Figure 3-106 Edit CPE Device Window

Device Name:

ence51

Site Name:

Site-ence51

Customer Name:

Customer1

Management Type:

Managed

Pre-shared Keys:

Edit

IPsec High Availability Options:

☒ None
 ☐ Normal Failover
 ☐ Stateful Failover

IPsec Public IP Address:

IP Address Ranges

10.5.5.0/30, 192.168.129.136/30

Edit

Show Interfaces with

Name

Matching

Find

Showing 1 - 6 of 6 records

#	Interface Name	IP Address	IP Address Type	Encapsulation	Description	IPsec	Firewall	NAT	QoS Candidate
1.	Ethernet0	192.168.129.137/30	STATIC	UNKNOWN	Link to ensu3 (192.168.129.138) ! DON'T MODIFY or REMOVE !	None	None	Inside	None
2.	Ethernet1	10.5.5.1/30	STATIC	UNKNOWN	GRE Tunnel Unnumbered Interface ! DON'T MODIFY or REMOVE !	None	Inside	Outside	None
3.	FastEthernet0		STATIC	UNKNOWN		None	Outside	None	None
4.	Loopback0	192.168.115.81/32	STATIC	UNKNOWN	DNS entry for ence51 ! DON'T MODIFY or REMOVE !	None	None	None	None
5.	Loopback1	11.11.11.1/32	STATIC	UNKNOWN	IPSec Secured Tunnel Endpoint ! DON'T MODIFY or REMOVE !	None	None	None	None
6.	Loopback2	12.12.12.1/32	STATIC	UNKNOWN	IPSec Secured Tunnel Endpoint ! DON'T MODIFY or REMOVE !	None	None	None	None

Rows per page:

All

Go to page:

1

of 1

Go

Save

Cancel

116251

Delete CPE Device

Click to delete selected CPE device(s) (select by clicking the corresponding box). Enabled only if one or more CPE devices are selected.

Providers

This section describes how to create and manage providers. This section includes the following:

- [Accessing the Providers Window, page 3-115](#)
- [Creating a Provider, page 3-115](#)
- [Editing a Provider, page 3-116](#)
- [Deleting Providers, page 3-117](#)
- [Creating Provider Regions, page 3-118](#)
- [Creating PE Devices, page 3-120](#)

- [Creating Access Domains, page 3-121](#)

Accessing the Providers Window

The Providers feature is used to create and manage providers.

To access the Providers window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Providers** to access the Providers window shown in [Figure 3-107](#).

Figure 3-107 Providers Window

The screenshot shows the 'Providers' window. At the top, there is a search bar with the text 'Show Providers with Provider Name matching' followed by an asterisk and a text input field, and a 'Find' button. Below the search bar, it says 'Showing 1-3 of 3 records'. The main part of the window is a table with three columns: '#', 'Provider Name', and 'BGP AS'. The table contains three rows of data:

#	Provider Name	BGP AS
1.	Provider1	100
2.	Provider2	200
3.	ProviderA	300

Below the table, there is a 'Rows per page:' dropdown menu set to '10'. At the bottom right of the window, there are three buttons: 'Create', 'Edit', and 'Delete'.

The Providers window contains the following:

- **Provider Name** Lists the names of providers. You can sort the list by provider name.
- **BGP AS** The Unique number assigned to each BGP autonomous system.

From the Providers window, you can create, edit, or delete providers using the following buttons:

- **Create** Click to create new providers. Enabled only if no customer is selected.
- **Edit** Click to edit selected provider (select the corresponding box). Enabled only if a single provider is selected.
- **Delete** Click to delete a selected provider (select the corresponding box). Enabled only if one or more providers are selected.

Creating a Provider

From the Create Provider window, you can create different providers.

To create a provider, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Providers**.

Step 2 Click the **Create** button.

The Create Provider window appears, as shown in [Figure 3-108](#).

Figure 3-108 Create Provider Window

The Create Provider window contains the following fields:

- **Name** (required) Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters.
- **BGP AS** (required) Each BGP autonomous system is assigned a unique 16-bit number by the same central authority that assigns IP network numbers. Range: 1 to 65535.
- **Contact Information** (optional) Any pertinent information about the provider that could be helpful to service provider operators. Limited to 256 characters.

Step 3 Enter the name, BGP AS, and any contact information for the Provider that you are creating.

Step 4 Click **Save**.

The Providers window reappears with the new provider listed.

Editing a Provider

From the Edit Provider window, you can modify the fields that have been specified for a particular provider.

To access the Edit Provider window, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Providers**.

Step 2 Select a single provider to modify by selecting the check box to the left of the Provider Name.

Step 3 Click the **Edit** button. This button is only enabled if a customer is selected.

The Edit Provider window appears, as shown in [Figure 3-109](#).

Figure 3-109 Edit Provider Window

Edit Provider

Name * : ProviderA

BGP AS * : 100 (1 - 65535)

Contact Info:

Save Cancel

Note: * - Required Field

95244

Step 4 Enter the changes you want to make to the selected provider.

Step 5 Click **Save**.

The changes are saved and the Providers window reappears.

Deleting Providers

From the Delete window, you can remove selected providers from the database.

To access the Delete window, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Providers**.

Step 2 Select provider(s) to delete by selecting the check box to the left of the Provider Name.

Step 3 Click the **Delete** button. This button is only enabled if one or more Providers are selected.

The Confirm Delete window appears, as shown in [Figure 3-110](#).

Figure 3-110 Confirm Delete Window

Delete Provider(s)

Confirm Delete

Showing 1-1 of 1 records

#	Name
1.	ProviderA

Rows per page:
10

Delete
Cancel

- Step 4

Click the **Delete** button to confirm that you want to delete the provider(s) listed.
The Providers window reappears with the specified provider(s) deleted.

Creating Provider Regions


A Provider Region is considered to be a group of provider edge routers (PEs) within a single BGP autonomous system. The primary objective for defining Provider Regions is to allow a provider to employ unique IP address pools in large Regions, such as Europe, Asia Pacific, and so forth.

To access the Provider Regions window, follow these steps:

- Step 1

Navigate **Service Inventory > Inventory and Connection Manager**.
- Step 2

Click on **Provider Regions** listed in the Inventory and Connection Manager tree in the left column, as shown in [Figure 3-111](#).
- The Provider Regions window appears.

Figure 3-111 *Provider Regions Window*

The Provider Regions window contains the following:

- **Region Name** Lists the names of regions. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by region name.
- **Provider Name** Lists the names of providers. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by provider name.

From the Provider Regions window, you can create, edit, or delete provider regions using the following buttons:

- **Create** Click to create new provider regions. Enabled only if no customer is selected.
- **Edit** Click to edit selected provider regions (select the corresponding box). Enabled only if a single provider region is selected.
- **Delete** Click to delete selected provider regions (select the corresponding box). Enabled only if one or more provider regions are selected.

Creating PE Devices

The PE Devices feature provides a list of provider edge routers (PEs) that have been associated with the region, either through the PE editor or Inventory Manager.

To access the PE Devices window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager**.
- Step 2** Click on **PE Devices** listed in the Inventory and Connection Manager tree in the left column, as shown in [Figure 3-112](#).

The PE Devices window appears.

Figure 3-112 PE Devices Window

The screenshot shows the Cisco IP Solution Center interface. The top navigation bar includes tabs for Service Inventory, Service Design, Monitoring, Diagnostics, and Administration. The left sidebar contains a tree view with categories like Service Requests, Traffic Engineering Management, Inventory Manager, Topology Tool, Devices, Device Groups, Customers, Customer Sites, CPE Devices, Providers, Provider Regions, PE Devices (selected), Access Domains, Resource Pools, CE Routing Communities, VPNs, AAA Servers, Named Physical Circuits, and NPC Rings. The main content area displays the 'PE Devices' window. It features a search bar with 'Device Name' selected and a 'Find' button. Below the search bar is a table with 5 records. The table columns are #, Device Name, Provider Name, PE Region Name, Role Type, and Service Request. The records are: 1. pe1, Provider1, region_1, N-PE, QoS MPLS VPLS L2VPN; 2. pe3, Provider1, region_1, N-PE, QoS MPLS VPLS L2VPN; 3. sw2, Provider1, region_1, U-PE, VPLS L2VPN; 4. sw3, Provider1, region_1, U-PE, VPLS L2VPN; 5. sw4, Provider1, region_1, U-PE, VPLS L2VPN. At the bottom of the table, there is a 'Rows per page' dropdown set to 10, a 'Go to page' field set to 1 of 1, and buttons for 'Create', 'Edit', and 'Delete'.

The PE Devices window contains the following:

- **Device Name** Lists the names of devices. The first character must be a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limit: 80 characters. You can sort the list by device name.
- **Provider Name** Lists the names of providers. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by provider name.
- **Region Name** Lists the names of regions. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by region name.
- **Role Type** Choices include: N-PE, U-PE, P, PE_AGG.

From the PE Devices window, you can create, edit, or delete providers using the following buttons:

- **Create** Click to create new PE device. Enabled only if no PE device is selected.
- **Edit** Click to edit selected PE device (select the corresponding box). Enabled only if a single PE device is selected.
- **Delete** Click to delete selected PE device(s) (select the corresponding box). Enabled only if one or more PE devices are selected.


Creating Access Domains

To access the Access Domains window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager**.
- Step 2** Click on **Access Domains** listed in the Inventory and Connection Manager tree in the left column, as shown in [Figure 3-113](#).

The Access Domains window appears.

Figure 3-113 Access Domains Window



The Access Domains window contains the following:

- **Access Domain Name** Lists the names of access domain. The first character must be a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limit: 80 characters. You can sort the list by access domain name.
- **Provider Name** Lists the names of providers. Must begin with a letter. Can contain letters, numbers, and these punctuation characters: period, underscore, and dash. Limited to 80 characters. You can sort the list by provider name.

From the Access Domains window, you can create, edit, or delete access domains using the following buttons:

- **Create** Click to create new access domain. Enabled only if no access domain is selected.
- **Edit** Click to edit selected access domain (select the corresponding box). Enabled only if a single access domain is selected.
- **Delete** Click to delete selected access domain(s) (select the corresponding box). Enabled only if one or more access domains are selected.

Resource Pools

Cisco IP Solution Center enables multiple pools to be defined and used during operations. The following resource pools are available:

- **IP address pool:** The IP address pool can be defined and assigned to regions or VPNs. This feature gives the service operator the flexibility to manage the allocation of all IP addresses in the network.
- **Multicast pool:** The Multicast pool is used for Multicast MPLS VPNs.
- **Route Target (RT) pool:** A route target is the MPLS mechanism that informs PEs as to which routes should be inserted into the appropriate VRFs. Every VPN route is tagged with one or more route targets when it is exported from a VRF and offered to other VRFs. The route target can be considered a VPN identifier in MPLS VPN architecture. RTs are a 64-bit number.
- **Route Distinguisher (RD) pool:** The IP subnets advertised by the CE routers to the PE routers are augmented with a 64-bit prefix called a route distinguisher (RD) to make them unique. The resulting 96-bit addresses are then exchanged between the PEs, using a special address family of Multiprotocol BGP (referred to as MP-BGP). The RD pool is a pool of 64-bit RD values that Cisco IP Solution Center uses to make sure the IP addresses in the network are unique.
- **Site of origin pool:** The pool of values for the site-of-origin (SOO) attribute. The site-of-origin attribute prevents routing loops when a site is multihomed to the MPLS VPN backbone. This is achieved by identifying the site from which the route was learned, based on its SOO value, so that it is not readvertised back to that site from a PE in the MPLS VPN network.
- **VC ID pool:** VC ID pools are defined with a starting value and a size of the VC ID pool. (VC ID is a 32-bit unique identifier that identifies a circuit/port.) A given VC ID pool is not attached to any Inventory object. During the deployment of an Ethernet Service (EWS, ERS for example), VC ID is auto-allocated from the VC ID pool.
- **VLAN ID pool:** VLAN ID pools are defined with a starting value and a size of the VLAN pool. A given VLAN ID pool can be attached to an Access Domain. During the deployment an Ethernet Service (EWS, ERS for example), VLAN ID can be auto-allocated from the Access Domain's VLAN pools. This gives the Service Provider a tighter control of VLAN ID allocation.

All these resources, that are made available to the service provider, enable the automation of service deployment.

This section describes how you can create and manage pools for various types of resources. This section includes the following:

- [Accessing the Resource Pools Window, page 3-123](#)
- [Creating an IP Address Pool, page 3-124](#)
- [Creating a Multicast Pool, page 3-125](#)

- [Creating a Route Distinguisher and Route Target Pool, page 3-126](#)
- [Creating a Site of Origin Pool, page 3-128](#)
- [Creating a VC ID Pool, page 3-130](#)
- [Creating a VLAN Pool, page 3-130](#)
- [Deleting Resource Pools, page 3-132](#)

Accessing the Resource Pools Window

The Resource Pools feature is used to create and manage various types of resource pools.

To access the Resource Pools window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Resource Pools** to access the Resource Pools window shown in [Figure 3-114](#).

Figure 3-114 Resource Pools Window

Resource Pools

Pool Type:

Show IP Address Pools with Pool Name matching of type

Showing 1-6 of 6 records

#	<input type="checkbox"/>	Start	Pool Mask	Pool Size	Status	Type	Pool Name
1.	<input type="checkbox"/>	2.0.0.0	32	16777216	Available	VPN	Customer2:VPN-1
2.	<input type="checkbox"/>	10.10.10.0	30	1	Available	Region	Provider1:US
3.	<input type="checkbox"/>	10.10.10.4	30	1	Allocated	Region	Provider1:US
4.	<input type="checkbox"/>	10.10.10.8	30	62	Available	Region	Provider1:US
5.	<input type="checkbox"/>	10.10.20.0	32	256	Available	Region	Provider1:US
6.	<input type="checkbox"/>	1.0.0.0	30	4194304	Available	Region	Provider2:Western

Rows per page:

965247

From the Resource Pools window, you have access to the following buttons:

- **Pool Type** Choices include: IP Address, Multicast, Route Distinguisher, Route Target, Site of Origin, VC ID, and VLAN. The fields displayed in the Resource Pools window vary depending on the pool type selected.
- **Create** Click to create new resource pools. Enabled only if no resource pool is selected.
- **Delete** Click to delete selected resource pools (select by clicking the corresponding box). Enabled only if one or more resource pools are selected.

Creating an IP Address Pool

ISC uses IP address pools to automatically assign IP addresses to PEs and CEs. Each Region has an IP address pool to use for IP numbered addresses (/30 pools) and a separate IP address pool for IP unnumbered addresses (/32 loopback address pools).

Within a VPN or extranet, all IP addresses must be unique. Customer IP addresses must not overlap with the provider's IP addresses. Overlapping IP addresses are only possible when two devices cannot see each other—that is, when they are in isolated VPNs.

From the Create IP Address Pool window, you can create IP address pools.

To create an IP address pool, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Resource Pools**.
- Step 2** Select **IP address** from the **Pool Type** in the upper left of the Resource Pools window.
- Step 3** Click the **Create** button.

The Create IP Address Pool window appears, as shown in [Figure 3-115](#).

Figure 3-115 Create IP Address Pool Window

Create IP Address Pool

IP Address Pool*: (IP Address / Mask)

Pool Mask (bits)*: ☐ 30 ☐ 32

Pool Association*: Region

Note: * - Required Field

The Create IP Address Pool window contains the following fields:

- **IP Address Pool** (required) Text field in the format a.b.c.d/mask, for example 172.0.0.0/8.
- **Pool Mask (bits)** (required) Choices include: **30** and **32**
 where:
30 is used for IP numbered address pools (/30)
32 is used for IP unnumbered loopback address pools (/32).
- **Pool Association** (required) Choices include: Region and VPN Customer.



Note If you choose **VPN**, an additional optional field appears, **Pool Name Suffix**, when you return to [Figure 3-115](#). This field allows the creation of multiple address pools within the same VPN. If you are creating this address pool for DMVPN usage, the recommendation is to use this field to specify a suffix.

- Step 4** Enter the required information for the IP address pool you are creating.

Step 5 Click **Save**.

The Resource Pools window reappears with the new IP address pool listed.

Creating a Multicast Pool

From the Create Multicast Pool window, you can create multicast pools. These pools are global and are not associated with any provider or customer.

To create a multicast pool, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Resource Pools**.

Step 2 Select **Multicast** from the **Pool Type** in the upper left of the Resource Pools window.

Step 3 Click the **Create** button.

The Create Multicast Pool window appears, as shown in [Figure 3-116](#).

Figure 3-116 Create Multicast Pool Window

Create Multicast Pool

Multicast Address *	<input type="text"/>	(IP Address / Mask)
Use for Default MDT:	<input checked="" type="checkbox"/>	
Use for Data MDT:	<input checked="" type="checkbox"/>	

Save Cancel

Note: * - Required Field

96303

The Create Multicast Pool window contains the following fields:

- **Multicast Address** (required) Text field in the format a.b.c.d/mask, for example 239.0.0.0/8. Range: 224.0.1.0/8 to 239.255.255.255/32.
- **Use for default MDT** (optional) This is a check box. Default: selected.
- **Use for Data MDT** (optional) This is a check box. The *data MDT* contains a range of multicast group addresses and a bandwidth threshold. Thus, whenever a CE behind a multicast-VRF exceeds that bandwidth threshold while sending multicast traffic, the PE sets up a new data MDT for the multicast traffic from that source. The PE informs the other PEs about this data MDT and, if they have receivers for the corresponding group, the other PEs join this data MDT. Default: selected.

Step 4 Enter the required information for the multicast pool you are creating.

Step 5 Click **Save**.

The Resource Pools window reappears with the new multicast pool listed.

Creating a Route Distinguisher and Route Target Pool

MPLS-based VPNs employ Border Gateway Protocol (BGP) to communicate between PE's to facilitate customer routes. This is made possible through extensions to BGP that carry addresses other than IPv4 addresses. A notable extension is called the route distinguisher (RD).

The purpose of the route distinguisher (RD) is to make the prefix value unique across the network backbone. Prefixes should use the same RD if they are associated with the same set of route targets (RTs) and anything else that is used to select routing policy. The community of interest association is based on the route target (RT) extended community attributes distributed with the Network Layer Reachability Information (NLRI). The RD value must be a globally unique value to avoid conflict with other prefixes.

The MPLS label is part of a BGP routing update. The routing update also carries the addressing and reachability information. When the RD is unique across the MPLS VPN network, proper connectivity is established even if different customers use non-unique IP addresses.

For the RD, every CE that has the same overall role should use a VRF with the same name, same RD, and same RT values. The RDs and RTs are only for route exchange between the PE's running BGP. That is, for the PE's to do MPLS VPN work, they have to exchange routing information with more fields than usual for IPv4 routes; that extra information includes (but is not limited to) the RDs and RTs.

From the Create Route Distinguisher Pool window, you can create route distinguisher pools.

To create a route distinguisher pool, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Resource pools**.
- Step 2** Select **Route Distinguisher** from the **Pool Type** in the upper left of the Resource Pools window.
- Step 3** Click the **Create** button.

The Create Route Distinguisher Pool window appears, as shown in [Figure 3-117](#).

Figure 3-117 Create Route Distinguisher Pool Window

Create Route Distinguisher Pool

RD Pool Start *	0	(0 - 2147483646)
RD Pool Size *	0	(1 - 2147483647)
Provider *		Select

Save Cancel

Note: * - Required Field

95304

The Create Route Distinguisher Pool window contains the following fields:

- **RD Pool Start** (required) Range: 0 to 2147483646.
- **RD Pool Size** (required) Range: 1 to 2147483647.
- **Provider** (required)

- Step 4** Enter the **RD Pool Start** and **Size** information for the route distinguisher pool you are creating.

Step 5 Click the **Select** button.

The Provider for new Resource Pool window appears, as shown in [Figure 3-118](#).

Figure 3-118 Provider for New Resource Pool Window

The screenshot shows a window titled 'Provider for New Resource Pool Window'. At the top, there is a search bar with the text 'Show Providers with Provider Name matching' followed by an asterisk and a text input field containing 'Provider1'. To the right of the input field is a 'Find' button. Below the search bar, it says 'Showing 1 - 1 of 1 record'. There is a table with two columns: '#' and 'Provider Name'. The first row contains '1.' and 'Provider1'. Below the table, there is a 'Rows per page' dropdown set to '10', a 'Go to page' field set to '1' of '1', and a 'Go' button. At the bottom right are 'Select' and 'Cancel' buttons. A vertical text '149148' is visible on the right side of the window.

Step 6 Select one of the providers listed and click **Select**.

Step 7 Click **Save**.

The Resource Pools window reappears with the new route distinguisher pool listed.

To create a Route Target Pool, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > Resource pools**.

Step 2 Select **Route Target** from the **Pool Type** in the upper left of the Resource Pools window.

Step 3 Click the **Create** button.

The Create Route Target Pool window appears, as shown in [Figure 3-119](#).

Figure 3-119 Create Route Target Pool Window

The screenshot shows a window titled 'Create Route Target Pool'. It contains three main input fields: 'RT Pool Start' with a value of '0' and a range '(0 - 2147483646)', 'RT Pool Size' with a value of '0' and a range '(1 - 2147483647)', and 'Provider' with a dropdown menu and a 'Select' button. At the bottom right are 'Save' and 'Cancel' buttons. A note at the bottom left states 'Note: * - Required Field'. A vertical text '95299' is visible on the right side of the window.

The Create Route Target Pool window contains the following fields:

- **RT Pool Start** (required) Range: 0 to 2147483646.
- **RT Pool Size** (required) Range: 1 to 2147483647.
- **Provider** (required)

Step 4 Enter the **RT Pool Start** and **Size** information for the route target pool you are creating.

Step 5 Click the **Select** button.

The Provider for new Resource Pool window appears, as shown in [Figure 3-120](#).

Figure 3-120 Provider for New Resource Pool Window

Step 6 Select one of the providers listed and click **Select**.

Step 7 Click **Save**.

The Resource Pools window reappears with the new route target pool listed.

Creating a Site of Origin Pool

In MPLS VPN, CE sites use private/public AS numbers and when one AS number is used for each VPN, all sites belonging to the same VPN share the same private/public AS number. The default BGP behavior is to drop any prefix if its own AS number is already in the AS path. As a result, a customer site does not learn prefixes of a remote site in this situation. AS-OVERRIDE must be configured (if there are hub sites involved, ALLOWAS-IN must be configured) to allow those prefixes to be sent by PE routers but a routing loop can occur.

For example, CE1 and CE2 belong to the same customer VPN and have the same AS number 65001. The AS path between two customer sites is 65001 - 1234 - 65001 and prefixes cannot be exchanged between customer sites because AS 65001 is already in the path. To solve this problem, AS-OVERRIDE options are configured on PE routers; but it introduces a routing loop into the network without using extended community site of origin attributes.

Site of origin is a concept in MPLS VPN architecture that prevents routing loops in sites that are multi-homed to the MPLS VPN backbone and in sites using AS-OVERRIDE in conjunction. Site of origin is a type of BGP extended community attribute used to identify a prefix that originated from a site so that the re-advertisement of that prefix back to the site can be prevented. This attribute uniquely identifies the site from which the PE router learned the route. Site of origin is tagged at PE in peering with BGP neighbors using an inbound route-map and works in conjunction with BGP CE-PE routing protocol.

Site of origin must be unique per customer site per VPN/customer (when these sites are multi-homed). Therefore, the same value of site of origin must be used on PE routers connected to the same CE router or to the same customer site.



Note

Each time a customer site is created, ISC generates a unique site of origin value from the selected site of origin provider pool if Site of Origin is enabled. This site of origin value must be unique per customer site per customer/VPN.

From the Create Site of Origin Pool window, you can create site of origin pools.
To create a site of origin pool, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Resource pools**.
Step 2 Select **Site of Origin** from the **Pool Type** in the upper left of the Resource Pools window.
Step 3 Click the **Create** button.

The Create Site of Origin Pool window appears, as shown in [Figure 3-121](#).

Figure 3-121 Create Site of Origin Pool Window

Create Site of Origin Pool

SOO Pool Start*: 0 (0 - 2147483646)

SOO Pool Size*: 0 (1 - 2147483647)

Provider*:

Note: * - Required Field

The Create Site of Origin Pool window contains the following fields:

- **SOO Pool Start** (required) Range: 0 to 2147483646.
- **SOO Pool Size** (required) Range: 1 to 2147483647.
- **Provider** (required)

- Step 4** Enter the **SOO Pool Start** and **Size** information for the site of origin pool you are creating.
Step 5 Click the **Select** button.

The Provider for new Resource Pool window appears, as shown in [Figure 3-122](#).

Figure 3-122 Provider for New Resource Pool Window

Show Providers with Provider Name matching*

Showing 1 - 1 of 1 record

#	Provider Name
1.	Provider1

Rows per page: 10

- Step 6** Select one of the providers listed and click **Select**.
Step 7 Click **Save**.

The Site of Origin pools window reappears with the new route target pool listed.

Creating a VC ID Pool

From the Create VC ID Pool window, you can create VC ID pools. These pools are global and are not associated with any provider or customer.

To create a VC ID pool, follow these steps:

-
- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Resource pools**.
- Step 2** Select **VC ID** from the **Pool Type** in the upper left of the Resource Pools window.
- Step 3** Click the **Create** button.

The Create VC ID Pool window appears, as shown in [Figure 3-123](#).

Figure 3-123 Create VC ID Pool Window

The Create VC ID Pool window contains the following fields:

- **VC Pool Start** (required) Range: 1 to 2147483646.
- **VC Pool Size** (required) Range: 1 to 2147483647.

- Step 4** Enter the required information for the site of origin pool you are creating.
- Step 5** Click **Save**.

The VC ID Pools window reappears with the new VC ID pool listed.


Creating a VLAN Pool

From the Create VLAN Pool window, you can create VLAN pools.

To create a VLAN pool, follow these steps:

-
- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Resource pools**.
- Step 2** Select **VLAN** from the **Pool Type** in the upper left of the Resource Pools window.
- Step 3** Click the **Create** button.

The Create VLAN Pool window appears, as shown in [Figure 3-124](#).

Figure 3-124 Create VLAN Pool Window


The 'Create VLAN Pool' window contains the following fields:

- VLAN Pool Start** (required): 0 (Range: 1 - 4094)
- VLAN Pool Size** (required): 0 (Range: 1 - 4094)
- Access Domain** (required): [Empty field] **Select**

Buttons: **Save**, **Cancel**

Note: * - Required Field


The Create VLAN Pool window contains the following fields:

- **VLAN Pool Start** (required) Range: 1 to 4094.
- **VLAN Pool Size** (required) Range: 1 to 4094.
- **Access Domain** (required)

Step 4 Enter the **VLAN Pool Start** and **Size** information for the VLAN pool you are creating.

Step 5 Click the **Select** button.

The Access Domain for new VLAN Pool window appears, as shown in [Figure 3-125](#).

Figure 3-125 Access Domain for new VLAN Pool Window


The 'Access Domain for new VLAN Pool' window displays a search interface for access domains.

Search criteria: Show Access Domains with **Access Domain Name** matching *

Results: Showing 1-1 of 1 records

#	Select	Access Domain Name	Provider Name
1.	<input type="radio"/>	Sonera_Access	Telia_Sonera

Rows per page: 10

Buttons: **Select**, **Cancel**

Step 6 Select one of the access domains listed and click **Select**.

Step 7 Click **Save**.

The VLAN Pools window reappears with the new VLAN pool listed.

Deleting Resource Pools

From the Resource Pool window, you can delete specific resource pools.

To delete resource pools, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Resource pools**.
- Step 2** Select a pool type from the **Pool Type** in the upper left of the Resource Pools window.
- Step 3** Select one or more resource pools to delete by selecting the check box to the left of the resource pool(s).
- Step 4** Click the **Delete** button.

The Confirm Delete window appears, as shown in [Figure 3-126](#).

Figure 3-126 Confirm Delete Window

The screenshot shows a 'Confirm Delete' dialog box. At the top, it says 'Confirm Delete' and 'Showing 1-1 of 1 records'. Below this is a table with the following data:

#	IP Address Pool	Mask	Size	Type	Pool Name
1.	18.0.0.4	30	4194303	Region	ServiceProvider1:Region1

Below the table, there is a 'Rows per page:' dropdown menu set to '10'. At the bottom right, there are two buttons: 'Delete' and 'Cancel'.

- Step 5** Click the **Delete** button to confirm that you want to delete the resource pool(s) listed.

The Resource Pools window reappears with the specified pool(s) deleted.

CE Routing Communities

A VPN can be organized into subsets called *CE routing communities*, or CERCs. A CERC describes how the CEs in a VPN communicate with each other. Thus, CERCs describe the logical topology of the VPN. Cisco IP Solution Center can be employed to form a variety of VPN topologies between CEs by building hub and spoke or full mesh CE routing communities. CERCs are building blocks that allow you to form complex VPN topologies and CE connectivity.

The most common types of VPNs are *hub-and-spoke* and *full mesh*.

- A hub-and-spoke CERC is one in which one or a few CEs act as hubs, and all spoke CEs talk only to or through the hubs, never directly to each other.
- A full mesh CERC is one in which every CE connects to every other CE.

These two basic types of VPNs—full mesh and hub and spoke—can be represented with a single CERC. Whenever you create a VPN, the Cisco IP Solution Center software creates one default CERC for you. This means that until you need advanced customer layout methods, you will not need to define new

CERCs. Up to that point, you can think of a CERC as standing for the VPN itself—they are one and the same. If, for any reason, you must override the software's choice of route target values, you can do so only at the time you create a CERC in the Cisco IP Solution Center software.

To build very complex topologies, it is necessary to break down the required connectivity between CEs into groups, where each group is either fully meshed, or has a hub and spoke pattern. (Note that a CE can be in more than one group at a time, if each group has one of the two basic patterns.) Each subgroup in the VPN wants its own CERC. Any CE that is only in one group just joins the corresponding CERC (as a spoke if necessary). If a CE is in more than one group, then you can use the Advanced Setup choice during provisioning to add the CE to all the relevant groups in one service request. Given this information, the provisioning software does the rest, assigning route target values and VRF tables to arrange exactly the connectivity the customer requires. You can use the Topology tool to double-check the CERC memberships and resultant VPN connectedness.

Cisco IP Solution Center supports multiple CEs per site and multiple sites connected to the same PE. Each CERC has unique route targets (RT), route distinguisher (RD), and VPN Routing and Forwarding instance (VRF) naming. After provisioning a CERC, it is a good idea to run the audit reports to verify the CERC deployment and view the topologies created by the service requests. The product supports linking two or more CE routing communities in the same VPN.

This section describes how you can create and manage CE routing communities. This section includes the following:

- [Accessing the CE Routing Communities Window, page 3-133](#)
- [Creating CE Routing Communities, page 3-134](#)
- [Deleting CE Routing Communities, page 3-135](#)

Accessing the CE Routing Communities Window

The CE Routing Communities feature is used to create and manage CERCs.

To access the CE Routing Communities window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > CE Routing Communities** to access the CE Routing Communities window shown in [Figure 3-127](#).

Figure 3-127 CE Routing Communities Window

The screenshot shows the 'CE Routing Communities' window. At the top, there is a search bar with the text 'Show CERCs with' followed by a dropdown menu set to 'Name', a text input field with an asterisk, and a 'Find' button. Below this, it says 'Showing 1 - 2 of 2 records'. The main area contains a table with the following data:

#	Name	HRT	SRT	Provider	VPN
1.	Mpls-VPN-1	99:1	99:2	Provider1	Mpls-VPN-1
2.	Mpls-VPN-2	99:3	99:4	Provider1	Mpls-VPN-2

Below the table, there is a 'Rows per page:' dropdown set to '10'. To the right, there is a pagination control showing 'Go to page: 1 of 1' with navigation arrows. At the bottom right, there are three buttons: 'Create', 'Edit', and 'Delete'.

From the CE Routing Communities window, you can create, edit, or delete CE routing communities using the following buttons:

- **Create** Click to create new CE routing communities. Enabled only if no CE routing community is selected.
 - **Edit** Click to edit selected CE routing communities (select by clicking the corresponding box). Enabled only if one CE routing community is selected.
 - **Delete** Click to delete selected CE routing communities (select by clicking the corresponding box(es)). Enabled only if one or more CE routing communities are selected.
-

Creating CE Routing Communities

When you create a VPN, the Cisco IP Solution Center software creates one default CE routing community (CERC) for you. But if your network topology and configuration require customized CERC definitions, you can define CERCs customized for your network.



Tip

Customized CERCs should be defined only in consultation with the VPN network administrator. To build complex topologies, it is necessary to break down the required connectivity between CEs into groups, where each group is either fully meshed or has a hub-and-spoke pattern. A CE can be in more than one group at a time, as long as each group has one of the two basic configuration patterns.

Each subgroup in the VPN wants its own CERC. Any CE that is only in one group just joins the corresponding CERC (as a spoke if necessary). If a CE is in more than one group, then you can use the Advanced Setup choice during provisioning to add the CE to all the relevant groups in one service request. Given this information, Cisco IP Solution Center does the rest, assigning route target values and VRF tables to arrange the precise connectivity the customer requires.

To create a CE routing community, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > CE Routing Communities**.

Step 2 Click **Create**.

The Create CE Routing Community window appears, as shown in [Figure 3-128](#).

Figure 3-128 Create CE Routing Community Window

Create CE Routing Community

Provider * **Select**

Name *

CERC Type: ☒ Hub and Spoke ☐ Fully Meshed

Auto-pick route target values: ☒

Route Target 1:

Route Target 2:

Save **Cancel**

Note: * - Required Field

96294

- Step 3** Complete the CERC fields as required for the CE Routing Community:
- Provider** (required) To specify the service provider associated with this CERC, click **Select**.
The Select Provider dialog box is displayed.
 - Choose the name of the service provider, then click **Select**.
 - Name** (required) Enter the name of the CERC.
 - CERC Type** Specify the CERC type: Hub and Spoke or Fully Meshed.
 - Auto-Pick Route Target Values** Choose to either let Cisco IP Solution Center automatically set the route target (RT) values or set the RT values manually.
By default, the **Auto-pick route target values** check box is selected. If you deselect the check box, you can enter the Route Target values manually.

**Caution**

If you choose to bypass the **Auto-pick route target values** option and set the route target (RT) values manually, note that the RT values cannot be edited after they have been defined in the ISC software.

- Step 4** When you have finished entering the information in the Create CE Routing Community dialog box, click **Save**.
After creating the CERC, you can add it to the VPN.

Deleting CE Routing Communities

From the CE Routing Community window, you can delete specific CERCs.
To delete CERC(s), follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > CE Routing Communities**

Step 2 Select CERC(s) to delete by selecting the check box(es) to the left of the CERC name.

Step 3 Click the **Delete** button.

The Confirm Delete window appears.

Step 4 Click **OK** to confirm that you want to delete the CERC(s) listed.

The CE Routing Communities window reappears with the specified CERC(s) deleted.

VPNs

At its simplest, a virtual private network (VPN) is a collection of sites that share the same routing table. A VPN is also a framework that provides private IP networking over a public infrastructure such as the Internet. In Cisco IP Solution Center: MPLS VPN Management, a VPN is a set of customer sites that are configured to communicate through a VPN service. A VPN is defined by a set of administrative policies.

A VPN is a network in which two sites can communicate over the provider's network in a private manner; that is, no site outside the VPN can intercept their packets or inject new packets. The provider network is configured such that only one VPN's packets can be transmitted through that VPN—that is, no data can come in or out of the VPN unless it is specifically configured to allow it. There is a physical connection from the provider edge network to the customer edge network, so authentication in the conventional sense is not required.

This section describes how you can create and manage pools for various types of resources. This section includes the following:

- [Accessing the VPNs Window, page 3-136](#)
- [Creating a VPN, page 3-137](#)
- [Deleting VPNs, page 3-140](#)

Accessing the VPNs Window

The VPN feature is used to create and manage various types of VPNs.

To access the VPN window, follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > VPN** to access the VPN window shown in [Figure 3-129](#).

Figure 3-129 **VPNs Window**

The screenshot shows the 'VPNs' window with a search bar at the top. Below the search bar, it says 'Showing 1 - 6 of 6 records'. The table has two columns: 'VPN Name' and 'Customer Name'. The table contains six rows of data. At the bottom, there are buttons for 'Create', 'Edit', and 'Delete', and a 'Rows per page' dropdown set to 10.

#	VPN Name	Customer Name
1.	Mpls-VPN-1	Customer1
2.	Mpls-VPN-2	Customer1
3.	Vpn1	Customer1
4.	Vpn2	Customer1
5.	Vpn3	Customer2
6.	Vpn4	Customer2

Rows per page: 10 Go to page: 1 of 1 Create Edit Delete

From the VPNs window, you can create, edit, or delete VPNs using the following buttons:

- **Create** Click to create new VPNs. Enabled only if no VPN is selected.
- **Edit** Click to edit selected VPNs (select the corresponding box). Enabled only if one VPN is selected.
- **Delete** Click to delete selected VPNs (select the corresponding box). Enabled only if one or more VPNs is selected.

Creating a VPN

To create a VPN, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > VPN**.
- Step 2** Click **Create**.

The Create VPN window appears, as shown in [Figure 3-130](#).

Figure 3-130 Create VPN Window

Create VPN

Name * :

Customer * : **Select**

MPLS Attributes

Create Default CE Routing Community: ☐

Enable Multicast: ☐

Enable Auto Pick MDT Addresses: ☒

Default MDT Address * : (a.b.c.d)

Data MDT Subnet: (a.b.c.d)

Data MDT Size:

Data MDT Threshold: (1 - 4294967 kilobits/sec)

Default PIM Mode:

MDT MTU: (576 - 18010)

Enable PIM SSM: ☐

SSM List Name * :

Multicast Route Limit: (1 - 2147483647)

Enable Auto RP Listener: ☐

Configure Static-RP: ☐

PIM Static-RPs * :

#	Static-RP Unicast Address	Multicast-Group List Name	Override
Showing 0 of 0 records			

Rows per page: Go to page: of 1 **Go**

CE Routing Communities: **Select** **Remove**

VPLS Attributes

Enable VPLS: ☐

VPN ID: (1-2147483646)

Service Type:

Topology:

Save **Cancel**

Note: * - Required Field

149139

- Step 3** Complete the fields as required for the VPN:
- Name** (required) Enter the name of the VPN.
 - Customer** (required) To select the customer associated with this VPN, choose **Select**.
 - From the list of customers, select the appropriate customer, then click **Select**.
 - If you want MPLS attributes, complete the fields in the MPLS Attributes section of the window. For VPLS, skip to step **t**.

- e. **Create Default CE Routing Community** (optional) To create a default CE routing community, select the **Create Default CE Routing Community** check box and select a provider.
- f. **Enable Multicast** To enable multicast VPN routing, select the **Enable Multicast** check box.

An IP address that starts with the binary prefix *1110* is identified as a *multicast group address*. There can be more than one sender and receiver at any time for a given multicast group address. The senders send their data by setting the group address as the destination IP address. It is the responsibility of the network to deliver this data to all the receivers in the network who are listening to that group address.



Note Before you can create a VPN with multicast enabled, you must define one or more multicast resource pools.

- g. **Enable Auto Pick MDT Addresses** (optional) To enable auto picking MDT addresses, select the **Enable Auto Pick MDT Addresses** check box.
- h. **Default MDT Address** If **Enable Auto Pick MDT Addresses** is set on, **Default MDT Address** is required.

- i. **Data MDT Subnet** (optional)

- j. **Data MDT Size** (optional) If **Enable Multicast** is set on, **Data MDT Size** is required. From the drop-down list, select the data MDT size.

MDT refers to a *multicast distribution tree* (MDT). The MDT defined here carries multicast traffic from customer sites associated with the multicast domain.

- k. **Data MDT Threshold** (optional) If **Enable Multicast** is set on, **Data MDT Threshold** is required. Enter the bandwidth threshold for the data multicast distribution tree.

The *data MDT* contains a range of multicast group addresses and a bandwidth threshold. Thus, whenever a CE behind a multicast-VRF exceeds that bandwidth threshold while sending multicast traffic, the PE sets up a new data MDT for the multicast traffic from that source. The PE informs the other PEs about this data MDT and, if they have receivers for the corresponding group, the other PEs join this data MDT.

- l. **Default PIM Mode** (optional)

- m. **Enable PIM SSM** (optional)

- n. **SSM List Name**

- o. **Multicast Route Limit** (optional)

- p. **Enable Auto RP Listener** (optional)

- q. **Configure Static-RP** (optional)

- r. **CE Routing Communities** (optional) If **Enable Multicast** is set on, **CE Routing Communities** is required. If you do not choose to enable the default CERC, you can select a customized CERC that you have already created in ISC. From the CE Routing Communities pane, click **Select**.

The Select CE Routing Communities dialog box is displayed.

- s. Select the check box for the CERC you want used for this service policy, then click **Select**.

You return to the Create VPN dialog box, where the new CERC selection is displayed, along with its hub route target (HRT) and spoke route target (SRT) values.

- t. If you want VPLS attributes, the optional fields for that are in [u.](#) to [x.](#)

- u. **Enable VPLS** (optional) Select this check box to enable VPLS.

- v. **VPN ID** (optional)
- w. **Service Type** (optional) Click the drop-down list and choose from ERS (Ethernet Relay Service) or EWS (Ethernet Wire Service).
- x. **Topology** (optional) Select the VPLS topology from the drop-down list: Full Mesh (each CE will have direct connections to every other CE) or Hub and Spoke (only the Hub CE has connection to each Spoke CE and the Spoke CEs do not have direct connection to each other).

Step 4 When satisfied with the settings for this VPN, click **Save**.

You have successfully created a VPN, as shown in the **Status** display in the lower left corner of the VPNs dialog box.

Deleting VPNs

From the VPNs window, you can delete specific VPNs.

To delete VPN(s), follow these steps:

Step 1 Navigate **Service Inventory > Inventory and Connection Manager > VPN**.

Step 2 Select VPN(s) to delete by selecting the check box to the left of the VPN name.

Step 3 Click the **Delete** button.

The Confirm Delete window appears.

Step 4 Click **OK** to confirm that you want to delete the VPN(s) listed.

The VPNs window reappears with the specified VPN(s) deleted.

AAA Servers

This feature is not supported in this release.

Named Physical Circuits

Named physical circuits (NPCs) are named circuits that describe a physical connection between a CPE or U-PE and an N-PE. The intermediate nodes of the NPCs can either be CPE or PE. They can be connected in a circular fashion forming a ring of devices, which is represented by an entity known as NPC Rings. NPC Rings represent the circular topology between devices (CPE or PE) to the Named Physical Circuits. To create an NPC, you must specify how the source CPE/U-PE and the destination N-PE are connected and specify the intermediate nodes.

The connectivity of the NPCs is defined by specifying a set of devices serving as physical links; each device has two interfaces that are part of the NPC connections. The Incoming Interface defines the interface from the CE direction. The Outgoing Interface defines the interface toward the PE direction.

You can also add (meaning after the chosen device) or insert (meaning before the chosen device) an NPC Ring in the link.

Keep in mind the following when you are creating an NPC:

- In the ISC software, the device you select can be any node in the link. The ISC software only shows the appropriate devices. The first device *must* be a CPE or U-PE and the last device *must* be an N-PE.
- NPCs should be created before the MPLS multi-device, VPLS, or L2VPN service request is created with cpe1 and pe1. So when you create the SR, you would select the policy, cpe1, pe1, and the NPC that defines the link between cpe1 and pe1.

This section describes how you can create and delete NPCs and create, edit, and delete NPC Rings. This section includes the following:

- [Accessing the Named Physical Circuits Window, page 3-141](#)
- [Creating a Named Physical Circuit, page 3-142](#)
- [Deleting Named Physical Circuits, page 3-145](#)
- [Creating NPC Rings, page 3-146](#)
- [Editing NPC Rings, page 3-149](#)
- [Deleting NPC Rings, page 3-150](#)


Accessing the Named Physical Circuits Window

The Named Physical Circuits feature is used to create and delete NPCs. You cannot edit or modify.

To access the Named Physical Circuits window, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Named Physical Circuits** to access the window shown in [Figure 3-131, “Named Physical Circuits Window.”](#)

Figure 3-131 *Named Physical Circuits Window*



From the Named Physical Circuits window, you can create or delete NPCs using the following buttons:

- **Create** Click to create new NPCs. Enabled only if no NPC is selected.

- **Delete** Click to delete selected NPCs (select by clicking the corresponding box(es)). Enabled only if one or more NPCs are selected.

Creating a Named Physical Circuit

To add an NPC physical link, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Named Physical Circuit**.
- Step 2** Click the **Create** button in [Figure 3-131](#), “**Named Physical Circuits Window**,” and a window, as shown in [Figure 3-132](#), “**Create a Named Physical Circuit Window**,” appears.

Figure 3-132 Create a Named Physical Circuit Window

Each line represents a physical link and each physical link contains the following attributes:

- **Device**
- **Incoming Interface**
- **Outgoing Interface**
- **Ring** (optional)



Note Before adding a ring in an NPC, create a ring and save it in the repository, as explained in the [“Creating NPC Rings”](#) section on page 3-146.



Note An NPC must have at least one link defined. The link must have two Devices, an Incoming Interface, and an Outgoing Interface.

- Step 3** Click **Add Device** or **Insert Device** and a window as shown in [Figure 3-133](#), “**Select Device Window**,” appears.

Figure 3-133 *Select Device Window*

#	Device Name	Customer Name	Site Name	Management Type
1.	ce13	Customer1	east	MANAGED
2.	ce3	Customer1	east	MANAGED
3.	ce8	Customer1	east	MANAGED

Step 4 Be sure that the drop-down list in **Show** is **CPE** or **PE**. Click a radio button next to a device and then click **Select**.

Step 5 Figure 3-132, “Create a Named Physical Circuit Window,” reappears with the chosen **Device**.

Figure 3-134 *Create Named Physical Circuit Window*

#	Device	Incoming Interface	Outgoing Interface	Ring
1.	ence21		Select outgoing interface	
2.	mlce203	Select incoming interface		

Step 6 If you want to add a device to your NPC as the last item or after the item selected in the check box, click the **Add Device** button in Figure 3-132 on page 3-142 and then add device and interface information as explained in the previous steps. If you want to insert a device to your NPC as the first item or before the item selected in the check box, click the **Insert Device** button in Figure 3-132 on page 3-142 and then add device and interface information as explained in the previous steps.

Step 7 In the **Outgoing Interface** column in this new version of Figure 3-132, “Create a Named Physical Circuit Window,” click **Select outgoing interface** and a window as shown in Figure 3-135, “Select Outgoing Interface Window,” appears with a list of interfaces.

Figure 3-135 *Select Outgoing Interface Window*

Interfaces for device **encl11**

ShowDevice Interfaces with matching

Showing 1-6 of 6 records

#	Select	Name	IP Address	Interface Logical Name
1.	<input type="radio"/>	Ethernet0	192.168.129.189/30	
2.	<input type="radio"/>	Ethernet1	192.168.132.9/29	
3.	<input type="radio"/>	Loopback0	192.168.115.70/32	
4.	<input type="radio"/>	Loopback1	14.1.1.1/32	
5.	<input type="radio"/>	Serial0		
6.	<input type="radio"/>	Serial1		

Rows per page:

- Step 8** Click a radio button next to the interface to be the source interface for this NPC and then click **Select**.
- Step 9** [Figure 3-132](#), “[Create a Named Physical Circuit Window](#),” reappears with the chosen **Interface**.
- Step 10** In the **Incoming Interface** column in this new version of [Figure 3-132](#), “[Create a Named Physical Circuit Window](#),” click **Select incoming interface** and a window as shown in [Figure 3-136](#), “[Select Incoming Interface Window](#),” appears with a list of interfaces.

Figure 3-136 *Select Incoming Interface Window*

Interfaces for device **encl11**

ShowDevice Interfaces with matching

Showing 1-10 of 18 records

#	Select	Name	IP Address	Interface Logical Name
1.	<input type="radio"/>	ATM5/0		
2.	<input type="radio"/>	Ethernet2/0		
3.	<input type="radio"/>	Ethernet2/1		
4.	<input type="radio"/>	Ethernet2/2		
5.	<input type="radio"/>	Ethernet2/3		
6.	<input type="radio"/>	FastEthernet0/0		
7.	<input type="radio"/>	FastEthernet4/0		
8.	<input type="radio"/>	Hssi1/0		
9.	<input type="radio"/>	Hssi1/1		
10.	<input type="radio"/>	Loopback0	192.168.115.64/32	

Rows per page:

- Step 11** Click a radio button next to the interface to be the incoming interface for this NPC and then click **Select**.
- Step 12** [Figure 3-132](#), “[Create a Named Physical Circuit Window](#),” reappears with the chosen **Incoming Interface**.

- Step 13** If you created an NPC ring that you want to insert or add into this NPC, as explained in the [“Creating NPC Rings” section on page 3-146](#), you can click **Insert Ring** or **Add Ring** and the ring appears at the beginning or before the item selected in the check box for **Insert Ring** or the ring appears at then end or after the item selected in the check box for **Add Ring**, as shown in [Figure 3-137](#), [“Select NPC Ring Window.”](#)

**Note**

When inserting a ring, select the source device of the ring that connects to a source device or an NPC and the destination device of the ring that connects to the destination device of the NPC.

If you have not created an NPC ring that you want to insert into this NPC, proceed to [Step 17](#).

Figure 3-137 **Select NPC Ring Window**

- Step 14** Click a radio button next to the ring you choose and then click **Select**.
- Step 15** [Figure 3-132](#), [“Create a Named Physical Circuit Window,”](#) reappears with the chosen **Ring**.
- Step 16** Select the missing devices and interfaces as explained in the [“Creating NPC Rings” section on page 3-146](#).
- Step 17** Click **Save**.
- Step 18** [Figure 3-132](#), [“Create a Named Physical Circuit Window,”](#) reappears with the new NPC listed.

Deleting Named Physical Circuits

To delete NPC(s), follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Named Physical Circuits** to access the window shown in [Figure 3-131](#), [“Named Physical Circuits Window.”](#)
- Step 2** Select one or more NPCs to delete by selecting the check box(es) on the left.
- Step 3** Click the **Delete** button.
- The Delete NPC window appears.

**Note**

If the specified NPC is being used by any of the Service Requests, you will not be allowed to delete it. An error message appears explaining this.

- Step 4** Click the **Delete** button to confirm that you want to delete the NPCs listed.
- Figure 3-131, “Named Physical Circuits Window,” reappears with the specified NPCs deleted.

Creating NPC Rings

To create NPC rings, follow these steps:

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > NPC Rings** and a window as shown in Figure 3-138, “NPC Rings Window,” appears.

Figure 3-138 NPC Rings Window

- Step 2** Click the **Create** button and a window as shown in Figure 3-139, “Create Ring Window,” appears. A ring has a minimum of three physical links that form a ring.

Figure 3-139 Create Ring Window



Note At any time, if you click **Cancel**, everything you have chosen disappears.

- Step 3** Start with the first line, which represents the first physical link.
- Step 4** In the **Source Device** column, click **Select source device** and a window as shown in Figure 3-140, “Select Source Device — CPE/PE Window,” appears.



Note The CPE you choose *must* be a Multi-VRF CE.

Figure 3-140 Select Source Device — CPE/PE Window

Showing 1 - 3 of 3 records

#	Device Name	Customer Name	Site Name	Management Type
1.	<input type="radio"/> ce13	Customer1	east	MANAGED
2.	<input type="radio"/> ce3	Customer1	east	MANAGED
3.	<input type="radio"/> ce8	Customer1	east	MANAGED

Rows per page: 10 Go to page: 1 of 1

Select Cancel

Step 5 Click a radio button next to the device to be the source device for this physical link and then click **Select**.

Step 6 Figure 3-139, “Create Ring Window,” reappears with the chosen **Source Device**.

**Note**

When choosing the **Source Device** for a physical link, this same choice is made for the **Destination Device** for the previous physical link (or the last physical link if you are choosing for the first physical link). For a selected device, do not select the same interface for the source and destination interface.

Step 7 In the **Source Interface** column in this new version of Figure 3-139, “Create Ring Window,” click **Select source interface** and a window as shown in Figure 3-141, “Select Source Interface Window,” appears with a list of interfaces.

Figure 3-141 Select Source Interface Window

Interfaces for device **encl11**

Showing 1-6 of 6 records

#	Select	Name	IP Address	Interface Logical Name
1.	<input type="radio"/>	Ethernet0	192.168.129.189/30	
2.	<input type="radio"/>	Ethernet1	192.168.132.9/29	
3.	<input type="radio"/>	Loopback0	192.168.115.70/32	
4.	<input type="radio"/>	Loopback1	14.1.1.1/32	
5.	<input type="radio"/>	Serial0		
6.	<input type="radio"/>	Serial1		

Rows per page: 10 Go to page: 1 of 1

Select Cancel

Step 8 Click a radio button next to the interface to be the source interface for this physical link and then click **Select**.

Step 9 Figure 3-139, “Create Ring Window,” reappears with the chosen **Source Interface**.

Step 10 In the **Destination Device** column in this new version of Figure 3-139, “Create Ring Window,” click **Select destination device** and a window as shown in Figure 3-142, “Select Destination Device — CPE/PE Window,” appears.

Figure 3-142 Select Destination Device — CPE/PE Window

Showing 1 - 3 of 3 records

#	Device Name	Customer Name	Site Name	Management Type
1.	ce13	Customer1	east	MANAGED
2.	ce3	Customer1	east	MANAGED
3.	ce8	Customer1	east	MANAGED

Rows per page: 10 Go to page: 1 of 1

Select Cancel

Step 11 Click a radio button next to the device to be the destination device for this physical link and then click **Select**.

Step 12 [Figure 3-139, “Create Ring Window,”](#) reappears with the chosen **Destination Device**.

**Note**

When choosing the **Destination Device** for the a physical link, this same choice is made for the next **Source Device**. Do not choose the same Interface for these devices.

Step 13 In the **Destination Interface** column in this new version of [Figure 3-139, “Create Ring Window,”](#) click **Select destination interface** and a window as shown in [Figure 3-143, “Select Destination Interface Window,”](#) appears with a list of interfaces.

Figure 3-143 Select Destination Interface Window

Showing 1-10 of 18 records

#	Select	Name	IP Address	Interface Logical Name
1.	<input type="radio"/>	ATM5/0		
2.	<input type="radio"/>	Ethernet2/0		
3.	<input type="radio"/>	Ethernet2/1		
4.	<input type="radio"/>	Ethernet2/2		
5.	<input type="radio"/>	Ethernet2/3		
6.	<input type="radio"/>	FastEthernet0/0		
7.	<input type="radio"/>	FastEthernet4/0		
8.	<input type="radio"/>	Hssi1/0		
9.	<input type="radio"/>	Hssi1/1		
10.	<input type="radio"/>	Loopback0	192.168.115.64/32	

Rows per page: 10 Go to page: 1 of 2

Select Cancel

Step 14 Click a radio button next to the interface to be the destination interface for this NPC and then click **Select**.

Step 15 [Figure 3-139, “Create Ring Window,”](#) reappears with the chosen **Destination Interface**.

- Step 16** Repeat [Step 4](#) to [Step 15](#) for the middle physical links and [Step 4](#) to [Step 9](#) for the last physical link.
- Step 17** If you want to insert an extra physical link in the ring, select the check box for the line that represents the physical link you want the new physical link to follow and click **Insert**. Implement [Step 4](#) to [Step 15](#) to fill in the remaining entries in this new physical link.
- Step 18** If you want to delete a physical link in the ring but a minimum of three physical links will remain, select the check box for the line that represents the physical link you want to delete and click **Delete**.
- Step 19** If you want to establish additional cross links between non-adjacent devices in this ring, you can click **Edit Cross Links** in [Figure 3-139](#), “[Create Ring Window](#),” and you then view a new window like [Figure 3-139](#) with no entry. Click the **Add** button and you can choose from the devices already in your ring. The result is a new entry in [Figure 3-139](#) with this device as the **Source Device**. Establish the Destination Device and Source and Destination Interfaces as you did when creating the ring. The choices of devices and interfaces is limited to those already established in your ring.
- Step 20** When you are completed setting up your ring, click **Save**.
- Step 21** The new ring is added in [Figure 3-138](#), “[NPC Rings Window](#),” and a green check for Succeeded appears. The new ring is identified by the source device-source interface.
- Step 22** To create a ring with more than three physical links, select the check box for the link in [Figure 3-139](#) on [page 3-146](#) to which you want to insert and the **Insert** button is then enabled. Proceed in adding links as explained in this section.

Editing NPC Rings

To edit NPC rings, follow these steps:



Note

If the specified NPC Ring is participating in any of the Named Physical Circuits, then you can not edit the ring. An error message appears containing IDs of the NPCs that contain the NPC Ring.

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > NPC Rings** and a window as shown in [Figure 3-144](#), “[NPC Rings Window](#),” appears.

Figure 3-144 NPC Rings Window

101989

- Step 2** Select the check box next to the line that represents an NPC ring and then click **Edit**. A window as shown in [Figure 3-139](#), “[Create Ring Window](#),” appears with all the data for this ring. Proceed as in the “[Creating NPC Rings](#)” section on [page 3-146](#) to make any changes you want.
- Step 3** When you have the ring as you want it, click **Save**.
- Step 4** [Figure 3-138](#), “[NPC Rings Window](#),” appears with the appropriate name (source device-source interface) and a green check for Succeeded appears.

Deleting NPC Rings

To delete NPC rings, follow these steps:



Note

If the specified NPC Ring is participating in any of the Named Physical Circuits, then you can not delete the ring. An error message appears containing IDs of the NPCs that contain the NPC Ring.

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > NPC Rings** and a window as shown in [Figure 3-145](#), “[NPC Rings Window](#),” appears.

Figure 3-145 NPC Rings Window

- Step 2** Select the check box(es) next to the line(s) that represent(s) NPC ring(s) that you want to delete and then click **Delete**. A window as shown in [Figure 3-146](#), “[Delete Rings Window](#),” appears with the chosen ring(s) for deletion.

Figure 3-146 Delete Rings Window

#	Name
1.	2-ence11-Ethernet0

Rows per page: 10

Go to page: 1 of 1

101991

- Step 3** Click **Cancel** if you change your mind about deleting the chosen ring(s) or click **Delete** to actually delete the ring.
- Step 4** [Figure 3-145](#), “NPC Rings Window,” appears with the remaining ring names and a green check for Succeeded appears.



Service Inventory—Discovery

This chapter describes how to use the Discovery feature to discover devices, connections, and services for the IP Solution Center (ISC) provisioning process. It contains the following sections:

- [Overview of ISC Discovery, page 4-1](#)
- [Technical Notes for ISC Discovery, page 4-3](#)
- [Summary of Tasks for Discovery \(Cisco ISC MPLS VPN Management and L2VPN Management\), page 4-6](#)
- [Summary of ISC Discovery Steps for MPLS Diagnostics Expert, page 4-10](#)
- [Step 1: Perform Preliminary Steps, page 4-13](#)
- [Step 2: Perform Device Discovery, page 4-26](#)
- [Step 3: Perform Configuration Collection, page 4-36](#)
- [Step 4: Perform Role Assignment, page 4-36](#)
- [Step 5: Perform NPC Discovery, page 4-49](#)
- [Step 6: Perform MPLS VPN Service Discovery \(Optional\), page 4-56](#)
- [Step 7: Perform L2VPN \(Metro Ethernet\) Service Discovery \(Optional\), page 4-65](#)
- [Step 8: Create and Run a Collect Config Task for the Discovered Devices, page 4-77](#)
- [Step 9: View and Edit Services, page 4-78](#)

Overview of ISC Discovery

ISC simplifies the process for building a network device inventory by discovering the devices, connections, and services that your MPLS VPN or L2VPN Metro Ethernet network comprises.

The ISC Discovery feature can be used to provision three of the applications in the Cisco ISC application suite:

- Cisco IP Solution Center MPLS VPN Management
- Cisco IP Solution Center L2 VPN Management
- Cisco IP Solution Center MPLS Diagnostics Expert

The Cisco IP Solution Center Traffic Engineering Management has its own Discovery interface and process. This is documented in Chapter 3 of the [Cisco IP Solution Center Traffic Engineering Management User Guide, 4.1](#), “TE Network Discovery,” at the following URL:

http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/tem/isctmu03.htm

The Discovery process stores the information that it discovers in the ISC Repository database. Therefore, each time that you run Discovery, the existing Repository and any configuration information in it is overwritten. For this reason, you normally run Discovery only once.

The Discovery process provides you with several choices on how to discover your network topology.

1. If you are running Discovery to provision Cisco IP Solution Center MPLS VPN Management or Cisco IP Solution Center L2 VPN Management, you can choose between two Discovery methods:
 - You can use the Cisco Discovery Protocol (CDP) to discover devices connected to an initial device whose IP address you provide in a **policy.xml** file.
 - You can use a device and topology based method. This method uses XML files that specify device and NPC topology information.


Note

If you are using ISC Discovery with Cisco IP Solution Center MPLS Diagnostics Expert, then you *must* use Device/Topology based Discovery.

2. You can choose the network topology to discover
 - You can discover an MPLS VPN topology, a L2VPN (Metro Ethernet) topology, or both.
 - If you choose L2VPN (Metro Ethernet) Discovery, you can discover either a Metro Ethernet with an MPLS core or a Metro Ethernet with an Ethernet core; however, you cannot discover both an MPLS VPN core and an Ethernet core.

Figure 4-1 illustrates the phases in the Discovery process.

Figure 4-1 **ISC Discovery Steps**




Table 4-1 describes the phases in the Discovery process.

Table 4-1 Steps in the Discovery Process

Step	Description
Device Discovery	Discovers devices in the MPLS VPN and/or Metro Ethernet topology.
Collect Configuration	Collects the IOS configuration for the devices
Role Assignment	Prompts you to assign devices as PEs or CEs and specify the device role in the network topology.
NPC Discovery	Displays discovered NPCs and allows addition or removal of NPCs.
MPLS VPN Discovery	Discovers the topology for your MPLS VPN network and lets you change it as required. Note The MPLS VPN Discovery step is not required if you are using ISC Discovery with Cisco IP Solution Center MPLS Diagnostics Expert.
(L2VPN) Metro Ethernet Discovery	Discovers the topology for your Metro Ethernet network and lets you change it as required. Note The (L2VPN) Metro Ethernet Discovery step is not required if you are using ISC Discovery with Cisco IP Solution Center MPLS Diagnostics Expert.

Technical Notes for ISC Discovery

This section presents technical tips and general information about the ISC Discovery process.

The ISC Discovery feature can be used to provision three of the applications in the Cisco ISC application suite:

- Cisco IP Solution Center MPLS VPN Management
- Cisco IP Solution Center L2VPN Management
- Cisco IP Solution Center MPLS Diagnostics Expert

Although the general steps are similar, there are some differences in the workflow for the various types of Discovery. These are described in the section covering each ISC application:

- [Using ISC Discovery with Cisco IP Solution Center MPLS VPN Management, page 4-5](#)
- [Using ISC Discovery With Cisco IP Solution Center L2VPN Management, page 4-5](#)
- [Using ISC Discovery With Cisco IP Solution Center MPLS Diagnostics Expert, page 4-5](#)
- [Using ISC Discovery With Cisco IP Solution Center Traffic Engineering Management, page 4-6](#)

**Note**

Cisco IP Solution Center Traffic Engineering Management has its own Discovery interface and process. This is documented in Chapter 3 of the *Cisco IP Solution Center Traffic Engineering Management User Guide, 4.1*, “TE Network Discovery,” at the following URL:

http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/tem/isctmu03.htm

For technical notes on using ISC Discovery in installations that include both Cisco IP Solution Center Traffic Engineering Management and Cisco IP Solution Center MPLS VPN Management, see [Using ISC Discovery With Cisco IP Solution Center Traffic Engineering Management, page 4-6](#).

General Notes

Note the following points before running ISC Discovery.

- When you run Discovery, the entire existing Repository and any configuration information in it is overwritten. For this reason, you normally run Discovery only once.
- If you plan to use ISC discovery, do not enter any inventory objects using the ISC GUI before you run the Discovery process or start provisioning or any other activity.
- Make sure that you start with a blank Repository as described in [Ensure the Repository Is Empty, page 4-15](#).
- Only one user can control the Discovery workflow interface at a given time.
- The procedures in the chapter show a “generic” procedure. If you do not have licenses for a particular application, you will not see the selections for that application on the start screen for ISC Discovery.
- Perform “manual” device collection after discovery is over.
- The **inventory.xml** file is required, however it can be empty.
- After you have started the Discovery process, a **Restart** button appears on the Discovery Workflow window. You can click the **Restart** button to restart the Discovery process. However, note the following regarding the Restart button.
 - If you restart the Discovery process, any work done during the Discovery workflow is discarded and you will start at the beginning, with a blank Repository.
 - You cannot restart the process after the final Discovery step (Service Discovery) is complete. At that point the **Restart** button no longer appears on the Discovery Workflow window.

Using the Discovery Log Files

A log file is written for each phase of the Discovery process. You can view a log file by clicking the **View** selection in the Log column next to each discovery phase summary on the Discovery Workflow window.

The log file provides useful information in the event a discovery step fails.

Using ISC Discovery with Cisco IP Solution Center MPLS VPN Management

If you are running the Discovery process to discover an MPLS VPN network that will be provisioned and managed using Cisco IP Solution Center MPLS VPN Management note the following points:

- You must perform all of the main steps in the Discovery process.
- You can use either CDP Discovery or Device/Topology based Discovery
- ISC does not support partial mesh VPN topologies. If the Discovery process discovers a Partial Mesh VPN, you must split the partial mesh VPN into smaller units (usually a combination of full mesh VPNs and Hub and Spoke VPNs).
- After completion of the automated Discovery process, you must schedule and run a **Task Manager > Collect Config** task for all discovered devices.

Using ISC Discovery With Cisco IP Solution Center L2VPN Management

If you are running the Discovery process to discover an MPLS VPN network that will be provisioned and managed using Cisco IP Solution Center L2VPN Management, note the following points:

- You must perform all of the main steps in the Discovery process.
- You can use either CDP Discovery or Device/Topology based Discovery
- The Discovery process for Cisco IP Solution Center L2VPN Management can discover Metro Ethernet with either an MPLS core or an Ethernet core, but not both.
- Prior to performing the NPC Discovery step for Cisco IP Solution Center L2VPN Management, you must use the Inventory Manager interface to do the following:
 - Assign Access Domains
 - Create Resource Pools
 - Edit Inter N-PE Interfaces
- After completion of the automated Discovery process, you must schedule and run a **Task Manager > Collect Config** task for all discovered devices.

Using ISC Discovery With Cisco IP Solution Center MPLS Diagnostics Expert

If you are running the Discovery process to provision Cisco IP Solution Center MPLS Diagnostics Expert, note the following points.

- You cannot use CDP Discovery with Cisco IP Solution Center MPLS Diagnostics Expert. You *must* use Device/Topology based Discovery.
- You must provide a **topology.xml** file in order for Device Discovery to run. However, this file can be “blank,” in effect, you can code a **<topology>** tag and a **</topology>** tag that do not include any connection entries.

See [Coding the topology.xml File, page 4-24](#) for more information on coding the **topology.xml** file

- For Cisco IP Solution Center MPLS Diagnostics Expert, you only need to perform the Device Discovery, Collect Configuration, and Role Assignment Steps. You do not need to perform the NPC Discovery step or the Service Discovery step. However, you can let the NPC Discovery process run.

See [Figure 4-4 on page 4-11](#) for a flowchart of the required steps for ISC Discovery with Cisco IP Solution Center MPLS Diagnostics Expert.

- If you are using Cisco IP Solution Center MPLS Diagnostics Expert, then you normally only need to discover PE devices. Therefore, when you perform the Role Assignment step for discovered devices, you only need to assign roles to the P and PE devices.



Note If you do discover any CE devices, you must assign them CE roles.

- After completion of the automated Discovery process, you must schedule and run a **Task Manager > Collect Config** task for all discovered devices.

Using ISC Discovery With Cisco IP Solution Center Traffic Engineering Management

Normally you do not have to run the ISC Discovery process if you are using Cisco IP Solution Center Traffic Engineering Management. Cisco IP Solution Center Traffic Engineering Management has its own discovery process. This process is documented in Chapter 3 of the *Cisco IP Solution Center Traffic Engineering Management User Guide, 4.1*, “TE Network Discovery,” at the following URL:

http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/tem/isctmu03.htm

However, if you are running *both* Cisco IP Solution Center Traffic Engineering Management (TEM) and Cisco IP solution Center MPLS VPN Management, you must run the Discovery process for Cisco IP solution Center MPLS VPN Management.

Note the following points:

- One region (default region) is used for TEM
- If you are also running ISC Discovery for MPLS VPN Management, make sure that you run the Discovery workflow described in this chapter FIRST, and then run the Cisco IP Solution Center Traffic Engineering Management process later.

Summary of Tasks for Discovery (Cisco ISC MPLS VPN Management and L2VPN Management)

Figure 4-2 provides a general workflow diagram for the Discovery process used with the Cisco IP Solution Center MPLS VPN Management or Cisco IP Solution Center L2 VPN Management application.



Note

Figure 4-4 on page 4-11 provides a general workflow diagram for the Discovery process as used with the MPLS Diagnostics Expert application.

Figure 4-2 *Basic Workflow for Discovery with Cisco ISC MPLS VPN Management or Cisco ISC L2VPN Management*




Table 4-2 describes each task in the Discovery workflow for Cisco ISC MPLS VPN Management and Cisco ISC L2VPN Management.

Table 4-2 *Description of Discovery Steps for MPLS VPN Management and L2VPN Management*


Step	Description
Step 1: Perform Preliminary Steps	<p>Perform preliminary steps that are required for ISC Discovery. See Step 1: Perform Preliminary Steps, page 4-13.</p> <ul style="list-style-type: none"> Review System Requirements See Review System Requirements, page 4-14. Ensure the Repository Is Empty See Ensure the Repository Is Empty, page 4-15 Install Licenses See Install Licenses, page 4-15 (CDP Discovery Only) Verify That There a Unique TIBCO Port Is Defined See (CDP Discovery Only) Verify That a Unique TIBCO Port Is Defined, page 4-16 (CDP Discovery Only) Verify That CDP is Running on Devices To Be Discovered See (CDP Discovery Only) Verify That CDP Is Running on Devices To Be Discovered, page 4-16 Code XML Files Required for Discovery See Code XML Files Required for Discovery, page 4-17
Step 2: Perform Device Discovery	<ul style="list-style-type: none"> Start Device Discovery See Starting Device Discovery, page 4-27. After Device Discovery is complete, enter device passwords For information on entering device passwords, see Setting Password Attributes (Required Step), page 4-32. Enter additional device information as required See Setting General Device Attributes, page 4-34 and Setting Cisco CNS Attributes, page 4-35.
Step 3: Perform Configuration Collection	Start configuration collection. No input is required for this step. See Step 3: Perform Configuration Collection , page 4-36.
Step 4: Perform Role Assignment	Assign device roles to each device. See Step 4: Perform Role Assignment , page 4-36.

Table 4-2 *Description of Discovery Steps for MPLS VPN Management and L2VPN Management (continued)*

Step	Description
Step 5: Perform NPC Discovery	<p>If you are discovering a Metro Ethernet Network with an Ethernet Core, perform the required preliminary steps. See Preliminary Steps Before Completing NPC Discovery for Metro Ethernet Networks with an Ethernet Core, page 4-49</p> <ul style="list-style-type: none"> Start NPC Discovery See Step 5: Perform NPC Discovery, page 4-49 Modify and/or add NPCs as required. See Adding a Device for an NPC, page 4-53, Adding a Ring, page 4-54, Inserting a Device, page 4-55, Inserting a Ring, page 4-55, or Deleting a Device or a Ring, page 4-55.
Step 6: Perform MPLS VPN Service Discovery (optional)	<p>Start MPLS VPN Service Discovery. See Step 6: Perform MPLS VPN Service Discovery (Optional), page 4-56.</p> <p>This step is required for the Cisco IP Solution Center MPLS VPN Management application,</p> <p>Note This step is not required for the Cisco IP Solution Center L2VPN Management application or the Cisco IP Solution Center MPLS Diagnostics Expert application.</p>
Step 7: Perform L2VPN Service Discovery (optional)	<p>Specify discovery of an MPLS core or an Ethernet Core and then start L2VPN Service discovery. See Step 7: Perform L2VPN (Metro Ethernet) Service Discovery (Optional), page 4-65.</p> <p>This step is required for the Cisco IP Solution Center L2VPN Management application.</p> <p>Note This step is not required for the Cisco IP Solution Center MPLS VPN Management application or the Cisco IP Solution Center MPLS Diagnostics Expert application.</p>
Step 8: Create and Run a Collect Config Task for Discovered Devices	<p>From the ISC Start Page, select Monitoring > Task Manager. Select the Collect Config task and select all of the devices discovered in the Device Discovery step; then submit the task.</p> <p>See Step 8: Create and Run a Collect Config Task for the Discovered Devices, page 4-77.</p>
Step 9: View and Edit Services	<p>View the services that have been created and modify them as required. See Step 9: View and Edit Services, page 4-78.</p>

Within each step, additional tasks must be performed and choices must be made. [Figure 4-3](#) shows a detailed flowchart that illustrates all of the steps in the Discovery workflow.

Figure 4-3 Detailed Diagram of Discovery Steps (Cisco ISC MPLS VPN Management and Cisco ISC L2VPN Management)



138984

Summary of ISC Discovery Steps for MPLS Diagnostics Expert

Figure 4-4 shows the basic Discovery steps for Cisco ISC with the MPLS Diagnostics Expert (MDE) application. For MDE, several of the steps required for Cisco ISC MPLS VPN Management and Cisco ISC L2VPN Management are not required.


Figure 4-4 *Discovery Workflow for the MPLS Diagnostics Expert Application*

Table 4-3 *Description of Discovery Steps for MPLS Diagnostics Expert*

Step	Description
Step 1: Perform Preliminary Steps	<p>Perform preliminary steps that are required for ISC Discovery.</p> <ul style="list-style-type: none"> • Review System Requirements See Review System Requirements, page 4-14. • Ensure the Repository Is Empty See Ensure the Repository Is Empty, page 4-15 • Install Licenses See Install Licenses, page 4-15 • Code XML Files Required for Discovery If you are running ISC Discovery with Cisco MDE, you must use the Device/Topology based Discovery method. For this method, you need to code an inventory.xml file, a device.xml file, and a topology.xml file. However, the topology.xml file, although it must be present, does not have to contain any actual topology entries. For specific instructions, see the following sections: <ul style="list-style-type: none"> – Coding the inventory.xml File, page 4-17 – Coding the device.xml File, page 4-22 – Coding the topology.xml File, page 4-24
Step 2: Perform Device Discovery	<ul style="list-style-type: none"> • Start Device Discovery See Starting Device Discovery, page 4-27. • After Device Discovery is complete, enter device passwords For information on entering device passwords, see Setting Password Attributes (Required Step), page 4-32. • Enter additional device information as required See Setting General Device Attributes, page 4-34 and Setting Cisco CNS Attributes, page 4-35.
Step 3: Perform Configuration Collection	<p>Start configuration collection. No input is required for this step. See Step 3: Perform Configuration Collection, page 4-36.</p>

Table 4-3 Description of Discovery Steps for MPLS Diagnostics Expert (continued)


Step	Description
Step 4: Perform Role Assignment	<p>Assign device roles to each device. See Step 4: Perform Role Assignment, page 4-36.</p> <p>For MDE, you normally discover only PEs and assign PE roles to them. However, if you discover CEs, assign CE roles to the CE devices.</p> <p>Note Although you do not have to edit NPCs for MPLS Diagnostics Expert, after you perform role assignment this step should complete.</p>
Step 5: Create and Run a Collect Config Task for Discovered Devices	<p>From the ISC Start Page, select Monitoring > Task Manager. Select the Collect Config task and select all of the devices discovered in the Device Discovery step; then submit the task.</p> <p>See Step 8: Create and Run a Collect Config Task for the Discovered Devices, page 4-77.</p>

Step 1: Perform Preliminary Steps

Before you initiate the ISC Discovery process, complete the following preliminary steps:

- Review System Requirements
- Ensure the Repository Is Empty
- Install Licenses
- (CDP Discovery Only) Verify That a Unique TIBCO Port Is Defined
- (CDP Discovery Only) Verify That CDP is Running on Devices To Be Discovered
- Code XML Files Required for Discovery

[Figure 4-5](#) summarizes the preliminary steps for ISC Discovery.

Figure 4-5 Summary of Preliminary Steps for Discovery

138987

Review System Requirements

Cisco recommends that you thoroughly review the system requirements for ISC 4.1 before planning your installation, to be sure that you have all the hardware and software which you must successfully install.

The system recommendations and requirements for ISC 4.1 are listed in Chapter 1, “System Recommendations” of the *Cisco IP Solution Center Installation Guide, 4.1*. This document is located at the following URL:

http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/install/index.htm

Ensure the Repository Is Empty

To run successfully, ISC Discovery requires a Repository that is empty of inventory objects. Before you run the Discovery process, start with a new installation or copy an empty Repository before starting the watchdog.

Note also that migrated repositories are not supported and discovery is disabled in these installations.

Copying an Empty Repository

If you copy an empty Repository, make sure that the database is initialized. Follow these steps to copy a Repository and initialize it:

-
- Step 1** Copy the empty Repository.
- a. If there is an existing Repository, delete it or save it to a backup directory.
 - b. Copy the empty Repository.
- Step 2** Issue the following commands to initialize the database.
- ```
> startdb

> initdb.sh

> startwd
```
- 

## Install Licenses

Before starting Discovery, the appropriate licenses (both Activation and VPN licenses) must be installed. Also, each license must be large enough to handle all possible discovered objects. For information on installing licenses, see the “Installing License Keys” section of Chapter 2 of the *Cisco IP Solution Center Installation Guide, 4.1*, “Installing and Logging Into ISC” at the following URL:

[http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4\\_1/install/instlog.htm](http://www.cisco.com/univercd/cc/td/doc/product/rtrmgmt/isc/4_1/install/instlog.htm)

## (CDP Discovery Only) Verify That a Unique TIBCO Port Is Defined


If you are using CDP Discovery to discover the network topology, make sure the TIBCO Port is unique. Otherwise, CDP discovery will fail.

During installation, the TIBCO port can be specified if the “custom” Installation Type is selected at the start of the installation process. Otherwise, the default port installed is 7530. You specify the TIBCO port on the Choose TIBCO Port dialog.

The port number that is specified must be unique throughout the network, and no other ISC installations are allowed with the same port.

Figure 4-6 shows the Choose TIBCO port dialog.

**Figure 4-6** Choose TIBCO Port



## (CDP Discovery Only) Verify That CDP Is Running on Devices To Be Discovered

If CDP Discovery is going to be used, use the **show cdp** command to ensure that CDP is running on all of the devices intended to be discovered.

For each device, enter the **show cdp** command as shown in Example 4-1.

**Example 4-1** The **show cdp** Command:

```
Router# show cdp
Global CDP information:
 Sending CDP packets every 120 seconds
 Sending a holdtime value of 180 seconds
 Sending CDPv2 advertisements is enabled
Router#
```

## Code XML Files Required for Discovery

Before you can run ISC Discovery, you must code XML files that are required for the Discovery process. A different set of files is required, depending on whether you use CDP Discovery or Device/Topology based Discovery.

Table 4-4 describes the XML files and indicates which files are required for each type of discovery method.

**Table 4-4** XML Files Used with ISC Discovery

| XML File             | Description                                                                                                                                                                     | Required for CDP Discovery | Required for Device/Topology Based Discovery |
|----------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------|----------------------------------------------|
| <b>inventory.xml</b> | Specifies rules used to create provider names and associated provider regions and discovers customers and sites based on a set of customer, site, provider, and region objects. | Yes                        | Yes                                          |
| <b>policy.xml</b>    | Specifies one or more seed IP addresses that can be reached from the specified seed device and a maximum hop count for the device discovery process                             | Yes                        | No                                           |
| <b>device.xml</b>    | Specifies information used to locate devices, such as device IP addresses and Object IDs (OIDs).                                                                                | No                         | Yes                                          |
| <b>topology.xml</b>  | Specifies information used to build the MPLS NPC VPN and/or Metro Ethernet topology.                                                                                            | No                         | Yes                                          |



**Note**

Make sure that the coding in your XML files is accurate. If there are errors in the files, you might need to re-run the Discovery process.

## Sample XML Files

The initial installation of ISC 4.1 provides sample XML files that you can use as a starting point in coding your own XML files. The sample XML files are located in the following directory:

```
<install_directory>/resources/discovery/sample
```

where *install\_directory* is the installation directory that you specified when prompted by the ISC installation program.

## Coding the inventory.xml File

The **inventory.xml** file:

- Is required for both CDP-based Discovery and Device/Topology based Discovery.
- Specifies rules used to create provider names and associated provider regions and discovers customers and sites based on a set of customer, site, provider, and region objects.

- Is not required if you are provisioning only the Cisco IP Solution Center Traffic Engineering Management application.

Example 4-2 shows the sample **inventory.xml** file that is provided with the ISC 4.1 installation.

#### Example 4-2 Sample inventory.xml File

```
<?xml version="1.0" encoding="UTF-8" ?>
- <create-inventory xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xsi:noNamespaceSchemaLocation="../xml_schemas/inventory.xsd">
 <!--

 This is a sample inventory.xml file. The inventory XML file will be used
 by the ISC discovery process to create an inventory of Provider,
 Customer, Site and Region objects in the discovery staging Repository.
```

Note: Please change the xsi:noNamespaceSchemaLocation attribute above to point to the actual XML schema as following:

```
 xsi:schemaLocation="http://<isc server name>:<isc server
port>/isc/home/discovery/inventory.xsd
```

```
-->
 <!--
```

The following sample creates one provider "Cisco" with AS number 100 and three regions.

```
-->
<create-provider>
<provider-name>Cisco</provider-name>
<as-number>100</as-number>
<create-region>
<region-name>Cisco HQ</region-name>
</create-region>
 <create-region>
<region-name>Cisco SJ</region-name>
</create-region>
 <create-region>
<region-name>Cisco NYC</region-name>
</create-region>
</create-provider>
 <!--
```

The following sample creates a customer "Customer1" with two sites.

```
-->
<create-customer>
<customer-name>Customer1</customer-name>
<create-site>
<site-name>C1S1</site-name>
</create-site>
 <create-site>
<site-name>C1S2</site-name>
</create-site>
</create-customer>
 <!--
```

The following sample creates a customer "Customer2" with two sites.

```
-->
 <create-customer>
<customer-name>Customer2</customer-name>
<create-site>
<site-name>C2S1</site-name>
</create-site>
 <create-site>
<site-name>C2S2</site-name>
</create-site>
</create-customer>
</create-inventory>
```

Table 4-5 describes the XML tags used in the **inventory.xml** file.

**Table 4-5 XML Tags Used in the inventory.xml File**

Tag	Description
<b>&lt;create-provider&gt;</b>	Starts a <b>create-provider</b> rule. The <b>create-provider</b> rule creates a service provider object.  The <b>create-provider</b> rule must contain the following tags: <ul style="list-style-type: none"> <li>• <b>&lt;provider-name&gt;</b></li> <li>• <b>&lt;as-number&gt;</b></li> <li>• <b>&lt;create-region&gt;</b></li> </ul>
<b>&lt;provider-name&gt;</b>	Specifies the name of the provider.
<b>&lt;as-number&gt;</b>	Specifies the autonomous system (AS) number for the provider. The AS number can be an integer between 1 and 65535.
<b>&lt;create-region&gt;</b>	Starts a <b>create-region</b> rule. The <b>create-region</b> rule creates a region object. The <b>create-region</b> rule must contain a <b>region-name</b> tag.
<b>&lt;region-name&gt;</b>	Specifies the name of a region.
<b>&lt;customer-name&gt;</b>	Specifies a customer name. Required within the <b>create-customer</b> rule.
<b>&lt;create-customer&gt;</b>	Starts a <b>create-customer</b> rule. The <b>create-customer</b> rule creates a region object. the <b>create-customer</b> rule must contain the following tags: <ul style="list-style-type: none"> <li>• <b>&lt;customer-name&gt;</b></li> <li>• <b>&lt;create-site&gt;</b></li> </ul>
<b>&lt;create-site&gt;</b>	Starts a <b>create-site</b> rule. The <b>create-site</b> rule must contain a <b>&lt;site-name&gt;</b> tag.
<b>&lt;site-name&gt;</b>	Specifies a site name.

The **inventory.sample.xml** file that is provided with the initial ISC installation specifies provider names, provider regions, customer names, and customer sites that are used in the Discovery process.

You must provide this file for both Discovery methods—CDP-based Discovery and Device/Topology based Discovery.

Follow these steps to edit the **inventory.xml** file:

- Step 1** Edit the information provided in the sample file and replace it with information that is accurate for your network
- To specify providers, include **create-provider** rules:

## Step 1: Perform Preliminary Steps

- Edit the values provided with the **provider-name** XML tag and replace them with provider names for your MPLS VPN network.
- For each provider name that you specify, edit the values provided with the **region-name** XML tags after the provider names and replace them with provider regions for your MPLS VPN network.
- b. To specify customer names, edit the values provided with the **customer-name** XML tag and replace them with customer names for your network.
- To specify customer sites, include **create-customer** rules:
- edit the values provided with the **customer-site** XML tags after the customer names and replace them with customer sites for your MPLS VPN network.

**Step 2** Save the **inventory.sample.xml** file in the following file:

**inventory.xml**

**Step 3** Place the **inventory.xml** file in an appropriate directory on the ISC host.

---

## Coding the policy.xml File

The **policy.xml** file:

- Is required for CDP Discovery.
- Is not required for Device/Topology based Discover.
- Is not required for Cisco IP Solution Center MPLS Diagnostics Expert or Cisco IP Solution Center Traffic Engineering Management.
- Provides a seed IP address that the CDP protocol uses to discover devices near the seed device.

[Example 4-3](#) shows the sample **policy.xml** file that is provided with the ISC installation.

### Example 4-3 Sample policy.xml File

```
<?xml version='1.0' encoding='UTF-8'?>
<DISCOVERY_POLICY overwrite_existing_policy="true">
 <DISCOVERY_METHOD>
 <CDP ipaddress="209.168.133.232" hop="1"/>
 </DISCOVERY_METHOD>
 <SNMP_COMMUNITY>
 <RO_COMMUNITY>
 <COMMUNITY community="public"/>
 </RO_COMMUNITY>
 <RW_COMMUNITY>
 <COMMUNITY community="public"/>
 </RW_COMMUNITY>
 </SNMP_COMMUNITY>
</DISCOVERY_POLICY>
```

If there are additional routers that are on the other side of PE routers on the edge of the core segment of the network, you can specify more than one seed IP address in order to discover these devices.

[Example 4-4](#) shows a **policy.xml** file that contains two seed IP addresses.

**Example 4-4 Policy.xml File with Two IP Addresses**

```
<?xml version='1.0' encoding='UTF-8'?>
<DISCOVERY_POLICY overwrite_existing_policy="true">
 <DISCOVERY_METHOD>
 <CDP ipaddress="209.168.133.241" hop="8"/>
 </DISCOVERY_METHOD>
 <DISCOVERY_METHOD>
 <CDP ipaddress="209.168.133.244" hop="8"/>
 </DISCOVERY_METHOD>
 <SNMP_COMMUNITY>
 <RO_COMMUNITY>
 <COMMUNITY community="public"/>
 </RO_COMMUNITY>
 <RW_COMMUNITY>
 <COMMUNITY community="private"/>
 </RW_COMMUNITY>
 </SNMP_COMMUNITY>
</DISCOVERY_POLICY>
```

Table 4-6 describes the XML tags used in the **policy.xml** file.

**Table 4-6 XML Tags and Attributes Used in the policy.xml File**

Tag	Description
<DISCOVERY_METHOD>	Starts a <DISCOVERY_METHOD> tag. The <DISCOVERY_METHOD> tag must contain a <CDP> tag.
<CDP>	Starts a <CDP> tag. The <CDP> tag specifies an seed IP address and a hop count.  The <CDP> tag must contain the following attributes: <ul style="list-style-type: none"> <li>• <b>ipaddress</b></li> <li>• <b>hop</b></li> </ul>
<b>ipaddress</b>	Specifies the IP address of a seed device. Required attribute for the <CDP> tag.
<b>hop</b>	Specifies the number of hops from the device identified by the ipaddress attribute to go in discovering devices. Required attribute for the <CDP> tag.

Follow these steps to edit the sample **policy.xml** file:

- Step 1** Edit the sample file and replace the IP address specified with the **ipaddress** XML attribute with an appropriate IP address from your network.

This IP address is a device that can be reached from the ISC host. For each seed device, an accessible interface on the starting point is configured, because the management interface must be provided. The management interface is the address on the device that the ISC host uses to reach the device.



**Note** You can provide more than one IP address. This is useful in situations where one network domain is on the other side of a PE router on the edge of the core segment of the network.

- Step 2** Edit the hop count specified with the **hop** attribute and specify a hop count that will be used when the Discovery process is initialized.
- When you choose the seed devices and hop count, pick a seed device that can reach a large section of the network. Pick one or more of them until you think these devices will enable you to reach your entire managed network.
- Point-of-presence (POP) routers are usually good choices. If you choose all the POPs in your network as the collection of seed devices and put in the appropriate number of hubs, you discover the entire managed network.
- To pick the hop count number, go to the CE that is the furthest from its associated POP, and count the number of devices between them. If this number is N, the hop number is N+1, assuming you are picking the POP as the seed.
- Step 3** If you need to add additional IP addresses for seed devices, code additional **<DISCOVERY\_METHOD>** tags.
- Within the additional **<DISCOVERY\_METHOD>** tags, include **<CDP>** tags.
- For each **<CDP>** tag, specify an IP address with the **ipaddress** attribute and a hop count with the **hops** attributes.
- Step 4** Save the **policy.xml** file to an appropriate directory on the ISC host.
- 

When you run the Discovery process, the process queries the starting point device for its CDP table. From this table, all of those devices are queried for their CDP information. This process continues until the maximum hop count from the starting point is reached. When you use the CDP-based method, note that only devices running CDP are discovered.

## Coding the device.xml File

The **device.xml** file:

- Is required for Device/Topology based Discovery.
- Is not required for CDP-based Discovery.
- Is required for Cisco IP Solution Center MPLS VPN Management, Cisco IP Solution Center L2VPN Management, and ISC MPLS Diagnostics Expert.
- Is not required for Cisco IP Solution Center Traffic Engineering Management.
- Specifies information used to locate devices, such as device IP addresses and Object IDs (OIDs).

[Example 4-5](#) shows a sample **device.xml** file. Use the sample file as an example and save your edited file in an appropriate directory.

### Example 4-5 Sample device.xml file

```
<network>
<device>
<device-name>mlpe8</device-name>
<ip-address>209.168.133.244</ip-address>
<system-object-id>.1.3.6.1.4.1.9.1.509</system-object-id>
<snmp-info>
<ro-community>public</ro-community>
</snmp-info>
</device>
```



```

<device>
<device-name>mlsw11</device-name>
<ip-address>209.168.133.170</ip-address>
<system-object-id>.1.3.6.1.4.1.9.1.574</system-object-id>
<snmp-info>
<ro-community>public</ro-community>
</snmp-info>
</device>

<device>
<device-name>mlsw16</device-name>
<ip-address>209.168.133.175</ip-address>
<system-object-id>.1.3.6.1.4.1.9.1.574</system-object-id>
<snmp-info>
<ro-community>public</ro-community>
</snmp-info>
</device>

<device>
<device-name>mlsw17</device-name>
<ip-address>209.168.133.176</ip-address>
<system-object-id>.1.3.6.1.4.1.9.1.574</system-object-id>
<snmp-info>
<ro-community>public</ro-community>
</snmp-info>
</device>

</network>

```

Table 4-7 describes the XML tags used in the **device.xml** file.

**Table 4-7 XML Tags Used in the device.xml File**

Tag	Description
<device>	<p>Starts a &lt;device&gt; tag. The &lt;device&gt; tag must contain the following tags:</p> <ul style="list-style-type: none"> <li>• &lt;device-name&gt;</li> <li>• &lt;ip-address&gt;</li> </ul> <p>The following tags are optional within the &lt;device&gt; tag:</p> <ul style="list-style-type: none"> <li>• &lt;system-object-id&gt;</li> <li>• &lt;snmp-info&gt;</li> </ul>
<device-name>	Specifies the name of the device. Required within the <device> tag.
<ip-address>	Specifies the IP address of the device. Required within the <device> tag.
<system-object-id>	(optional) Can be included to specify the SNMP Object ID (OID) for the device. If this is provided, it is specified within the <device> tag.

**Table 4-7 XML Tags Used in the device.xml File (continued)**

Tag	Description
<b>&lt;snmp-info&gt;</b>	Specifies SNMP information for the device. The <b>&lt;snmp-info&gt;</b> tag must contain a <b>&lt;ro-community&gt;</b> tag. Optional within the <b>&lt;device&gt;</b> tag.
<b>&lt;ro-community&gt;</b>	Specifies the level of SNMP access for the device. Normally, this should be “public.” Required within the <b>&lt;snmp-info&gt;</b> tag.

Follow these steps to code the **device.xml** file:

- 
- Step 1** Edit the sample **device.xml** file provided with the installation.
- Step 2** For each device that is to be discovered by ISC, code a **<device>** entry. Each **<device>** entry must contain the following tags:
- A **<device-name>** tag specifying the device name.
  - An **<ip-address>** tag specifying the IP address for the device.
  - A **<system-object-id>** tag specifying the OID for the device.
  - An **<snmp-info>** tag specifying **<ro-community>** information
- Step 3** Save the **device.xml** file to an appropriate directory on the ISC host.
- 

## Coding the topology.xml File

The **topology.xml** file:

- Is required for Device/Topology-based Discovery.
- Is not required for CDP-based Discovery.
- Is required to perform ISC Discovery for Cisco IP Solution Center MPLS VPN Management, Cisco IP Solution Center L2VPN Management, and Cisco IP Solution Center MPLS Diagnostics Expert.



**Note** Although the **topology.xml** file is required to run Device/Topology based Discovery, when you are running ISC Discovery for the Cisco IP Solution Center MPLS Diagnostics Expert application, you can code a “blank” **topology.xml** file that contains **<topology>** and **</topology>** XML tags with no content included between the tags.

---

- Is not required for Cisco IP Solution Center Traffic Engineering Management.
- Specifies information used to locate devices, such as device IP addresses and Object IDs (OIDs).

If you choose Device/Topology based Discovery, you must code a **topology.xml** file.

The **topology.xml** file specifies the discovery protocol that is used in the discovery process, and, for each connection, specifies the starting IP address, the starting interface, the end device, and the end interface

Example 4-6 shows a sample **topology.xml** file. Use the sample file as an example and save your edited file in an appropriate directory.

**Example 4-6 Sample topology.xml File**

```
<topology>
<connection discovery-protocol="CDP" fromDevice="mlsw19" fromIP="209.168.133.178"
fromInterface="GigabitEthernet1/1/2" toDevice="mlsw21" toIP="209.168.133.220"
toIF="GigabitEthernet1/1/1" >
</connection>

<connection discovery-protocol="CDP" fromDevice="mlsw19" fromIP="209.168.133.178"
fromInterface="FastEthernet1/0/23" toDevice="mlsw21" toIP="209.168.133.220"
toIF="FastEthernet1/0/24" >
</connection>

<connection discovery-protocol="CDP" fromDevice="mlsw19" fromIP="209.168.133.178"
fromInterface="FastEthernet
1/0/24" toDevice="mlsw18" toIP="209.168.133.177" toIF="FastEthernet1/0/23" >
</connection>

<connection discovery-protocol="CDP" fromDevice="mlsw19" fromIP="209.168.133.178"
fromInterface="FastEthernet1/0/22" toDevice="mlsw22" toIP="209.168.133.221"
toIF="FastEthernet1/0/24" >
</connection>

</topology>
```

Table 4-8 describes the XML tags used in the **topology.xml** file.

**Table 4-8 XML tags and Attributes Used in the topology.xml File**

Tag	Description
<b>&lt;connection&gt;</b>	Starts a <b>&lt;connection&gt;</b> tag. The <b>&lt;connection&gt;</b> tag must specify the following attributes: <ul style="list-style-type: none"> <li>• <b>discovery-protocol</b></li> <li>• <b>fromDevice</b></li> <li>• <b>FromIP</b></li> <li>• <b>FromInterface</b></li> <li>• <b>toDevice</b></li> <li>• <b>toIP</b></li> <li>• <b>toIF</b></li> </ul>
<b>discovery-protocol</b>	Specifies the Discovery protocol used to discover the network topology. Normally, this is "CDP."
<b>fromDevice</b>	Specifies the name of the device from which the Named Physical Circuit starts. Required attribute for the <b>&lt;connection&gt;</b> tag.
<b>FromIP</b>	Specifies the management IP address of the device from which the Named Physical Circuit starts. Required attribute for the <b>&lt;connection&gt;</b> tag.

**Table 4-8 XML tags and Attributes Used in the topology.xml File (continued)**

Tag	Description
<b>FromInterface</b>	Specifies the name of the device interface from which the Named Physical Circuit starts. Required attribute for the <b>&lt;connection&gt;</b> tag.
<b>toDevice</b>	Specifies the name of the device to which the Named Physical Circuit connects. Required attribute for the <b>&lt;connection&gt;</b> tag.
<b>toIP</b>	Specifies the management IP address of the device from which the Named Physical Circuit connects. Required attribute for the <b>&lt;connection&gt;</b> tag.
<b>toIF</b>	Specifies the device interface on the device to which the Named Physical Circuit connects. Required attribute for the <b>&lt;connection&gt;</b> tag.

Follow these steps to code the **topology.xml** file:

- 
- Step 1** Edit the sample **topology.xml** file provided with the installation.
- Step 2** For each NPC connection that is to be discovered by ISC, code a **<connection>** entry. Each **<connection>** entry must contain the following tags:
- A **discovery-protocol** attribute specifying the CDP protocol.
  - A **fromDevice** attribute specifying the device from which the NPC starts.
  - A **FromIP** attribute specifying the management IP address from which the NPC starts.
  - A **FromInterface** attribute specifying the device interface from which the NPC starts.
  - A **toDevice** attribute specifying the name of the device to which the NPC connects.
  - A **toIP** attribute specifying the management IP address of the device to which the NPC connects.
  - A **toIF** attribute specifying the name of the interface on the device to which the NPC connects.
- Step 3** Save the **topology.xml** file to an appropriate directory on the ISC host.
- 

## Step 2: Perform Device Discovery

This section describes how to start the device discovery process and edit device configuration.



### Note

If you are using CDP discovery, save all of the XML files created by the first Discovery run. If you need to re-run discovery, you can use the file-based option and specify the saved files as the starting point for the process.

## Starting Device Discovery

To start discovery, follow these steps:

- Step 1** Log into ISC.
- Step 2** Click the **Service Inventory** tab.
- Step 3** The Service Inventory window appears, as shown in [Figure 4-7](#).

**Figure 4-7** Service Inventory Window




- Step 4** Click **Discovery**.

The Discovery window appears, as shown in [Figure 4-8](#).

Initially, the CDP Discovery method is selected and the window displays the required input for this method.

**Figure 4-8** Discovery Window




**Step 5** Choose a Discovery method:

- To use the Cisco Discovery Protocol (CDP) method, select the **CDP** radio button.
- To use the Device/Topology method, select the **Device/Topology** button.

If you choose the Device/Topology method, the Discovery window changes and displays the required fields for the Device/Topology method, as shown in [Figure 4-9](#).

**Figure 4-9** Discovery Window with Device/Topology Fields



**Step 6** In the Discovery window, specify the settings indicated in [Table 4-9](#).

**Table 4-9** Discovery Settings

Setting	Description
<b>CDP</b>	Click this radio button to select Cisco Discovery Protocol (CDP) as the Discovery method.
<b>Device/Topology</b>	Click this radio button to select the Device/Topology Discovery method.
<b>Policy File</b>	<p>If you click the <b>CDP</b> button, specify the path to your <b>policy.xml</b> file here. This file is an XML file that indicates the IP address of one or more devices used as a starting point for the discovery process.</p> <p>For more information on the <b>policy.xml</b> file, see <a href="#">Coding the policy.xml File</a>, page 4-20.</p>


Table 4-9 Discovery Settings (continued)

Setting	Description
<b>Devices File</b>	<p>If you click the <b>Device/Topology</b> button, specify the path to your <b>device.xml</b> file here. This file contains information used to locate the devices in your network, such as IP addresses and OIDs.</p> <p>For more information on the <b>device.xml</b> file, see <a href="#">Coding the device.xml File, page 4-22</a>.</p>
<b>NPC Topology File</b>	<p>If you click the <b>Device/Topology</b> button, specify the path to your <b>topology.xml</b> file here. This file contains information used to determine the NPC topology of your network.</p> <p>For more information on the <b>topology.xml</b> file, see <a href="#">Coding the topology.xml File, page 4-24</a>.</p>
<b>Inventory File</b>	<p>You must specify the directory path and filename for the <b>inventory.xml</b> file.</p> <p>For more information on the <b>inventory.xml</b> file, see <a href="#">Coding the inventory.xml File, page 4-17</a>.</p>
<b>MPLS VPN</b>	To discover devices used in an MPLS VPN service, click the <b>MPLS VPN</b> radio button.
<b>L2VPN (Metro Ethernet Discovery)</b>	<p>To discover layer 2 devices used in a Metro Ethernet service, click the <b>L2VPN (Metro Ethernet) Discovery</b> radio button.</p> <p>If you check the L2VPN (Metro Ethernet Discovery) check box, you can choose to discover services in one of two ways:</p> <ul style="list-style-type: none"> <li>To discover Metro Ethernet services in an MPLS core network, click the <b>MPLS Core</b> radio button.</li> <li>To discover Metro Ethernet services in an Ethernet core network, click the <b>Ethernet Core</b> radio button.</li> </ul>

**Step 7** Click the **Start** button.

The discovery process starts and the Discovery Workflow window appears, as shown in [Figure 4-10](#).


Figure 4-10 Discovery Workflow Window



The Discovery Workflow window indicates the progress of each phase of device discovery:

- When the window first appears, The status indicator is yellow and indicates that the device discovery process is **Initializing**.
- The status indicator then indicates that the process is **In Progress**.
- After the discovery processes has completed, the display indicates how many devices were discovered, and the status indicator changes to orange and indicates that there is **Pending Input**, as shown in Figure 4-11.

Figure 4-11 Discovery Workflow Window with Device Input Pending



The Progress area at the bottom of the window indicates how many devices were discovered.

At the lower left of the window there is a **Restart** button. You can click this button to restart the entire discovery process. However, if you restart the Discovery process, any work that has been done previous to restarting Discovery is lost.



Note

After each phase of the Discovery process, make sure that you check the log file to ensure that there were no errors in the process. For specific instructions, see [Using the Discovery Log Files, page 4-4](#).



## Editing Device Configurations

After the initial discovery of devices in your network, you must edit the information that ISC maintains about the devices. This allows the Discovery process to collect configuration information about the devices that is required to determine the network topology and generate service requests.

Editing device configuration includes these steps:

- Setting Password Attributes (a required step)
- Setting General Device Attributes
- Setting Cisco CNS Attributes

Follow these steps to edit device configurations:

- Step 1** When the Discovery Workflow window indicates that the Device Discovery is **Pending Input**, click the **Continue** button.
- Step 2** The General Attributes - Devices window appears, as shown in [Figure 4-12](#).

**Figure 4-12** The General Attributes-Devices Window

The screenshot displays the 'General Attributes - Devices' window in the IP Solution Center. The window has a header with the Cisco Systems logo and navigation tabs: Service Inventory, Service Design, Monitoring, Diagnostics, and Administration. Below the tabs, there's a breadcrumb trail: 'You Are Here: Service Inventory > Inventory and Connection Manager'. The main content area shows a table of devices. The table has columns for #, Host, Device Type, Description, Management IP Address, Device Domain Name, Terminal Session Protocol, and Config Access Protocol. There are 10 rows of data, all for Cisco IOS Devices. At the bottom of the window, there are buttons for 'Attributes', 'Edit', 'Delete', 'Cancel', and 'Continue'. A sidebar on the left shows the 'Inventory Manager' section.

#	Host	Device Type	Description	Management IP Address	Device Domain Name	Terminal Session Protocol	Config Access Protocol
1.	m1sw12	Cisco IOS Device		192.168.133.171		Telnet	UNKNOWN
2.	m1pe5	Cisco IOS Device		192.168.133.241	cisco.com	Telnet	UNKNOWN
3.	m1sw11	Cisco IOS Device		192.168.133.170		Telnet	UNKNOWN
4.	m1sw18	Cisco IOS Device		192.168.133.177		Telnet	UNKNOWN
5.	m1sw13	Cisco IOS Device		192.168.133.172		Telnet	UNKNOWN
6.	m1sw19	Cisco IOS Device		192.168.133.178		Telnet	UNKNOWN
7.	m1sw20	Cisco IOS Device		192.168.133.179		Telnet	UNKNOWN
8.	m1sw15	Cisco IOS Device		192.168.133.174		Telnet	UNKNOWN
9.	m1sw14	Cisco IOS Device		192.168.133.173		Telnet	UNKNOWN
10.	m1sw21	Cisco IOS Device		192.168.133.220		Telnet	UNKNOWN

The General Attributes - Devices window allows you to do the following:

1. Delete devices.  
If devices appear in the device list that you do not want to configure, you can delete them. See step 10 later in this procedure for information on how to delete devices.
2. Set the following groups of attributes for each device:
  - **General Attributes**—The general attributes include the hostname of the device, the device type, the management IP address, and other settings.

You can accept the default attributes shown in the General Attributes - Devices window or change them as required.

For a list of the general attributes, see [Setting General Device Attributes, page 4-34](#).

- **Password Attributes**—The password attributes include the username and password for the device and the enable username and password for the device. You *must* set these attributes.
- **CNS Attributes**—If the device is a CNS device, set the CNS attributes.

**Step 3** If you want to filter the devices that appear in the window, enter part of the device name for the devices that you want to view, preceded or followed by the asterisk (\*) and then click the **Find** button.

If the Find field displays an asterisk, all devices are displayed.

The setting in the Find field will apply to all of the attributes windows.

**Step 4** To change the display to show one of the attributes areas, click the **Attributes** button at the bottom of the window and use the pull-down list to select the attributes area to display.

- If you need to change the general attributes for the device, such as the protocol used to configure the device (Config Access Protocol), you can do this in the initial window that appears.

If the General Attributes - Devices window is not the current window, click the **Attributes** button and select **General Attributes** from the pull-down list.

See [Setting Password Attributes \(Required Step\), page 4-32](#) for instructions on setting the General Attributes.

- To set the password attributes, click the **Attributes** button and then select Password Attributes from the pull-down list.

For instructions on setting the password attributes, see [Setting Password Attributes \(Required Step\), page 4-32](#).



**Note** This is a required step. To enable configuration collection, you *must* set the password attributes.

- If you need to change the CNS attributes, see [Setting Cisco CNS Attributes, page 4-35](#).

**Step 5** If you want to delete one or more devices, follow these steps:

- a. Check the check box next to each device that you want to delete.

If you need to delete more than one device, you can check the check box next to the heading for the list of the devices. This selects all of the devices in the list. You can then uncheck the boxes next to any devices that you do not want to delete.

- b. To delete the devices, click the **Delete** button.

## Setting Password Attributes (Required Step)

In order for the Configuration Collection phase to succeed, you *must* set the password attributes for each device. Follow these steps to set password attributes:

**Step 1** If the Password Attributes window is not the current window, click the **Attributes** button and select **Password Attributes** from the pull-down list.

**Step 2** The Password Attributes window appears, as shown in [Figure 4-13](#).

**Figure 4-13 Password Attributes Window**

The screenshot shows the Cisco IP Solution Center interface. The top navigation bar includes links for Home, Shortcuts, Account, Index, Help, About, and Logout. The user is logged in as 'admin'. The main menu includes Service Inventory, Service Design, Monitoring, Diagnostics, and Administration. The 'Service Inventory' tab is selected, and the 'Inventory and Connection Manager' sub-tab is active. The 'Password Attributes' window is displayed, showing a table of devices with columns for Device Name, Login User, Login Password, Enable User, and Enable Password. The table lists 10 devices (mlsw12 through mlsw21). The 'Attributes' button is highlighted at the bottom.

#	<input type="checkbox"/>	Device Name	<input type="checkbox"/> Login User	<input type="checkbox"/> Login Password	<input type="checkbox"/> Enable User	<input type="checkbox"/> Enable Password
1.	<input type="checkbox"/>	mlsw12				
2.	<input type="checkbox"/>	mlpe5				
3.	<input type="checkbox"/>	mlsw11				
4.	<input type="checkbox"/>	mlsw18				
5.	<input type="checkbox"/>	mlsw13				
6.	<input type="checkbox"/>	mlsw19				
7.	<input type="checkbox"/>	mlsw20				
8.	<input type="checkbox"/>	mlsw15				
9.	<input type="checkbox"/>	mlsw14				
10.	<input type="checkbox"/>	mlsw21				

Rows per page: 10 Go to page: 1 of 2

Buttons: Attributes, Edit, Delete, Cancel, Continue

**Step 3** Follow these steps to select the devices and password attributes to configure:

- a. Check the check box next to a device whose password attributes you want to configure.

If several devices have the same password attributes, you can check multiple check boxes. If all of the devices have the same password attributes, you can select the box to the left of the heading row to select all of the devices in the list. If this check box is checked, you can uncheck it to deselect all of the devices.

- b. To select the password attributes to configure, check one or more of the check boxes next to the attribute names in the heading row.

**Step 4** Click the **Edit** button.

The Edit Attributes window for passwords appears, as shown in [Figure 4-14](#).

**Figure 4-14** Edit Attributes Window for Password Attributes

**Step 5** Enter the following information for the device:

- **Login Password**—Enter the login password for the device
- **Login User**—Enter the username for the device
- **Enable User**—Enter the name of a user with enable privileges
- **Enable Password**— Enter the enable password for the enable user

**Step 6** Click **Save**.

The information that you entered appears in the Password Attributes window.

## Setting General Device Attributes

After you complete the device discovery process, the General Attributes - Devices window displays the current general attributes settings for each device.

Follow these steps to change the general attributes for a device:

**Step 1** Click on the attribute that you want to change.

An Edit Attributes dialog box appears for the selected attribute.

**Step 2** In the dialog box, indicate the new setting for the attribute.

The General Device attributes include the following:

- **Host Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. This field is required and must match the name configured on the target router device. Limited to 256 characters.
- **Device Type**—The device type includes the following devices:
  - Cisco Router
  - Catalyst OS device

- Terminal server
- IE2100 (Cisco CNS appliance)
- **Device Description (not editable from this window)**—Can contain any pertinent information about the device, such as the type of device, its location, or other information that might be helpful to service provider operators. Limited to 80 characters.
- **Management Address**—Valid IP address of the device that ISC uses to configure the target router device. This IP address must be reachable from the ISC host.
- **Domain Name**—Must begin with a letter, digit, or underscore followed by letters, digits, underscores, spaces, hyphens, or dots ending with a letter, digit, or underscore. The name must match the domain name on the target router device.
- **Config Access Protocol**—Administers the access protocol for config upload and download. Choices include: Telnet, Terminal, TFTP, and RCP.

## Setting Cisco CNS Attributes

If one of the devices is a Cisco CNS device, follow these steps to set CNS attributes:

- Step 1** If the CNS Attributes window is not the current window, click the **Attributes** button and select **CNS Attributes** from the pull-down list.
- Step 2** The CNS Attributes window appears, as shown in [Figure 4-15](#).

**Figure 4-15** CNS Attributes Window

The screenshot shows the IP Solution Center interface. The top navigation bar includes links for Home, Shortcuts, Account, Index, Help, About, and Logout. The main menu has tabs for Service Inventory, Service Design, Monitoring, Diagnostics, and Administration. The left sidebar shows the breadcrumb path: You Are Here: Service Inventory > Inventory and Connection Manager. The main content area is titled 'CNS Attributes' and contains a sub-section 'CNS Attributes - Devices'. Below this is a search bar with the text 'Show entries with Host matching' and a 'Find' button. A table displays 10 records, showing columns for #, Device Name, IE2100 Name, Event Identification, and CNS Identification. The table lists devices mls12 through mls21, all with 'Host Name' in the Event Identification column. At the bottom of the table, there is a 'Rows per page' dropdown set to 10, a 'Go to page' field set to 1 of 2, and buttons for 'Attributes', 'Edit', 'Delete', 'Cancel', and 'Continue'.

#	Device Name	IE2100 Name	Event Identification	CNS Identification
1.	mls12		Host Name	
2.	mlpe5		Host Name	
3.	mls11		Host Name	
4.	mls18		Host Name	
5.	mls13		Host Name	
6.	mls19		Host Name	
7.	mls20		Host Name	
8.	mls15		Host Name	
9.	mls14		Host Name	
10.	mls21		Host Name	

- Step 3** Click an existing Event Identification item.
- The Edit Attributes dialog box for Event Identification appears.

- Step 4** From the pull-down list for Event Identification attribute, select one the following:
- **Event-Identification**—Indicates whether the CNS Identification field contains a HOST NAME or CNS ID. Default: HOST NAME.

## Saving the Device Configuration

After you are done making device configuration changes, click the **Continue** button.

The Device Discovery indicator turns green and indicates that Device Discovery is **Complete**.

The Collect Configuration phase begins automatically.

## Step 3: Perform Configuration Collection

After you save your device configuration settings, the Collect Configuration phase of Device Discovery starts automatically.


While Cisco IP Solution Center is collecting the device configurations, the Collect Configuration indicator is yellow and indicates that the process is **In Progress**.

When the Collect Configuration phase is complete, the indicator changes to green and indicates that the process is **Complete**. You are now ready to assign device roles.

## Step 4: Perform Role Assignment

After the Collect Configuration phase of Device Discovery is complete, the Discovery Workflow window indicates that the Role Assignment phase is **Pending Input**, as shown in [Figure 4-16](#).

**Figure 4-16** Discovery Workflow with Role Collection Pending Input



149109

Follow these steps to assign device roles:

- Initiate Device Role Assignment
- Change the Device Assignment Display
- Change Device Assignments
- Determine Device Roles
- Assign CE Device Roles
- Assign PE Device Roles


The following sections describe each of these steps.

## Initiating Device Role Assignment

Follow these steps to initiate device role assignment:

- Step 1** In the Discovery Workflow window, click **Continue**.  
The Role Assignment - Un-assigned Devices window appears, as shown in [Figure 4-17](#).

**Figure 4-17** Role Assignment - Un-assigned Devices Window



On the Role Assignment - Un-assigned Devices window, if you select a single device, you are prompted directly for the device role assignment. However, if you select more than one device, either the Role Assignment - CEs window or the Role Assignment - PEs window appears. On these windows you can specify the desired device roles.

- Step 2** If you want to change the way that the devices are displayed, see the following section, [Changing the Device Assignment Display](#), page 4-38.

## Changing the Device Assignment Display

You can change the way that devices that are displayed in the Role Assignment window in the following ways:

- You can change the display to show unassigned devices, PE devices, or CE devices using the pull-down list at the bottom of the Role Assignment window.
- You can change the range of devices that are displayed using the **Show devices with** selection at the top of the window in combination with the **matching** field.

Follow these steps to change the category of devices that is displayed:


- 
- Step 1** To change the category of devices that is displayed, select a value from the pull-down list at the bottom of the Role Assignment window:
- To view PE devices, select **PEs**.
  - To view CE devices, select **CEs**.
  - To view unassigned devices, select **Un-assigned Devices**.
- Step 2** To change the range of devices that are displayed, use the **Show devices with** selection at the top of the window in combination with the **matching** field.
- To list devices by hostname, select **Device Host Name** and enter a search value in the matching field, then click **Find**.
  - To list devices by domain name, select **Device Domain Name** name and enter a search value in the matching field, then click **Find**.
  - To list devices by management IP address, select Management IP Address and enter a search value in the matching field, then click **Find**.

The value in the **matching** field specifies a search mask that controls which devices are displayed. An asterisk (\*) specifies display of all devices by the selected search criteria. A string followed by an asterisk specifies display of all devices starting with part of a hostname, domain name, or management IP address. And a string preceded by an asterisk specifies display of all devices ending with part of a hostname, domain name, or management IP address.

You can specify more than one wildcard (asterisk) value in a search string. For example, to display all devices that have “ce” in the hostname, enter \*ce\* in the matching field.

The display changes depending on the selection that you made. For example, if two devices have been assigned the CE role, the Role Assignment - CEs window appears and shows a listing similar to the one in [Figure 4-18](#).



**Figure 4-18**      **Role Assignment - CEs Window**

149.107

## Changing Device Assignments

In some instances, the device discovery process assigns the wrong device role to groups of devices. For example, devices that should be PEs can be assigned as CEs.

If this occurs, perform these steps:

- If all of the devices that you expected would appear as PEs are not listed on the Role Assignment - PEs window, check the Role Assignment - Unassigned Devices window and the Role Assignment - CEs window and assign the devices as PE devices.
  - Go to the Role Assignment - CEs window and select any devices that should be PE devices
  - Click the **Assign as PEs** button

The Role Assignment - PEs window appears and now lists the devices that you assigned as PEs

- If other devices are not assigned as desired, change their basic device assignment as required.

## Assigning Devices Individually or in Bulk

Using the windows provided for Role Assignment, you can assign device roles one device at a time or using bulk assignment (by selecting several devices and assigning them all the same role).

If you assign device roles for a single device, you can also assign the other device attributes, such as Site, Region, etc. However, if you assign device roles in bulk, then you cannot assign the other attributes at this time. You will have to go to the PEs or CEs window later to assign the other attributes.

## Determine Device Roles

The purpose of device assignment is to categorize the devices discovered in the provider's network into two general groups:

- Provider-related devices—Provider Edge (PE) devices.

See [Assigning the PE Role, page 4-40](#) for instructions on assigning the PE roles (U-PE, N-PE, P, or PE-AGG).



### Note

The Internet Engineering Task Force (IETF) designations for provider devices have changed since the previous release of Cisco ISC. Therefore, in ISC 4.1, new designation for “PE\_POP” devices is N-PE, and the new designation for “PE\_CLE” devices is U-PE.

- Customer-related devices—Customer Edge (CE) devices

See [Assigning the CE Role, page 4-43](#) for instructions on assigning the CE role.

For PE devices, use the following guidelines to determine device roles:

- Assign a device that is at the “center” of a core domain as a P device.
- Assign any devices that interface with users of the VPN services as U-PE devices. These are devices that are on the customer facing edge of a domain.
- Assign any devices that are on the edge of the MPLS core domain or L2VPN core domain as N-PE devices.
- Assign any devices that are in device rings or which connect to multiple U-PE devices as PE-AGG devices.

For CE devices, see the descriptions of the CE roles in the section on assigning CE roles ([Assigning the CE Role, page 4-43](#)) for specific information.

## Assigning the PE Role

Follow these steps to assign a device as a PE device:

- Step 1** In the Role Assignment - Un-assigned Devices window, select a device that you want to assign as a PE.
  - To select a device, check the check box next to the device name.
  - To deselect a device, uncheck the check box next to the device name.
- Step 2** Click the **Assign as PE(s)** button.  
The Assign as PE window appears, as shown in [Figure 4-19](#).

**Figure 4-19 Assign as PE Window**

The screenshot shows the 'Assign as PE' window in the IP Solution Center. The window has a header with the Cisco Systems logo and navigation tabs: Service Inventory, Service Design, Monitoring, Diagnostics, and Administration. Below the tabs, there are links for Inventory and Connection Manager, Discovery, and Device Console. The main content area contains the 'Assign as PE' form. The form has three input fields: 'Device Host Name' with the value 'syd-3620-ce-f', 'PE Region Name' with a 'Select' button, and 'PE Role' with a dropdown menu showing 'N\_PE'. At the bottom of the form are 'OK' and 'Cancel' buttons. A note at the bottom left states: 'Note: \* - Required Field'.

**Step 3** In the Assign as PE window, assign the required information for the PE.

- a. To assign a PE Region Name, click the **Select** button.

The PE Region Name window appears, as shown in [Figure 4-20](#).

**Figure 4-20 PE Region Name Window**

The screenshot shows the 'Select Region/Provider' window. The window has a title bar that says 'Select Region/Provider - Microsoft Internet Explorer provided by Ci...'. The main content area has a search bar with the text 'Show Regions with Region Name matching \*' and a 'Find' button. Below the search bar, it says 'Showing 1 - 4 of 4 records'. There is a table with 4 records, each with a radio button and a region name: Cisco HQ, Cisco NYC, Cisco Paris, and Cisco SJ. At the bottom of the window are 'Select' and 'Cancel' buttons.

- b. In the PE Region Name window, click the radio button next to the region name that you want to assign and then click **Select**.

The Assign as PE window appears with the region name in the PE Region field.

- c. To assign a PE role, select a value from the pull-down list for the PE Role field.

The PE role specifies the architectural role that a PE router performs. Assign the PE role based on the network layer to which the device belongs.

You can select the following PE roles:

- **N-PE**—Assign devices that are at the edge of domains (within the Edge layer) as Network Facing Provider Edge (N-PE) devices.
- **U-PE**—Assign devices within the User Facing Provider Edge as U-PE devices.
- **P**—Assign a device that is at the “center” of a core domain as a Provider Core (P) device.
- **PE-AGG**—Assign devices within the Aggregation Layer as Provider Edge Aggregation (PE-AGG) devices.



**Note**

The Internet Engineering Task Force (IETF) designations for provider devices have changed since the previous release of Cisco ISC. Therefore, in ISC 4.1, new designation for “PE\_POP\_” devices is N-PE, and the new designation for “PE\_CLE” devices is U-PE.

d. Click **OK**.

The Role Assignment - PEs window appears with the specified values shown.


## Editing the PE Role

After you have assigned one or more devices as PE devices and they appear in the Role Assignment - PEs window, you can edit the PE role. You can edit the PE role even if no values have been assigned in the Assign as PE window.

Follow these steps to edit the Role Assignment values for a PE device:

- Step 1** While the Role Assignment phase of Device Discovery is active, navigate to the Role Assignment - PEs window.
- If the Role Assignment - Un-assigned Devices or the Role Assignment - CEs window is active, select **Role-Assignment - PEs** from the pull-down list at the bottom of the window.
- The Role Assignment - PEs window appears, as shown in [Figure 4-21](#).

**Figure 4-21 Role Assignment - PEs Window**



Note that on this window, sorting is disabled for the following columns:

- PE Device Host Name
- PE Provider Name
- PE Region Name.

In the sample window shown in [Figure 4-21](#), one of the PEs has role information assigned. The other two PEs have been assigned as PEs but do not have role information assigned. You can edit any of the information for the PEs, whether information has been entered or not.

**Step 2** Select one or more PEs to edit.

- To select a specific PE, check the check box next to the device name.
- To select all the PEs shown in the window, check the check box in the heading row.

**Step 3** To edit the PE role, follow these steps:

a. Select the **Edit** button at the bottom of the window and choose **PE Role** from the pull-down list. You are prompted to select a PE role.

b. Select a value from the pull-down list for the PE Role field.

You can select the following PE roles:

- **N-PE**—Assign devices within the Edge layer as Network Facing Provider Edge (N-PE) devices.
- **U-PE**—Assign devices within the User Facing Provider Edge as U-PE devices.
- **P**—Assign devices within the Core layer as Provider Core (P) devices.
- **PE-AGG**—Assign devices within the Aggregation Layer as Provider Edge Aggregation (PE-AGG) devices.

The specified PE role appears in the Role Assignment - PEs window.

**Step 4** To edit the PE provider name or PE region name, follow these steps:

a. Select the **Edit** button at the bottom of the window and choose **Region/Provider** from the pull-down list.

You are prompted for a Region name.

b. Click the radio button next to one of the region names listed in the pop-up window and then click the **Select** button.

The specified Region Name and its associated Provider Name appear in the Role Assignment - PEs window.

## Assigning the CE Role

Follow these steps to assign a device as a CE device:

**Step 1** In the Role Assignment - Un-assigned Devices window, select a device that you want to assign as a CE.

- To select a device, check the check box next to the device name.
- To deselect a device, uncheck the check box next to the device name.

**Step 2** Click the **Assign as CE(s)** button.

**Step 3** The Assign as CE window appears, as shown in [Figure 4-22](#).

**Figure 4-22 Assign as CE Window**

The screenshot shows the 'Assign as CE' window in the IP Solution Center. The window has a title bar with 'Cisco Systems' and 'IP Solution Center'. The main content area contains the following fields:

- Device Host Name: l0n-3620-ce-e
- Customer Name: (empty field with a 'Select' button)
- CE Management Type: MANAGED\_REGULAR (dropdown menu)

At the bottom of the form are 'OK' and 'Cancel' buttons. A note below the form states: 'Note: \* - Required Field'. The breadcrumb trail at the top indicates 'You Are Here: Service Inventory > Discovery'.

**Step 4** In the Assign as CE window, assign the required information for the CE.

- a. To assign a Customer Name (required field), click the **Select** button.

The Customer Name window appears, as shown in [Figure 4-23](#).

**Figure 4-23 Customer Name Window**

The screenshot shows the 'Select Customer' window. The window has a title bar with 'Select Customer - Microsoft Internet Explorer provided by Cisco System...'. The main content area contains the following elements:

- Search bar: 'Show Customers with Customer Name matching' with a text input field and a 'Find' button.
- Results: 'Showing 1 - 2 of 2 records'. A table with two rows:
 

#	Customer Name
1.	Customer1
2.	Customer2
- Navigation: 'Rows per page: 10' and 'Go to page: 1 of 1' with 'Go' and 'Cancel' buttons.
- Buttons: 'Select' and 'Cancel' buttons at the bottom.

- b. To assign a customer name, click the radio button next to the customer name that you want to assign and then click the **Select** button.

The Assign as CE window appears with the specified customer name displayed.

- c. To assign a CE management type, select a value from the pull-down list for the CE Management Type.

The CE Management type specifies the architectural role that a CE router performs. Assign the CE management type based on the network layer to which the device belongs.

You can select the following CE management types:

- **MANAGED-REGULAR**—This is the default CE role assignment. Assign this role to CEs that you want the Provider to manage. The CE must be reachable from an ISC server. When you assign this role, then when you create a router in the Inventory Manager interface, the router configuration is automatically downloaded.
- **UNMANAGED**—Assign this role to device that you want to manage “manually.” If this role is assigned, then the device configuration is not assigned automatically when a new device is created and the device must be configured manually. An unmanaged CE cannot be provisioned directly by the provider. If Unmanaged is selected, the provider can use ISC to generate a configuration, and then send the configuration to the customer for placement on the CE.
- **MANAGED-MGMT-LAN**—Specifies that the device management is linked to the PE configuration. The configuration will be downloaded automatically when a new device is created. A managed Management LAN or Management CE (MCE) is configured like a managed CE router, but it resides in the provider space. Normally, an MCE acts as the network operations center (NOC) gateway router.
- **UNMANAGED-MGMT-LAN**—Specifies that the device management is linked to the PE configuration, but the configuration will not be downloaded automatically when a new device is created. An unmanaged Management LAN or MCE is configured like an unmanaged CE router, but it resides in the provider space. Normally, an MCE acts as the network operations center (NOC) gateway router.
- **DIRECT-CONNECTED-REGULAR**—In most cases, the CE is connected to a PE router. In this case, the CE is connected to a workstation or other device.
- **DIRECT-CONNECTED-MGMT-HOST**—In most cases, the CE is connected to a PE router. In this case, the CE is connected to a workstation or other device, on which ISC resides.
- **MULTI-VRF**—Specifies that there is a device between the PE and the CE. that is a VPN routing/forwarding instance (VRF). A multi-VRF CE (MVRFCCE) is owned by the customer, but resides in the provider space. It is used to off load traffic from the PE.
- **UNMANAGED-MULTI-VRF**—An unmanaged multi-VRF CE is provisioned like an unmanaged CE (configurations are not uploaded or downloaded to the device by the provider). It is owned by the customer and resides in the provider space.

d. Click **OK**.

The Role Assignment - CEs window appears with the specified values shown.



**Note** The CE Site value is unassigned at this point. To assign this value, you must edit the settings. See [Editing the CE Role, page 4-45](#) for instructions on this task.

## Editing the CE Role

After you have assigned one or more devices as CE devices and they appear in the Role Assignment - CEs window, you can edit the CE role. You can edit the CE role even if no values have been assigned in the Assign as CE window.


Follow these steps to edit the Role Assignment values for a CE device:

**Step 1** While the Role Assignment phase of Device Discovery is active, navigate to the Role Assignment - CEs window.

If the Role Assignment - Un-assigned Devices or the Role Assignment - PE window is active, select **Role-Assignment - CEs** from the pull-down list at the bottom of the window.

The Role Assignment - CEs window appears, as shown in Figure 4-24.

**Figure 4-24 Role Assignment - CEs Window**



In the sample Role Assignment - CEs window shown in Figure 4-24, two of the CEs have role assignment information assigned, and two have no information assigned. You can edit any of the information for the CEs, whether information has been entered or not.

Note that on this window, sorting is disabled on the following columns:

- CE Device Host Name
- CE Site Name
- CE Customer Name

**Step 2** Select one or more CEs to edit.

- To select a specific CE, check the check box next to the device name.
- To select all the CEs shown in the window, check the check box in the heading row.

**Step 3** To edit the Customer name, follow these steps:

- Select the **Edit** button at the bottom of the window and choose **Customer** from the pull-down list. You are prompted to select a customer name.
- To select a customer name, click the radio button next to one of the customer names that is displayed and then click the **Select** button.

The Role Assignment - CEs window appears with the specified customer name displayed.

**Step 4** To edit the CE management type, follow these steps:

- Select one or more CEs to edit.
- Select the **Edit** button at the bottom of the window and choose **CE Management Type** from the pull-down window.



The CE Management type specifies the architectural role that a CE router performs. Assign the CE management type based on the network layer to which the device belongs.

You can select the following CE management types:

- **MANAGED-REGULAR**—This is the default CE role assignment. Assign this role to CEs that you want the Provider to manage. The CE must be reachable from an ISC server. When you assign this role, then when you create a router in the Inventory Manager interface, the router configuration is automatically downloaded.
- **UNMANAGED**—Assign this role to device that you want to manage “manually.” If this role is assigned, then the device configuration is not assigned automatically when a new device is created and the device must be configured manually. An unmanaged CE cannot be provisioned directly by the provider. If Unmanaged is selected, the provider can use ISC to generate a configuration, and then send the configuration to the customer for placement on the CE.
- **MANAGED-MGMT-LAN**—Specifies that the device management is linked to the PE configuration. The configuration will be downloaded automatically when a new device is created. A managed Management LAN or Management CE (MCE) is configured like a managed CE router, but it resides in the provider space. Normally, an MCE acts as the network operations center (NOC) gateway router.
- **UNMANAGED-MGMT-LAN**—Specifies that the device management is linked to the PE configuration, but the configuration will not be downloaded automatically when a new device is created. An unmanaged Management LAN or MCE is configured like an unmanaged CE router, but it resides in the provider space. Normally, an MCE acts as the network operations center (NOC) gateway router.
- **DIRECT-CONNECTED-REGULAR**—In most cases, the CE is connected to a PE router. In this case, the CE is connected to a workstation or other device.
- **DIRECT-CONNECTED-MGMT-HOST**—In most cases, the CE is connected to a PE router. In this case, the CE is connected to a workstation or other device, on which ISC resides.
- **MULTI-VRF**—Specifies that there is a device between the PE and the CE. that is a VPN routing/forwarding instance (VRF). A multi-VRF CE (MVRFCE) is owned by the customer, but resides in the provider space. It is used to off load traffic from the PE.
- **UNMANAGED-MULTI-VRF**—An unmanaged multi-VRF CE is provisioned like an unmanaged CE (configurations are not uploaded or downloaded to the device by the provider). It is owned by the customer and resides in the provider space.

c. Click **Select**.

The Role Assignment - CEs window appears with the specified CE management type displayed.

**Step 5** To specify a site name or edit an existing site name, follow these steps:

- a. Select one or more CEs to edit.
- b. Select the **Edit** button at the bottom of the window and choose **Site** from the pull-down window.

The Site Name window appears, as shown in [Figure 4-25](#).

Figure 4-25 Site Name Window

#	Site Name
1.	<input type="radio"/> C1S1
2.	<input type="radio"/> C1S2
3.	<input type="radio"/> C1S3
4.	<input type="radio"/> C1S4
5.	<input type="radio"/> C1S5
6.	<input type="radio"/> C1S6
7.	<input type="radio"/> C1S7
8.	<input type="radio"/> C2S1
9.	<input type="radio"/> C2S2
10.	<input type="radio"/> C2S3

- c. In the Site Name window, click the radio button next to the site name that you want to assign and then click the **Select** button.

The Role Assignment - CEs window appears with the specified site names displayed.

## Saving the Role Assignment Information

After you are done assigning roles to the devices, click the **Continue** button.

The Role Assignment Discovery indicator turns green and indicates that Role Assignment is **Complete**.

You are now ready to start the NPC Discovery phase of Device Discovery.

## Step 5: Perform NPC Discovery

After the Role Assignment phase of Device Discovery is complete, the Discovery Workflow window indicates that the NPC Discovery phase is **Pending Input**, as shown in [Figure 4-26](#).

**Figure 4-26** Discovery Workflow with NPC Discovery Pending Input



Follow these general steps to view a list of the NPCs that have been discovered and add or remove NPCs as required:

- If you are discovering a *Metro Ethernet topology with an Ethernet core*, perform the steps described in [Preliminary Steps Before Completing NPC Discovery for Metro Ethernet Networks with an Ethernet Core](#), page 4-49.
- Complete the steps for starting NPC assignment as described in [Starting NPC Assignment](#), page 4-51
- If necessary, complete steps for adding or modifying NPCs as described in [Adding a Device for an NPC](#), page 4-53 and the sections that follow.

## Preliminary Steps Before Completing NPC Discovery for Metro Ethernet Networks with an Ethernet Core

Follow these steps if you are discovering a Metro Ethernet topology with an Ethernet core.

- Create one or more Access Domains and assign the devices that were discovered in the Device Discovery phase to the Access Domain(s).
- Create at least one Resource Pool.
- Edit the “inter N-PE interface” for each device.

These steps are performed using the Inventory and Connection Manager in the Service Inventory interface (**Service Inventory > Inventory and Connection Manager**).

## Create Access Domains

Follow these steps to create access domains and add discovered devices to the domains:

- 
- Step 1** In the ISC start page, select **Service Inventory**.
- Step 2** In the Service Inventory window, select **Inventory and Connection Manager**.  
The Inventory and Service manager window appears.
- Step 3** In the left area of the window, select **Access Domains**.  
The Access Domains window appears.
- Step 4** Create one or more Access Domains and assign the devices in the L2VPN Metro Ethernet topology to these Access Domains.  
For detailed instructions on creating Access Domains, see the “Creating Access Domains” section in [Chapter 3, “Service Inventory — Inventory and Connection Manager.”](#)
- 

## Create Resource Pools

Follow these steps to create resource pool:

- 
- Step 1** In the ISC start page, select **Service Inventory**.
- Step 2** In the Service Inventory window, select **Inventory and Connection Manager**.  
The Inventory and Service manager window appears.
- Step 3** In the left area of the window, select **Resource Pools**.  
The Resource Pools window appears.
- Step 4** Create a Resource Pools.
- Step 5** For the **Pool Type**, make sure that you select **VLAN**.
- Step 6** For the **Start** value, enter 2.
- Step 7** For the **Pool Size** value, enter a value large enough to accommodate the number of devices in the resource pool, for example, 500.  
For detailed instructions on creating Resource Pools, see “Resource Pools” in [Chapter 3, “Service Inventory — Inventory and Connection Manager.”](#)
- 

## Edit Inter-N-PE Interfaces

Follow these steps to edit the “Inter N-PE” interfaces for the devices in your Metro Ethernet topology:

- 
- Step 1** In the ISC start page, select **Service Inventory**.
- Step 2** In the Service Inventory window, select **Inventory and Connection Manager**.  
The Inventory and Service manager window appears.

**Step 3** In the left area of the window, select **PE Devices**.

The PE Devices window appears.

**Step 4** Select each PE device in your topology and do the following:

a. Click the **Edit** button

The Edit PE window appears.

b. Locate the interface that connects to each device that the device is connected to.

c. For each interface, in the Metro Ethernet column, change **Any** to **None**.

d. Save your changes

Go the following section, [Starting NPC Assignment, page 4-51](#) and follow the steps for starting NPC assignment.


## Starting NPC Assignment

Follow these steps to initiate NPC assignment:

**Step 1** In the Discovery Workflow window, click **Continue**.

The Named Physical Circuits window appears, as shown in [Figure 4-27](#).

**Figure 4-27** *Named Physical Circuits Window*



The Named Physical Circuits window initially displays any discovered circuits.

At this point, you can create, add, or remove NPCs as required.


Named physical circuits (NPCs) are named circuits that describe a physical connection between a CPE or PE-CLE and a PE-POP. The intermediate nodes of the NPCs can either be CPE or PE. They can be connected in a circular fashion forming a ring of devices, which is represented by an entity known as NPC Rings. NPC Rings represent the circular topology between devices (CPE or PE) to the Named Physical Circuits. To create an NPC, you must specify how the source CPE/PE-CLE and the destination PE-POP are connected and specify the intermediate nodes.

**Step 2** If you need to define a NPC, follow these steps:

- a. In the Named Physical Circuits window, click **Create**.

The Create a Physical Circuit window appears, as shown in [Figure 4-28](#).

**Figure 4-28 Create Physical Circuits Window.**




Initially, the list of NPCs is empty.

- b. Click the **Add Device** button

The Select a Device window appears, as shown in [Figure 4-29](#)

**Figure 4-29 Select a Device Window**



**Step 3** In this window, select the radio button for a device and then click the **Select** button.

The Create a Named Physical Circuit window appears with an initial device added, as shown in [Figure 4-30](#).

**Figure 4-30** Create a Named Physical Circuit Window with Initial Device Added

The buttons on the window are now active.

- c. Click a device that appears in the screen and then select one of the following actions:
  - To insert a device, click the **Insert Device** button.
  - To insert a ring, click the **Insert Ring** button.
  - To add a device, click the **Add Device** button.
  - To add a ring, click the **Add Ring** button.
  - To delete an existing device or ring, select a device and then click the **Delete** button.

**Step 4** Refer to the following sections for additional information.

## Adding a Device for an NPC

- Step 1** To select an incoming interface on the Create a Named Physical Circuit window click on **Select Incoming Interface**.

The Select Device Interface window appears, as shown in [Figure 4-31](#).

Figure 4-31 Select Device Interface Window

#	Interface Name	IP Address	Logical Name
1.	<input type="radio"/> GigabitEthernet0/1	192.168.133.160/24	
2.	<input type="radio"/> GigabitEthernet0/10		
3.	<input type="radio"/> GigabitEthernet0/11		
4.	<input type="radio"/> GigabitEthernet0/12		
5.	<input type="radio"/> GigabitEthernet0/2		
6.	<input type="radio"/> GigabitEthernet0/3		
7.	<input type="radio"/> GigabitEthernet0/4		
8.	<input type="radio"/> GigabitEthernet0/5		
9.	<input type="radio"/> GigabitEthernet0/6		
10.	<input type="radio"/> GigabitEthernet0/7		

This window shows the interfaces on the selected device.

- Step 2** Select the radio button next to an interface in the list and then click the **Select** button.  
The selected interface now appears in the Create a Named Physical Circuit window.
- Step 3** To select an outgoing interface, click on **Select Outgoing Interface**.  
A list of interfaces configured on the device appears
- Step 4** Select the radio button next to an interface in the list and then click the **Select** button.  
The outgoing interface now appears in the Create a Named Physical Circuit window.
- Step 5** Select additional devices as required and specify incoming and/or outgoing interfaces.
- Step 6** After you are done, click the **Save** button in the Create a Named Physical Circuit window.

## Adding a Ring

Follow these steps to add a ring before the currently selected device:

- Step 1** In the Create a Named Physical Circuit window, click **Add Ring**.  
The Select NPC Rings window appears. This window shows any rings that exist in the network topology.
- Step 2** Click the radio button next to a ring listed in the window and then click the **Select** button.  
The selected ring now appears in the Create a Named Physical Circuit window.



## Inserting a Device

To insert a device after the last device in the topology, follow these steps:

- 
- Step 1** In the Create a Named Physical Circuit window, click the **Insert Device** button.  
The Select a Device window appears, as shown in [Figure 4-29](#).
  - Step 2** Check the check box next to a device that you want to insert and then click the **Select** button.  
The device now appears on the Create a Named Physical Circuit window.
  - Step 3** Click **select incoming interface**.  
A list of interfaces on the selected device appears.
  - Step 4** Check the check box next to the interface that you want to choose and then click **Select**.  
The selected interface now appears on the list of interfaces.
- 

## Inserting a Ring

To insert a ring after the last device in the topology, follow these steps:

- 
- Step 1** In the Create a Named Physical Circuit window, click the **Insert Ring** button.  
A list of the currently existing rings appears.
  - Step 2** In the list of rings, click the check box next to the ring that you want to insert and then click **Select**.  
The selected ring now appears on the Create a Named Physical Circuit window.
- 

## Deleting a Device or a Ring

Follow these steps to delete a device or a ring:

- 
- Step 1** In the Create a Named Physical Circuit window, select a device or ring and then click the **Delete** button.  
The create NPC window appears with the device deleted.
- 

## Saving the NPC Configuration

After you have selected two devices and have configured the connection between them, follow these steps to save the NPC configuration:


- 
- Step 1** In the Create a Named Physical Circuit window, click **Save**.  
The NPC process validates the NPC configuration.

Step 6: Perform MPLS VPN Service Discovery (Optional)

Step 2 Click **Continue** to continue.

The workflow window appears with NPC discovery marked as completed, as shown in Figure 4-32.


Figure 4-32 NPC Complete Window



# Step 6: Perform MPLS VPN Service Discovery (Optional)

After you have completed the NPC Discovery phase of Device discovery, if you selected **MPLS VPN Discovery** when you initiated the Discovery process, the NPC Discovery phase is marked as complete, and the MPLS VPN Discovery step is marked as **Pending Input**, as shown in Figure 4-33.

Figure 4-33 Discovery Workflow Window with MPLS VPN Discovery Pending Input



You are now ready to initiate configuration of the discovered MPLS VPN using the MPLS VPN Discovery user interface. Follow these steps to configure MPLS VPN services:


**Step 1** In the Discovery Workflow window, click **Continue**.

The MPLS VPNs window appears and lists the MPLS VPNs that were discovered. The status of the discovered MPLS VPNs is indicated as follows:

- If the MPLS VPN topology for a discovered MPLS is valid and ready to save in the ISC Repository, then the VPN Status indicates a **Valid** VPN and the status indicator is green.
- If the MPLS VPN topology for a discovered MPLS is invalid (the topology is Partial Mesh), is missing a Customer assignment, or includes an invalid CERC, then the VPN Status indicates an **Invalid** VPN and the status indicator is yellow. Partial Mesh topology VPNs are not supported by Cisco ISC 4.1, and must be broken up into Full Mesh and/or Hub and Spoke components.

The MPLS VPN window shown in [Figure 4-34](#) shows an invalid MPLS VPN (the topology is Partial Mesh and the Customer Name is blank).

**Figure 4-34 MPLS VPNs Window with Invalid MPLS VPN**



**Note**

If the MPLS VPN Discovery process discovers an MPLS VPN with a Partial Mesh topology, you must split the VPN into two or more separate VPNS that have a supported topology (Hub and Spoke or Full Mesh).

**Step 2** Do one of the following:

- If you want to change the view in the MPLS VPNs window, select another view option.  
For a description of the MPLS VPN view options, see [Filtering the MPLS VPN View, page 4-58](#).
- If the MPLS VPNs are valid and you do not need to make any changes to the MPLS VPN topology at this time, click **Continue** to create MPLS VPN services based on the discovered topology.
- If one or more of the discovered MPLS VPNs are invalid, you must complete the following steps:
  - **Split the VPN**—Select an invalid VPN and then click the **Split VPN** button.  
See [Splitting a VPN, page 4-58](#) for instructions.

- **Create New VPNs and add CERCs**—You must create new VPNs containing the devices in the VPN that you have split up and add CERCs to each new VPN.  
See [Creating a VPN, page 4-61](#) for instructions.

## Filtering the MPLS VPN View

Follow these steps to change the view in the MPLS VPNs screen:

- 
- Step 1** Pull down the menu next to the **Show VPNs with** field.
- You can filter the list of VPNs by VPN Name, Customer Name, Topology, VPN Type, or Description.
- Step 2** To limit which VPNs are displayed within the selected category, enter a value in the **Matching** field.
- The value in the **matching** field specifies a search mask that controls which sites are displayed. An asterisk (\*) specifies display of all sites by the selected search criteria. A string followed by an asterisk specifies display of all sites starting with part of the element specified in the **Show VPNs with** field.
- You can specify more than one wildcard (asterisk) value in a search string. For example, to display all VPNs that have “cisco” as part of the Customer Name, enter \*cisco\* in the matching field.
- The display changes to display the VPNs with the selected criteria.
- 

## Splitting a VPN

In some situations, you might need to split an existing MPLS VPN before you complete the MPLS VPN Discovery process and actually create the MPLS VPN services.

For example:

- If the MPLS Service Discovery process discovers an invalid MPLS VPN (an MPLS VPN with a Partial Mesh topology), you must split the VPN into two or more CERCs that have a supported topology (Hub and Spoke or Full Mesh).
- You might also choose to split MPLS VPNs to change your topology, depending on your processing needs. Only one VPN can be split at a time.

Follow these steps to split a VPN:

- 
- Step 1** In the MPLS VPNs window, check the check box next to a VPN that you want to split.
- Step 2** Click the **Split VPN** button.

The Split VPN window appears, as shown in [Figure 4-35](#) and [Figure 4-36](#).

Figure 4-35 Split VPN Window (Left Portion)





Figure 4-36 Split VPN Window (Right Portion)



**Step 3** In the Split VPN window, select several of the links

In the example shown in Figure 4-36, you should select the links that would comprise either a Hub and Spoke or Full Mesh topology.

For example, in the Split VPN window shown in Figure 4-35 and Figure 4-36, the first three links all have Route Targets of **1:102** and together form a Full Mesh topology.

The remaining two links have Route Targets of **1:106** and **1:105**. These links together form a Hub and Spoke topology.


To split this VPN, the first three links need to be associated with one CERC, and the two remaining links need to be associated with another CERC. Then we can split this VPN into two separate VPNs following the ISC best practice convention of one CERC per VPN.

Step 6: Perform MPLS VPN Service Discovery (Optional)

- Step 4** Click the **Create/Modify CERC** button.  
You are prompted for a CERC name.
- Step 5** Enter the new CERC name and then click the **Save** button.
- Step 6** Repeat these steps for the rest of the devices that are included in invalid VPNs.  
For example, in the topology shown [Figure 4-35](#) and [Figure 4-36](#), select the devices that have the route target **1:106 to 1:105**.
- Step 7** Click the **Create/Modify CERC** button.
- Step 8** When you are prompted for a CERC name, enter the new CERC name and then click the **Save** button.  
The Split VPNs window appears again, and the right portion of the window shows the new CERCs that have been created.

[Figure 4-37](#) shows an example.

**Figure 4-37** Split VPNs Window After Creation of a Valid CERC Topology



Notice that in the example in [Figure 4-37](#), the two new CERCs that have been created (**valid\_cerc\_one** and **valid\_cerc\_two**), have valid topologies. The first CERC, **valid\_cerc\_one**, has a Full Mesh topology and the second CERC, **valid\_cerc\_two**, has a Hub and Spoke topology.


- Step 9** Click the **Save** button.  
You are now ready to continue to the next step, creating VPNs and adding CERCs to the VPNs.

## Creating a VPN

After you have created a CERC, you must create a VPN and then add the CERC to it. Follow these steps to create a VPN:


- Step 1** In the Split VPN window, select **Create/Modify VPN**.  
The Create VPN window appears, as shown in [Figure 4-38](#).

**Figure 4-38 Create VPN Window**



- Step 2** Select the CERCs that you want to assign to the VPN.  
In the example shown in [Figure 4-38](#), select **valid\_cerc\_one**.
- Step 3** In the VPN Name field, enter a name for the VPN.  
For this example, enter **vpn\_one**.
- Step 4** Click the **Assign VPN Name** button.
- Step 5** Click **Save**.  
The VPN is created and appears in the Split VPN window in the VPN Name field.
- Step 6** Create any additional VPNs as needed.  
Continuing with the CERCs shown in the sample windows in [Splitting a VPN, page 4-58](#), a VPN must be created and have a CERC assigned to it. To do this:
- In the Split VPN window, click **Create/Modify VPN**.
  - In the Create VPN window, create a second VPN and assign a CERC to it.  
In the example screen, you could select the second CERC (**valid\_cerc\_two**) to the newly created VPN to it.
- Step 7** After you are finished creating VPNs, click the **Save** button in the Split VPN window.  
The MPLS VPNs window appears, as shown in [Figure 4-39](#).

Figure 4-39 MPLS VPNs Window with Valid VPN and Invalid VPN



Note

In the example shown in Figure 4-39, one of the VPNs is marked as **Valid** and has a green status indicator. However, the other VPN shown in the window is marked as **Invalid** and has a yellow indicator.

This occurs because in some instances, the MPLS Discovery process cannot completely validate the data. In this situation, you can still continue with the Service Discovery process and create MPLS VPN services. However, the process will skip the invalid VPN, and you must configure the VPN service manually using the ISC provisioning commands.

**Step 8** Follow these steps to assign a Customer to each VPN:

- a. Select a VPN entry in the MPLS VPNs window and then click the **Edit** button.

The Edit VPN window appears, as shown in Figure 4-40.



Figure 4-40 Edit VPN Window

The screenshot shows the 'Edit VPN' window in the IP Solution Center. The window has a header with the Cisco Systems logo and the title 'IP Solution Center'. Below the header is a navigation bar with tabs for 'Service Inventory', 'Service Design', 'Monitoring', 'Diagnostics', and 'Administration'. The 'Service Inventory' tab is selected, and the 'Discovery' sub-tab is active. The main content area is titled 'Edit VPN' and contains the following fields and buttons:

- VPN Name \***: A text box containing 'vpn\_one'.
- Customer Name \***: A text box containing 'Customer2' and a 'Select' button.
- CE Routing Communities**: A list box containing 'valid\_cerc\_one' and a 'Rename' button.
- Description**: A text area containing 'MPLS VPN discovered by ISC'.
- Buttons**: 'Save' and 'Cancel' buttons at the bottom right.

At the bottom left of the window, there is a note: 'Note: \* - Required Field'. The top right corner of the window shows the user 'admin' and the customer 'None'. The bottom right corner of the window has a vertical label '149085'.

- b. Click the **Select** button next to the Customer Name field.  
A list of customer names appears.
- c. Select the radio button next to customer name and then **Select**.
- d. If you want to rename the CERC, click **Rename** and then rename it.
- e. Click **Save**.

The Customer name now appears in the MPLS VPNs window.



#### Note

In some cases, an apparently valid VPN will be marked as invalid. This VPN will be skipped in the processing. You will then have to configure it manually using the ISC provisioning commands.


- Step 9** After you are done editing VPNs, click the **Continue** button to initiate the MPLS VPN service creation process.

## Viewing VPN Link Details

Follow these steps to view details of VPNs that were discovered:

- Step 1** In the MPLS VPNs window, select a VPN whose details you want to view and then click the **Details** button.  
The MPLS VPN Link window appears, as shown in [Figure 4-41](#).

Figure 4-41 MPLS VPN Links Window



**Step 2** To filter the MPLS VPN links that are displayed, select a value from the pull-down list in the **Show Sites with** field.

You can filter the list of VPNs by From Site, From CE, From CE Domain, Route Target, To Site, To CE, or to CE Domain.

The value in the **matching** field specifies a search mask that controls which sites are displayed. An asterisk (\*) specifies display of all sites by the selected search criteria. A string followed by an asterisk specifies display of all sites starting with part of the element specified in the **Show Sites with** field.

You can specify more than one wildcard (asterisk) value in a search string. For example, to display all sites that have “realtime” in the From CE Name, select **From CE Name** in the **Show Sites with** field and then name, enter \*realtime\* in the matching field.

The display changes to show only the specified links.

## Saving the MPLS VPNs and Initiating MPLS VPN Service Creation

After you are done editing the data for the discovered MPLS VPNs in the MPLS VPNs window, click the **Continue** button.

The Discovery process creates VPN services. After the process is complete, the Discovery Workflow window indicates that the MPLS VPN Discovery process is **COMPLETE** and the status indicator is green.

If you also selected **L2VPN (Metro Ethernet) Discovery** in the Discovery window before starting the Discovery process, you can now proceed to Metro Ethernet service discovery.

## Step 7: Perform L2VPN (Metro Ethernet) Service Discovery (Optional)

If you selected **L2VPN (Metro Ethernet) Discovery** in the Discovery window before starting the Discovery process, then after the previous steps are complete, the Discovery Workflow window shows the L2VPN (Metro Ethernet) Discovery as **Pending Input**, as shown in Figure 4-42.

**Figure 4-42** Discovery Workflow Window with MPLS Ethernet Discovery Pending Input

The screenshot shows the IP Solution Center interface. The top navigation bar includes 'Service Inventory', 'Service Design', 'Monitoring', 'Diagnostics', and 'Administration'. The 'Discovery' tab is selected. The 'Discovery Workflow' section displays a table of discovery steps. The 'L2VPN (Metro Ethernet) Discovery' step is highlighted with an orange status bar and labeled 'Pending Input'. Below the table, there is a 'Progress' section with a 'Continue' button and an 'Auto Refresh' checkbox.

Step	Status	Start Time	End Time	Log	Summary
Device Discovery	Complete	2005-09-28 15:47:16	2005-09-28 15:53:38	<a href="#">[View]</a>	<a href="#">[View]</a>
Collect Configuration	Complete	2005-09-28 15:53:42	2005-09-28 15:56:33	<a href="#">[View]</a>	<a href="#">[View]</a>
Role Assignment	Complete	2005-09-28 15:56:37	2005-09-28 16:00:59	<a href="#">[View]</a>	<a href="#">[View]</a>
NPC Discovery	Complete	2005-09-28 16:01:01	2005-09-28 16:03:23	<a href="#">[View]</a>	<a href="#">[View]</a>
L2VPN (Metro Ethernet) Discovery	Pending Input	2005-09-28 16:03:33		<a href="#">[View]</a>	<a href="#">[View]</a>

Progress: Select 'Continue' to edit and view L2VPN (Metro Ethernet) Services. [Continue](#)

Auto Refresh: ☒

Follow these steps to initiate Metro Ethernet Service Discovery:

- Step 1** Before you initiate Metro Ethernet Service Discovery, follow these steps:
- Navigate to **Service Inventory > Inventory and Connection Manager**.
  - In the task pane at the left of the Inventory and Connection Manager window, select **Access Domains**.
  - Create access domains for any N-PE devices in the Metro Ethernet topology.  
For detailed instructions, see the “Creating Access Domains” section in the *Cisco IP Solution Center Infrastructure Reference, 4.1* at the following URL:  
[http://www.cisco.com/en/US/products/sw/netmgts/ps4748/products\\_technical\\_reference\\_chapter\\_09186a008037209e.html#wp1103637](http://www.cisco.com/en/US/products/sw/netmgts/ps4748/products_technical_reference_chapter_09186a008037209e.html#wp1103637)
  - Navigate to **Service Inventory > Inventory and Connection Manager**.
  - In the task pane at the left of the Inventory and Connection Manager window, select **Resource Pools**.
  - Create resource pools for each of the access domains that you created.  
For detailed instructions, see “Resource Pools” in Chapter 3, “Service Inventory — Inventory and Connection Manager.”


g. Navigate to **Service Inventory > Discovery**.

The Discovery Workflow window shows the L2VPN (Metro Ethernet) Discovery process as **Pending Input**.

**Step 2** Click **Continue**.

The L2VPN Discovery (Ethernet Services) window appears, as shown in [Figure 4-43](#).

**Figure 4-43 L2VPN Discovery (Ethernet Services) Window**



**Step 3** Select one of the following actions:

- **View/Edit Discovered Layer 2 Services grouped by VPN**—Lets you view the discovered L2VPN services and edit them as required.
- **View/Edit Discovered Layer 2 End to End Wires**—Lets you view the discovered Layer 2 End to End wires and edit them as required.
- **View/Edit Discovered Layer 2 VPLS Links**—Lets you view the discovered Layer 2 Virtual Private LAN Service (VPLS) links and edit them as required.


The following sections of this chapter describe each of these actions.

## Viewing Discovered Layer 2 Services Grouped by VPN

Follow these steps to view discovered Layer 2 services grouped by VPN:

**Step 1** In the L2VPN Discovery (Ethernet Services) window, click the **VPNs** button.

The L2 VPNs window appears, as shown in [Figure 4-44](#).


**Figure 4-44 L2 VPNs Window**

The L2 VPNs window allows you to perform the following tasks:

- View detailed information about a Layer 2 VPN.  
This task is explained in the following steps of this procedure.
- Display a window that allows you to edit the configuration information for an existing Layer 2 VPN.  
See [Editing Discovered Layer 2 Services Grouped by VPN](#), page 4-68 for detailed instructions.
- Delete an existing Layer 2 VPN.  
See [Deleting Discovered Layer 2 Services Grouped by VPN](#), page 4-69 for instructions on this task.

**Step 2** To view detailed information about a Layer 2 service, check the check box next to a VPN whose details you want to view and then click the **Details** button.

The Link Details window appears, as shown in [Figure 4-45](#).

**Figure 4-45 Link Details Window**

The Link Details window shows the details about the discovered VPN, such as the User-Network Interface (UNI), in a table format.

**Step 3** When you are done viewing the link details, click the **Close** button.

## Editing Discovered Layer 2 Services Grouped by VPN

You can edit a discovered Layer 2 VPN service to change the policy that is applied to the service. Follow these steps to edit a Layer 2 VPN service:

**Step 1** In the L2 VPNs window, check the check box next to a VPN that you want to edit and then click the **Edit** button.

The Edit Link Policy window appears, as shown in [Figure 4-46](#).

**Figure 4-46** Edit Link Policy Window

The screenshot shows the 'Edit Link Policy' window in the Cisco IP Solution Center. The window has a header with the Cisco logo and navigation tabs: Service Inventory, Service Design, Monitoring, Diagnostics, and Administration. Below the tabs are links for Inventory and Connection Manager, Discovery, and Device Console. The main content area is titled 'Edit Link Policy' and contains a 'Policy Name' field with a 'Select' button, 'Save' and 'Cancel' buttons, and a table of 'Selected Links'. The table has columns for '#', 'UNI', 'U-PE', 'N-PE', and 'Policy Name'. One link is listed: '1. GigabitEthernet0/9 mlsr1 mlpe8' with policy 'DiscoveredVPLSPolicy\_VPLS\_ERMS\_NO\_CE'. A note at the bottom states '\* - Required Field'.

**Step 2** To change the link policy for the service, follow these steps:

- a. Click the **Policy** button next to the Policy Name field.

A list of policies appears.

You can change the list of policies by choosing a filter from the pull-down list in the **Show VPN policies with** field and/or entering a search mask in the **Matching** field.

You can filter the policy list by Policy Name, Customer Name, Provider Name, or Global policy name. And you can limit the lists of policies displayed in the selected category by entering a value in the Matching field.

**Step 3** Select the radio button next to a policy that you want to apply to the service and then click **Select**.

**Step 4** Do one of the following:

- Click **Save** to save your changes.
- Click **Cancel** to cancel the changes.

## Deleting Discovered Layer 2 Services Grouped by VPN

Follow these steps to delete a Layer 2 service:

- Step 1** In the L2 VPNs window, check the check box next to a VPN that you want to delete and then click the **Delete** button.

The following message appears:

Links/End to End wires associated with all selected VPNs will be deleted as a result of this operation. Do you really want to Delete?


- Step 2** If you are sure that you want to delete the VPN, click **OK**; otherwise, click **Cancel**.  
If you click **OK**, the VPN and associated links and end-to-end wires are deleted.

## Viewing Discovered Layer 2 End to End Wires

Follow these steps to view discovered Layer 2 end to end wires:

- Step 1** In the L2VPN Discovery (Ethernet Services) window, click the **End-End Wires** button.  
The Metro Ethernet End to End Wires window appears, as shown in [Figure 4-47](#).

**Figure 4-47 Metro Ethernet End- to-End Wires Window**



The Metro Ethernet End to End Wires window allows you to perform the following tasks:

- View detailed information about a Metro Ethernet end-to-end wire.  
This task is explained in the following steps of this procedure.
- Edit the VPN associated with the end-to-end wire.  
See [Editing the VPN Associated with an End-to-End Wire](#), page 4-71 for a description of this task.
- Split an existing end-to-end wire into two end-to-end wires  
See [Splitting Layer 2 Service End to End Wires](#), page 4-72 for a description of this task.

Step 7: Perform L2VPN (Metro Ethernet) Service Discovery (Optional)

- Join existing end-to-end wires into a single end-to-end wire  
See [Joining Layer 2 Service End to End Wires](#), page 4-73 for a description of this task.
- Delete an existing end-to-end wire.  
See [Deleting Discovered Layer 2 Services Grouped by VPN](#), page 4-69 for instructions on this task.

**Step 2** To view detailed information about a Layer 2 service, check the check box next to a VPN whose details you want to view and then click the **Details** button.

The Link Details window appears, as shown in [Figure 4-48](#).

**Figure 4-48 Link Details Window**

The screenshot shows a window titled "Link Detail" with two main sections: "General" and "Link Properties".

General	
VPN Name:	DiscoveredVPLSVPN_vpls_mpls_ers-1003
Customer Name:	Default_Customer
Policy Name:	DiscoveredVPLSPolicy_VPLS_ERMS_NO_CE

Link Properties	
N-PE:	mlpe8
NPE Interface:	GigabitEthernet7/2
U-PE:	mlsw1
UNI:	GigabitEthernet0/9
VLAN:	753
CE:	
CE Interface:	

At the bottom right of the window is a "Close" button. On the far right edge of the window, the number "149091" is visible.

- Step 3** When you are done viewing the link details, click the **Close** button.
- Step 4** If you want to view the details of the interfaces in the end-to-end wire, click the interface name in either the AC1 UNI or AC2 UNI field.
- If you click on an interface name, the Interface Detail window appears, as shown in [Figure 4-49](#).



**Figure 4-49**      **Interface Detail Window**

Interface Detail	
<b>General</b>	
VPN Name:	DiscoveredVPWSVPN_1005
Provider Name:	
Customer Name:	
<b>Device Information</b>	
Device Host Name:	mlpe5
Device Domain Name:	cisco.com
<b>Interface Detail</b>	
Interface Name:	FastEthernet8/2
Interface Description:	
Is Subinterface ?:	false
Maximum Allowed MAC Address:	
Encapsulation:	DOT1Q
Interface Type:	FastEthernet
Switch Mode:	TRUNK
MAC Access Group:	
Speed:	UNKNOWN
Duplex:	UNKNOWN
Close	

The Interface Detail window shows details about the selected interface, such as the hostname of the host where the interface is located, the type of encapsulation used on the interface, and the switch mode used on the interface.

**Step 5** When you are done viewing the interface details, click the **Close** button.

## Editing the VPN Associated with an End-to-End Wire

From the Metro Ethernet End to End Wires window, you can also edit the VPN that is associated with the end-to-end wire.

Follow these steps to edit the VPN associated with an end-to-end wire:

**Step 1** In the Metro Ethernet End to End Wires window, click a VPN name shown in the VPN name field. The Edit VPN window appears, as shown in [Figure 4-50](#).

**Figure 4-50** Edit VPN Window for L2VPN VPNs

**Step 2** To edit the VPN name, enter a new VPN name in the VPN Name field.

**Step 3** To edit the Customer Name, follow these steps:

- a. Click the **Select** button next to the Customer Name.  
A list of customers appears.
- b. Select the radio button next to the new Customer Name that you want to configure.
- c. Click the **Save** button.

The new VPN name and/or Customer Name appears in the Metro Ethernet End to End Wires window.

## Splitting Layer 2 Service End to End Wires

You can split off an existing end-to-end wire from the VPN that it is associated with and associate it with a new VPN.

Follow these steps to split an end-to-end wire from an existing VPN:

**Step 1** In the Metro Ethernet End to End Wires window, check the check box next to an end-to-end wire entry that you want to split from a VPN.



**Note** If there is only one ID for the VPN associated with the end-to-end wire, then you cannot perform a split action on the wire.

**Step 2** Click the **Split** button.

A message appears asking if you want to proceed.

**Step 3** If you want to continue with the process, click **OK**.

The end-to-end wires are split and are associated with two new VPNs. These names of the VPNs are created by the system by adding a new number the end of the existing VPN name.

## Joining Layer 2 Service End to End Wires

You can join two existing end-to-end wires to a single VPN.

Follow these steps to join two existing end-to-end wires:

- 
- Step 1** In the Metro Ethernet End to End Wires window, check the check box next to several end-to-end wire entries that you want to join
- A message appears asking if you want to proceed.
- Step 2** If you want to continue with the process, click **OK**.
- The selected end-to-end wires are joined to a new VPN. The name for this VPN is created by the system by adding a new number to the end of the existing highest numbered VPN name.
- 

## Deleting Layer 2 Service End to End Wires

Follow these steps to delete an existing end-to-end wire:


- 
- Step 1** In the Metro Ethernet End to End Wires window, check the check box next to one or more end-to-end wires that you want to delete.
- A message appears asking if you want to proceed.
- Step 2** If you want to continue with the process, click **OK**.
- The selected end-to-end wire (or wires) is deleted. Any Attachment Circuit(s) associated with the wire(s) are also deleted.
- Step 3** Click **Close** to close the Metro Ethernet End to End Wires window.
- 

## Viewing Discovered Layer 2 VPLS Links

Follow these steps to view discovered Layer 2 VPLS links:

- 
- Step 1** In the L2VPN Discovery (Ethernet Services) window, click the **VPLS Links** button.
- The VPLS Links window appears, as shown in [Figure 4-51](#).

Figure 4-51 VPLS Links Window




The VPLS Links window allows you to perform the following tasks:

- View detailed information about a VPLS link.  
This task is explained in the following steps of this procedure.
- Display a window that allows you to edit the configuration information for an existing VPLS link.  
See [Editing Discovered Layer 2 VPLS Links, page 4-75](#) for detailed instructions.
- Delete an existing Layer 2 VPN.  
See [Deleting Discovered Layer 2 VPLS Links, page 4-76](#) for instructions on this task.

**Step 2** To view detailed information about a VPLS link, check the check box next to a VPLS link whose details you want to view and then click the **Details** button.

The Link Details window appears, as shown in [Figure 4-52](#).

**Figure 4-52**      **Link Details Window**


The screenshot shows a 'Link Detail' window with two sections: 'General' and 'Link Properties'. The 'General' section contains fields for VPN Name, Customer Name, and Policy Name. The 'Link Properties' section contains fields for N-PE, NPE Interface, U-PE, UNI, VLAN, CE, and CE Interface. A 'Close' button is located at the bottom right of the window. A vertical label '149091' is visible on the right side of the window.

Link Detail	
<b>General</b>	
VPN Name:	DiscoveredVPLSVPN_vpls_mpls_ers-1003
Customer Name:	Default_Customer
Policy Name:	DiscoveredVPLSPolicy_VPLS_ERMS_NO_CE
<b>Link Properties</b>	
N-PE:	mlpe8
NPE Interface:	GigabitEthernet7/2
U-PE:	mlsw1
UNI:	GigabitEthernet0/9
VLAN:	753
CE:	
CE Interface:	
Close	

The Link Details window shows the details about the discovered VPN, such as the User-Network Interface (UNI), in a table format.

**Step 3** When you are done viewing the link details, click the **Close** button.

## Editing Discovered Layer 2 VPLS Links

You can edit a discovered Layer 2 VPLS link to change the policy that is applied to the service. Follow these steps to edit a Layer 2 VPLS link:

**Step 1** In the VPLS Links window, check the check box next to a VPLS link that you want to edit and then click the **Edit** button.

The Edit Link Policy window appears, as shown in [Figure 4-53](#).

**Figure 4-53** Edit Link Policy Window

**IP Solution Center**

Service Inventory | Service Design | Monitoring | Diagnostics | Administration

Inventory and Connection Manager | **Discovery** | Device Console

You Are Here: Service Inventory > Discovery

### Edit Link Policy

Policy Name:

Selected Links:

#	UNI	U-PE	N-PE	Policy Name
1.	GigabitEthernet0/9	mls w1	mlpe8	DiscoveredVPLSPolicy_VPLS_ERMS_NO_CE

Showing 1 - 1 of 1 record

Rows per page: 10 Go to page: 1 of 1

Note: \* - Required Field

**Step 2** To change the link policy for the link, follow these steps:

- a. Select the **Policy** button next to the Policy Name field.

A list of policies appears.

You can change the list of policies by choosing a filter from the pull-down list in the **Show VPN policies with** field and/or entering a search mask in the **Matching** field.

You can filter the policy list by Policy Name, Customer Name, Provider Name, or Global policy name. And you can limit the lists of policies displayed in the selected category by entering a value in the Matching field.

**Step 3** Select the radio button next to a policy that you want to apply to the service and then click **Select**.

**Step 4** Do one of the following:

- Click **Save** to save your changes.
- Click **Cancel** to cancel the changes.

## Deleting Discovered Layer 2 VPLS Links

Follow these steps to delete a VPLS link:

**Step 1** In the VPLS Links window, check the check box next to a VPLS link that you want to delete and then click the **Delete** button.

The following message appears:

The selected link(s) will be deleted. Do you really want to Delete?

**Step 2** If you are sure that you want to delete the VPLS, click **OK**; otherwise, click **Cancel**.

If you click **OK**, the VPLS link(s) are deleted.

**Step 3** Click **Close** to close the VPLS links window.

## Saving the L2VPN Metro Ethernet Policy and Initiating Service Creation


After you are done viewing or editing the discovered L2VPN Metro Ethernet topology, click the **Close** button to return to the L2 VPN Discovery (Ethernet Services) window.

Click the **Continue** button to initiate the L2 VPN Service Discovery process.

The Discovery Workflow window appears and indicates that the L2 VPN Service Discovery process is **In Progress**; the status indicator is yellow.

After the L2 VPN Service Discovery process is complete, the status indicator changes to green, and the Discovery Workflow window indicates that the L2 VPN Service Discovery process is **Complete**, as shown in Figure 4-54.

**Figure 4-54** Discovery Workflow Window with L2 VPN Service Discovery Completed



## Step 8: Create and Run a Collect Config Task for the Discovered Devices

Before you view and edit services, follow these steps to run a Create Config task for the devices:



### Note

For additional information on the Create Config task, see the “Create” subsection in the section “Task Manager” in [Chapter 7, “Monitoring.”](#)

**Step 1** On the ISC Start page, select **Monitoring**.

The Monitoring window appears.

**Step 2** Select **Task Manager**.

The Tasks window appears.

- Step 3** Select the **Create** button and choose **Collect Config** from the pull-down list.  
The Create Task window appears.
- Step 4** Click the **Next** button.  
The Collect Config Task window appears.
- Step 5** On the Collect Config task window, follow these steps to create and run a Collect Config task:
- Click the **Select/Deselect** button.  
A dialog window appears listing the devices that were discovered by the Discovery process.
  - Select all of the devices shown on the list.
  - Click the **Select** button.  
The Collect Config Task window appears again.
  - Specify the additional settings for the Collect Config task as required.
  - Click the **Submit** button.
- You are now ready to view and edit services as described in the following section, [Step 9: View and Edit Services, page 4-78](#)
- 

## Step 9: View and Edit Services

After you have successfully completed the MPLS VPN and/or L2VPN Metro Ethernet service creation process, you can view the services that were created and modify them using the service requests editors. Follow these steps to view the L2VPN services:

- 
- Step 1** If the Service Inventory window is not currently active, click the **Service Inventory** tab.  
The Service Inventory window is now active.
- Step 2** In the Service Inventory window, click **Service Inventory**.  
The Inventory and Connection Manager window appears, as shown in [Figure 4-55](#).




Figure 4-55 Inventory and Connection Manager Window

**Step 3** Click **Service Requests**.

The Service Requests window appears, as shown in Figure 4-56.

Figure 4-56 Service Requests Window



You can modify the service requests shown in the Service Requests window as required.

**Note**

If you need to edit MPLS VPNs as part of this process, see the [Splitting a VPN, page 4-58](#), [Creating a VPN, page 4-61](#), [Viewing VPN Link Details, page 4-63](#), and [Saving the MPLS VPNs and Initiating MPLS VPN Service Creation, page 4-64](#).

- Step 4** For detailed information on modifying Service Requests for L2VPN Metro Ethernet networks, see the *Cisco IP Solution Center L2VPN User Guide, 4.1*.
- Step 5** For general information on the release, see the *Release Notes for Cisco IP Solution Center, 4.1*, provided with the release.



## Service Inventory—Device Console

From the Home window of Cisco IP Solution Center (ISC), which you receive upon logging in, click the **Service Inventory** tab or area in the data pane of the window, and you receive a window as shown in [Figure 5-1](#), “[Service Inventory Selections](#).”

**Figure 5-1**      *Service Inventory Selections*



Click on **Device Console** and you proceed to [Figure 5-2](#), “[Example of Device Console Selections](#)” and can choose one of the device related operations.

## Device Console

**Device Console** is the starting point for many operations. To navigate through **Device Console**, follow these steps:

- Step 1**      Navigate **Service Inventory > Device Console** and you receive a window as shown in the example in [Figure 5-2](#), “[Example of Device Console Selections](#).”



**Note**

The radio button last selected will be the one shown in [Figure 5-2](#).

**Figure 5-2 Example of Device Console Selections**

**Step 2** To select one of the operations, click the radio button for one of the following selections and then click **Next**:

**Note**

All operations apply only to Live mode, *not* ECHO mode.

- [Download Commands, page 5-2](#) Download operation commands and configlets. The **Select Operation Method** selections of **Simplified** and **Advanced (via wizard)** are only available for **Download Commands** and are explained in that section.
- [Download Template, page 5-3](#) Downloads template configlets to the specified devices.
- [Device Configuration Manager, page 5-7](#) Displays different versions of configuration files created on a repository per timestamp and writes to running-configuration or start-up configuration.
- [EXEC Commands, page 5-9](#) Allows you to send to target devices any Cisco IOS commands that can be executed in enable mode.
- [Reload, page 5-13](#) Remotely reloads devices.

## Download Commands

To download commands, follow these steps:

- Step 1** Navigate **Service Inventory > Device Console > Download Commands**.
- Step 2** The **Select Operation Method** default is **Simplified**, which indicates that in a single window you have the options for selecting the Devices, Device Groups, and Operation Commands. You do not need to multi-click. In a single window you can submit the required parameters to complete the task. **Advanced (via wizard)** indicates you must go to multiple windows to achieve the task. In this method, you select Device, click **Next**, select Device Groups, click **Next**, select Operation Command, and then the summary.
- Step 3** Click **Next**. A window as shown in [Figure 5-3, “Device Console—Download Commands: Select Devices,”](#) appears.

**Figure 5-3** Device Console—Download Commands: Select Devices

**Device Console - Download Commands**

Devices: Select/Deselect

Groups: Select/Deselect

Operation Commands: Load File

Options: ☐ Upload Config After Download ☐ Retrieve device attributes

OK Cancel

Note: \* - Required Field

129042


- Step 4** In the **Devices** row, click **Select/Deselect**. In the new window, select the check box for each device you want. Deselect a check box if you do not want this device. Then click **Select**. [Figure 5-3](#) then reappears with the selected devices in the **Devices** row.
- Step 5** In the **Groups** row, click **Select/Deselect**. In the next window, select the check box for each group you want. Deselect a check box if you do not want this group. Then click **Select**. The selected groups appear in the **Groups** row.
- Step 6** In the **Operation Commands** field, enter the commands you want to download or click **Load File** to select a set of commands to place in the **Operation Commands** field.
- Step 7** If you leave the **Upload Config After Download** check box deselected, you do *not* upload the configuration file after the download.
- Step 8** If you leave the **Retrieve device attributes** check box deselected, you do not retrieve any device attributes. If you select the **Retrieve device attributes** check box, after the template is downloaded, SNMP is used to retrieve interface information and issue additional **show** commands, such as **show version**.
- Step 9** Click **OK** to submit the download and you receive a window with the **Device Console Operation Result** and in the bottom left corner a **Status**. You can click **Download** or **Done**.
- Step 10** When you click **Download**, you return to [Step 6](#) to download additional commands on the selected devices.
- Step 11** When you click **Done**, you return to [Figure 5-2](#).

## Download Template

To download a template, follow these steps:


- Step 1** Navigate **Service Inventory > Device Console > Download Template** from [Figure 5-2](#) and click **Next**. A window as shown in [Figure 5-4](#), “**Device Console—Download Template: Select Devices**,” appears.

Figure 5-4 Device Console—Download Template: Select Devices



- Step 2** Continue with [Step 3](#) if you want to add devices; proceed to [Step 8](#) to delete devices; or click **Next** to proceed to [Step 10](#) for **3. Select Device Groups**.
- Step 3** Click **Add**, as shown in [Figure 5-4](#), to **2. Select Devices**.
- Step 4** From the resulting window, as shown in [Figure 5-5](#), “[Device Selection](#),” select the check box(es) for each device you want to select. Then click **Select**.

Figure 5-5 Device Selection



- Step 5** You return to [Figure 5-4](#) with the added devices.

- Step 6** For each device, you can click the added **Clear** button to clear the **Upload to Customer/Site** column to reflect **none selected**, or you can click the added **Select** button and a new window allows you to **Create Customer**, **Create Site**, **Select**, or **Cancel**. When you click **Select** in this new window, you return to [Figure 5-4](#) with the added customer or site.
- Step 7** You can repeat [Step 3](#) to [Step 6](#) to add more devices, you can delete devices, as explained in [Step 8](#), or you can proceed by going to [Step 9](#).
- Step 8** To delete devices, select the check box(es) for the devices you want to delete and then click **Delete**. Select carefully, because there is no chance to confirm this deletion.
- Step 9** When you have all the devices you want, click **Next**. You proceed to **3. Select Device Groups**, starting in [Step 10](#).
- Step 10** Continue with [Step 11](#) if you want to add device groups; proceed to [Step 14](#) to delete device groups; or click **Next** to proceed to [Step 16](#) for **4. Enter Download Commands**.
- Step 11** Click **Add**, as shown in [Figure 5-6](#), to **3. Select Device Groups**. Adding Device Groups is optional.

**Figure 5-6** *Device Group Selection*

149019

- Step 12** From the resulting window, as shown in [Figure 5-7](#), “**Group Association**,” select the check box(es) for each device group you want to select. Then click **Select**.

**Figure 5-7** *Group Association*

149018

- Step 13** You return to [Figure 5-6](#) with the added device groups. You can repeat [Step 11](#) to [Step 12](#) to add more device groups, you can delete device groups, as explained in [Step 14](#), or you can proceed by going to [Step 15](#).
- Step 14** To delete device groups, select the check box(es) for the devices you want to delete and then click **Delete**. Select carefully, because there is no chance to confirm this deletion.

- Step 15** When you have all the device groups you want, click **Next**. You proceed to **4. Select Download Template**, starting in [Step 16](#).
- Step 16** For **4. Select Download Template**, the resulting window is shown in [Figure 5-8](#), “**Select Download Template**.”

**Figure 5-8** *Select Download Template*

#	Template	Data File	Action
Showing 0 of 0 records			

Rows per page: 10 Go to page: 1 of 1 Go

Select

- Step 17** In [Figure 5-8](#), you can click the **Select** button.
- Step 18** A window as shown in [Figure 5-9](#), “**Add/Remove Templates**,” appears. Click **Add** to add templates or **Remove** to remove templates. When you have the templates you want, click **OK**.
- When you click **Add** you get a Template Datafile Chooser window with the template choices in the tree. Click + to open the folders and subfolders in the tree, until you get the property you want to choose. Click on that property and it is added to your list. Repeat this until all the templates you want are in your list. In each added property, you can click **View** and you receive the configlet for that data file. To return, click **OK**. In [Figure 5-9](#), select the check box(es) for the template(s) you want. In each template row, click the **Action** drop-down list and choose **APPEND** or **PREPEND** to add information after or before, respectively; select or deselect the **Active** check box; and then click **OK**.

**Figure 5-9** *Add/Remove Templates*

#	Template	Data File	Action	Active
1.	/DIA-Channelization/10K-CHOC12-STS1-PATH SR_Data		APPEND	<input checked="" type="checkbox"/>

Showing 1 - 1 of 1 record

Rows per page: 10 Go to page: 1 of 1 Go

Add Remove OK Cancel

- Step 19** You return to [Figure 5-8](#) with the updated information.
- Step 20** Click **Next** and you proceed to **5. Download Template Summary**, as explained in [Step 21](#).
- Step 21** For **5. Download Commands Summary**, a window as shown in [Figure 5-10](#), “**Download Template Summary**,” appears.



**Figure 5-10 Download Template Summary**

Mode: ADDING	Devices:	pe1 sw2 ce3
<input checked="" type="checkbox"/> 1. Choose Operation	Device Groups:	Device-Group-1
<input checked="" type="checkbox"/> 2. Select Devices	Template:	/DIA-Channelization/10K-CHOC12-STS1-PATH
<input checked="" type="checkbox"/> 3. Select Device Groups	<input type="checkbox"/> Upload Config After Download	
<input checked="" type="checkbox"/> 4. Select Download Template	<input type="checkbox"/> Retrieve device attributes	
<input type="checkbox"/> 5. Download Template Summary		

- Step 22** In [Figure 5-10](#), if you leave the **Upload Config After Download** check box deselected, you do *not* upload the configuration file after the download. If you select the **Upload Config After Download** check box, you upload the new configuration file after you download the templates in [Step 18](#). If you leave the **Retrieve device attributes** check box deselected, you do not retrieve any device attributes. If you select the **Retrieve device attributes** check box, after the template is downloaded, SNMP is used to retrieve interface information and issue additional **show** commands, such as **show version**.
- Step 23** Click **Back** until you correct any information you want to change or click **Finish** to submit the download and you receive a window with the **Download Template Results** and in the bottom left corner a **Status** with a green check mark for **Succeeded**.
- Step 24** Click **Done** and you return to [Figure 5-2](#) on page 5-2.

## Device Configuration Manager

To display the configuration, download the configuration to the startup configuration on the device, or download the configuration to the running configuration on the device, follow these steps:

- Step 1** Navigate **Service Inventory > Device Console > Device Configuration Manager** and from [Figure 5-2](#) click **Next**. A window as shown in [Figure 5-11](#), “**Device Configuration Manager**,” appears.

**Figure 5-11** Device Configuration Manager

**Step 2** In the **Device** row, click **Select** and a window as shown in [Figure 5-12](#), “**Device Selection**,” appears.

**Figure 5-12** Device Selection

#	Device Name	Management IP Address	Type	Parent Device Name
1.	pe1		Cisco IOS Device	
2.	pe3		Cisco IOS Device	
3.	sw2		Cisco IOS Device	
4.	sw3		Cisco IOS Device	
5.	sw4		Cisco IOS Device	
6.	ce3		Cisco IOS Device	
7.	ce8		Cisco IOS Device	
8.	ce13		Cisco IOS Device	

**Step 3** From the devices listed, click the radio button for the device you want to select. Then click **Select**.

**Step 4** You return to [Figure 5-11](#) with the added device. You can repeat [Step 2](#) to [Step 3](#) to change the device.

**Step 5** When you have selected the device you want, go to the **Configuration to Display** row and click the **Select a Version...** drop-down list. Click the version you want and then click **Load** to load that configuration file.

**Step 6** Click one of the following radio buttons or keep the default:

- **Display only** The configuration file can only be viewed.
- **Download to startup** The configuration file is downloaded to the start up configuration of the selected router.



**Note** For **Download to startup**, the Device Access Protocol (defined in device creation) must be either **ftp** or **tftp**. If this is not the case, the Device Configuration Manager Results window appears and indicates that you must set up either **ftp** or **tftp**.

- **Download to running** The configuration file is downloaded to the router's running configuration file.



**Note** When the DCPL property **copy-running-to-startup** in the **GTL/ios** folder is set to the default of **true**, the router's running configuration file is also copied to the start up configuration.

**Step 7** Click **Finish**. If in [Step 6](#) you chose **Display only**, you automatically return to [Figure 5-2 on page 5-2](#). If in [Step 6](#) you clicked **Download to startup** or **Download to running**, you get a Device Configuration Manager Results window. In the **Status** box, you get a green check mark for **Succeeded** or a red **Failed** status and you must click **Done** to return to [Figure 5-2 on page 5-2](#).

## EXEC Commands

**EXEC Commands** allows you to send to target devices any Cisco IOS commands that can be executed in enable mode. You can only view the router information. You cannot edit or delete the information.

To execute **EXEC Commands**, follow these steps:

**Step 1** Navigate **Service Inventory > Device Console > EXEC Commands** and in [Figure 5-2](#) click **Next**. A window as shown in [Figure 5-13](#), “[Device Console—EXEC Commands: Select Devices](#),” appears.

**Figure 5-13** Device Console—EXEC Commands: Select Devices

- Step 2** Continue with [Step 3](#) if you want to add devices; proceed to [Step 6](#) to delete devices; or click **Next** to proceed to [Step 8](#) for **3. Select Device Groups**.
- Step 3** Click **Add**, as shown in [Figure 5-13](#), to **2. Select Devices**.
- Step 4** From the resulting window, as shown in [Figure 5-14](#), “**Device Selection**,” select the check box(es) for each device you want to select. Then click **Select**.

**Figure 5-14** Device Selection

#		Device Name	Management IP Address	Type	Parent Device Name
1.	<input type="checkbox"/>	pe1		Cisco IOS Device	
2.	<input type="checkbox"/>	pe3		Cisco IOS Device	
3.	<input type="checkbox"/>	sw2		Cisco IOS Device	
4.	<input type="checkbox"/>	sw3		Cisco IOS Device	
5.	<input type="checkbox"/>	sw4		Cisco IOS Device	
6.	<input type="checkbox"/>	ce3		Cisco IOS Device	
7.	<input type="checkbox"/>	ce8		Cisco IOS Device	
8.	<input type="checkbox"/>	ce13		Cisco IOS Device	

- Step 5** You return to [Figure 5-13](#) with the added devices. You can repeat [Step 3](#) to [Step 4](#) to add more devices, you can delete devices, as explained in [Step 6](#), or you can proceed by going to [Step 7](#).
- Step 6** To delete devices, select the check box(es) for the devices you want to delete and then click **Delete** in [Figure 5-13](#). Select carefully, because there is no chance to confirm this deletion.

- Step 7** When you have all the devices you want, click **Next**. You proceed to **3. Select Device Groups**, starting in [Step 8](#).
- Step 8** Continue with [Step 9](#) if you want to add device groups; proceed to [Step 12](#) to delete device groups; or click **Next** to proceed to [Step 14](#) for **4. Enter EXEC Commands**.
- Step 9** Click **Add**, as shown in [Figure 5-15](#), to **3. Select Device Groups**.

**Figure 5-15 Device Group Selection**


- Step 10** From the resulting window, as shown in [Figure 5-16](#), “**Group Association**,” select the check box(es) for each device group you want to select. Then click **Select**.

**Figure 5-16 Group Association**

- Step 11** You return to [Figure 5-15](#) with the added device groups. You can repeat [Step 9](#) to [Step 10](#) to add more device groups, you can delete device groups, as explained in [Step 12](#), or you can proceed by going to [Step 13](#).
- Step 12** To delete device groups, select the check box(es) for the devices you want to delete and then click **Delete**. Select carefully, because there is no chance to confirm this deletion.
- Step 13** When you have all the device groups you want, click **Next**. You proceed to **4. Enter EXEC Commands**, starting in [Step 14](#).

**Step 14** For **4. Enter EXEC Commands**, the resulting window is shown in [Figure 5-17](#), “**Operation Commands**.”

**Figure 5-17**      *Operation Commands*




**Step 15** In [Figure 5-17](#), you can click the **Browse** button to input an existing file with Cisco IOS configuration commands. Then click the **Load File** button to put the file’s information in the **Commands** field. Otherwise, you can enter the Cisco IOS configuration commands directly in the **Commands** field.

**Step 16** Click **Next** and you proceed to **5. EXEC Commands Summary**, as explained in [Step 17](#).

**Step 17** For **5. EXEC Commands Summary**, a window as shown in [Figure 5-18](#), “**EXEC Commands Summary**,” appears.

**Figure 5-18**      *EXEC Commands Summary*



**Step 18** Click **Back** until you correct any information you want to change or click **Finish** to retrieve the information from the router. You then receive a window with the **EXEC Commands Results** and a **Status** with a green check mark for **Succeeded**. You can click **EXEC** or **Done**.

- Step 19** When you click **EXEC**, you return to [Step 14](#) to enter additional commands on the selected devices.
- Step 20** When you click **Done**, you return to [Figure 5-2 on page 5-2](#).

## Reload

To reload (reboot) the router, follow these steps:

- Step 1** Navigate **Service Inventory > Device Console > Reload** and from [Figure 5-2](#) click **Next**. A window as shown in [Figure 5-19](#), “**Device Console—Reload: Select Devices**,” appears.

**Figure 5-19** *Device Console—Reload: Select Devices*

- Step 2** Continue with [Step 3](#) if you want to add devices; proceed to [Step 6](#) to delete devices; or click **Next** to proceed to [Step 8](#) for **3. Select Device Groups**.
- Step 3** Click **Add**, as shown in [Figure 5-19](#), to **2. Select Devices**.
- Step 4** From the resulting window, as shown in [Figure 5-20](#), “**Device Selection**,” select the check box(es) for each device you want to select. Then click **Select**.

**Figure 5-20 Device Selection**

#	<input type="checkbox"/>	Device Name	Management IP Address	Type	Parent Device Name
1.	<input type="checkbox"/>	pe1		Cisco IOS Device	
2.	<input type="checkbox"/>	pe3		Cisco IOS Device	
3.	<input type="checkbox"/>	sw2		Cisco IOS Device	
4.	<input type="checkbox"/>	sw3		Cisco IOS Device	
5.	<input type="checkbox"/>	sw4		Cisco IOS Device	
6.	<input type="checkbox"/>	ce3		Cisco IOS Device	
7.	<input type="checkbox"/>	ce8		Cisco IOS Device	
8.	<input type="checkbox"/>	ce13		Cisco IOS Device	

Rows per page: 10 Go to page: 1 of 1 Go

Select Cancel

- Step 5** You return to [Figure 5-19](#) with the added devices. Repeat [Step 3](#) to [Step 4](#) to add more devices; delete devices, as explained in [Step 6](#); or proceed by going to [Step 7](#).
- Step 6** To delete devices, select the check box(es) for the devices you want to delete and then click **Delete**. Select carefully, because there is no chance to confirm this deletion.
- Step 7** When you have all the devices you want, click **Next**. You proceed to **3. Select Device Groups**, starting in [Step 8](#).
- Step 8** Continue with [Step 9](#) if you want to add device groups; proceed to [Step 12](#) to delete device groups; or click **Next** to proceed to [Step 14](#) for **4. Reload Devices Summary**.
- Step 9** Click **Add**, as shown in [Figure 5-21](#), to **3. Select Device Groups**.

**Figure 5-21 Device Group Selection**

Device Console - Reload: Select Device Groups

ShowDevice Groups with Device Group Name matching \* Find

Showing 0 of 0 records

#	<input type="checkbox"/>	Device Group Name	Description
---	--------------------------	-------------------	-------------

Rows per page: 10 Go to page: 1 of 1 Go

Add Delete

- Step 3 of 4 -

< Back Next > Finish Cancel



- Step 10** From the resulting window, as shown in [Figure 5-22](#), “Group Association,” select the check box(es) for each device group you want to select. Then click **Select**.

**Figure 5-22 Group Association**

#	Device Group Name	Description
1.	Device-Group-1	
2.	Device-Group-2	

- Step 11** You return to [Figure 5-21](#) with the added device groups. Repeat [Step 9](#) to [Step 10](#) to add more device groups; delete device groups, as explained in [Step 12](#); or proceed by going to [Step 14](#).
- Step 12** To delete device groups, select the check box(es) for the devices you want to delete in [Figure 5-21](#) and then click **Delete**. Select carefully, because there is no chance to confirm this deletion.
- Step 13** When you have all the device groups you want, click **Next**. You proceed to **4. Reload Devices Summary**, starting in [Step 14](#).
- Step 14** For **4. Reload Devices Summary**, a window as shown in [Figure 5-23](#), “Reload Summary,” appears.

**Figure 5-23 Reload Summary**

- Step 15** Click **Back** until you correct any information you want to change or click **Finish** to submit the reload and you receive a window with the **Reload Results** and a **Status** with a green check mark for **Succeeded**.
- Step 16** Click **Finish** and you return to [Figure 5-2 on page 5-2](#).






# Service Design

From the Home window of Cisco IP Solution Center (ISC), you receive upon logging in, click the **Service Design** tab and you receive a window as shown in [Figure 6-1](#), “[Service Design Selections](#).”

**Figure 6-1**      **Service Design Selections**



Next you can navigate to the following selections:

- [Policies, page 6-1](#) Create and manage Policies for licensed services.
- [Templates, page 6-2](#) Create and manage Templates and associated data.
- [Link QoS, page 6-37](#) Create and manage IP Link QoS and Ethernet Link QoS settings.

## Policies

Policies is explained in each of the *User Guides* for each of the licensed services.

# Templates

Templates supports the browsing, creation, and deletion of Template Folders, Templates, and Data Files and it supports the viewing of Template-generated configurations. The configuration created from the template and data file can be downloaded to devices. When creating a Service Request, you can select from the list of templates and data files and associate them with the Service Request. At Deploy time, the template and data file are instantiated and the configuration is appended or prepended to the configlet generated by ISC.

ISC provides a way to integrate a template with ISC configlets.

For a given customer edge router and/or provider edge router, you specify the following:

- template name
- template data file name
- whether the template configuration file should be appended or prepended to the ISC configlet
- whether the template configuration file is active or inactive for downloading to the edge device


The template data files are tightly linked with the corresponding template. You can use a data file and its associated template to create a template configuration file. The template configuration file is merged with (either appended or prepended to) the ISC configlet. ISC downloads the combined ISC configlet and template configuration file to the edge device router.

- You can download a template configuration file to a router.
- You can apply the same template to multiple edge routers, assigning the appropriate template data file for each device. Each template data file includes the specific data for a particular device (for example, the management IP address or host name of each device).

To use Templates, follow these steps:

- Step 1** Navigate to **Service Design > Templates** and you receive a window as shown in [Figure 6-2](#), “[Templates](#).”

**Figure 6-2**      *Templates*



Template examples are shown in the left column. A complete list of template examples is specified in the “[Template Examples](#)” section on page 6-21. A complete list of Repository variables is shown in the “[Summary of Repository Variables](#)” section on page 6-23.

- Step 2** Then you can do any of the following:
- [View Templates Tree and Data Pane, page 6-3](#)
  - [Create Folders and Subfolders, page 6-4](#)
  - [Create Template, page 6-5](#)
  - [Create Data File, page 6-14](#)
  - [Edit, page 6-19](#)
  - [Delete, page 6-20](#)
- 

## View Templates Tree and Data Pane

When you navigate to **Service Design > Templates**, you receive a window as shown in [Figure 6-3](#), “[Tree and Data Pane Structure](#).”

The Templates tree is in the left column. You can continue clicking the + sign next to each created folder and subfolder until you get to the last level of information. The last possible level is the template name. Data file information is not kept in the tree.

The right section of the window is the data pane. The name of the folder or template is in the upper-left corner. When you select the check box next to the template or data file information, the **Create Template**, **Create Data File**, **Edit**, or **Delete** buttons are enabled as described in the following sections.

When there are many templates in a folder or many data files in a template, the **Show Template Matching** or **Show Data File Matching** filter in the upper right-hand corner of the data pane can be very useful. For example, you might just want to work with templates or data files that start with **abc**. In this case, enter **abc\*** in the field and then click the **Show** button. Only the templates or data files that start with **abc** appear.

You can also **View** configurations when the table displays data files.

Figure 6-3 Tree and Data Pane Structure



## Create Folders and Subfolders

To create a new folder or subfolder, follow these steps:


- Step 1** Navigate to **Service Design > Templates**.
- Step 2** In the **Templates** tree, right-click in the white area and select **New > Folder** to create a new folder or right-click on an existing folder or subfolder and select **New > Folder** to create a subfolder.



### Note

There is no limit to the number of levels of folders and subfolders you can create.

- Step 3** In the new text field that appears in the **Templates** tree, type the new folder or subfolder name, as shown in the first entry of the **Templates** tree in [Figure 6-4, "Folder Naming."](#)

**Figure 6-4 Folder Naming**

## Copying Folders or Subfolders

To copy a folder or subfolder and paste it into another folder or subfolder, follow these steps:

- Step 1** Select a folder or subfolder and then right-click and you receive the opportunity to copy. Click **Copy**.
- Step 2** Right-click on the folder or subfolder into which you want to paste the copied folder or subfolder and all its content and click **Paste**.
- Step 3** You will see the new folder or subfolder and all its content in the selected location. You can edit and rename from there.



### Note


This function works with Internet Explorer but not with Netscape.

## Create Template


You can either create a new template in an existing folder or you can create a new folder first and then create the template. To create a new folder, see the section [“Create Folders and Subfolders”](#).

To create a new template, follow these steps:

- Step 1** Navigate to **Service Design > Templates**.
- Step 2** In the **Templates** tree, click on the folder in which you want to create a new template.
- Step 3** A window appears as shown in [Figure 6-5, “Folder with Existing Templates.”](#)

**Figure 6-5** Folder with Existing Templates

**Step 4** Click the **Create Template** button and you receive a window as shown in Figure 6-6, “Template Editor.”

**Figure 6-6** Template Editor

**Step 5** Enter the following:

- **Template Name** (required) This must be a unique name within a folder. This name must begin with an alphabetic character and can only contain alphanumeric characters, underscores, and hyphens.
- **Description** (optional) You can enter any description here.
- **Body** (required) Enter the configuration text, Velocity template language directives, and variables that you want included.



**Note**

The Velocity template language is explained at <http://jakarta.apache.org/velocity/user-guide.html>.

An example template is shown in Figure 6-7, “Example Template.”

**Figure 6-7 Example Template**

The screenshot shows the 'Template Editor' window. The 'Template Name' field contains '/Examples/CEWanCOS'. The 'Description' field is empty. The 'Body' field contains the following Velocity template code:

```
This template demonstrate if-else statements, repeat statements,
mathematic
expression, 1 dimensional variables

access-list 103 permit host $CE-lo0 $mgt-prefix $mgt-mask
access-list 104 permit $protocol.get(0)
!
#foreach ($class in $class-maps)
 class-map match-all $class
 match $class-match.get($velocityCount)
 #end
!
policy-map $service-policy
#foreach ($class in $class-maps)
 class $class
 #if ($class == "business")
```

At the bottom of the editor, there are checkboxes for 'Required Fields' (checked) and 'Has User Section' (unchecked). On the right side, there is a 'Select & Click Go' dropdown menu, and 'Go', 'Save', and 'Close' buttons. A vertical label '93447' is visible on the right edge of the window.

ISC has the template system predefined variable **\$TMSysstem** that can be used within the template body text to access template system functions. The syntax is as follows, where, \$ipAddrMask is a string that contains an IP address and its mask in the format of: 10.33.4.5/30:

\$TMSysstem.getAddr (\$ipAddrMask) returns: 10.33.4.5

\$TMSysstem.getMask (\$ipAddrMask) returns: 255.255.255.252

\$TMSysstem.getReverseMask (\$ipAddrMask) returns: 0.0.0.3

\$TMSysstem.getNetworkAddr (\$ipAddrMask) returns: 10.33.4.4

\$TMSysstem.getClassfulNetworkAddr (\$ipAddrMask) returns: 10.0.0.0

**Step 6** Click the **Select & Click Go** drop-down list. If you want to validate the information you entered in Step 5, select **Validate** and then click the **Go** button. Otherwise, select **Variables** and then click the **Go** button and you receive a window as in Figure 6-8, *Template Variables*”.

**Figure 6-8** *Template Variables*

Template Variables – Netscape				
Showing 1-10 of 34 records				
		Variable	Type	Description
1.	<input type="radio"/>	class-match	String	
2.	<input type="radio"/>	bestEffort-pct	String	
3.	<input type="radio"/>	manag-pct	String	
4.	<input type="radio"/>	goldBurst	Integer	
5.	<input type="radio"/>	business-weighting-constant	Integer	
6.	<input type="radio"/>	silverBurst	String	
7.	<input type="radio"/>	be-mark	String	
8.	<input type="radio"/>	rp-que-limit	String	
9.	<input type="radio"/>	be-min-thresh	String	
10.	<input type="radio"/>	GESubInterface	String	

Rows per page: 10 Go to page: 1 of 4 Pages

**Step 7** Click the radio button for the Variable you want to edit and click **Edit**. You receive a window as in [Figure 6-9](#), “Variable Definition—Type String.”

**Figure 6-9** *Variable Definition—Type String*

**Variable bestEffort-pct**

Type: String

Description:

Required: ☒

Dimension: 0

Pattern:

Minimum Length:

Maximum Length:

☒ Default Value:

☐ Available Values (comma separated):

\* Required Fields

**Step 8** In [Figure 6-9](#), click the drop-down list for **Type** to receive the following choices:

- **String** Proceed to [Step 9](#).
- **Integer** Proceed to [Step 10](#).

- **Float** Proceed to [Step 11](#).
- **IPv4 Address** Proceed to [Step 12](#).
- **Sub-Template** Proceed to [Step 13](#).
- **Dynamic Java Class** Proceed to [Step 14](#).
- **Dynamic URL** Proceed to [Step 15](#).

- Step 9** The default Type to appear is **String**, a combination of ASCII characters considered as a group. The resulting Variable window is shown in [Figure 6-9](#) and its attributes are as follows:
- **Description** (optional) You can enter any descriptive statement about this variable here.
  - **Required** Leave the default of the selected check box if this variable is required. Otherwise, deselect it.
  - **Dimension** Choose **0** (default), which indicates a scalar or enum variable; choose **1**, in which case the variable becomes a one-dimensional array; or choose **2**, in which case the variable becomes a two-dimensional array.
  - **Pattern** (optional) Specify a regular expression pattern of the string. For example, a pattern of `isc[0-9]+` defines a string that starts with `isc` followed by one or more digits from **0** to **9**.
  - **Minimum Length** (optional) If you specify a minimum length, the string cannot be less than the length specified here.
  - **Maximum Length** (optional) If you specify a maximum length, the string cannot exceed the length specified here.
  - Radio Button: **Default** (optional) If there is a default value for the specified variable, specify it here.
  - Radio Button: **Available Values** (optional) Enter string values for this variable. Separate the values by commas.

After you enter all the data, click **OK** to accept this information for the specified variable; continue editing all variables you want to change in this same way, then click **OK** in a window such as [Figure 6-8](#), which now includes these updated variables; click **Save** and then **Close** or click **Close** and when asked, agree to **Save** for a window such as [Figure 6-6](#). Create a Data File is shown in the “[Create Data File](#)” section on page 6-14, **Edit** is shown in the “[Edit](#)” section on page 6-19, and **Delete** is shown in the “[Delete](#)” section on page 6-20.

- Step 10** When you choose the Type **Integer**, a whole number, the resulting Variable window is shown in [Figure 6-10](#) and its attributes are as follows:
- **Description** (optional) You can enter any descriptive statement about this variable here.
  - **Required** Leave the default of the selected check box if this variable is required. Otherwise, deselect it.
  - **Dimension** Choose **0** (default), which indicates a scalar or enum variable; choose **1**, in which case the variable becomes a one-dimensional array; or choose **2**, in which case the variable becomes a two-dimensional array.
  - **Minimum Value** (optional) If you specify a minimum value, the integer cannot be less than the value specified here.
  - **Maximum Value** (optional) If you specify a maximum value, the integer cannot exceed the value specified here.
  - Radio Button: **Default** (optional) If there is a default value for the specified variable, specify it here.
  - Radio Button: **Available Values** (optional) Enter string values for this variable. Separate the values by commas.

After you enter all the data, click **OK** to accept this information for the specified variable; continue editing all variables you want to change in this same way, then click **OK** in a window such as [Figure 6-8](#), which now includes these updated variables; click **Save** and then **Close** or click **Close** and when asked, agree to **Save** for a window such as [Figure 6-6](#). Create a Data File is shown in the “[Create Data File](#)” section on page 6-14, **Edit** is shown in the “[Edit](#)” section on page 6-19, and **Delete** is shown in the “[Delete](#)” section on page 6-20.

**Figure 6-10** Variable Definition — Type Integer

The screenshot shows a window titled "Variable Definition" for the variable "bestEffort-pct". The window has a title bar and a main content area with the following fields:

- Type:** A dropdown menu set to "Integer".
- Description:** An empty text box.
- Required:** A checked checkbox.
- Dimension:** A dropdown menu set to "0".
- Minimum Value:** An empty text box.
- Maximum Value:** An empty text box.
- Default Value:** A radio button that is selected.
- Available Values (comma separated):** An empty text box.

At the bottom right of the window are "OK" and "Cancel" buttons. Below the main content area is a legend indicating that an asterisk (\*) denotes "Required Fields".

**Step 11** When you choose the Type **Float**, a number that has no fixed number of digits before or after the decimal point, the resulting Variable window is shown in [Figure 6-11](#) and its attributes are as follows:

- **Description** (optional) You can enter any descriptive statement about this variable here.
- **Required** Leave the default of the selected check box if this variable is required. Otherwise, deselect it.
- **Dimension** Choose **0** (default), which indicates a scalar or enum variable; choose **1**, in which case the variable becomes a one-dimensional array; or choose **2**, in which case the variable becomes a two-dimensional array.
- **Minimum Value** (optional) If you specify a minimum value, the floating point value cannot be less than the value specified here.
- **Maximum Value** (optional) If you specify a maximum value, the floating point value cannot exceed the value specified here.
- Radio Button: **Default** (optional) If there is a default value for the specified variable, specify it here.
- Radio Button: **Available Values** (optional) Enter string values for this variable. Separate the values by commas.

After you enter all the data, click **OK** to accept this information for the specified variable; continue editing all variables you want to change in this same way, then click **OK** in a window such as [Figure 6-8](#), which now includes these updated variables; click **Save** and then **Close** or click **Close** and when asked, agree to **Save** for a window such as [Figure 6-6](#). Create a Data File is shown in the “[Create Data File](#)” section on page 6-14, **Edit** is shown in the “[Edit](#)” section on page 6-19, and **Delete** is shown in the “[Delete](#)” section on page 6-20.

**Figure 6-11** Variable Definition—Type Float

The screenshot shows a dialog box titled "Variable bestEffort-pct". It has several input fields and controls:

- Type:** A dropdown menu set to "Float".
- Description:** An empty text box.
- Required:** A checked checkbox.
- Dimension:** A dropdown menu set to "0".
- Minimum Value:** An empty text box.
- Maximum Value:** An empty text box.
- Default Value:** A radio button that is selected.
- Available Values (comma separated):** A radio button that is not selected.
- Buttons:** "OK" and "Cancel" buttons at the bottom right.
- Footer:** A message "Required Fields" with a red 'x' icon at the bottom left.

**Step 12** When you choose the Type **IPv4 Address**, the resulting Variable window is shown in [Figure 6-12](#) and its attributes are as follows:

- **Description** (optional) You can enter any descriptive statement about this variable here.
- **Required** Leave the default of the selected check box if this variable is required. Otherwise, deselect it.
- **Dimension** Choose **0** (default), which indicates a scalar or enum variable; choose **1**, in which case the variable becomes a one-dimensional array; or choose **2**, in which case the variable becomes a two-dimensional array.
- **Subnet Mask** (optional) Enter a valid subnet mask.
- **Class** (optional) Enter the class of the IP address. The options are: **Undefined**, **A**, **B**, or **C**.
- Radio Button: **Default** (optional) If there is a default value for the specified variable, specify it here.
- Radio Button: **Available Values** (optional) Enter string values for this variable. Separate the values by commas.

After you enter all the data, click **OK** to accept this information for the specified variable; continue editing all variables you want to change in this same way, then click **OK** in a window such as [Figure 6-8](#), which now includes these updated variables; click **Save** and then **Close** or click **Close** and when asked, agree to **Save** for a window such as [Figure 6-6](#). Create a Data File is shown in the “[Create Data File](#)” section on page 6-14, **Edit** is shown in the “[Edit](#)” section on page 6-19, and **Delete** is shown in the “[Delete](#)” section on page 6-20.

**Figure 6-12** Variable Definition — Type IPv4

The screenshot shows a 'Variable Definition' dialog box for a variable named 'bestEffort-pct'. The 'Type' is set to 'IPv4 Address'. The 'Required' checkbox is checked. The 'Dimension' is set to '0'. The 'Class' is set to 'Undefined'. There are 'OK' and 'Cancel' buttons at the bottom right. A status bar at the bottom left indicates 'Required Fields'.

**Step 13** When you choose the Type **Sub-Template**, you instantiate one subtemplate into the Main template. The resulting Variable window is shown in [Figure 6-13](#) and its attributes are as follows:

- **Description** (optional) You can enter any descriptive statement about this variable here.
- **Required** Leave the default of the selected check box if this variable is required. Otherwise, deselect it.
- **Location** (required) Enter the full path name of the parent template. For example `/test2/testyy`.

The variable `varName` is defined as the subtemplate type (by selecting **Variables** and clicking **Go**). The Sub-Template defined earlier is called and you must provide the subtemplate path. The syntax is as follows:

`$<varName>.callWithDatafile (<DatafileName>)`

After you enter all the data, click **OK** to accept this information for the specified variable; continue editing all variables you want to change in this same way, then click **OK** in a window such as [Figure 6-8](#), which now includes these updated variables; click **Save** and then **Close** or click **Close** and when asked, agree to **Save** for a window such as [Figure 6-6](#). Create a Data File is shown in the “[Create Data File](#)” section on page 6-14, **Edit** is shown in the “[Edit](#)” section on page 6-19, and **Delete** is shown in the “[Delete](#)” section on page 6-20.

**Figure 6-13** Variable Definition—Type Sub-Template

**Step 14** When you choose the Type **Dynamic Java Class**, the resulting Variable window is shown in [Figure 6-14](#) and its attributes are as follows:

- **Description** (optional) You can enter any descriptive statement about this variable here.
- **Required** Leave the default of the selected check box if this variable is required. Otherwise, deselect it.

The variable varName is defined as the Dynamic Java Class type (by selecting **Variables** and clicking **Go**). The syntax is as follows:

```
$<varName>.<method_name_in_Java_class> ([<parameters>])
```

After you enter all the data, click **OK** to accept this information for the specified variable; continue editing all variables you want to change in this same way, then click **OK** in a window such as [Figure 6-8](#), which now includes these updated variables; click **Save** and then **Close** or click **Close** and when asked, agree to **Save** for a window such as [Figure 6-6](#). Create a Data File is shown in the “[Create Data File](#)” section on page 6-14, **Edit** is shown in the “[Edit](#)” section on page 6-19, and **Delete** is shown in the “[Delete](#)” section on page 6-20.

**Figure 6-14** Variable Definition—Type Dynamic Java Class

**Step 15** When you choose the Type **Dynamic URL**, the resulting Variable window is shown in [Figure 6-15](#) and its attributes are as follows:

- **Description** (optional) You can enter any descriptive statement about this variable here.
- **Required** Leave the default of the selected check box if this variable is required. Otherwise, deselect it.

The variable `varName` is defined as the Dynamic URL type (by selecting **Variables** and clicking **Go**). The syntax is as follows:

```
$<varName>.callURL (<url-address>)
```

After you enter all the data, click **OK** to accept this information for the specified variable; continue editing all variables you want to change in this same way, then click **OK** in a window such as [Figure 6-8](#), which now includes these updated variables; click **Save** and then **Close** or click **Close** and when asked, agree to **Save** for a window such as [Figure 6-6](#). Create a Data File is shown in the “[Create Data File](#)” section on page 6-14, **Edit** is shown in the “[Edit](#)” section on page 6-19, and **Delete** is shown in the “[Delete](#)” section on page 6-20.

**Figure 6-15** Variable Definition—Type Dynamic URL

The screenshot shows a dialog box titled "Variable a". It has a "Type:" dropdown menu set to "Dynamic URL". Below it is a "Description:" text field. Underneath is a "Required:" checkbox which is checked. At the bottom right are "OK" and "Close" buttons. A small vertical text "93455" is visible on the right side of the dialog box. Below the dialog box, there is a small text "\* Required Fields".

## Copying Templates

To copy a template and paste it into another folder, follow these steps:

- Step 1** Select a template and then right-click and you receive the opportunity to copy. Click **Copy**.
- Step 2** Right-click on the folder into which you want to paste the copied template and all its data files and click **Paste**.
- Step 3** You will see the new template and all its data files in the selected location. You can edit and rename from there.



### Note

This function works with Internet Explorer but not with Netscape.

## Create Data File

You can create a new data file from an existing template. If the template you want is not available, go to the “[Create Template](#)” section on page 6-5.


To create a data file, follow these steps:

- Step 1** Navigate to **Service Design > Templates**.



- Step 2** In the **Templates** tree in the left part of your window, do one of the following
1. Left-click on the folder or subfolder in which the template for which you want to create a data file exists or
  2. Click on the + next to the folder of choice and then click on the template for which you want to create a data file.
- Step 3** If you chose 1. in [Step 2](#), a window appears as shown in [Figure 6-16](#), “Choose Existing Template > Create Data File.”

**Figure 6-16** Choose Existing Template > Create Data File




Select the check box for the template for which you want to create a data file and click **Create Data File**. Then proceed to [Step 5](#).

Otherwise, proceed to [Step 4](#).

- Step 4** If you chose 2. in [Step 2](#), the buttons appear as shown in [Figure 6-17](#), “Choose Existing Template > Create Data File.”

**Figure 6-17** Choose Existing Template > Create Data File



Click **Create Data File** and proceed to [Step 5](#).

- Step 5** An example of a window that appears is shown in [Figure 6-18](#), “Template Data File Editor.”

**Figure 6-18** Template Data File Editor

**Step 6** In the **General** area, fill in the following:

- **Data File Name** (required) This must be a unique name. This name must begin with an alphabetic character and can only contain alphanumeric characters and the underscore.
- **Description** (optional) Enter any description that helps you identify this data file.

**Step 7** In the example in [Figure 6-18](#), in the **Variables** area, **ctrlName** is a string variable (**Dimension** defined when the template was created was **0**); you can also create a one-dimensional array (**Dimension** defined when the template was created was **1**); and **t1-list** is a two-dimensional array (**Dimension** defined when the template was created was **2**).

If **t1-list** is a Dynamic Java Class variable, you *must* enter the entire Java Class package name. For example: com.cisco.isc.class\_name.

**Step 8** If you click **Vars** as shown in [Figure 6-18](#), you receive a window as shown in [Figure 6-19](#), “[Template Data File Editor](#).”

**Figure 6-19** Template Data File Editor

Click the **Services** drop-down list to have access to variables for:

- MPLS
- L2VPN
- QoS
- VPLS

Then click the entry in **Variables** that you want to use and click **Select**.

If you have a **0** dimensional entry (set as **Dimension 0** when creating a template), you can only enter variables in the provided field.


**Step 9** When you click **Edit**., as shown in [Figure 6-18](#), the resulting window depends on whether you are editing a **1** or **2** dimensional array.

Proceed to [Step 10](#) for information about a **1** dimensional array.

Proceed to [Step 13](#) for information about a **2** dimensional array.


**Step 10** For a one-dimensional array (set as **Dimension 1** when creating the template), when you click **Edit**, you receive a window as shown in [Figure 6-20](#), “Editing a One-Dimensional Array.”

**Figure 6-20** Editing a One-Dimensional Array



**Step 11** To add a variable, click **Add** and a window, as shown in [Figure 6-21](#), “Adding a Variable,” appears in which you can add the variable. Then click **OK**.


**Figure 6-21** Adding a Variable



**Step 12** To edit or delete a variable, highlight the variable in [Figure 6-20](#) and click **Edit** or **Delete**. For **Edit** you receive a figure as in [Figure 6-21](#). Then click **OK**. For **Delete**, *be sure* you want to delete. After you click **Delete**, it automatically occurs and the window is updated. Proceed to [Step 19](#).


- Step 13** For a two-dimensional array (set as **Dimension 2** when creating the template), when you click **Edit**, you receive a window as shown in [Figure 6-22](#), “[Editing a Two-Dimensional Array](#).”

**Figure 6-22** *Editing a Two-Dimensional Array*




- Step 14** Click **Add Row** in [Figure 6-22](#) and a window, as shown in [Figure 6-23](#), “[Enter Row Information](#),” appears. Enter a value and click **OK**.

**Figure 6-23** *Enter Row Information*



- Step 15** Click **Add Column** in [Figure 6-22](#) and a window as shown in [Figure 6-24](#), “[Enter Column Information](#),” appears. Enter a value and click **OK**.

**Figure 6-24** *Enter Column Information*



- Step 16** A resulting window, as shown in [Figure 6-25](#), “[Two-Dimensional Array Results](#),” appears.



**Figure 6-25** Two-Dimensional Array Results

- Step 17** You can select any of the check boxes (toggles) and you can then **Edit** or **Delete** that row or column. You can also continue to **Add Row** and **Add Column** as shown in [Step 15](#) and [Step 16](#), respectively.
- Step 18** When you complete setting up your two-dimensional array, click **OK** in [Figure 6-25](#).
- Step 19** A window as shown in [Figure 6-18](#) is updated to reflect the new data file information.
- Step 20** You can then click **Save** and then **Close** to save this information and close this file; click **Configure** to show the configuration file; or click **Close** and then be sure to click **OK**, if you want to save the information you have created. If you do not want to save this information, click **Close** and then click **Cancel**.

## Edit

To edit a Template or Data File, follow these steps:

- Step 1** Navigate to **Service Design > Templates**.
- Step 2** In the **Templates** tree, left-click on the folder or subfolder in which the template you want to edit exists or the template in which the data file you want to edit exists. Alternatively, when the name in the upper left corner of the data pane is a template, you can click on the template name to edit the template.
- Step 3** To edit a template, a window appears as shown in [Figure 6-26](#), “[Choose Existing Template > Edit](#).” To edit a data file, a window appears as shown in [Figure 6-27](#), “[Choose Existing Data File > Edit](#).”

**Figure 6-26** Choose Existing Template > Edit**Figure 6-27** Choose Existing Data File > Edit

**Step 4** Select the check box for the template or data file you want to edit.

**Note**

For a data file, there is a **Configlet** column in which you can click **View** to view the configuration file.



**Step 5** Click **Edit**.

**Step 6** When editing a template, you receive a window as shown in [Figure 6-6](#), “[Template Editor](#).” Then proceed as in the “[Create Template](#)” section on page 6-5. When editing a data file, you receive a window as shown in [Figure 6-17](#), “[Choose Existing Template > Create Data File](#).” Then proceed as in [Step 5](#) in the “[Create Data File](#)” section on page 6-14.

## Delete

To delete a Template or Data File, follow these steps:

- Step 1** Navigate to **Service Design > Templates**.
- Step 2** In the **Templates** tree, left-click on the folder or subfolder in which the template you want to delete exists or the template in which the data file you want to delete exists.
- Step 3** To delete a template, a window appears as shown in [Figure 6-28](#), “[Choose Existing Template > Delete](#).” To delete a data file, a window appears as shown in [Figure 6-29](#), “[Choose Existing Data File > Delete](#).”

**Figure 6-28** Choose Existing Template > Delete**Figure 6-29** Choose Existing Data File > Delete

**Step 4** Select the check box for the template or data file you want to delete.



**Note** For a data file, there is a **Configlet** column in which you can click **View** to view the configuration file.

**Step 5** Click **Delete**.

**Step 6** You receive an updated window as shown in [Figure 6-28](#), “Choose Existing Template > Delete” or [Figure 6-29](#), “Choose Existing Data File > Delete” with the deleted template or data file no longer available.

## Template Examples

In the left column, the hierarchy pane, of **Service Design > Templates**, as shown in [Figure 6-2](#), “**Templates**,” template examples appear. See [Table 6-1](#), “**Template Examples and Their Descriptions**.”

**Table 6-1**      *Template Examples and Their Descriptions*

Folder	Template	Description
DIA-Channelization	10K-CHOC12-STS1-PATH	Sample template to break down channelized OC12 to STS-1 paths.
	10K-CT3-CHANNELIZED	Sample template creates T1 out of channelized T3 line card.
	10K-CT3-UNCHANNELIZED	Sample template Creates either a fullrate T3 or a subrate T3 interface out of a channelized T3.
	PA-MC-E3-CHANNELIZED	Sample template Creates E1 (channel groups) out of E3.
	PA-MC-STM1-AU3-CHANNELIZE	Sample template Creates E1 (channel groups) out of TUG-2. This template uses AU-3 AUG mapping that further creates TUG-2s.
	PA-MC-STM1-AU4-CHANNELIZE	Sample template Creates E1 (channel groups) out of TUG-2. This template uses AU-4 AUG mapping that creates TUG-3s and TUG-2s.
	PA-MC-T3-CHANNELIZED	Sample template Creates T1 (channel groups) out of T3.
Examples	AccessList	Demonstrates templates with nested repeat loop and multi-dimension variable.
	AccessList1	Demonstrates the simplest template variable substitution.
	CEWanCOS	Demonstrates if-else statements, repeat statements, mathematical expressions, and one-dimensional variables.
QoS/L2/ATM	CLP_Egress	Sample template to demonstrate the setting of qos_group and ATM Cell Loss Priority at the output of an interface.
	CLP_Ingress	Sample template sets MPLS experimental bit of the ATM Cell, marked with Cell Loss Priority, at the input of an interface.
QoS/L2/FrameRelay	classification	Sample template to demonstrate the bandwidth reservation based on FrameRelay DLCI value.



## Summary of Repository Variables

This section contains the following tables:

- [Table 6-2 on page 6-23, “L2VPN Repository Variables”](#)
- [Table 6-3 on page 6-26, “MPLS Repository Variables”](#)
- [Table 6-4 on page 6-33, “QoS Repository Variables”](#)
- [Table 6-5 on page 6-35, “VPLS Repository Variables”](#)

[Table 6-2](#) provides a summary of the L2VPN Repository variables available from ISC Templates.

**Table 6-2 L2VPN Repository Variables**

Repository Variable	Dimension	Description
AC_Loopback_Address	0	PE loopback address also known as the router ID
CE_DLCI	0	DLCI value on CE for Frame Relay encapsulation
CE_Encap	0	Encapsulation of the CE interface
CE_Intf_Desc	0	Interface description for the CE interface
CE_Intf_Main_Name	0	Major interface name for the CE interface
CE_Intf_Shutdown	0	Shutdown flag for the CE interface
CE_VCD	0	VCD value on CE for ATM encapsulation
CE_VCI	0	VCI value on CE for ATM encapsulation
CE_Vlan_ID	0	VLAN ID on CE for Ethernet encapsulation
CE_VPI	0	VPI value on CE for ATM encapsulation
L2VPNCLECeFacingEncapsulation	0	Encapsulation of the UNI
L2VPNCLECeFacingInterfaceName	0	Name of the UNI
L2VPNCLEPeFacingEncapsulation	0	Encapsulation of the NNI (should always be dot1q)
L2VPNCLEPeFacingInterfaceName	1	Name of the NNI (uplinks) (the number can be more than 1 in case of a ring topology, hence any array)
L2VPNDFBIT_SET	0	Indicates not to fragment the bit set (for L2TPv3 only)
L2VPNDynamicModeUseDefaults	0	Dynamic session setup using ISC default values (for L2TPv3 only)
L2VPN_intf_main_name	1	The main interface name for a CE or PE port
L2VPNIP_PMTU	0	Enable the discovery of the path MTU for tunneled traffic (for L2TPv3 only)
L2VPNIP_TOS	0	Configure the value of the TOS byte in IP headers of tunneled packets or reflects the TOS byte value from the inner IP header (for L2TPv3 only)

**Table 6-2** L2VPN Repository Variables (continued)

Repository Variable	Dimension	Description
L2VPNIP_TTL	0	Configure the value of the time to live byte in the IP headers (for L2TPv3 only)
L2VPNL2TP_CLASS_NAME	0	The L2TP class name to overwrite the default L2TP class name (for L2TPv3 only)
L2VPNL2TPv3Sequence	0	Specifies the direction in which sequencing of data packets in a pseudo wire is enabled (for L2TPv3 only)
L2VPNLocalCookieHighValue	0	Specifies the last 4 bytes of the value that the peer PE must include in the cookie field of incoming L2TP packets (for L2TPv3 only)
L2VPNLocalCookieLowValue	0	Specifies the first 4 bytes of the value that the peer PE must include in the cookie field of incoming L2TP packets (for L2TPv3 only)
L2VPNLocalCookieSize	0	Specifies the size (0, 4, or 8) of the cookie field of incoming L2TP packets (for L2TPv3 only)
L2VPNLocalLoopBack	1	The head of the L2TPv3 tunnel
L2VPNLocalSessionId	0	Specifies the ID for the local L2TPv3 session (for L2TPv3 only)
L2VPNLocalSwitchLoopBack1	1	The loopback1 for the local switch (for L2TPv3 only)
L2VPNLocalSwitchLoopBack2	1	The loopback2 for the local switch (for L2TPv3 only)
L2VPNRemoteCookieHighValue	1	Specifies the last 4 bytes of the value that this PE must include in the cookie field of incoming L2RP packets (for L2TPv3 only)
L2VPNRemoteCookieLowValue	1	Specifies the first 4 bytes of the value that this PE must include in the cookie field of incoming L2RP packets (for L2TPv3 only)
L2VPNRemoteCookieSize	1	Specifies the size (0, 4, or 8) of the cookie field of outgoing L2TP packets (for L2TPv3 only)
L2VPNRemoteLoopback	0	The tail of the L2TPv3 tunnel
L2VPNRemoteSessionID	1	Specifies the ID for the remote L2TPv3 session (for L2TPv3 only)
L2VPNSessionSetupMode	0	Defines how the L2TPv3 session is set up (static or dynamic) (for L2TPv3 only)
L2VPNTransportMode	0	Defines how the L2TPv3 data is transferred (for Frame Relay: DLCI or Port; for ATM: VP or VC) (for L2TPv3 only)
L2VPNUniMajorInterfaceName	0	The main interface name of the UNI
L2VPNVCId	0	The virtual circuit ID of the L2TPv3 or AToM tunnel

**Table 6-2 L2VPN Repository Variables (continued)**

Repository Variable	Dimension	Description
PE_DLCI	0	DLCI value on PE for Frame Relay encapsulation
PE_Encap	0	Encapsulation of the PE interface
PE_Intf_Desc	0	Interface description for the PE interface
PE_Intf_Main_Name	0	Major interface name for the PE interface
PE_VCD	0	VCD value on PE for ATM encapsulation
PE_VCI	0	VCI value on PE for ATM encapsulation
PE_Vlan_ID	0	VLAN ID on PE for Ethernet encapsulation
PE_VPI	0	VPI value on PE for ATM encapsulation
PseudoWire_Class_Type_Of_Core	0	Core type of the Service Provider over which L2VPN is provisioned
Uni_Aging	0	Length of time the MAC address can stay on the port security table
Uni_Cdp_Enable	0	Flag to enable or disable layer 2 tunnelling on a Cisco Discover Protocol (CDP)
Uni_Cdp_Threshold	0	Number of packets per second to be received before the interface is shut down for the CDP protocol
Uni_Mac_Address	0	Number of MAC addresses allowed for port security
Uni_Port_Security	0	Flag to enable or disable security on a UNI interface
Uni_Protocol_Tunnelling	0	Flag to enable or disable Layer 2 Bridge Protocol Data Unit (BPDU) protocol tunnelling on a UNI interface
Uni_Recovery_Interval	0	Amount of time to wait before recovering a UNI port
Uni_Shutdown	0	Flag indicating whether the User Network Interface (UNI) is shutdown
Uni_Speed	0	Value of the UNI link speed
Uni_Stp_Enable	0	Flag to enable or disable layer 2 tunnelling on a Spanning Tree Protocol (STP)
Uni_Stp_Threshold	0	Flag to enable or disable layer 2 tunnelling on an STP
Uni_Violation_Access	0	Action taken when a port security violation is detected
Uni_Vtp_Enable	0	Flag to enable or disable layer 2 tunnelling on a VLAN Trunk Protocol (VTP)
Uni_Vtp_Threshold	0	Flag to enable or disable layer 2 tunnelling on a VTP

Table 6-3 provides a summary of the MPLS Repository variables available from ISC Templates.

**Table 6-3 MPLS Repository Variables**

Repository Variable	Dimension	Description
Advertised_Routes_To_CE	2	List of one or more IP addresses of the advertised static route to be placed on the PE to define the CE's address space
CE_BGP_AS_ID	0	BGP AS ID on a CE when the routing protocol between a CE and a PE is BGP
CE_DLCI	0	DLCI value on CE for Frame Relay encapsulation
CE_EIGRP_AS_ID	0	EIGRP AS ID on a CE when the routing protocol between a CE and a PE is EIGRP
CE_Facing_MVRFCE_BGP_AS_ID	0	BGP AS ID on an MVRFCE when the routing protocol between a CE and an MVRFCE is BGP, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_DLCI	0	DLCI value on CE facing MVRFCE interface for Frame Relay encapsulation, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_EIGRP_AS_ID	0	EIGRP AS ID on an MVRFCE when the routing protocol between a CE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_Intf	0	Name of the CE facing interface on an MVRFCE, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_Intf_Address	0	IP address assigned to the CE facing MVRFCE interface, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_Intf_Encap	0	Encapsulation for CE facing of an MVRFCE interface, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_Intf_Name	0	Name of the CE facing MVRFCE interface, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_Intf_Type	0	Interface type for CE facing of an MVRFCE interface, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_Ospf_Process_ID	0	OSPF process ID on MVRFCE when the routing protocol between a CE and an MVRFCE is OSPF, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_Tunnel_Src_Addr	0	Tunnel source address on CE facing MVRFCE interface for GRE encapsulation when an MPLS link includes an MVRFCE

**Table 6-3 MPLS Repository Variables (continued)**

Repository Variable	Dimension	Description
CE_Facing_MVRFCE_VCD	0	VCD value on CE facing MVRFCE interface for ATM encapsulation, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_VCI	0	VCI value on CE facing MVRFCE interface for ATM encapsulation, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_VLAN_ID	0	VLAN ID on CE facing MVRFCE interface for Ethernet encapsulation, when an MPLS link includes an MVRFCE
CE_Facing_MVRFCE_VPI	0	VPI value on CE facing MVRFCE interface for ATM encapsulation, when an MPLS link includes an MVRFCE
CE_Intf_Address	0	IP address assigned to the CE interface
CE_Intf_Encap	0	Encapsulation of the CE interface
CE_Intf_Name	0	Name of the CE interface
CE_MVRFCE_Bandwidth_Metric_For_Redistribution	0	Bandwidth metric for redistribution of EIGRP when the routing protocol between a CE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFC
CE_MVRFCE_BGP_AS_ID	0	BGP AS ID on a CE when the routing protocol between a CE and an MVRFCE is BGP, when an MPLS link includes an MVRFCE
CE_MVRFCE_Delay_Metric_For_Redistribution	0	Delay metric for redistribution of EIGRP when the routing protocol between a CE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFC
CE_MVRFCE_EIGRP_AS_ID	0	EIGRP AS ID on a CE when the routing protocol between a CE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
CE_MVRFCE>Loading_Metric_For_Redistribution	0	Loading metric for redistribution of EIGRP when the routing protocol between a CE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFC
CE_MVRFCE_MTU_Metric_For_Redistribution	0	MTU metric for redistribution of EIGRP when the routing protocol between a CE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFC
CE_MVRFCE_Ospf_Process_ID	0	OSPF process ID on CE when the routing protocol between a CE and an MVRCE is OSPF, when an MPLS link includes an MVRFCE

**Table 6-3 MPLS Repository Variables (continued)**

Repository Variable	Dimension	Description
CE_Ospf_Process_ID	0	OSPF process ID on CE when the routing protocol between a CE and a PE is OSPF
CE_Tunnel_Src_Addr	0	Tunnel source address on CE for GRE encapsulation
CE_VCD	0	VCD value on CE for ATM encapsulation
CE_VCI	0	VCI value on CE for ATM encapsulation
CE_Vlan_ID	0	VLAN ID on CE for Ethernet encapsulation
CE_VPI	0	VPI value on CE for ATM encapsulation
Export_Map	0	Name of the export map associated with the VRF
Extra_CE_Loopback_Required	0	Flag to indicate whether an extra loopback request is required on the CE
Import_Map	0	Name of the import map associated with the VRF
Is_Default_Info_Originate	0	Flag to indicate whether the <b>default-information originate</b> command for BGP on the PE when STATIC is a running protocol between a CE and a PE
Is_Default_Routes_Sent_To_CE	0	Flag to indicate whether the default routes are sent to a remote CE
Join_Grey_Mgmt_Vpn	0	Flag to indicate whether MPLS will join a Grey Management VPN
Max_route_threshold	0	Percentage of the maximum number of routes that can be imported into the VRF
Max_Routes	0	Maximum number of routes than can be imported into the VRF
MPLSExportRouteTargets	1	List of Route Targets that are exported for a particular VRF associated with the MPLS VPN link
MPLSImportRouteTargets	1	List of Route Targets that are imported for a particular VRF associated with the MPLS VPN link
MPLSCLEPeFacingInterfaceName	0	The name of the interface on the device facing the PE for that particular MPLS VPN link
MPLSCLEPeFacingEncapsulation	0	The encapsulation of the interface on the device facing the PE for that particular MPLS VPN link
MPLSCLECeFacingInterfaceName	0	The name of the interface on the device facing the CE for that particular MPLS VPN link
MPLSCLECeFacingEncapsulation	0	The encapsulation of the interface on the device facing the CE for that particular MPLS VPN link

**Table 6-3 MPLS Repository Variables (continued)**

Repository Variable	Dimension	Description
MPLSCeInterfaceMask	0	The mask of the IP address assigned to the CE interface for a particular MPLS VPN link
MPLSPeInterfaceMask	0	The mask of the IP address assigned to the PE interface for a particular MPLS VPN link
MPLSCeLoopbackAddress	0	The IP address of the extra CE loopback address for a particular MPLS VPN link
MVRFCE_CE_Advertised_Routes_To_CE	2	List of one or more IP addresses of the advertised static route to be placed on the PE to define the CE's address space, when the MPLS link includes an MVRFCE
MVRFCE_CE_IP_Unnumbered	0	Flag to indicate whether the MVRCE to CE link is unnumbered, when an MPLS link includes an MVRFCE
MVRFCE_CE_Is_Default_routes_Sent_To_CE	0	Flag to indicate whether the default routes are sent to a remote CE, when an MPLS link includes an MVRFCE
MVRFCE_CE_NBR_ALLOW_AS_IN	0	AllowASIn flag when the routing protocol between a CE and an MVRFCE is BGP, when an MPLS link includes an MVRFCE
MVRFCE_CE_NBR_AS_OVERRIDE	0	ASOverride flag when the routing protocol between a CE and an MVRFCE is BGP, when an MPLS link includes an MVRFCE
MVRFCE_CE_Ospf_Area_Number	0	OSPF area number when the routing protocol between a CE and an MVRCE is OSPF, when an MPLS link includes an MVRFCE
MVRFCE_CE_Routes_To_Reach_Other_Sites	2	List of one or more IP addresses to specify the static routes to put on the CE, when the MPLS link includes an MVRFCE
MVRFCE_CE_Routing_Protocol	0	Routing protocol between MVRFCE and CE
PE_BGP_AS_ID	0	BGP AS ID on a PE when the routing protocol between a CE and a PE is BGP
PE_Cable_Both_Helper_Address_List	1	List of DHCP server IP addresses to which both cable modem and host UDP broadcasts are forwarded
PE_Cable_Modem_Helper_Address_list	1	List of DHCP server IP addresses to which cable modem UDP broadcasts are forwarded
PE_Cable_Modem_Host_Helper_Address_List	1	List of DHCP server IP addresses to which host UDP broadcasts are forwarded
PE_Cable_Modem_Secondary_Address_List	1	List of cable modem secondary addresses for cable interfaces
PE_CE_Bandwidth_Metric_For_Redistribution	0	Bandwidth metric for redistribution of EIGRP when the routing protocol between a CE and a PE is EIGRP

**Table 6-3** *MPLS Repository Variables (continued)*

Repository Variable	Dimension	Description
PE_CE_Delay_Metric_For_Redistribution	0	Delay metric for redistribution of EIGRP when the routing protocol between a CE and a PE is EIGRP
PE_CE_IP_Unnumbered	0	Flag to indicate whether the PE to CE link is unnumbered
PE_CE>Loading_Metric_For_Redistribution	0	Loading metric for redistribution of EIGRP when the routing protocol between a CE and a PE is EIGRP
PE_CE_MTU_Metric_For_Redistribution	0	MTU metric for redistribution of EIGRP when the routing protocol between a CE and a PE is EIGRP
PE_CE_NBR_Allow_AS_In	0	AllowASIn flag when the routing protocol between a CE and a PE is BGP
PE_CE_NBR_AS_Override	0	ASOverride flag when the routing protocol between a CE and a PE is BGP
PE_CE_Ospf_Area_Number	0	OSPF area number when the routing protocol between a CE and a PE is OSPF
PE_CE_Reliability_Metric_For_Redistribution	0	Reliability metric for redistribution of EIGRP when the routing protocol between a CE and a PE is EIGRP
PE_CE_Routing_Protocol	0	Routing protocol between PE and CE
PE_DLCI	0	DLCI value on PE for Frame Relay encapsulation
PE_EIGRP_AS_ID	0	EIGRP AS ID on a PE when the routing protocol between a CE and a PE is EIGRP
PE_Facing_MVRFCE_BGP_AS_ID	0	BGP AS ID on an MVRFCE when the routing protocol between a PE and an MVRFCE is BGP, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_DLCI	0	DLCI value on PE facing MVRFCE interface for Frame Relay encapsulation, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_EIGRP_AS_ID	0	EIGRP AS ID on an MVRFCE when the routing protocol between a PE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_Intf	0	Name of the PE facing interface on an MVRFCE, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_Intf_Address	0	IP address assigned to the PE facing MVRFCE interface, when an MPLS link includes an MVRFCE



**Table 6-3 MPLS Repository Variables (continued)**

Repository Variable	Dimension	Description
PE_Facing_MVRFCE_Intf_Encap	0	Encapsulation for PE facing of an MVRFCE interface, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_Intf_Name	0	Name of the PE facing MVRFCE interface, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_Intf_Type	0	Interface type for PE facing of an MVRFCE interface, when an MPLS link includes an MVRFCE
PE_FACING_MVRFCE_OSPF_Process_ID	0	OSPF process ID on an MVRFCE when the routing protocol between a PE and an MVRCE is OSPF, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_Tunnel_Src_Addr	0	Tunnel source address on PE facing MVRFCE interface for GRE encapsulation when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_VCD	0	VCD value on PE facing MVRFCE interface for ATM encapsulation, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_VCI	0	VCI value on PE facing MVRFCE interface for ATM encapsulation, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_VLAN_ID	0	VLAN ID on PE facing MVRFCE interface for Ethernet encapsulation, when an MPLS link includes an MVRFCE
PE_Facing_MVRFCE_VPI	0	VPI value on PE facing MVRFCE interface for ATM encapsulation, when an MPLS link includes an MVRFCE
PE_Intf_Address	0	IP address assigned to the PE interface
PE_Intf_Desc	0	Interface description for the PE interface
PE_Intf_Encap	0	Encapsulation of the PE interface
PE_Intf_Name	0	Name of the PE interface
PE_Intf_Shutdown	0	Shutdown flag for the PE interface
PE_IS_Cable_Modem_Maintenance_Interface	0	Flag to indicate whether the interface is a maintenance interface
PE_MVRFCE_Bandwidth_Metric_For_Redistribution	0	Bandwidth metric for redistribution of EIGRP when the routing protocol between a PE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
PE_MVRFCE_BGP_AS_ID	0	BGP AS ID on a PE when the routing protocol between a PE and an MVRFCE is BGP, when an MPLS link includes an MVRFCE

**Table 6-3 MPLS Repository Variables (continued)**

Repository Variable	Dimension	Description
PE_MVRFCE_Delay_Metric_For_Redistribution	0	Delay metric for redistribution of EIGRP when the routing protocol between a PE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
PE_MVRFCE_EIGRP_AS_ID	0	EIGRP AS ID on a PE when the routing protocol between a PE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
PE_MVRFCE_IP_Unnumbered	1	Flag to indicate whether the PE to MVRFCE link is unnumbered, when an MPLS link includes an MVRFCE
PE_MVRFCE>Loading_Metric_For_Redistribution	0	Loading metric for redistribution of EIGRP when the routing protocol between a PE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
PE_MVRFCE_MTU_Metric_for_redistribution	0	MTU metric for redistribution of EIGRP when the routing protocol between a PE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
PE_MVRFCE_NBR_ALLOW_AS_IN	0	AllowASIn flag when the routing protocol between a PE and an MVRFCE is BGP, when an MPLS link includes an MVRFCE
PE_MVRFCE_NBR_AS_OVERRIDE	0	ASOverride flag when the routing protocol between a PE and an MVRFCE is BGP, when an MPLS link includes an MVRFCE
PE_MVRFCE_Ospf_Area_Number	0	OSPF area number when the routing protocol between a PE and an MVRCE is OSPF, when an MPLS link includes an MVRFCE
PE_MVRFCE_OSPF_Process_ID	0	OSPF process ID on PE when the routing protocol between a PE and an MVRCE is OSPF, when an MPLS link includes an MVRFCE
PE_MVRFCE_Reliability_Metric_For_Redistribution	0	Reliability metric for redistribution of EIGRP when the routing protocol between a PE and an MVRFCE is EIGRP, when an MPLS link includes an MVRFCE
PE_MVRFCE_Routing_Protocol	0	Routing protocol between PE and MVRFCE, when an MPLS link includes an MVRFCE
PE_OSPF_PROCESS_ID	0	OSPF process ID on PE when the routing protocol between a CE and a PE is OSPF
PE_Tunnel_Src_Addr	0	Tunnel source address on PE for GRE encapsulation
PE_VCD	0	VCD value on PE for ATM encapsulation
PE_VCI	0	VCI value on PE for ATM encapsulation

**Table 6-3 MPLS Repository Variables (continued)**

Repository Variable	Dimension	Description
PE_Vlan_ID	0	VLAN ID on PE for Ethernet encapsulation
PE_VPI	0	VPI value on PE for ATM encapsulation
rd	0	Route Distinguisher value for the VRF
Redistribute_Connected	0	Flag to indicate whether the connected routes are redistributed into BGP on the PE
Redistribute_Static	0	Flag to indicate whether the static routes are redistributed into BGP on the PE
Redistributed_Protocol	1	List of routing protocols to be redistributed
Rip_Metrics	0	Metric for redistribution associated with RIP
Routes_To_Reach_Other_Sites	2	List of one or more IP addresses to specify the static routes to put on the CE.
vrfName	0	Name of the VRF

Table 6-4 provides a summary of the QoS Repository variables available from ISC Templates.

**Table 6-4 QoS Repository Variables**

Repository Variable	Dimension	Description	Example
QoS_Customer	0	Name of the customer	ABC
QoS_Policy	0	Name of the QoS policy	Gold
QoS_Supported_MPLS	0	Boolean flag to indicate whether MPLS is supported in the core. The value is either <b>true</b> or <b>false</b> .	true false
QoS_PE_Remarking_ReRateLimiting	0	Boolean flag to indicate whether re-marking and re-rate-limiting is required on PE. The value is either <b>true</b> or <b>false</b> .	true false
QoS_CE_Marking_RateLimiting_Interfaces	1	List of marking and rate-limiting interfaces on CE	serial0 serial1 ethernet1
QoS_CE_Marking_RateLimiting_Interface_Encap	1	List of interface encapsulation types of the marking and rate-limiting interfaces on CE (same order as QoS_CE_Marking_RateLimiting_Interfaces)	HDLC HDLC ethernet

**Table 6-4 QoS Repository Variables (continued)**

Repository Variable	Dimension	Description	Example
QoS_PECLE_Marking_RateLimiting_Interface	0	Name of the marking and rate-limiting interface on PECLE (for Ethernet QoS)	ethernet1
QoS_PECLE_Marking_RateLimiting_Interface_Encap	0	Interface encapsulation type of the marking and rate-limiting interface on PECLE (for Ethernet QoS)	ethernet
QoS_Link_Bandwidth	0	Bandwidth of the CE and PE link (bps)	128000
QoS_LinkEndpoint_Role	0	Role of the link endpoint (that is, CPE or PE)	CPE_Endpt PE_Endpt
QoS_LinkEndpoint_Hostname	0	Hostname of the link endpoint	enpe1
QoS_LinkEndpoint_Platform	0	Platform type of the link endpoint	7206
QoS_LinkEndpoint_Linecard_Model	0	Line-card model of the link endpoint	8OC03_ATM_TS-IR-B
QoS_LinkEndpoint_Interface	0	Interface name of the link endpoint	FastEthernet8/10.700
QoS_LinkEndpoint_Interface_Encap	0	Interface encapsulation type of the link endpoint interface	DOT1Q
QoS_LinkEndpoint_Type	0	Enumerator to indicate the type of the link endpoint (“Interface”, “ATM”, or “FRAME_RELAY”)	FRAME_RELAY
QoS_LinkEndpoint_FR_Dlci	0	Frame-Relay DLCI number of the link endpoint	102
QoS_LinkEndpoint_ATM_VPI	0	VPI value of the ATM VC of the link endpoint	110
QoS_LinkEndpoint_ATM_VCI	0	VCI value of the ATM VC of the link endpoint	256
QoS_LinkEndpoint_ATM_VCD	0	VCD value of the ATM VC of the link endpoint	Atm1
QoS_LinkEndpoint_ATM_PA_Model	0	The ATM port adaptor model of the link endpoint	PA-A1-OC3MM

**Table 6-4 QoS Repository Variables (continued)**

Repository Variable	Dimension	Description	Example
QoS_Link_UPE_UNI_VLAN_ID		The service's VLAN ID on the UNI port of the device that is acting as a U_PE (Ethernet QoS only)	800
QoS_Link_UPE_NNI_VLAN_ID		The service's VLAN ID on the NNI port of the device that is acting as a U_PE (Ethernet QoS only)	800
QoS_Link_NPE_NNI_VLAN_ID	0	The service's VLAN ID on the NNI port of the device that is acting as an N_PE (Ethernet QoS only)	800

Table 6-5 provides a summary of the VPLS Repository variables available from ISC Templates.

**Table 6-5 VPLS Repository Variables**

Repository Variables	Dimension	Description
VPLSCeEncapsulation	0	The encapsulation of the CE interface for a particular VPLS link
VPLSCeInterfaceName	0	The name of the CE interface for a particular VPLS link
VPLSCeMajorInterfaceName	0	The name of a major interface on a CE for a particular VPLS link
VPLSCLECeFacingEncapsulation	0	The encapsulation of interfaces for a particular device facing the CE
VPLSCLECeFacingInterfaceName	0	The interface name for a particular device facing the CE (the number can be more than 1 in case of a ring topology, hence any array)
VPLSCLEPeFacingEncapsulation	0	The encapsulation of interfaces for a particular device facing the PE
VPLSCLEPeFacingInterfaceName	1	The list of interface names for a particular device facing the PE (the number can be more than 1 in case of a ring topology, hence any array)
VPLSDisableCDP	0	The flag to specify if the CDP has been disabled on a UNI for a particular VPLS link
VPLSFilterBPDU	0	The flag to specify whether the BPDUs will be filtered on a UNI for a particular VPLS link
VPLSPeEncapsulation	0	The encapsulation of the PE interface for a particular VPLS link

**Table 6-5 VPLS Repository Variables (continued)**

Repository Variables	Dimension	Description
VPLSPeInterfaceDescription	0	The description assigned to the PE interface for a particular VPLS link
VPLSPeInterfaceName	0	The name of the PE interface for a particular VPLS link
VPLSPeMajorInterfaceName	0	The name of a major interface on a PE for a particular VPLS link
VPLSPeNeighbors	1	The list of PE POPs participating in a particular VPLS VPN
VPLSPeVfiName	0	The VFI name assigned to a particular VPLS instance existing on the PE POP
VPLSPeVlanId	0	The VLAN ID assigned to the PE for a particular VPLS link
VPLSPeVpnId	0	The VPN ID assigned to a particular VPLS VPN
VPLSSystemMTU	0	The maximum MTU value for a packet arriving on a UNI for a particular VPLS link
VPLSTunnelCDPEnable	0	The flag to specify if the CDP packets will be tunneled to the remote site for a particular VPLS link
VPLSTunnelCDPThreshold	0	The threshold value assigned for a CDP protocol before a violation action is reported on a UNI for a particular VPLS link
VPLSTunnelRecoveryInterval	0	Interval for the UNI to recover from a shutdown scenario
VPLSTunnelSTPEnable	0	The flag to specify if the STP packets will be tunneled to the remote site for a particular VPLS link
VPLSTunnelSTPThreshold	0	The threshold value assigned for a STP protocol before a violation action is reported on a UNI for a particular VPLS link
VPLSTunnelVTPEnable	0	The flag to specify if the VTP packets will be tunneled to the remote site for a particular VPLS link
VPLSTunnelVTPThreshold	0	The threshold value assigned for a VTP protocol before a violation action is reported on a UNI for a particular VPLS link
VPLSUniAging	0	The aging timer set on a UNI for a particular VPLS link
VPLSUniDuplex	0	The duplex assigned to the UNI for a particular VPLS link
VPLSUniMajorInterfaceName	0	The name of a major interface on a UNI device for a particular VPLS link

**Table 6-5 VPLS Repository Variables (continued)**

Repository Variables	Dimension	Description
VPLSUniMaxMacAddress	0	The maximum number of Mac addresses that can be learned on a UNI for a particular VPLS link
VPLSUniPortSecurity	0	The port security option on a UNI for a particular VPLS link
VPLSUniProtocolTunneling	0	The flag to specify if the protocols will be tunneled to the remote site for a particular VPLS link
VPLSUniSecureMacAddresses	1	The explicit list of Mac addresses that can be learned on a UNI for a particular VPLS link
VPLSUniShutdown	0	The shutdown flag on a UNI for a particular VPLS link
VPLSUniSpeed	0	The speed assigned to the UNI for a particular VPLS link
VPLSUniViolationAction	0	The violation action option on a UNI for a particular VPLS link
VPLSUseNativeVlan	0	The flag to specify if the native VLAN will be used on a UNI for a particular VPLS link

## Link QoS

The Link QoS feature provides separate settings for IP QoS and Ethernet QoS.

IP QoS deals with link-level QoS settings that depend on Layer2 encapsulation and link bandwidth, such as Aggregate Shapers (FRTS; ATM Shapers, parent-level cb-shaper), Link Efficiency Mechanisms (FRF.12, LFIoMLPPP, and cRTP), and Interface-based Aggregated Rate Limiter.

Ethernet QoS allows you to configure Shape, Bandwidth, and Trust (CoS or DSCP) settings.

You can create a link QoS setting for a network independent of a VPN service. To manage **IP Link QoS Settings** for an MPLS service or **Ethernet Link QoS Settings** for an L2VPN service, see [Cisco IP Solution Center Quality of Service User Guide, 4.1](#).







## CHAPTER

# Monitoring

From the Home window of Cisco IP Solution Center (ISC), which you receive upon logging in, click the **Monitoring** tab and you receive a window as shown in [Figure 7-1](#), “[Monitoring Selections](#).”

**Figure 7-1**      **Monitoring Selections**



Next you can navigate to the following selections:

- [Task Manager, page 7-1](#) Create and schedule tasks and monitor task run details.
- [Ping, page 7-8](#) Perform Ping connectivity tests.
- [SLA, page 7-11](#) Manage probes and view reports.
- [TEM Performance Report, page 7-41](#) TEM performance report.
- [Reports, page 7-41](#) Create and schedule reports.

## Task Manager

ISC provides a Task Manager that allows you to view pertinent information about both current and expired tasks of all types, and to create and schedule new tasks, delete specified tasks, and delete the active and expired tasks.

This section contains the following subsections:

- [Tasks, page 7-2](#)
- [Task Logs, page 7-7](#)

## Tasks

This section contains the following topics:

- [Starting Task Manager, page 7-2](#)
- [Create, page 7-3](#)
- [Audit, page 7-5](#)
- [Details, page 7-6](#)
- [Schedules, page 7-6](#)
- [Logs, page 7-7](#)
- [Delete, page 7-7](#)

## Starting Task Manager

To start Task Manager, follow this step:

- Step 1** Click the **Task Manager** icon. The Tasks list page appears, as shown in [Figure 7-2, “Tasks.”](#)

**Figure 7-2** Tasks

#	Task Name	Type	Targets	Schedule	User Name	Created on
1.	SLA enable_traps 2005-11-22 21:11:00.0	SLA Traps Enable		Single run at 2005-11-22 21:11:00.0	admin	2005-11-22 21:11:32.237
2.	SLA enable_probes 2005-11-22 21:11:00.0	SLA Enable		Single run at 2005-11-22 21:11:00.0	admin	2005-11-22 21:11:18.524
3.	SLA Creation 2005-11-22 18:53:00.0	SLA Creation		Single run at 2005-11-22 18:53:00.0	admin	2005-11-22 18:50:47.189

The Tasks window displays information about each task by **Task Name**, **Type**, **Targets**, **Schedules** date and time, the **User Name** who created those tasks, and the date **Created on**. To view, schedule, or delete the listed tasks, select the corresponding check box.

New Tasks can also be created or audited using this window.

## Create

To create a new task, follow these steps:

- Step 1** From the **Tasks** page, as shown in Figure 7-2, “**Tasks**,” click **Create**. From the resulting drop-down list, you can choose from the following and that choice becomes the **Type** in Figure 7-3, “**Create Tasks**,”:
- **Collect Config** - collects configuration from devices.
  - **Password Management** - manages user passwords and SNMP community strings.
  - **SLA Collection** - collects data from SLA enabled devices.
  - **Service Deployment** - deploys an existing SR.
  - **TE Discovery** - populates the repository with tunnel and route data from the Traffic Engineering network.
  - **TE Interface Performance** - calculates tunnel and interface bandwidth utilization using SNMP.

**Figure 7-3 Create Tasks**

**Create Task**

<b>Name :</b>	Service Deployment 2005-12-06 18:14:24.448
<b>Type:</b>	Service Deployment
<b>Description:</b>	Created on 2005-12-06 18:14:24.448
<b>Task Configuration Method:</b>	<input checked="" type="radio"/> Simplified <input type="radio"/> Advanced (via wizard)

Note: \* - Required Field

149191

- Step 2** **Name:** Enter the name of the task. You can accept the default value.
- Step 3** **Type:** Defined in Step 1.
- Step 4** **Description:** (optional) Enter a description.
- Step 5** **Task Configuration Method** (default: **Simplified**) Choose **Simplified** or **Advanced (via wizard)**. If you choose **Simplified**, you can make many selections in one window. If you choose **Advanced (via wizard)**, you navigate through many windows to make your selections.

- Step 6** Click **Next** to continue. Depending on what type of task you select, the Task Devices or Task Service Requests page appears, as shown in [Figure 7-4](#), “Task Devices” and [Figure 7-5](#), “Service Deployment Task,” respectively, with variations.

**Figure 7-4 Task Devices**

<b>Devices:</b>		Select/Deselect
<b>Groups:</b>		Select/Deselect
<b>Options:</b>	<input checked="" type="checkbox"/> Retrieve device attributes <input checked="" type="checkbox"/> Retrieve Interfaces	
<b>Schedule:</b>	<input checked="" type="radio"/> Now <input type="radio"/> Later <input type="radio"/> None	
<b>Task Owner:</b>	<input type="radio"/> Customer <input type="radio"/> Provider <input checked="" type="radio"/> None	
		Submit Cancel

Note: \* - Required Field

**Figure 7-5 Service Deployment Task**

Service Deployment Task		
Deployment Task: Service Deployment 2005-12-06 18:14:24.448		
<b>Service Requests *</b>		Select/Deselect
<b>Options:</b>	<input type="checkbox"/> Force Deployment <input checked="" type="checkbox"/> Provision and Audit <input type="checkbox"/> Regenerate IPsec Pre-shared Keys	
<b>Schedule:</b>	<input checked="" type="radio"/> Now <input type="radio"/> Later <input type="radio"/> None	
<b>Task Owner:</b>	<input type="radio"/> Customer <input type="radio"/> Provider <input checked="" type="radio"/> None	
		Submit Cancel

Note: \* - Required Field

- Step 7** Click **Select/Deselect** to add devices or service requests.
- Step 8** In the resulting selection window, select the devices or service requests and click **Select**. The selected devices or service requests appear in [Figure 7-4](#), “Task Devices” or [Figure 7-5](#), “Service Deployment Task,” respectively.
- Step 9** **Groups** might or might not appear depending on the task you specify in the previous step. If it does appear, you can add groups of devices, similarly to [Step 7](#) and [Step 8](#). If it does not appear or after you complete this device group selection, proceed to [Step 10](#).

**Step 10** Choose the **Options**.

**Step 11** For **Schedule**, click **Now**, **Later**, or **None**. If you choose **Later**, a Later Schedule category appears. You are then required to click the **Edit** button and the Task Scheduler page appears, as shown in [Figure 7-6](#), “Task Schedule Details.”

**Figure 7-6 Task Schedule Details**

**Task Schedule**

Single Run: ☒ Now ☐ Once

Periodic Run: ☐ Minute ☐ Hourly ☐ Daily ☐ Weekly ☐ Monthly

**Periodic Run Attributes**

Run Interval:

Run Limits:

**Start Date and Time**

Date: March 28 2003

Time: 4 49 PM

**End Date and Time (Default is unlimited)**

Date: Month Day Year

Time: Hour Min AM

OK Cancel

93470

**Step 12** Select information to schedule the task and click **OK** (default is to schedule **Now**).

**Step 13** Click **Submit** to continue. The new task is added to the list of tasks.

## Audit

To get audit information, follow these steps:

**Step 1** From the **Tasks** page, as shown in [Figure 7-2](#), “Tasks,” click **Audit**. From the resulting drop-down list, you can choose from the following and that choice becomes the **Type** in [Figure 7-3](#), “Create Tasks,”:

- **Config Audit** - compares ISC generated configlet against the one in the device.
- **L2VPN (L2TPv3) Functional Audit** - audits L2TPv3 functionality.
- **MPLS Functional Audit** - audits MPLS functionality.
- **TE Functional Audit** - checks the Label-Switch Path (LSP) on a router against the LSP stored in the repository.

## Details

To get details about a particular task, follow these steps:

- 
- Step 1** From the **Tasks** page, as shown in [Figure 7-2](#), “**Tasks**,” select a check box for one task for which you want to see a detailed list of information.
  - Step 2** Click **Details**.
  - Step 3** Click **OK** to return to [Figure 7-2](#), “**Tasks**.”
- 

## Schedules

To change the scheduling of an existing task, follow these steps:

- 
- Step 1** From the **Tasks** page, as shown in [Figure 7-2](#), “**Tasks**,” select a check box for the one task for which you want to reset the scheduling directions.
  - Step 2** Click **Schedules**.
  - Step 3** If you want to delete this task, proceed to [Step 4](#). If you want to reset the scheduling directions, proceed to [Step 5](#).
  - Step 4** In the new window, select the check box for the task you want to delete and click the **Delete** button. Then proceed to [Step 7](#).
  - Step 5** In the new window, click **Create**, and you receive a window as shown in [Figure 7-7](#), “**Task Scheduling**.”

**Figure 7-7 Task Scheduling**

- 
- Step 6** Make the new scheduling selections you want and click **Save** to reset the scheduling directions.
  - Step 7** Deselect any check boxes and click **OK** to return to [Figure 7-2](#), “**Tasks**.”
-

## Logs

This selection from the **Tasks** page, as shown in [Figure 7-2](#), “**Tasks**,” is another way of doing what is explained in the “**Task Logs**” section on page 7-7.

## Delete

To delete one or more tasks, follow these steps:


- 
- Step 1** From the **Tasks** page, as shown in [Figure 7-2](#), “**Tasks**,” select one or more check boxes for the task(s) you want to delete.
- Step 2** You receive a confirmation window. If you want to delete, click **OK**. If not, click **Cancel**.
- Step 3** You return to an updated **Tasks** page, as shown in [Figure 7-2](#), “**Tasks**.”
- 

## Task Logs

Task Logs can be used to understand the status of a task, whether it completed successfully. You can also use the Task Logs to troubleshoot why a task has failed. To view the Task Logs, follow these steps:


- 
- Step 1** Click **Task Manager**. The Tasks page appears, as shown in [Figure 7-8](#), “**Tasks**.”

**Figure 7-8** **Tasks**



- Step 2** Click **Logs** under the TOC heading located on the left-hand side. The Task Logs page appears, as shown in the [Figure 7-9](#), “**Task Logs**.”

**Figure 7-9** **Task Logs**



This window displays the task by **Runtime Task Name**, and the **Action**, **Start Time**, **End Time**, and the **Status** of the task. You can use this window to view or delete the logs.

- Step 3** To view the log, select the check box for the row that represents the task and click the **View Log** button.
- Step 4** The Task Log page appears, as shown in Figure 7-10, “Task Log.”

**Figure 7-10 Task Log**



It is possible to set the types of log level you want to view. Specify the Log Level and click on the Filter button to view that information you want to view.

- Step 5** Click **Return to Logs** to specify another log to view.

## Ping

Ping is the way ISC monitors the VPN connectivity, that is verifies the connectivity among various edge devices comprising the VPN. To achieve this, you can perform a series of pings among these devices. Ping has the following benefits:

- Ping is service independent and therefore can be used for functional auditing of MPLS applications.
- Ping can establish whether a service is working without doing a functional audit for that service.
- Ping can be used to verify IPv4 connectivity among CPEs prior to VPN service deployment.

However, Ping does not do the following:

- Ping does not work in environments where ICMP traffic is blocked, for example, in a Cisco IOS router with an access-list denying all ICMP traffic.
- Ping can only inform you that there is a connectivity problem. It does not offer any service-specific information. The connectivity problem can be due to many reasons, such as device failure, misconfiguration, and so on, which ping cannot distinguish.
- Only the immediate subnet behind the router's customer-facing (also, inside or nonsecured) interface is supported. Campus subnets cannot be supported.



The Ping GUI supports all possible pings for MPLS service requests. This section explains how to ping MPLS service requests.

**Note**

ISC has a component Cisco MPLS Diagnostics Expert that might help you. See [Cisco MPLS Diagnostics Expert 1.0 User Guide on ISC 4.1](#).

After you navigate **Monitoring > Ping**, you receive a window as shown in [Figure 7-11](#), “Services.”

**Figure 7-11 Services**

**Services**

Show Services with Job ID matching \* of Type MPLS VPN Find

Showing 1 - 2 of 2 records

#	Job ID	State	Type	Operation Type	Creator	Customer Name	Policy Name	Last Modified	Description
1.	1	REQUESTED	MPLS	ADD	admin	Customer1	MPLSPolicy_PECE	10/27/05 5:25 PM	
2.	2	REQUESTED	MPLS	ADD	admin	Customer1	MPLSPolicyNO_CE	10/27/05 5:25 PM	

Rows per page: 10 Go to page: 1 of 1 Go

Auto Refresh: ☒ Configure Ping Parameters

The **Type** field indicates **MPLS**. Follow these steps:

- Step 1** Select the check box next to each row for which you want to configure ping parameters.
- Step 2** Click the **Configure Ping Parameters** button, which becomes enabled. A window as shown in [Figure 7-12](#), “MPLS Parameters,” appears.

**Figure 7-12 MPLS Parameters**

**MPLS Parameters**

Ping Type: ☒ Do PE to CE Ping ☐ Do CE to CE Ping

Two-way Ping: ☐

Packet Repeat Count: 5

Datagram Size: 100

Start Ping

Fill in the following and then click **Start Ping**:

- **Ping Type—Do PE to CE Ping** When this radio button is chosen, a VRF ping occurs for all PE CE pairs that form an MPLS VPN link. The IP addresses taken for this ping are the link end-point addresses. For example, assume that an MPLS service request has two linked PE1<>CE1 and

PE2<>CE2. Then this selection initiates four VRF pings: (PE1, CE1), (PE2, CE2), (PE1, CE2), and (PE2, CE1). When this selection is chosen, then after you click **Start Ping**, you go directly to [Step 6](#) and receive a result page.

- **Ping Type—Do CE to CE Ping** When this radio button is chosen, a ping occurs between all CEs that make the end-point in the service request. When this selection is chosen, then after you click **Start Ping**, you go to [Step 3](#).
- **Two-way Ping** (default: unavailable and deselected) This check box is only available when you select **Do CE to CE Ping**. When a ping occurs from device1 to device2 and this check box is selected, then a ping from device2 to device1 also occurs.
- **Packet Repeat Count** (default: 5) This value indicates how many ICMP packets to use for a ping.
- **Datagram size** (default: 100) This value is the packet size of ICMP used for pinging.

**Step 3** For **Do CE to CE Ping**, you proceed to a window as shown in [Figure 7-13](#), “MPLS CE Selection.”

**Figure 7-13 MPLS CE Selection**

Showing 1-1 of 1 records								
#	<input type="checkbox"/>	Job ID	Source CE	Source IP Address	Source Site	Destination CE	Destination IP Address	Ping Result
1.	<input type="checkbox"/>	2	ence51		Site-ence51	ence61		Incomplete
Rows per page: 10								
Start MPLS CE Ping								

**Step 4** Select the check box next to each row for which you want to select a CE.

**Step 5** Click the **Start MPLS CE Ping** button, which becomes enabled.

**Step 6** You receive a results window as shown in [Figure 7-14](#), “MPLS Ping Test Results.”

**Figure 7-14 MPLS Ping Test Results**

Showing 1-4 of 4 records

#	Property Name	Property Value
1.	Packet repeat count	5
2.	Datagram size	100
3.	Two-way Ping	no
4.	Do PE to CE ping	no

Showing 1-2 of 2 records

#	Job ID	PE	Source IP Address	Source Region	CE	Destination IP Address	Destination Site	Ping Result
1.	12	mlpe2	40.40.40.13	West	mlce3	40.40.40.14	SJ	0/5 success
2.	27	mlpe2	40.40.40.29	West	mlce1	40.40.40.30	SF	0/5 success

Rows per page: 10

Auto Refresh: ☐

Redo Ping

View Job Logs

Refresh

Close

**Step 7** The buttons at the bottom of the window are as follows:

- **Redo Ping** When you click this button, you restart all the pings. The parameters used are the same as those specified in the last request.
- **View Job Logs** When you click this button, you receive logs of all the ISC jobs created for doing ping. The ping application creates one job per selected service request.
- **Refresh** To selectively refresh, turn off the **Auto Refresh** button and click this button whenever you want to update the results.
- **Close** Click this button to close the current ping request. You return to the **Monitoring** page.



**Note**

Any column heading in blue indicates that by clicking that column header, you can sort on that column.

**Step 8** Click **Close** and you are finished with this Ping session.

## SLA

A service-level agreement (SLA) defines a level of service provided by a service provider to any customer. Performance is monitored through the SLA server. ISC monitors the service-related performance criteria by provisioning, collecting, and monitoring SLAs on Cisco IOS routers that support the Service Assurance Agent (SA Agent) devices. To provision the SLAs and to collect statistics for each SLA, the data collection task requires minimal user input.

The SLA collection task collects the relevant performance data, stores it persistently, aggregates it, and presents useful reports. The SLA collection task collects from the SA Agent MIB on devices. ISC leverages the SA Agent MIB to monitor SLA performance on a 24 x 7 basis. Using the MIB, you can monitor network traffic for the popular protocols:

- Dynamic Host Configuration Protocol (DHCP)
- Domain Name System (DNS)
- File Transfer Protocol (FTP)
- Hyper text Transfer Protocol (HTTP)
- Internet Control Message Protocol Echo (ICMP Echo)
- Jitter (voice jitter)
- Transmission Control Protocol Connect (TCP Connect)
- User Datagram Protocol Echo (UDP Echo).



**Note**

SLA uses the embedded Sybase database, independent of whether you choose Oracle as your database.



**Note**

The SLA operations **Create**, **Delete**, **Enable Probes**, **Disable Probes**, **Enable Traps**, and **Disable Traps** automatically result in the creation of a task, which executes the actual operation. You can view the status of the task by navigating **Monitoring > Task Manager > Logs**.

This section explains how to configure SLA probes, collect SLA data, and view SLA reports about these SLA probes.

Before you navigate **Monitoring > SLA**, implement the setup procedures in the “[Setup Prior to Using SLA](#)” section on page 7-12.”

Then navigate **Monitoring > SLA** and you can select one of the following:

- [Probes, page 7-12](#) is the default selection.
- [Reports, page 7-35](#)

## Setup Prior to Using SLA

SLA is an SNMP activity. Be sure SNMP is enabled and the SNMP settings on the router match the settings in the repository.

When creating an SLA **From MPLS CPE** or **From MPLS PE or MVRF-CE**, the service requests associated with the devices *must* be in the Deployed state.

## Probes

When you navigate **Monitoring > SLA > Probes**, you receive a window as shown in [Figure 7-15](#), “[SLA Probes](#).”

**Figure 7-15** SLA Probes

The default button that is enabled is **Create** and from the **Create** drop-down list, you can choose to create SLA probes **From Any SA Agent Device(s)**; **From MPLS CPE**; or **From MPLS PE or MVRF-CE**. However, if you select one or more existing probes by clicking the row(s) of existing probe(s), then you have access to the other buttons, **Details**, **Delete**, **Enable**, and **Disable**. For **Enable** and **Disable**, the drop-down list contains options to enable or disable SLA **Probes** and SLA **Traps**.

The explanations of the buttons and subsequent drop-down lists is given as follows:

- [Create Common Parameters, page 7-13](#) This section explains the SLA common parameters for all of the probe creation types: **From Any SA Agent Device(s)**; **From MPLS CPE**; or **From MPLS PE or MVRF-CE**.
- [Create From Any SA Agent Device\(s\), page 7-15](#) This section explains how to create probes from any SA Agent device(s) and begins after creating common parameters.
- [Create from MPLS CPE, page 7-17](#) This section explains how to create probes from an MPLS CPE and begins after creating common parameters.

- [Create From MPLS PE or MVRF-CE, page 7-22](#) This section explains how to create probes from an MPLS PE or MVRF-CE and begins after creating common parameters.
- [Protocols, page 7-24](#) This section is common Probes information for each of the **Create** paths.
- [Details, page 7-30](#) This section gives details about a specified probe.
- [Delete, page 7-31](#) This section explains how to delete a probe.
- [Enable Probes, page 7-32](#) This section explains how to enable the Probe and change its status from Created to Active state.
- [Enable Traps, page 7-33](#) This section explains how to enable traps.
- [Disable Probes, page 7-34](#) This section explains how to disable the Probe and change its status from Active to Disabled.
- [Disable Traps, page 7-35](#) This sections explains how to disable traps.

## Create Common Parameters

When you navigate **Monitoring > SLA > Probes**, the default is the **Probes** page with only the **Create** button enabled, as shown in [Figure 7-15](#). From the **Create** drop-down list, you can select **From Any SA Agent Device(s)**, **From MPLS CPE**, or **From MPLS PE or MVRF-CE**. The first window to appear in all ways of creation is specified here. Then you proceed to the specific creation type you have chosen.

Follow these steps:

- Step 1** The window to appear is as shown in [Figure 7-16](#), “**SLA Common Parameters**.”

**Figure 7-16 SLA Common Parameters**

SLA Common Parameters	
SLA Life *	-1 (secs)
Threshold *	5000 (msecs)
Timeout *	5000 (msecs)
Frequency (0 - 604800) *	60 (secs)
TOS Category:	<input checked="" type="radio"/> Precedence <input type="radio"/> DSCP
TOS (0 - 7) *	0
Keep History:	<input type="checkbox"/>
Number of Buckets (1 - 60) *	15
Enable Traps:	<input type="checkbox"/>
Falling Threshold (1 - Threshold) *	3000 (msecs)

Note: \* - Required Field

149035

Accept the defaults or change the information in the fields of the common SLA parameters, as follows, and then click **Next**:

- **SLA Life** (required) is the number of seconds that the probe is active (with the maximum value of a 32-bit integer in seconds). If the value is set to **-1**, the typical and default value, the probe is active forever.

- **Threshold** (required) is an integer that defines the threshold limit in milliseconds. When this threshold is exceeded and traps are enabled, a trap is sent. The maximum value is the maximum value of a 32-bit integer. If the SA Agent operation time exceeds this limit, the threshold violation is recorded by the SA Agent. The value for **Threshold** must not exceed the value for **Timeout**. The default value is **5000**.
- **Timeout** (required) is the duration in milliseconds to wait for an SA Agent operation completion. The value for **Timeout** must be less than or equal to the value for **Frequency** and greater than or equal to the value for **Threshold**. The default value is **5000**.
- **Frequency (0 - 604800)** (required) is the duration in seconds between initiating each SA Agent operation. The value for **Frequency** must be greater than or equal to the value for **Timeout**. The default value is **60**.
- **TOS Category** (default: **Precedence**) If you select the **Precedence** radio button for **TOS Category**, you have one set of type of service (TOS) values. If you select the **DSCP** radio button for **TOS Category**, you have a different set of TOS values.
- **TOS** (required) is an integer. The range and meanings of the values depend on whether the radio button in the **TOS Category** is set to **Precedence** (values: 0 to 7) or **DSCP** (values: 0 to 63).
  - When the **TOS Category** is set to **Precedence**, the valid values are **0** to **7**. These values represent the three most significant bits of the ToS field in an IP header. The default value is **0**. The meanings of the **Precedence** values are specified in Table 7-1, “Meanings of Precedence Values.”

**Note**

Type of Service does not apply to the **DNS** and **DHCP** types of SLA probes. ISC ignores any ToS value set for these two types of SLA probes. For example, if you first select a ToS value of 5, then select the **DNS**, **DHCP**, and **ICMP Echo** protocols for an SLA probe, ISC applies the selected ToS value to the **ICMP Echo** probe only.

**Table 7-1**      *Meanings of Precedence Values*

ToS Value	Binary Value	Meaning
7	111	Network Control
6	110	Internetwork Control
5	101	CRITIC/ECP
4	100	Flash Override
3	011	Flash
2	010	Immediate
1	001	Priority
0	000	Routine

- When the **TOS Category** is set to **DSCP**, the valid values are **0** to **63**. These values represent the six most significant bits of this ToS field in an IP header. The default value is **0**. The interpretation of these **TOS** values is user specified.

**Note**

ISC maps the 0 - 7 PRECEDENCE values to the three most significant ToS bits by left-shifting the value by five positions. Similarly, the 0 - 63 DSCP values are left-shifted by two positions.

- **Keep History** (default: deselected) If you select the **Keep History** check box, you indicate to keep the recent History Table on the router. Specifically, it is kept in the SA Agent MIB that keeps the raw round-trip time (RTT) SLA measurement. This selection also enables you to indicate the **Number of Buckets** of raw history data to keep. If you leave the default of a deselected check box for **Keep History**, no raw history data is kept. **Keep History** is not supported for **HTTP** and **Jitter**.
- **Number of Buckets (1 - 60)** (required) The default is **15** when the **Keep History** check box is selected. The range is 1 to 60 and indicates the number of most recent raw data entries to be kept in the raw history data. When the specified **Number of Buckets** is surpassed, removal of buckets starts with the oldest bucket to keep only the number of raw data entries specified.
- **Enable Traps** (default: deselected, which means No) If you select the **Enable Traps** check box, the created SLA is configured to send three types of traps. This selection also enables you to indicate the **Falling Threshold**. If you leave the **Enable Traps** check box deselected, the traps are disabled on the SLAs created in this task.
- **Falling Threshold (1 - Threshold)** (required) The default is **3000** in milliseconds when the **Enable Traps** check box is selected. The range is **1** to the **Threshold** value in milliseconds. When traps are enabled and the delay meets the specified number of milliseconds, a trap is sent.

**Step 2** Next you proceed to [Create From Any SA Agent Device\(s\)](#), page 7-15, [Create from MPLS CPE](#), page 7-17, or [Create From MPLS PE or MVRP-CE](#), page 7-22.

## Create From Any SA Agent Device(s)

After you have completed the steps in [Create Common Parameters](#), page 7-13, follow these steps:



### Note

IP connectivity must be available between the SA Agent devices.

**Step 1** The next window to appear is as shown in [Figure 7-17](#), “SLA Source Devices.”

**Figure 7-17 SLA Source Devices**

SLA Source Devices			
			Showing 1 - 3 of 3 records
#	Device Name	Interface	Type
1. <input type="checkbox"/>	pe1	172.29.146.21 <input type="button" value="Select"/>	CISCO_ROUTER
2. <input type="checkbox"/>	sw2	172.29.146.38 <input type="button" value="Select"/>	CISCO_ROUTER
3. <input type="checkbox"/>	ce3	172.29.146.26 <input type="button" value="Select"/>	CISCO_ROUTER
Rows per page: <input type="text" value="10"/> <span style="float: right;">Go to page: <input type="text" value="1"/> of 1 <input type="button" value="Go"/></span>			
			<input type="button" value="Add"/> <input type="button" value="Delete"/>

**Step 2** Click the **Add** button and a window appears as shown in [Figure 7-18](#), “SLA Devices > Add,” which lists all the devices in the database that have a minimum of one interface. Select the check box next to each row for the device you want to select, then click **Select**.

**Figure 7-18** SLA Devices > Add

Showing 1 - 8 of 8 records

#	<input type="checkbox"/>	Device Name	Management IP Address	Type	Parent Device Name
1.	<input type="checkbox"/>	pe1		Cisco IOS Device	
2.	<input type="checkbox"/>	pe3		Cisco IOS Device	
3.	<input type="checkbox"/>	sw2		Cisco IOS Device	
4.	<input type="checkbox"/>	sw3		Cisco IOS Device	
5.	<input type="checkbox"/>	sw4		Cisco IOS Device	
6.	<input type="checkbox"/>	ce3		Cisco IOS Device	
7.	<input type="checkbox"/>	ce8		Cisco IOS Device	
8.	<input type="checkbox"/>	ce13		Cisco IOS Device	

Rows per page: 10 Go to page: 1 of 1 Go

Select Cancel

- Step 3** You return to [Figure 7-17](#) and the newly added source device(s) appear. The information about this source device is specified in the following columns:
- **Device Name** You can click this heading and the device names are organized alphabetically.
  - **Interface** You can click **Select** and from the resulting window, you can update the IP address. Select one radio button for an interface and click **Select** and the IP address changes in [Figure 7-17](#).
  - **Type** Gives you the type of the source device.
- Step 4** You can repeat [Step 2](#) to [Step 3](#) to add more devices, or you can delete any of the currently selected source devices. To delete, select the check box next to each row for the device you want to delete and then click **Delete**.

**Note**

There is no second chance for deleting source devices. There is no confirm window.

- Step 5** Click **Next**. The next window to appear is as shown in [Figure 7-19](#), “SLA Destination Devices.”



**Figure 7-19 SLA Destination Devices**

SLA Destination Devices			
			Showing 1 - 3 of 3 records
#	Device Name	Interface	Type
1. <input type="checkbox"/>	pe3	172.29.146.23 <a href="#">Select</a>	CISCO_ROUTER
2. <input type="checkbox"/>	sw3	172.29.146.39 <a href="#">Select</a>	CISCO_ROUTER
3. <input type="checkbox"/>	ce8	172.29.146.31 <a href="#">Select</a>	CISCO_ROUTER
Rows per page: 10 <span style="float: right;">Go to page: 1 of 1 <a href="#">Go</a></span>			
			<a href="#">Add</a> <a href="#">Delete</a>

149037

- Step 6** Click the **Add** button and a window appears as shown in [Figure 7-18](#), “SLA Devices > Add.” Select the check box next to each row for the device you want to select. Then click **Select**.
- Step 7** You return to [Figure 7-19](#) and the newly added destination device(s) appear. The information about this destination device is specified in the following columns:
- **Device Name** You can click this heading and the device names are organized alphabetically.
  - **Interface** You can click **Select** and from the resulting window, you can update the IP address. Select one radio button for an interface and click **Select** and the IP address changes in [Figure 7-19](#).
  - **Type** Gives you the type of the source device.
- Step 8** You can repeat [Step 6](#) to [Step 7](#) to add more devices, or you can delete any of the currently selected source devices. To delete, select the check box next to each row for the device you want to delete and then click **Delete**.

**Note**

There is no second chance for deleting destination devices. There is no confirm window.

- Step 9** Click **Next**. Proceed to the “[Protocols](#)” section on [page 7-24](#).”

## Create from MPLS CPE

After you have completed the steps in [Create Common Parameters](#), [page 7-13](#), follow these steps:

- Step 1** The next window to appear is as shown in [Figure 7-20](#), “SLA CPE Parameters.”

**Figure 7-20 SLA CPE Parameters**

**VPN Information**

VPN :

Customer:

**Source Device**

CPE :

CPE Interface :

**Destination Device(s)**

Type: ☒ Connected PE ☐ CPEs

Connected PE:

Connected PE Interface:

- Step 2** Click the **Select** button for **VPN** and a window appears as shown in [Figure 7-21](#), “[Select VPN](#),” which lists all the VPNs in the database.

**Figure 7-21 Select VPN**

Show VPNs with  matching

Showing 1 - 6 of 6 records

#	VPN Name	Customer Name
1.	Mpls-VPN-1	Customer1
2.	Mpls-VPN-2	Customer1
3.	Vpn1	Customer1
4.	Vpn2	Customer1
5.	Vpn3	Customer2
6.	Vpn4	Customer2

Rows per page:  Go to page:  of 1

Click the radio button for the VPN you want to select. Then click **Select**.

- Step 3** You return to [Figure 7-20](#) and the newly added VPN and Customer information appear and a **Select** button appears for **CPE**. You can change the VPN by repeating [Step 2](#).
- Step 4** Click the **Select** button for **CPE** and a window appears as shown in [Figure 7-22](#), “[Select CPE](#),” which lists the CPEs associated with the selected VPN. Click the radio button for the CPE you want to select. Then click **Select**.

**Figure 7-22 Select CPE**

Showing 1-2 of 2 records

#	Select	Customer Name	Site Name	Device Name	Management Type
1.	<input type="radio"/>	Customer1	Site-ence51	ence51	MANAGED
2.	<input type="radio"/>	Customer1	Site-ence61	ence61	MANAGED

Rows per page:

- Step 5** You return to [Figure 7-20](#) and the newly added **CPE** and its first interface appear and a **Select** button appears for **CPE Interface**. You can change the CPE by repeating [Step 4](#).
- Step 6** If you want to change the default **CPE Interface** information that appears, click **Select** and you receive a window as shown in [Figure 7-23](#), “**Interfaces**.”

**Figure 7-23 Interfaces**

Interfaces for device **encc51**

ShowDevice Interfaces with  matching

Showing 1-6 of 6 records

#	Select	Name	IP Address	Interface Logical Name
1.	<input type="radio"/>	Ethernet0	192.168.129.137/30	
2.	<input type="radio"/>	Ethernet1	10.5.5.1/30	
3.	<input type="radio"/>	FastEthernet0		
4.	<input type="radio"/>	Loopback0	192.168.115.81/32	
5.	<input type="radio"/>	Loopback1	11.11.11.1/32	
6.	<input type="radio"/>	Loopback2	12.12.12.1/32	

Rows per page:

Click the radio button next to the row for the VPN you want to select. Then click **Select**.

- Step 7** You return to [Figure 7-20](#) and the newly added **CPE Interface** appears. You can change the CPE Interface by repeating [Step 6](#).
- Step 8** You can keep the default **Type**, by leaving the radio button for **Connected PE** chosen, which creates an SLA between the CPE and its directly connected PE, or you can select the radio button for **CPEs** in the same VPN. If you keep the default of **Connected PE**, proceed to [Step 9](#). If you click the **CPEs** radio button, proceed to [Step 12](#).
- Step 9** Click **Select** for **Connected PE Interface** and a window appears as shown in [Figure 7-24](#), “**Connected PE Interface**.”

**Figure 7-24 Connected PE Interface**

Interfaces for device **enpe5**

Show Device Interfaces with  matching

Showing 1-9 of 9 records

#	Select	Name	IP Address	Interface Logical Name
1.	<input type="radio"/>	FastEthernet1/1		
2.	<input type="radio"/>	Loopback0	192.168.115.69/32	
3.	<input type="radio"/>	Switch1		
4.	<input type="radio"/>	Switch1.1	10.10.10.13/30	
5.	<input type="radio"/>	Switch1.100	14.14.14.1/30	
6.	<input type="radio"/>	Switch1.120	10.10.10.13/30	
7.	<input type="radio"/>	Switch1.152	192.168.12.17/30	
8.	<input type="radio"/>	Switch1.400		
9.	<input type="radio"/>	Tunnel1	10.10.10.5/30	

Rows per page:

93486

Click the radio button next to the row for the Name you want to select. Then click **Select**.

- Step 10** You return to [Figure 7-20](#) and the newly added **Connected PE Interface** appears. You can change the Connected PE Interface by repeating [Step 9](#).
- Step 11** Click **Next** and proceed to the “[Protocols](#)” section on page 7-24.
- Step 12** When you click **CPEs**, the window is as shown in [Figure 7-25](#), “**CPEs**.”

**Figure 7-25 CPEs**

You Are Here: [Monitoring](#) > [SLA](#) > [Probes](#)

**Mode: ADDING**

- ☒ 1. Common Parameters
- ☐ 2. SLA Devices
- ☐ 3. Protocols
- ☐ 4. Summary

**SLA Source and Destination Devices**

**VPN Information**

VPN \*: Mpls-VPN-1 Select

Customer: Customer1

**Source Device**

CPE \*: ce3 Select

CPE Interface \*: 172.29.146.26 Select

**Destination Device(s)**

Type: ☐ Connected PE ☒ CPEs

CPEs: Showing 0 of 0 records

#	Device Name	Interface	Select	Remove
Rows per page: 10 Go to page: 1 of 1 <span>Go</span>				

- Step 2 of 4 -

< Back Next > Finish Cancel

- Step 13** Click the **Select** button for **CPEs** and a window appears as shown in [Figure 7-26](#), “**Select CPE Associated with the Specified VPN**,” which lists all the CPEs associated with the specified VPN in the database.

**Figure 7-26 Select CPE Associated with the Specified VPN**

CPEs associated with **Customer1\_VPN**

Showing 1-2 of 2 records

#	<input type="checkbox"/>	Customer Name	Site Name	Device Name	Management Type
1.	<input type="checkbox"/>	Customer1	Site-ence51	ence51	MANAGED
2.	<input type="checkbox"/>	Customer1	Site-ence61	ence61	MANAGED

Rows per page: 10

Select Cancel

Select the check box next to the row(s) for the CPE(s) you want to select. Then click **Select**.

**Note**

Do *not* add a device chosen as a **Source Device** to **Destination Device(s)**.

- Step 14** You return to [Figure 7-25](#) and the newly added **Device Name** appears.
- Step 15** Click **Select** in the **Interface** column and a window appears as in [Figure 7-23](#). Click the radio button next to the row for the CPE you want to select. Then click **Select**.

- Step 16** You return to [Figure 7-25](#) and the newly added **CPE Interface** appears. You can change the CPE Interface by repeating [Step 15](#).
- Step 17** Select the check box next to each row for the Devices you want to remove. Then click the **Remove** button and a window as shown in [Figure 7-25](#) appears without the removed Device(s).
- Step 18** When [Figure 7-25](#) reflects what you want, click **Next** and proceed to the “[Protocols](#)” section on [page 7-24](#).

## Create From MPLS PE or MVRF-CE

After you have completed the steps in [Create Common Parameters, page 7-13](#), follow these steps:

- Step 1** The next window to appear is as shown in [Figure 7-27](#), “[SLA Source and Destination Devices](#).”

**Figure 7-27** *SLA Source and Destination Devices*

- Step 2** Click the **Select** button for **VPN** and a window appears as shown in [Figure 7-28](#), “[Select VPN](#),” which lists all the VPNs in the database. Click the radio button next to the row for the VPN you want to select. Then click **Select**.

**Figure 7-28** *Select VPN*

- Step 3** You return to [Figure 7-27](#) and the newly added VPN and Customer information appears. You can change the VPN and Customer by repeating [Step 2](#).
- Step 4** Click the new **Select** button for **PE/MVRF-CE** and you receive a drop-down list from which you can choose **PE** or **MVRF-CE**. If you choose **PE**, a window appears as shown in [Figure 7-29](#), “**Select PE**,” which lists all the PEs associated with the selected VPN. If you choose MVRF-CE, a window appears as shown in [Figure 7-30](#), “**Select CPE**,” which lists all the MVRF-CEs associated with the selected VPN. Click the radio button next to the row for the PE or MVRF-CE you want to select. Then click **Select** or **OK**.

**Figure 7-29**      **Select PE**

#	Provider Name	PE Region Name	Device Name	Role Type
1.	Provider1	region_1	pe1	N-PE

Showing 1 - 1 of 1 record

Rows per page: 10    Go to page: 1 of 1    Go

Select    Cancel

**Figure 7-30**      **Select CPE**

#	Customer Name	Site Name	Device Name	Management Type
---	---------------	-----------	-------------	-----------------

Showing 0 of 0 records

Rows per page: 10    Go to page: 1 of 1    Go

OK    Cancel

- Step 5** You return to [Figure 7-27](#) and the newly added PE or MVRF-CE information appears. You can change this selection by repeating [Step 4](#).
- Step 6** If in [Step 4](#) you chose MVRF-CE information, you can click the **VRF** drop-down list.
- Step 7** Click the new **Select** button for **Destination Device(s)**—PEs and CPEs and from a drop-down list, choose **PEs** or **CPEs**. If you choose **PEs**, a window appears as shown in [Figure 7-31](#), “**Select PEs**,” which lists all the PE Interfaces in the database. Click the radio button next to the row for the Device Interface you want to select. Then click **Select**.



**Note**

Do *not* add a device chosen as a **Source Device** to **Destination Device(s)**.

**Figure 7-31**      **Select PEs**

#	Provider Name	PE Region Name	Device Name	Role Type
1.	Provider1	region_1	pe1	N-PE

Rows per page: 10    Go to page: 1 of 1    Go

Select    Cancel

**Figure 7-32**      **Select CPEs**

#	Customer Name	Site Name	Device Name	Management Type
1.	Customer1	east	ce3	MANAGED

Rows per page: 10    Go to page: 1 of 1    Go

Select    Cancel

- Step 8**      You return to [Figure 7-27](#) and you receive interface information. Click **Select** and you get a window from which you can click a radio button next to a different interface. Click **Select** and the new interface replaces the old interface. You can change the Interface by repeating this step.
- Step 9**      Click **Next** and proceed to the “[Protocols](#)” section on [page 7-24](#).

## Protocols

You navigate to this location after you have completed all the steps in one of the **Create** functions: [Create Common Parameters](#), [page 7-13](#); [Create from MPLS CPE](#), [page 7-17](#); or [Create From MPLS PE or MVRP-CE](#), [page 7-22](#). Follow these steps:

- Step 1**      The next window to appear is as shown in [Figure 7-33](#), “[Protocols](#).”



**Figure 7-33      Protocols**

**Step 2** Click the **Add** drop-down list and select:

- **ICMP Echo** (only available if destination devices are available) Proceed to [Step 3](#).
- **TCP Connect** (not available for Create From MPLS PE or MVRF-CE; for all the other Creates, TCP Connect is only available if destination devices are available) Proceed to [Step 4](#).
- **UDP Echo** (only available if destination devices are available) Proceed to [Step 5](#).
- **Jitter** (only available if destination devices are available) Proceed to [Step 6](#).
- **FTP** (not available for Create from MPLS PE or MVRF-CE) Proceed to [Step 7](#).
- **DNS** (not available for Create from MPLS PE or MVRF-CE) Proceed to [Step 8](#).
- **HTTP** (not available for Create from MPLS PE or MVRF-CE) Proceed to [Step 9](#).
- **DHCP** (not available for Create from MPLS PE or MVRF-CE) Proceed to [Step 10](#).

**Step 3** From [Step 2](#), if you chose **ICMP Echo**, you receive a window as shown in [Figure 7-34](#), “Protocol ICMP Echo.”

**Figure 7-34      Protocol ICMP Echo**

Enter the required information as follows, click **OK**, and then proceed to [Step 11](#).

- **Request Size (0 - 16384)** (required) is a number that represents the number of octets (in bytes) to be placed into the data portion of the packet. The default is **28**.

**Step 4** From [Step 2](#), if you chose **TCP Connect**, you receive a window as shown in [Figure 7-35](#), “Protocol TCP Connect.”

**Figure 7-35 Protocol TCP Connect**

SLA Protocol	
Protocol:	TCP Connect
Destination Port *:	23 (1 - 65535)
Request Size:	1 (1 - 16384 bytes)
<div>OK Cancel</div>	
Note: * - Required Field	

Enter the required and optional information as follows, click **OK**, and then proceed to [Step 11](#).

- **Destination Port (1 - 65535)** (required) is the port number on the target to where the monitoring packets is sent. If you do not specify a specific port, port **23** is used.
- **Request Size (1 - 16384)** (optional) is a number that represents the number of octets (in bytes) to be placed into the data portion of the packet. The default is **1**.

**Step 5** From [Step 2](#), if you chose **UDP Echo**, you receive a window as shown in [Figure 7-36](#), “Protocol UDP Echo.”

**Figure 7-36 Protocol UDP Echo**

SLA Protocol	
Protocol:	UDP Echo
Destination Port *:	7 (1 - 65535)
Request Size:	16 (4 - 8192 bytes)
<div>OK Cancel</div>	
Note: * - Required Field	

Enter the required and optional information as follows, click **OK**, and then proceed to [Step 11](#).

- **Destination Port (1 - 65535)** (required) is the port number on the target to where the monitoring packets are sent. If you do not specify a specific port, port **7** is used.
- **Request Size (4 - 8192)** (optional) is a number that represents the number of octets (in bytes) to be placed into the data portion of the packet. The default is **16**.

**Step 6** From [Step 2](#), if you chose **Jitter**, you receive a window as shown in [Figure 7-37](#), “Protocol Jitter.”

**Figure 7-37 Protocol Jitter**

SLA Protocol	
Protocol:	Jitter
Destination Port*:	8000 (1 - 65535)
Request Size:	32 (16 - 1500 bytes)
Number of Packets:	10 (1 - 1000)
Interval:	20 (1 - 1000 msec)
<input type="button" value="OK"/> <input type="button" value="Cancel"/>	
Note: * - Required Field	

149 175

Enter the required and optional information as follows, click **OK**, and then proceed to [Step 11](#).

- **Destination Port (1 - 65535)** (required) is the port number on the target to where the monitoring packets are sent. If you do not specify a specific port, port **8000** is used.
- **Request Size (16 - 1500)** (optional) is a number that represents the number of octets (in bytes) to be placed into the data portion of the packet. The default is **32**.
- **Number of Packets (1 - 1000)** (optional) is an integer that represents the number of packets that must be transmitted. The default value is **10**.
- **Interval (1 - 1000)** (optional) is an integer, **1** to **1,000**, that represents the inter-packet delay between packets in milliseconds. The default value is **20**.

**Step 7** From [Step 2](#), if you chose **FTP**, you receive a window as shown in [Figure 7-38](#), “Protocol FTP.”

**Figure 7-38 Protocol FTP**

SLA Protocol	
Protocol:	FTP
User Name:	<input type="text"/>
Password:	<input type="text"/>
Host IP Address*:	<input type="text"/>
File Path*:	<input type="text"/>
<input type="button" value="OK"/> <input type="button" value="Cancel"/>	
Note: * - Required Field	

149 174

Enter the required and optional information as follows, click **OK**, and then proceed to [Step 11](#).

- **User Name** (optional) If blank, **anonymous** is used.
- **Password** (optional) If blank, **test** is used.
- **Host IP Address** (required) Enter the IP address for File Transfer Protocol (FTP).
- **File Path** (required) Enter the path of the file you want to FTP on the FTP server.

**Step 8** From [Step 2](#), if you chose **DNS**, you receive a window as shown in [Figure 7-39](#), “Protocol DNS.”

**Figure 7-39 Protocol DNS**

Protocol:	DNS	
Name Server *:	<input type="text"/>	
Name to be Resolved *:	<input type="text"/>	
Request Size *:	<input type="text" value="1"/>	(0 - 16384 bytes)

OK Cancel

Note: \* - Required Field

Enter the required information as follows, click **OK**, and then proceed to [Step 11](#).

- **Name Server** (required) is the string that specifies the IP address of the name server. The address is in dotted IP address format.
- **Name to be Resolved** (required) is a string that is either the name or the IP address that is to be resolved by the DNS server. If the string is a name, the length is 255 characters. If the string is an IP address, it is in dotted IP address format.
- **Request Size (0 - 16384)** (required) is a number that represents the number of octets (in bytes) to be placed into the data portion of the packet. The default is 1.

**Step 9** From [Step 2](#), if you chose **HTTP**, you receive a window as shown in [Figure 7-40](#), “Protocol HTTP.”

**Figure 7-40 Protocol HTTP**

<b>SLA Protocol</b>	
Protocol:	HTTP
Version:	<input type="text" value="1.0"/>
URL *:	<input type="text"/>
Cache:	<input checked="" type="checkbox"/>
Proxy Server:	<input type="text"/>
Name Server:	<input type="text"/>
Operation:	<input type="text" value="HTTPGet"/> ▼
Raw Request *:	<input type="text"/>
Request Size *:	<input type="text" value="1"/> (1 - 16384 bytes)

OK Cancel

Note: \* - Required Field

Enter the optional and required information as follows, click **OK**, and then proceed to [Step 11](#).

- **Version** (default: 1.0) is a string that specifies the version of the HTTP server. Do not change this. ISC only supports version 1.0.

- **URL** (required) is a string that represents the URL to which an HTTP probe should communicate, *HTTPServerName[/directory]/filename* or *HTTPServerAddress[/directory]/filename* (for example: **http://www.cisco.com/index.html** or **http://209.165.201.22/index.html**). If you specify the *HTTPServerName*, the **Name Server** is required. If you specify the *HTTPServerAddress*, the **Name Server** is not required.
- **Cache** (default: selected, which means Yes) For a deselected check box, the HTTP request should not download cached pages. For a selected check box, the HTTP request downloads cached pages if available, otherwise the request is forwarded to the HTTP server.
- **Proxy Server** (optional) is a string that represents the proxy server information (with a maximum of 255 characters). The default is the null string.
- **Name Server** (optional, dependent on the **URL** setting) is the string that specifies the IP address of the name server. The address is in dotted IP address format.
- **Operation** (default: **HTTPGet**) If you want **HTTPRaw**, which represents the HTTP request with user defined payload, instead of the default **HTTPGet** which represents the HTTP get request, use the drop-down list and make that choice.
- **Raw Request** (required if the **Operation** is **HTTPRaw**; not available if the **Operation** is **HTTPGet**) is a string that is only needed if the **Operation** is **HTTPRaw**. It allows you to invoke other types of HTTP operations other than the simple GET operation.
- **Request Size (1 - 16384)** (required) is a number that represents the number of octets (in bytes) to be placed into the data portion of the packet. The default is **28**.

**Step 10** From [Step 2](#), if you chose **DHCP**, you receive a window as shown in [Figure 7-41](#), “Protocol DHCP.”

**Figure 7-41 Protocol DHCP**

Enter the required information as follows, click **OK**, and then proceed to [Step 11](#).

- **Destination IP Address** (required)

**Step 11** You return to [Figure 7-33](#) and additional columns of information now appear based on the Protocol information you provided. Before you click **Next** to proceed, determine if you want to **Add** more protocols, in which case repeat [Step 2](#) to [Step 10](#), or **Delete** any of the currently selected protocols, in which case, click **Delete** and proceed much as in [Step 2](#) to [Step 10](#) to now delete protocols.



**Note**

There is no second chance for deleting destination devices. There is no confirm window.

**Step 12** The next window to appear is a Probe Creation Task Summary window that shows the **Description** (date and time created), **Common Parameters**, **Source Devices**, **Destination Devices**, and **Protocols** that you have defined. If all exists the way you want it, click **Finish**. Otherwise, click **Back** and make corrections.

## Details

When you navigate **Monitoring > SLA > Probes**, you can get details by following these steps:

- Step 1** Select an existing probe by selecting the corresponding check box for which you want details. Then you have access to the **Details** button, as shown in [Figure 7-42](#), “**SLA Probes > Details**.”

**Figure 7-42** *SLA Probes > Details*

The screenshot shows the 'Probes' management interface. At the top, there is a search bar: 'Show Probes with Source Device Name matching' followed by an input field containing an asterisk (\*), 'of Type' with a dropdown menu set to 'All', and a 'Find' button. Below this, it says 'Showing 1 - 1 of 1 record'. A table lists the probes with columns: #, ☒, ID, Source Device, Source IP, Destination Device, Destination IP, Type, Status, and Traps Enabled. The first row shows ID 1, Source Device 'pe1', Source IP '172.29.146.21', Destination IP, Type 'DHCP', Status 'Created', and Traps Enabled 'No'. The '1' in the checkbox column is highlighted with a dashed border. Below the table, there is a 'Rows per page' dropdown set to '10' and a 'Go to page: 1 of 1' with a 'Go' button. At the bottom, there are buttons for 'Details', 'Create', 'Enable', 'Disable', and 'Delete'. The 'Details' button is highlighted.

- Step 2** After you click the **Details** button, you receive a window as shown in [Figure 7-43](#), “**SLA Probes Details**.” This includes the **Common Attributes** information defined when you first **Create** and the **Protocol Specific Attributes** information defined in the section [Protocols](#).

**Figure 7-43** *SLA Probes Details*

The screenshot shows the 'Probe Details' window. It has a title bar 'Probe Details'. Below the title bar, there are two sections: 'Common Attributes' and 'Protocol Specific Attributes'. The 'Common Attributes' section contains a table with the following data: Probe Type: DHCP, Source IP Address: 172.29.146.21, Destination IP Address: 0.0.0.0, Status: Created, SLA Life: unlimited, Threshold: 5000 msec, Timeout: 5000 msec, Frequency: 60 seconds, TOS Category: PRECEDENCE, TOS: 0, Keep History: No, and Traps Enabled: No. The 'Protocol Specific Attributes' section is currently empty. At the bottom right of the window, there is an 'OK' button.

- Step 3** Click **OK** to return to a window as shown in [Figure 7-42](#). You can continue to select more **Details** or complete another function.

## Delete

When you navigate **Monitoring > SLA > Probes**, you can delete probes from the list by following these steps:

- Step 1** Select one or more existing probes by selecting the check box(es) for the row(s) of existing probe(s). Then you have access to the **Delete** button, as shown in [Figure 7-44](#), “**SLA Probes > Delete**.”

**Figure 7-44** *SLA Probes > Delete*

**Probes**

Show Probes with Source Device Name matching  of Type

Showing 1 - 1 of 1 record

#	<input checked="" type="checkbox"/>	ID	Source Device	Source IP	Destination Device	Destination IP	Type	Status	Traps Enabled
1	<input checked="" type="checkbox"/>	1	pe1	172.29.146.21			DHCP	Created	No

Rows per page:  Go to page:  of 1

- Step 2** After you click the **Delete** button, a window as shown in [Figure 7-45](#), “**Confirm Delete Probes**,” appears.

**Figure 7-45** *Confirm Delete Probes*

**Selected Probes**

**Confirm Delete Probes**

Showing 1 - 1 of 1 record

#	ID	Source Device	Source IP	Destination Device	Destination IP	Type	Status	Traps Enabled
1	1	pe1	172.29.146.21			DHCP	Created	No

Rows per page:  Go to page:  of 1

- Step 3** Click **OK** if [Figure 7-45](#) reflects what you want to delete or click **Cancel** if it does not.



**Note**

After the probe is deleted, it is deleted from the probe list page but still remains in the database.

- Step 4** You return to [Figure 7-44](#) with updated information.

## Enable Probes

When you navigate **Monitoring > SLA > Probes**, you can enable probes by following these steps:

- Step 1** Select one or more existing probes by selecting the check box(es) for the row(s) of existing probe(s). Then you have access to the **Enable** button. From the **Enable** drop-down list, you have access to **Probes**, as shown in [Figure 7-46](#), “**SLA Probes > Enable > Probes**.”

**Figure 7-46** *SLA Probes > Enable > Probes*

Probes

Show Probes with Source Device Name matching  of Type  Find

Showing 1 - 1 of 1 record

#	<input checked="" type="checkbox"/>	ID	Source Device	Source IP	Destination Device	Destination IP	Type	Status	Traps Enabled
1.	<input checked="" type="checkbox"/>	1	pe1	172.29.146.21			DHCP	Created	No

Rows per page:  10  of 1

Details Create Enable Disable Delete

Probes Traps

- Step 2** After you select **Enable > Probes**, a window as shown in [Figure 7-47](#), “**Confirm Enable Probes**,” appears.

**Figure 7-47** *Confirm Enable Probes*

Selected Probes

Confirm Enable Probes

Showing 1 - 1 of 1 record

#	ID	Source Device	Source IP	Destination Device	Destination IP	Type	Status	Traps Enabled
1.	1	pe1	172.29.146.21			DHCP	Created	No

Rows per page:  10  of 1

OK Cancel

- Step 3** Click **OK** if [Figure 7-47](#) reflects the probes you want to enable or click **Cancel** if it does not. In both cases, you return to [Figure 7-46](#).
- Step 4** If this was successful, you receive a Status window with a green check mark for **Succeeded**. The Status column is set to **Active** when the probe is created successfully on the router.



## Enable Traps

When you navigate **Monitoring > SLA > Probes**, you can enable traps by following these steps:

- Step 1** Select one or more existing probes by selecting the check box(es) for the row(s) of existing probe(s). Then you have access to the **Enable** button. From the **Enable** drop-down list, you have access to **Traps**, as shown in [Figure 7-48](#), “**SLA Probes > Enable > Traps**.”

**Figure 7-48** *SLA Probes > Enable > Traps*

The screenshot shows the 'Probes' management interface. At the top, there is a search bar: 'Show Probes with Source Device Name matching' followed by an input field containing an asterisk (\*), 'of Type' with a dropdown menu set to 'All', and a 'Find' button. Below this, it says 'Showing 1 - 1 of 1 record'. A table lists the probes with columns: #, ID, Source Device, Source IP, Destination Device, Destination IP, Type, Status, and Traps Enabled. The first row is: 1, 1, pe1, 172.29.146.21, , , DHCP, Created, No. Below the table, there is a 'Rows per page' dropdown set to 10, and a pagination control: 'Go to page: 1 of 1' with 'Go' and navigation arrows. At the bottom, there are buttons: 'Details', 'Create' (with a dropdown), 'Enable' (with a dropdown), 'Disable' (with a dropdown), and 'Delete'. The 'Enable' dropdown is open, showing 'Probes' and 'Traps' options.

- Step 2** After you select **Enable > Traps**, a window as shown in [Figure 7-49](#), “**Confirm Enable Traps**,” appears. All the traps have 3000 ms as the falling threshold set automatically

**Figure 7-49** *Confirm Enable Traps*

The screenshot shows the 'Confirm Enable Traps' dialog box. It has a title bar 'Selected Probes' and a subtitle 'Confirm Enable Traps'. Below the subtitle, it says 'Showing 1 - 1 of 1 record'. A table lists the selected probes with columns: #, ID, Source Device, Source IP, Destination Device, Destination IP, Type, Status, and Traps Enabled. The first row is: 1. 1, pe1, 172.29.146.21, , , DHCP, Created, No. Below the table, there is a 'Rows per page' dropdown set to 10, and a pagination control: 'Go to page: 1 of 1' with 'Go' and navigation arrows. At the bottom, there are 'OK' and 'Cancel' buttons.

- Step 3** Click **OK** if [Figure 7-49](#) reflects the traps you want to enable or click **Cancel** if it does not. In both cases you return to [Figure 7-48](#).
- Step 4** If this was successful, you receive a Status window with a green check mark for **Succeeded**. The Traps Enabled column is set to **yes** when the probes on the router are successfully changed.

## Disable Probes

When you navigate **Monitoring > SLA > Probes**, you can use **Disable Probes** to delete probes on the devices. Follow these steps:

- Step 1** Select one or more enabled probes by selecting the check box(es) for the row(s) of existing probe(s). Then you have access to the **Disable** button. From the **Disable** drop-down list, you have access to **Probes**, as shown in [Figure 7-50](#), “**SLA Probes > Disable > Probes**.”

**Figure 7-50** *SLA Probes > Disable > Probes*

Probes

Show Probes with Source Device Name matching  of Type

Showing 1 - 1 of 1 record

#	<input checked="" type="checkbox"/>	ID	Source Device	Source IP	Destination Device	Destination IP	Type	Status	Traps Enabled
1.	<input checked="" type="checkbox"/>	1	pe1	172.29.146.21			DHCP	Created	No

Rows per page:  Go to page:  of 1

- Step 2** After you select **Disable > Probes**, a window as shown in [Figure 7-51](#), “**Confirm Disable Probes**,” appears.

**Figure 7-51** *Confirm Disable Probes*

Selected Probes

Confirm Disable Probes

Showing 1 - 1 of 1 record

#	ID	Source Device	Source IP	Destination Device	Destination IP	Type	Status	Traps Enabled
1.	1	pe1	172.29.146.21			DHCP	Created	No

Rows per page:  Go to page:  of 1

- Step 3** Click **OK** if [Figure 7-51](#) reflects the probes you want to disable or click **Cancel** if it does not. In both cases you return to [Figure 7-50](#).
- Step 4** If this was successful, you receive a Status window with a green check mark for **Succeeded**, and the probe’s status becomes Disabled when the probe on the router is successfully removed.

## Disable Traps

When you navigate **Monitoring > SLA > Probes**, you can disable traps by following these steps:

- Step 1** Select one or more existing probes by selecting the check box(es) for the row(s) of existing probe(s). Then you have access to the **Disable** button. From the **Disable** drop-down list, you have access to **Traps**, as shown in [Figure 7-52](#), “[SLA Probes > Disable > Traps](#).”

**Figure 7-52** *SLA Probes > Disable > Traps*

The screenshot shows the 'Probes' management interface. At the top, there is a search bar with the text 'Show Probes with Source Device Name matching' followed by an input field containing an asterisk (\*), a dropdown menu set to 'All', and a 'Find' button. Below this, it says 'Showing 1 - 1 of 1 record'. A table lists the probes with columns: #, ID, Source Device, Source IP, Destination Device, Destination IP, Type, Status, and Traps Enabled. The first row shows a probe with ID 1, Source Device 'pe1', Source IP '172.29.146.21', Type 'DHCP', Status 'Created', and Traps Enabled 'No'. Below the table, there is a 'Rows per page' dropdown set to 10, and a 'Go to page' field set to 1 of 1. At the bottom, there are buttons for 'Details', 'Create', 'Enable', 'Disable', and 'Delete'. The 'Disable' button is highlighted, and a dropdown menu is open showing 'Probes' and 'Traps'.

- Step 2** After you select **Disable > Traps**, a window as shown in [Figure 7-53](#), “[Confirm Disable Traps](#),” appears.


**Figure 7-53** *Confirm Disable Traps*

The screenshot shows the 'Confirm Disable Traps' dialog box. It has a title bar 'Selected Probes' and a subtitle 'Confirm Disable Traps'. Below the subtitle, it says 'Showing 1 - 1 of 1 record'. A table lists the selected probes with columns: #, ID, Source Device, Source IP, Destination Device, Destination IP, Type, Status, and Traps Enabled. The first row shows a probe with ID 1, Source Device 'pe1', Source IP '172.29.146.21', Type 'DHCP', Status 'Created', and Traps Enabled 'No'. Below the table, there is a 'Rows per page' dropdown set to 10, and a 'Go to page' field set to 1 of 1. At the bottom, there are buttons for 'OK' and 'Cancel'.

- Step 3** Click **OK** if [Figure 7-53](#) reflects the traps you want to disable or click **Cancel** if it does not. In both cases you return to [Figure 7-52](#).
- Step 4** If this was successful, you receive a Status window with a green check mark for **Succeeded**. The traps are disabled when the probes on the router are successfully changed.

## Reports

When you navigate **Monitoring > SLA > Reports**, you receive a window as shown in [Figure 7-54](#), “[SLA Reports](#).”

**Figure 7-54 SLA Reports**

You can then click on any of the following choices and receive that report

- [Summary Report, page 7-36](#) This report summarizes all the information other than for HTTP and Jitter (ICMP Echo, TCP Connect, UDP Echo, FTP, DNS, and DHCP).
- [HTTP Report, page 7-39](#) This is a summary report for HTTP information.
- [Jitter Report, page 7-39](#) This is a summary report for Jitter information.
- [Summary CoS Report, page 7-39](#) This report a summary report for Class of Service (CoS) other than for HTTP and Jitter (ICMP Echo, TCP Connect, UDP Echo, FTP, DNS, and DHCP).
- [HTTP CoS Report, page 7-40](#) This report is for HTTP CoS information.
- [Jitter CoS Report, page 7-41](#) This report is for Jitter CoS information.

## Summary Report

From [Figure 7-54](#), select **Summary Report** and follow these steps:

- 
- Step 1** The resulting window is shown in [Figure 7-55](#), “Parameters of Summary Report.”

**Figure 7-55 Parameters of Summary Report**

**Parameters of Summary Report**

**Layout**

Value Displayed : All

Aggregate By : ☒ All ☐ Customer ☐ Provider ☐ VPN ☐ Source Router ☐ Probe

Timeline : ☒ All ☐ Yearly ☐ Monthly ☒ Weekly ☐ Daily ☐ Hourly

2003 JUN 5 00:00

**Filtering**

Customer: Select

Provider: Select

VPN: Select

Source Routers: Select

Destination Routers: Select

Probes: Select

Precedence: All

DSCP: All

Probe Type: All

OK Cancel

Note: \* - Required Field

**Step 2** For [Figure 7-55](#), fill in the **Layout** fields, as follows:

- **Value Displayed** (required) (default: **All**) Click the drop-down list and select one of the following:
  - **All** to display all the values
  - **Connections (#)** to display the number of connections
  - **Timeouts (#)** to display the number of timeouts
  - **Connectivity (%)** to display connectivity as a percentage
  - **Threshold Violations (%)** to display threshold violations as a percentage
  - **Max Delay (ms)** to display the maximum delay in milliseconds
  - **Min Delay (ms)** to display the minimum delay in milliseconds
  - **Avg Delay (ms)** to display the average delay in milliseconds.
- **Aggregate By** (required) (default: **All**) Click the radio button for how you want to aggregate the data, by **All**, **Customer**, **Provider**, **VPN**, **Source Router**, or **Probe**.
- **Timeline** (required) (default: **Weekly**; starting with midnight of the first day of the selected week) Click the radio button for the report data that you want to display, **All** data; **Yearly** data; **Monthly** data; **Weekly** data; **Daily** data; or **Hourly** data. Also click the drop-down lists for the year, month, day of the month, and time of day for which to start the report.

**Step 3** For [Figure 7-55](#), fill in the **Filtering** fields, as follows:



**Note**

The report contains only the data that fulfills all the conditions in the filtering fields (all the conditions are ANDed together).

- **Customer** (optional) Click the **Select** button and from the resulting list of Customers, filter the list if you choose. From the listed Customers, click the radio button for the Customer for which you want this SLA report. Then click **Select**. The result is that you return to [Figure 7-55](#) and the selected customer is listed for **Customer**. You can repeat this process if you want to change your selection.
- **Provider** (optional) Click the **Select** button and from the resulting list of Providers, filter the list if you choose. From the listed Providers, click the radio button for the Provider for which you want this SLA report. Then click **Select**. The result is that you return to [Figure 7-55](#) and the selected provider is listed for **Provider**. You can repeat this process if you want to change your selection.
- **VPN** (optional) Click the **Select** button and from the resulting list of VPNs, filter the list if you choose. From the listed VPNs, click the radio button for the VPN for which you want this SLA report. Then click **Select**. The result is that you return to [Figure 7-55](#) and the selected VPN is listed for **VPN**. You can repeat this process if you want to change your selection.
- **Source Routers** (optional) Click the **Select** button and from the resulting list of devices, filter the list if you choose. From the listed devices, select the check box(es) for device(s). Then click **Select**. The result is that you return to [Figure 7-55](#) and **Source Routers** contains the selected device(s). You can repeat this process if you want to change your selection.
- **Destination Routers** (optional) Click the **Select** button and from the resulting list of devices, filter the list if you choose. From the listed devices, select the check box(es) for device(s). Then click **Select**. The result is that you return to [Figure 7-55](#) and **Destination Routers** contains the selected device(s). You can repeat this process if you want to change your selection.
- **Probes** (optional) Click the **Select** button and from the resulting list of source probes, filter the list if you choose. From the listed source probes, select the check box(es) for source probe(s). Then click **Select**. The result is that you return to [Figure 7-55](#) and **Probes** contains the selected source probe(s). You can repeat this process if you want to change your selection.
- **Precedence** (default: **All**) Click the drop-down list to select the other **Precedence** TOS choices, **0** to **7**. These values represent the three most significant bits of the ToS field in an IP header. The meanings of the **Precedence** values are specified in [Table 7-1](#), “[Meanings of Precedence Values](#).”

**Note**

ISC maps the 0 - 7 PRECEDENCE values to the three most significant ToS bits by left-shifting the value by five positions.

**Note**

Type of Service does not apply to the **DNS** and **DHCP** types of SLA probes. ISC ignores any ToS value set for these two types of SLA probes. For example, if you first select a ToS value of 5, then select the **DNS**, **DHCP**, and **ICMP Echo** protocols for an SLA probe, ISC applies the selected ToS value to the **ICMP Echo** probe only.

- **DSCP** (default: **All**) Click the drop-down list to select the other **DSCP** TOS choices, **0** to **63**. These values represent the six most significant bits of this ToS field in an IP header. The interpretation of these **TOS** values is user specified.

**Note**

ISC maps the 0 - 63 DSCP values to the six most significant ToS bits by left-shifting the values by two positions.

- **Probe Type** (default: **All**) Click the drop-down list to select from the following types of probes: ICMP Echo; UDP Echo; TCP Connect; HTTP; DNS; Jitter; DHCP; FTP.



---

**Note** These probe types are explained in detail in the “[Protocols](#)” section on page 7-24.

---

**Step 4** Click **OK** in [Figure 7-55](#) after you have the information you want.

**Step 5** The result is a Summary Report with the selections you made listed. You can **Modify**, **Refresh**, **Print**, or **Close** this report with the appropriate button.



---

**Note** If you choose **Modify**, you receive a window such as [Figure 7-55](#) in which you can modify your selections as explained in the previous steps.

---

## HTTP Report

From [Figure 7-54](#), select **HTTP Report** and proceed similarly to the “[Summary Report](#)” section on page 7-36, with the following exceptions:

- Value Displayed
- There is no **Destination Routers** selection
- There is no **Probe Type** drop-down list in the equivalent of [Figure 7-55](#), because the probe type is automatically **HTTP**. The result is an HTTP Report.

## Jitter Report

From [Figure 7-54](#), select **Jitter Report** and proceed exactly as in the “[Summary Report](#)” section on page 7-36, with only two exceptions. There is no **Destination Routers** selection and there is no **Probe Type** drop-down list in the equivalent of [Figure 7-55](#), because the probe type is automatically **Jitter**. The result is a Jitter Report.

## Summary CoS Report

From [Figure 7-54](#), select **Summary CoS Report** for a summary of the Class of Service (CoS) reports, which are based on the TOS values of the SLA probes, and follow these steps:

---

**Step 1** The resulting window is shown in [Figure 7-56](#), “[Parameters of CoS Summary Report](#).”

**Figure 7-56 Parameters of CoS Summary Report**

**Parameters of CoS Summary Report**

---

**Layout**

Value Displayed \* :

TOS Type \* : ☒ Precedence ☐ DSCP

Aggregate By \* : ☒ All ☐ Customer ☐ Provider ☐ VPN ☐ Source Router ☐ Probe

Timeline \* : ☐ All ☐ Yearly ☐ Monthly ☒ Weekly ☐ Daily ☐ Hourly

2003

---

**Filtering**

Customer:

Provider:

VPN:

Source Routers:

Destination Routers:

Probes:

Probe Type:

---

Note: \* - Required Field

- Step 2** For Figure 7-56, fill in the **Layout** fields, as shown in Step 2 of the “Summary Report” section on page 7-36, with the following exception. After **Value Displayed** and before **Aggregate By**, select the radio button **Precedence** (default) or **DSCP** for the new **TOS Type**. The explanations are given in the Filtering section, Step 3 of the “Summary Report” section on page 7-36.
- Step 3** For Figure 7-56, fill in the **Filtering** fields, as shown in Step 3 of the “Summary Report” section on page 7-36, with the exception that there are no **Precedence** or **DSCP** drop-down lists, they are now in the **Layout** fields, as explained in Step 2 in this section.
- Step 4** Click **OK** in Figure 7-56 after you have the information you want.
- Step 5** The result is a CoS Summary Report with the selections you made listed. You can **Modify**, **Refresh**, **Print**, or **Close** this report with the appropriate button.

**Note**

If you choose **Modify**, you receive a window such as Figure 7-56 in which you can modify your selections as explained in the previous steps.

## HTTP CoS Report

From Figure 7-54, select **HTTP Report** and proceed exactly as in the “Summary CoS Report” section on page 7-39, with only two exceptions. There is no **Destination Routers** selection and there is no **Probe Type** drop-down list in the equivalent of Figure 7-56, because the probe type is automatically **HTTP**. The result is an HTTP CoS Report. This CoS report is based on the TOS values of the SLA probes.



## Jitter CoS Report

From [Figure 7-54](#), select **Jitter Report** and proceed exactly as in the “[Summary CoS Report](#)” section on [page 7-39](#), with only two exceptions. There is no **Destination Routers** selection and there is no **Probe Type** drop-down list in the equivalent of [Figure 7-56](#), because the probe type is automatically **Jitter**. The result is a Jitter CoS Report. This CoS report is based on the TOS values of the SLA probes.

## TEM Performance Report

TEM Performance Report for Traffic Engineering Management is explained in detail in [Cisco IP Solution Center Traffic Engineering Management User Guide, 4.1](#).

## Reports

When you navigate **Monitoring > Reports**, a tree of reports appears in the data pane. Click on the + sign for each folder in the data pane and you receive a listing of all the provided reports. The non-SAMPLE reports in the L2VPN folder are explained in [Cisco IP Solution Center L2VPN User Guide, 4.1](#) and the non-SAMPLE reports in the MPLS folder are explained in [Cisco IP Solution Center MPLS VPN User Guide, 4.1](#).

Click on any of the specific reports and you can define how to set up the report. [Figure 7-57](#), “[Inventory > SAMPLE - Template Report - Report Window](#),” shows the sample file under the folder **Inventory**.

**Figure 7-57** *Inventory > SAMPLE - Template Report - Report Window*

The screenshot shows the 'Reports' window with a tree view on the left containing 'Inventory', 'SAMPLE - Template Report', 'L2', and 'MPLS'. The main area is titled 'Layout' and contains the following sections:

- Title:** SAMPLE - Template Report
- Chart Type:** Tabular
- Filters (All field values are required, \* or a valid value.):**
  - Template Path: \*
  - Template Definition Name: \*
  - Template Name: \*
- Sorting:**
  - Field: Template Path
  - Order: Ascending
- Output Fields:**
  - Template Path
  - Template Definition Name
  - Template Name

A 'View' button is located at the bottom right of the window. The page number 149030 is visible in the bottom right corner.

This section explains the Reports feature and how to use it in the following areas:

- [Introducing Reports, page 7-42](#)
- [Accessing Reports, page 7-42](#)
- [Using Reports GUI, page 7-42](#)

- [Running Reports, page 7-43](#)
- [Using the Output from Reports, page 7-44](#)
- [Creating Custom Reports, page 7-46](#)

## Introducing Reports

Network operators often want to have detailed reports on the services provisioned. For example, for a given customer, you might want to see a list of the PE-CE connections and their detailed PE-CE configuration parameters or you might want to see specific Layer2 or Layer3 service requests on a PE. These reports help network operators by providing a centralized location for finding Service Requests (SRs) and VPN information.

When you navigate **Monitoring > Reports**, reports are grouped by type to allow for easy navigation. ISC displays only predefined (canned) reports for which the user has RBAC permission.

You can select the filtering criteria and the outputs to be displayed in the report. You can save reports to a variety of formats.

In addition to the predefined reports that are documented in [Cisco IP Solution Center L2VPN User Guide, 4.1](#) and [Cisco IP Solution Center MPLS VPN User Guide, 4.1](#), ISC provides additional sample reports. Sample reports are provided for informational purposes only and are untested and unsupported.

The data structures that ISC uses to provide reports in the GUI are defined in an XML format.

## Accessing Reports

To access the reports, follow these steps:

- 
- Step 1** To access the reports framework in the ISC GUI, select **Monitoring > Reports**.
  - Step 2** Click on the folders to display the available reports.  
The Reports window appears, as shown in [Figure 7-57](#).
  - Step 3** From the reports listed under one of the folders in the left navigation tree, click on the desired report to bring up the window associated with that report.
- 



### Note

Several sample reports are provided in each of the reports folders. These reports begin with the title **SAMPLE-**. These reports are provided for informational purposes only. They are untested and unsupported. You might want to use them, along with the supported reports, as a basis for creating your own custom reports. See the [“Creating Custom Reports” section on page 7-46](#) for information about custom reports.

---

## Using Reports GUI

This section provides some general comments on using the reports GUI. This information applies to all reports. When you invoke a report, you see a window like the one shown in [Figure 7-57](#).

The window is divided into several areas:

- [Layout, page 7-43](#)
- [Filters, page 7-43](#)
- [Output Fields, page 7-43](#)
- [Sorting, page 7-43](#)

## Layout

This area displays the title of the report and allows you to select the chart type. You can enter your own report title by overwriting the Title field.

**Note**

Only tabular output is supported.

## Filters

In this pane you can define inputs or search criteria for the reports. Values entered here are compared against corresponding values associated with data objects in the ISC repository. Values must be entered for all fields. An asterisk (\*) can be used as a wild-card character for an entire string.

For each filterable field, the GUI displays a label and a text input field. For certain fields, the GUI also displays a Select button that allows you to choose an existing object (for example, customer, Service Type, SR State, and so on). All available output fields are displayed in the window, allowing you to select the fields to include in the report. All output fields are selected by default.

**Note**

Filter values must be in the same format as the values represented within ISC. For example, a Service Request (SR) ID must be a number.

## Output Fields

In this pane you can choose output fields to be displayed in the report. You can choose any or all of the output fields by selecting them with the mouse. Use the Shift key to select a continuous range of output values. Or, use the Control key to select random output values.

## Sorting

This pane allows you to select how you want to sort the report output. For Field:, use the first drop-down list to select each filter field and then the second drop-down list to choose whether to display the report fields in ascending or descending order. The sort order can also be changed after you have the report output displayed (see [Figure 7-58](#)).

## Running Reports

To run the report, click **View** in the lower right corner of the report window. This generates the report output. An example of a report output is shown in [Figure 7-58](#).

**Figure 7-58** Report Output

Template Path	Template Definition Name	Template Name
1. ATM	CLP_Egress	Data0
2. ATM	CLP_Ingress	Data0
3. DIA-Channelization	10K-CHOC12-STSI-PATH	SR_Data
4. DIA-Channelization	10K-CT3-CHANNELIZED	SR_Data
5. DIA-Channelization	10K-CT3-UNCHANNELIZED	SR_Data
6. DIA-Channelization	PA-MC-E3-CHANNELIZED	SR_Data
7. DIA-Channelization	PA-MC-STM1-AU3-CHANNELIZED	SR_Data
8. DIA-Channelization	PA-MC-STM1-AU4-CHANNELIZED	SR_Data
9. DIA-Channelization	PA-MC-T3-CHANNELIZED	SR_Data
10. Examples	AccessList	Acl2000
11. Examples	AccessList1	Protocol-IP
12. Examples	AccessList1	Protocol-TCP
13. Examples	CEWanCOS	CEWanCOS
14. FrameRelay	classification	Data0

The reports GUI supports output in tabular format. The output is listed in columns, which are derived from the outputs you selected in the reports window.

Each row (or record) represents one match of the search criteria you set using the filter fields in the reports window.

In some cases, the value returned in a field can be displayed as one of the following:

- **-1** means no information updated for this field
- **F** means false
- **T** means true

The column heading with a triangle icon is the output that the records are sorted by. By clicking on any column heading, you can toggle between and ascending and descending sort order. To sort on another output value, click on the heading for that value.

For information on working with report output, see the [“Using the Output from Reports”](#) section on page 7-44.

## Using the Output from Reports


The icons at the upper right of the report output window (see [Figure 7-59](#)) provide the following functions, respectively, moving from left to right:

- Export explained in the [“Exporting Reports”](#) section on page 7-45
- Print explained in the [“Printing Reports”](#) section on page 7-45
- E-mail explained in the [“E-mailing Reports”](#) section on page 7-46
- Link to web-based product documentation explained in the [“Invoking Help”](#) section on page 7-46

**Figure 7-59** Report Output Icons

## Exporting Reports

Click on the **Export** icon to bring up a window like the one shown in [Figure 7-60](#) and then follow these steps:

**Figure 7-60** Exporting Report Window

- 
- Step 1** Select the appropriate radio button for the format you want:
- PDF file – Adobe’s portable document format.
  - CSV file – Comma Separated Values format that allows for the data to be easily exported into a variety of applications.
- Step 2** Select the rows you would like to save, then click **OK**.  
ISC generates the report in the format you selected.
- 




### Note

You must have the appropriate application on your system (for example, Acrobat Reader or Excel) to view and save the output.

---

## Printing Reports

Click on the **Print** icon to bring up a window like the one shown in [Figure 7-61](#).

**Figure 7-61** Print Report

This window allows you to display the report in a form more appropriate for printing. Select the desired rows, then click **OK**. The results are displayed in your web browser, from which you can print the report.

## E-mailing Reports

Click on the **E-mail** icon to bring up a window like the one shown in [Figure 7-62](#) and then follow these steps:

**Figure 7-62** *E-mail Report*

- 
- Step 1** In the To: field (required), specify one or more e-mail addresses to which the report should be sent.
  - Step 2** In the From: field (optional), enter an e-mail address you want to appear in the message header.  
This allows a reply message to be sent to a valid e-mail address.
  - Step 3** In the CC: field (optional), enter e-mail addresses for recipients you want to receive copies of this report.
  - Step 4** The subject field shows the title of the report being sent.  
You can overwrite this field to rename the report. This is what appears in the Subject field of the e-mail message.
  - Step 5** Select the radio button for the output format (PDF or CSV) in which you want the report sent.
  - Step 6** Select the number of rows you want sent.
  - Step 7** If applicable, in the Message field, write a message to announce the report, then click **Send**.
- 

## Invoking Help

Click on the **Help (?)** icon to link to the ISC documentation set on the Cisco Systems web site.

## Creating Custom Reports


The reports listed in the ISC GUI in the each folder are derived from an underlying configuration file. The file is in XML format. You can access the file in the following location:

**\$ISC\_HOME/resources/nbi/reports/ISC/<folder\_name>\_report.xml**

where <folder\_name> is **Inventory**, **L2**, or **MPLS**.

Each of the available reports (including sample reports) is defined by XML content contained within an `<objectDef name>` start and end tag under **packageDef name = “`<folder_name>`”**. The intervening XML content specifies the title of the report, all allowable filter parameters, outputs, and the default sorting behavior. You can modify existing reports or copy them to use as templates for new reports.

To do this, follow these steps:

- 
- Step 1** Stop the ISC server using the **stopall** command. See [Chapter 2, “WatchDog Commands”](#) for information on starting and stopping ISC.
- Step 2** Open the `$ISC_HOME/resources/nbi/reports/ISC/<folder_name>_report.xml` (where: `<folder_name>` is **Inventory**, **L2**, or **MPLS**) configuration file using an editing tool of your choice.
-  **Note** You should backup the file before making any changes to it.
- 
- Step 3** Depending on your needs, either modify an existing report or copy one and use it as the basis for a new one.
- Step 4** Save the modified `$ISC_HOME/resources/nbi/reports/ISC/<folder_name>_report.xml` file.
- Step 5** Restart the ISC server using the **startwd** command. See [Chapter 2, “WatchDog Commands”](#) for information on starting and stopping ISC.
- 

After restarting ISC, the modifications take effect, based on changes you made to the `$ISC_HOME/resources/nbi/reports/ISC/<folder_name>_report.xml` file.








## Diagnostics

From the Home window of Cisco IP Solution Center (ISC), which you receive upon logging in, click the **Diagnostics** tab and you receive a window as shown in [Figure 8-1](#), “[Diagnostics Selection](#).”

**Figure 8-1**      **Diagnostics Selection**



The Cisco MPLS Diagnostics Expert application is designed for network operations center (NOC) fault and assurance operators. It provides automated troubleshooting and diagnostics for access circuits, edge, and core failures in Layer 3 Multiprotocol Label Switching (MPLS) VPN deployments. This application is explained in detail in [Cisco MPLS Diagnostics Expert 1.0 User Guide on ISC 4.1](#).






# Administration

From the Home window of Cisco IP Solution Center (ISC), which you receive upon logging in, click the **Administration** tab and you receive a window as shown in [Figure 9-1](#), “Administration Selections.”

**Figure 9-1** Administration Selections



Then you can navigate to the following selections:

- [Security, page 9-1](#) Create and manage Users, User Groups, User Roles, and Object Groups
- [Control Center, page 9-23](#) Manage ISC configuration, servers, remote installation, and licensing
- [Active Users, page 9-34](#) View users currently connected to ISC. Disconnect users.
- [User Access Log, page 9-35](#) View the user access log.
- [Manage TIBCO Rendezvous, page 9-37](#) Specify attributes for proper messaging among all Java™ Web Start distributed applications.

## Security


This section describes how system administrators create, edit, and delete users, user groups, and user roles and how privileges are assigned to these entities.

The security features are only accessible to the user **admin** or users with the following roles:

- **SysAdminRole** gives access to all the ISC tools. This is similar to “root” in a UNIX system.
- **UserAdminRole** gives access to only the user management tools in **Administration > Security**.

Navigate **Administration > Security** to access the user management tools. The window shown in [Figure 9-2](#), “**Security Window**,” appears.

**Figure 9-2 Security Window**



From the Security window, navigate to the following:

- [Users, page 9-2](#) to manage users
- [User Groups, page 9-7](#) to manage user groups
- [User Roles, page 9-9](#) to manage user roles
- [Object Groups, page 9-16](#) to manage object groups.

For an example of how to use the Users, User Groups, User Roles, and Object Groups, see the “[User Roles Design Example](#)” section on [page 9-20](#).

## Users

Navigate **Administration > Security > Users** and follow these steps:

- 
- Step 1** The window in [Figure 9-3](#), “**Users Window**,” appears.

**Figure 9-3 Users Window**

Users

Show users with  matching

Showing 1 - 1 of 1 record

#	User ID	First Name	Last Name	Work Phone	Mobile Phone
1. <input type="checkbox"/>	admin	System	Administrator		

Rows per page:

Go to page:  of 1

**Step 2** The explanations of the buttons are given as follows:

- [Details, page 9-3](#) View a User Detail Report
- [Create, page 9-3](#) Create a new user
- [Copy, page 9-5](#) Make a copy of an existing user and make changes to create a new user
- [Edit, page 9-6](#) Edit selected user
- [Delete, page 9-6](#) Delete selected user(s).

## Details

When you click the **Details** button, located at the bottom of [Figure 9-3](#), you receive the following columns of information: **User ID**; **User Group** that a user belongs to; **Role** that a user occupies; **Resource Privilege** permissions that a user has for each role occupied; **Object Group** that a user role is associated with; **Customer View** that a user's role is limited to; **Provider View** that a user's role is limited to.

## Create

When you click the **Create** button, located at the bottom of [Figure 9-3](#), a user with the required privileges can create a new user. Follow these steps:

- Step 1** Navigate **Administration > Security > Users**.
- Step 2** Click the **Create** button and the window shown in [Figure 9-4](#), “**Create/Copy/Edit Users Window**,” appears.

**Figure 9-4** Create/Copy/Edit Users Window

Security	
User ID :	<input type="text"/>
Password :	<input type="password"/>
Verify Password :	<input type="password"/>
Permissions for Others:	<input checked="" type="checkbox"/> View <input checked="" type="checkbox"/> Edit <input type="checkbox"/> Delete
User Groups:	<input type="text"/> <input type="button" value="Edit"/>
Assigned Roles:	<input type="text"/> <input type="button" value="Edit"/>
Personal Information	
Full Name :	<input type="text"/> <input type="text"/> <input type="text"/>
Work Phone:	<input type="text"/>
Mobile Phone:	<input type="text"/>
Pager:	<input type="text"/>
Email:	<input type="text"/>
Location:	<input type="text"/>
Supervisor Information:	<input type="text"/>
User Preferences	
Language:	English <input type="button" value="v"/>
Rows per page:	10 <input type="button" value="v"/>
Logging Level:	Warning <input type="button" value="v"/>
Initial Screen:	Home <input type="button" value="v"/>
<input type="button" value="Save"/> <input type="button" value="Cancel"/>	

116 080

**Step 3** Enter information in the **Security** section, as follows:

- **User ID** (required) Enter a User ID for this new user.
- **Password** (required) New password to replace any existing password
- **Verify Password** (required) Confirm by re-entering the selected password
- **Permission for Others** Select each of the associated check boxes for the permission that the user (to be created) wants to give to other users. The user who creates the object is the owner of the objects. The creator can allow or disallow other users to **View**, **Edit**, and/or **Delete** the objects owned by the creator by defining permissions. This is the last line of defense. For UserA to delete an object X that UserB created, UserA must first have Delete permission for object X, then UserB's settings for permissions for others is checked, to finally decide whether UserA can delete object X. Permission for others can be enabled or disabled by setting the property: repository.rbac.checkCreatorPermissionEnabled. After you make a change, you must restart the WatchDog by entering **stopwd** followed by **startwd**. For more WatchDog details, see [Chapter 2, "WatchDog Commands"](#).

- **User Groups** Click **Edit** and you receive a list of the groups. Add this user to a user group(s). The user inherits all the roles assigned to the group(s). You can filter this list. From the selected groups, select the check box next to each group to which you want to add this user. Then click **OK**. You can repeat this procedure if you want to change your selection.

A user's group membership can also be changed in the group editor (see the [“Edit” section on page 9-8](#)).

- **Assigned Roles** Click **Edit** and you receive a list of the roles. You can filter this list. From the selected roles, select the check box next to each role to which you want to assign this user. Then click **OK**. You can repeat this procedure if you want to change your selection.

The user inherits all the privileges from the groups in which it participates and from the roles assigned to it. That is, the permissions received by the user is an OR result of the permissions in each role.

**Step 4** Enter information in the **Personal Information** section, as follows:

- **Full Name** (required) Click the drop-down list and select a title; enter the first name; and then enter the last name.
- **Work Phone** (optional) Enter the work phone number.
- **Mobile Phone** (optional) Enter the user's cell phone or mobile phone number.
- **Pager** (optional) Enter the user's pager number.
- **Email** (optional) Enter the user's e-mail address.
- **Location** (optional) Enter the user's location.
- **Supervisor Information** (optional) Enter information about the supervisor.

**Step 5** Enter information in the User Preferences section, as follows:

- **Language** (optional) Click the drop-down list to select a language (at this time only English is supported).
- **Rows per page** (optional) This defines the number of rows per page for object listing. The default is **10**. The choices are: **5, 10, 20, 30, 40, 50, 100, 500, 1000, and 2500**.
- **Logging Level** (optional) The default is **Warning**. The choices are: **Off, Severe, Warning, Config, Info, Fine, Finer, Finest, and All** (see all levels of logs). This defines the logging level for viewing logging events. The list progresses from the least number of messages to the most number of messages.
- **Initial Screen** (optional) The default is **Home**. The choices are: **Home, Service Inventory, Service Design, Monitoring, Administration, Site Index, and Diagnostics**. This is a way to specify the first window you will see after logging in.

**Step 6** Click **Save**. [Figure 9-3](#) reappears with the new user listed.

---

## Copy

The **Copy** button, located at the bottom of [Figure 9-3](#), provides a convenient way to create a new User by copying the information for an existing User including User Groups, Assigned Roles, and User Preferences. Follow these steps:


**Step 1** Navigate **Administration > Security > Users**.

**Step 2** Select one check box for the existing User you want to copy and edit to create a new User.

- Step 3** Click the **Copy** button and the window shown in [Figure 9-4](#), “Create/Copy/Edit Users Window,” appears.
  - Step 4** Required entries are a **User ID**, **Password**, **Verify Password**, and **Full Name**.
  - Step 5** Make all the other changes you want by following the instructions in the “Create” section on [page 9-3](#).
  - Step 6** Click **Save** and you will return to [Figure 9-3](#). The newly created **User** is added to the list and a Status Succeeded message appears in green.
- 

## Edit

The **Edit** button, located at the bottom of [Figure 9-3](#), allows a user with the required privileges to edit user-specific information. Follow these steps:

- Step 1** Navigate **Administration > Security > Users**.
  - Step 2** Select the check box for the row of the user you want to edit.
  - Step 3** Click the **Edit** button and a window as shown in [Figure 9-4](#), “Create/Copy/Edit Users Window,” appears.
- 
- 

**Note**

To change your password without the SysAdmin or UserAdmin privileges, click the **Account** tab on the top of the Home page. This allows the user to edit the user profile, including changing the password.
- 
- Step 4** Enter the desired information for the user profile, as specified in [Step 3](#) of the “Create” section on [page 9-3](#).
  - Step 5** Click **Save**. [Figure 9-3](#) reappears with the edited user listed.
- 

## Delete

The **Delete** button, located at the bottom of [Figure 9-3](#), allows a user with the required privileges to delete user-specific information. Follow these steps:

- Step 1** Navigate **Administration > Security > Users**.
- Step 2** Select the check box(es) for the row(s) of the user(s) you want to delete.
- Step 3** Click the **Delete** button and a window as shown in [Figure 9-5](#), “Users Confirm Delete” appears.



**Figure 9-5** Users Confirm Delete

Confirm Delete		
Showing 1 - 1 of 1 record		
#	User ID	Full Name
1.	new1	Jane Doe

Rows per page: 10    Go to page: 1 of 1    Go

Delete    Cancel

149047

- Step 4** Click **Delete** to continue with the process of deleting information for the specified user(s). Otherwise click **Cancel**.
- Step 5** [Figure 9-3](#), “[Users Window](#),” reappears. If this was successful, the newly updated information appears and a **Status** box appears in the lower left corner of the window with a green check mark for **Succeeded**.

## User Groups

A user group is a logical grouping of users with common privileges. The **User Groups** feature is used to create, edit, or delete user groups.

To access the User Groups window, navigate **Administration > Security > User Groups** and follow these steps:

- Step 1** The window in [Figure 9-6](#), “[User Groups Window](#)” appears.

**Figure 9-6** User Groups Window

Show groups with Name matching    Find

Showing 0 of 0 records

#	Name	Description
---	------	-------------

Rows per page: 10    Go to page: 1 of 1    Go

Create    Edit    Delete

149048

- Step 2** The explanations of the remainder of the buttons is given as follows:
- [Create, page 9-8](#) Create a new user group
  - [Edit, page 9-8](#) Edit selected user group
  - [Delete, page 9-9](#) Delete selected user group(s)

## Create

The **Create** button, located at the bottom of [Figure 9-6](#), allows a user with the required privileges to create a user group. Follow these steps:

- 
- Step 1** Navigate **Administration > Security > User Groups**.
- Step 2** Click the **Create** button and the window shown in [Figure 9-7](#), “Create/Edit User Groups Window,” appears.

**Figure 9-7** Create/Edit User Groups Window

- Step 3** Enter information for the user group profile, as follows:
- **Name** (required) Enter a name for the new user group.
  - **Description** (optional) Enter a description of this new user group.
  - **Roles** This allows you to assign roles to this user group. Click **Edit** and you receive a list of the roles. You can filter this list. From the selected roles, select the check box next to each role you want to attach to this user group. Then click **OK**. You can repeat this procedure if you want to change your selection.
  - **Users** This allows you to add users to this user group. Click **Edit** and you receive a list of the users. You can filter this list. From the selected users, select the check box next to each user you want to attach to this user group. Then click **OK**. You can repeat this procedure if you want to change your selection.
- Step 4** Click **Save**. [Figure 9-6](#) reappears with the new user group listed.
- 

## Edit

The **Edit** button, located at the bottom of [Figure 9-6](#), allows a user with the required privileges to edit user group-specific information. Follow these steps:

- 
- Step 1** Navigate **Administration > Security > User Groups**.
- Step 2** Select the check box for the row of the user group you want to edit.

- Step 3** Click the **Edit** button and a window as shown in [Figure 9-7](#), “Create/Edit User Groups Window,” appears.
- Step 4** Enter the desired information for the user group profile, as specified in [Step 3](#) of the “Create” section on [page 9-8](#).
- Step 5** Click **Save**. [Figure 9-6](#) reappears with the edited user group list.

## Delete

The **Delete** button, located at the bottom of [Figure 9-6](#), allows a user with the required privileges to delete user group-specific information. Follow these steps:

- Step 1** Navigate **Administration > Security > User Groups**.
- Step 2** Select the check box(es) for the row(s) of the user group(s) you want to delete.
- Step 3** Click the **Delete** button and a window as shown in [Figure 9-8](#), “User Groups Confirm Delete,” appears.

**Figure 9-8 User Groups Confirm Delete**

#	Name	Description
1.	newgroup1	

Showing 1 - 1 of 1 record

Rows per page: 10 Go to page: 1 of 1 Go

Delete Cancel

- Step 4** Click **Delete** to continue the process of deleting information for the specified user group(s). Otherwise click **Cancel**.
- Step 5** [Figure 9-6](#), “User Groups Window,” reappears. If this was successful, the newly updated information appears and a **Status** box appears in the lower left corner of the window with a green check mark for **Succeeded**.

## User Roles

A user role is a predefined or a user-specified role defining a set of permissions. The **User Roles** feature is used to create, edit, or delete user roles.

To better understand the way roles are managed, certain specific characteristics of roles are defined as follows:

- **Parent Role** All permission of the parent roles are inherited by the role that is being created or edited (child role). A child role always has the same or more privileges than its parent role.

- **Customer** If a role is associated with a customer, a user of this role does not have access to the objects associated with other customers. Object types that are constrained by customer view are: Persistent Task, Customer Site, VPN, CPE, SR, Policy, Service Order, and resource pools that are associated with a Customer, Customer Site, or VPN.
- **Provider** If a role is associated with a provider, a user of this role does not have access to the objects associated with other providers. Object types that are constrained by provider view are: Persistent Task, Access Domain, Region, PE, Policy, and some resource pools that are associated with a provider, Access Domain, Region, or PE.

Customer view and provider view within a role have no effect on those objects that do not belong to either a customer or a provider. Those object types are: task, probe, workflow, device, ISC host, and template.

Permission operation types in a Role editor, namely View, Create, Edit, and Delete mean View, Create, Modify, and Delete a database object. For example, SR modification (or subsumption) is viewed as Role Based Access Control (RBAC) Creation. SR purge is viewed as RBAC Delete.

A Role can be enabled to be associated with Object Group(s). When Object Group association is enabled, a Role can no longer be associated with a Customer or a Provider, and it cannot have a Parent Role. Resources are limited to PE, CPE, and Named Physical Circuit only. PE and CPE permission implies Device Permission.



#### Note

A global policy, the one that is not associated with any customer or provider, is accessible by both customer-view roles and provider-view roles.

Separate provider-view from customer-view roles when defining a role. When a role is associated with a provider, choose only the resources for which an access scope can be constrained by a provider view. Do the same for a customer-view role.

To access the User Roles window, navigate **Administration > Security > User Roles** and follow these steps:

- Step 1** The window in [Figure 9-9](#), “[User Roles Window](#),” appears.

**Figure 9-9** User Roles Window

**User Roles**

View roles with  matching

Showing 1 - 16 of 16 records

#	<input type="checkbox"/>	Name	Description
1.	<input type="checkbox"/>	CollectionRole	ISC predefined role. It has the permission to run collection on devices.
2.	<input type="checkbox"/>	DeviceImportRole	ISC predefined role. It has the permission to import devices.
3.	<input type="checkbox"/>	DiscoveryRole	ISC predefined role. It has the permission to manage Inventory and deploy Discovery Request.
4.	<input type="checkbox"/>	L2VPNRole	ISC predefined role. It has the permission to manage Inventory and deploy L2VPN Service Request.
5.	<input type="checkbox"/>	L2VPNServiceOpRole	ISC predefined role. It has the permission to deploy L2VPN Service Request.
6.	<input type="checkbox"/>	MPLSRole	ISC predefined role. It has the permission to manage Inventory and deploy MPLS Service Request.
7.	<input type="checkbox"/>	MPLSServiceOpRole	ISC predefined role. It has the permission to deploy MPLS Service Request.
8.	<input type="checkbox"/>	MplsDiagnosticsRole	ISC predefined role. It has the permission to perform MPLS Diagnostics Expert operations.
9.	<input type="checkbox"/>	QoSRole	ISC predefined role. It has the permission to manage Inventory and deploy QoS Service Request.
10.	<input type="checkbox"/>	QoSServiceOpRole	ISC predefined role. It has the permission to deploy QoS Service Request.
11.	<input type="checkbox"/>	SysAdminRole	ISC predefined role. It has full permission.
12.	<input type="checkbox"/>	TERole	ISC predefined role. It has the permission to manage Inventory and deploy TE Service Request.
13.	<input type="checkbox"/>	TEServiceOpRole	ISC predefined role. It has the permission to deploy TE Admission Service Request.
14.	<input type="checkbox"/>	UserAdminRole	ISC predefined role. It has full permission to manage User, Group and Role.
15.	<input type="checkbox"/>	VPLSRole	ISC predefined role. It has the permission to manage Inventory and deploy VPLS Service Request.
16.	<input type="checkbox"/>	VPLSServiceOpRole	ISC predefined role. It has the permission to deploy VPLS Service Request.

Rows per page:  Go to page:  of 1

149050

The predefined roles shown in [Figure 9-9](#) are provided with associated permissions that cannot be edited or deleted. They are intended to cover most of the needed use cases to facilitate a rapid assignment of roles to users and groups with minimum manual configuration. They can also be used as examples to create new roles.

**Step 2** The explanations of the buttons is as follows:

- [Create, page 9-11](#) Create a new user role
- [Copy, page 9-15](#) Copy selected user role
- [Edit, page 9-15](#) Edit selected user role
- [Delete, page 9-16](#) Delete selected user role(s)

## Create

The **Create** button, located at the bottom of [Figure 9-9](#), allows a user with the required privileges to create a new user role. Follow these steps:

**Step 1** Navigate **Administration > Security > User Roles**.

- Step 2** Click the **Create** button and a window comprised of [Figure 9-10](#), “Create/Copy/Edit User Roles Window (Top),” and [Figure 9-11](#), “Create/Copy/Edit User Roles Window (Bottom),” appears.

**Figure 9-10** Create/Copy/Edit User Roles Window (Top)

Name :	<input type="text"/>	
Enable Object Group Association:	<input type="checkbox"/>	
Parent Role:		<input type="button" value="Edit"/>
Customer:		<input type="button" value="Edit"/>
Provider:		<input type="button" value="Edit"/>
Object Groups:		<input type="button" value="Edit"/>
Description:	<input type="text"/>	
Users:		<input type="button" value="Edit"/>
User Groups:		<input type="button" value="Edit"/>

116.070

**Figure 9-11 Create/Copy/Edit User Roles Window (Bottom)**

Resource	All	Create	View	Modify	Delete
Persistent Task	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
SAA Probe	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Workflow	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Device	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
ISC Host	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Customer	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Provider	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
PE	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
CPE	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
QoS Policy	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
QoS Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
MPLS Policy	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
MPLS Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
L2VPN (P2P) Policy	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
L2VPN Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Firewall Policy	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Firewall Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
NAT Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
IPsec Policy	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
IPsec Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Deployment Flow	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Template	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
TE Provider	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
TE Router	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
TE Tunnel Policy	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
TE Tunnel & Resource Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
TE Traffic Admission Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
VPLS Policy	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
VPLS Service Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Service Order	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Object Group	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Named Physical Circuit	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
MPLS Diagnostics Expert	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
MPLS Diagnostics Expert Console Access	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
Discovery Request	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
					<input type="button" value="Save"/> <input type="button" value="Cancel"/>

149051

**Step 3** Enter the following information in [Figure 9-10](#):

- **Name** (required) Enter the name of this new user role.

- **Enable Object Group Association** The default is that this check box is deselected. In this case, **Parent Role**, **Customer**, and **Provider** are enabled and **Object Groups** is not enabled. [Figure 9-11](#) is complete as shown. If you select this check box, **Parent Role**, **Customer**, and **Provider** are not enabled and **Object Groups** is enabled. [Figure 9-11](#) is reduced to just **PE**, **CPE**, and **Named Physical Circuit**.
- **Parent Role** (optional) Click **Edit** and a list of the existing roles appears, similar to [Figure 9-9](#), from which you can click the radio button for the parent role you choose. Then click **Select**. You can repeat this procedure if you want to change your selection. Click the **Clear** button if you want no parent selection.
- **Customer** (optional) Click **Edit** and a list of the existing customers appears. You can filter this list. From the selected customers, click the radio button for the customer you want to select to own this role. Then click **Select**. You can repeat this procedure if you want to change your selection. Click the **Clear** button if you want no customer selection.

**Note**

A customer can only be associated with a logical device, such as **CPE** and **PE**. This is not possible with a physical device, such as **device**.

- **Provider** (optional) Click **Edit** and a list of the existing providers appears. You can filter this list. From the selected providers, click the radio button for the provider you want to select to own this role. Then click **Select**. You can repeat this procedure if you want to change your selection. Click the **Clear** button if you want no provider selection.
- **Object Groups** (optional) Click **Edit** and a list of the existing object groups appears. You can filter this list. From the selected object groups, select the check box(es) for the object group(s) you want to associate with this User Role. Then click **OK**. You can repeat this procedure if you want to change your selection. Deselect the **Enable Object Group Association** button if you want no object group selection.
- **Description** (optional) Enter the descriptive information about permissions in this field, as shown in the Description column of [Figure 9-9](#).
- **Users** (optional) Click **Edit** and a list of the existing users appears. You can filter this list. From the selected users, select the check box(es) for the user(s) you want assigned to this role. Then click **OK**. You can repeat this procedure if you want to change your selection.

**Note**

A user who is associated with a specific role cannot see objects associated with other customers or with other providers.

- **User Groups** (optional) Click **Edit** and a list of the existing user groups appears. You can filter this list. From the selected user groups, select the check box(es) for the user group(s) you want assigned to this role. Then click **OK**. You can repeat this procedure if you want to change your selection.

**Step 4**

In [Figure 9-11](#), click any combination of the following permissions: **Create**; **View**; **Modify**; **Delete**. If you want all the permissions, click **All**.

**Note**

**ISC Host** refers to **Administration > Control Center**. Here, you can view host details, perform configuration tasks, start and stop servers, activate a watchdog, and so on.



**Note**

**SAA Probe** is intended for management of SLA under **Monitoring > SLA**. Any user who wants to generate SLA reports *must* have **View** permission on **ISC Host** in addition to **View** permission on **SAA Probe**.

**Note**

The **Workflow** object is currently not used.

**Step 5** Click **Save**. [Figure 9-9](#) reappears with the new user role listed.

## Copy

The **Copy** button, located at the bottom of [Figure 9-9](#), provides a convenient way to copy the information from an existing User Role and edit it to create a new User Role. Follow these steps:

**Note**

All fields in the existing role are copied to the new role, even including Users and User Groups. You should edit the new role *carefully* to reflect your intention.

- Step 1** Navigate **Administration > Security > User Roles**.
- Step 2** Select one check box for the existing User Role you want to copy and edit to create a new User Role.
- Step 3** Click the **Copy** button and the window comprised of [Figure 9-10](#), “Create/Copy/Edit User Roles Window (Top),” and [Figure 9-11](#), “Create/Copy/Edit User Roles Window (Bottom)” appears.
- Step 4** The required entry is a **Name**. A default name is given, **Copy of** and the name of the original User Role. You cannot duplicate a **Name**.
- Step 5** Make all the other changes you want by following the instructions in the “Create” section on page 9-11.
- Step 6** Click **Save** and you will return to [Figure 9-9](#). The newly created **User** is added to the list and a Status Succeeded message appears in green.

## Edit

The **Edit** button, located at the bottom of [Figure 9-9](#), allows a user with the required privileges to edit user role-specific information. Follow these steps:

- Step 1** Navigate **Administration > Security > User Roles**.
- Step 2** Select the check box for the row of the user role you want to edit.
- Step 3** Click the **Edit** button and a window appears combining [Figure 9-10](#) and [Figure 9-11](#) for this user role.
- Step 4** Enter the desired information for the user role profile, as specified in [Step 3](#) and [Step 4](#) of the “Create” section on page 9-11.
- Step 5** Click **Save**. [Figure 9-9](#) reappears with the edited user roles listed.

## Delete

The **Delete** button, located at the bottom of [Figure 9-9](#), allows a user with the required privileges to delete user role-specific information. Follow these steps:

- Step 1** Navigate **Administration > Security > User Roles**.
- Step 2** Select the check box(es) for the row(s) of the user role(s) you want to delete.
- Step 3** Click the **Delete** button and a window as shown in [Figure 9-12](#), “**User Roles Confirm Delete**,” appears.

**Figure 9-12** *User Roles Confirm Delete*

Confirm Delete		
Showing 1 - 1 of 1 record		
#	Name	Description
1.	newrole1	Copy of ISC predefined role. It has the permission to manage Inventory and deploy L2VPN Service Request.

Rows per page: 20

Go to page: 1 of 1

Delete Cancel

149052

- Step 4** Click **Delete** to continue with the process of deleting information for the specified user role(s). Otherwise click **Cancel**.
- Step 5** [Figure 9-9](#), “**User Roles Window**,” reappears. If this was successful, the newly updated information appears and a Status box appears in the lower left corner of the window with a green check mark for **Succeeded**.

## Object Groups

An Object Group is a named aggregate entity comprised of a set of objects. The object types can be PE, CE, Named Physical Circuit (NPC), and interfaces of PEs or CEs. An Object Group provides instance level of access granularity for users.

An Object Group can be associated with different roles. A role can be associated with an Object Group or it can be associated with a grouping of Customer and Provider, but it cannot be associated with both of these. The association with a grouping of Customer and Provider is either with Customer(s), with Provider(s), or with Customer(s) and Provider(s). When a role is associated with Object Group(s), you can only define permissions for PE, CE, and NPC. Permissions on interfaces is implied PEs or CEs, that is, PE Create or CE Create implies Interface Create. PE or CE Edit implies Interface Create, Edit, or Delete. CE or PE Delete implies Interface Delete.

When instance level of access is desired for PE, CE, NPC, or interface of PEs and CEs, you can usually define a role associated with Object Group(s) that contains a collection of PEs and CEs you are limited to operate. Then define other roles to include permissions on other types of objects. See the “[User Roles Design Example](#)” section on page 9-20.

If an Object Group contains PEs (or CEs) only, with no explicit interface as a group member, you can access all interfaces of grouped PEs or CEs. If an Object Group contains any explicit interface as group members, every single interface that you want to access you must manually choose to include as group members.

**Note**

Permissions are the union of all roles that you occupy. If your intention is to limit access to a scope of devices or Named Physical Circuits (NPCs), define a role to be associated with Object Group(s), Device, CE, PE, and NPC.

To access the Object Groups window, navigate **Administration > Security > Object Groups** and follow these steps:

**Step 1** The window in [Figure 9-13](#), “Object Groups Window,” appears.

**Figure 9-13** Object Groups Window

**Step 2** The explanations of the buttons is as follows:

- [Create, page 9-11](#) Create a new object group
- [Edit, page 9-15](#) Edit a selected object group
- [Delete, page 9-16](#) Delete selected object group(s)

## Create

The **Create** button, located at the bottom of [Figure 9-13](#), allows a user with the required privileges to create a new object group. Follow these steps:

**Step 1** Navigate **Administration > Security > Object Groups**.

**Step 2** Click the **Create** button and the window [Figure 9-14](#), “Create/Edit Object Group Window,” appears.

**Figure 9-14** Create/Edit Object Group Window

Name \* :

Description:

PE Group Members:

#	Name	Interface Members
Rows per page: 10   Go to page: 1 of 1   Go		

CE Group Members:

#	Name	Interface Members
Rows per page: 10   Go to page: 1 of 1   Go		

NPC Group Members:

#	Name
Rows per page: 10   Go to page: 1 of 1   Go	

Save Cancel

Note: \* - Required Field

**Step 3** Enter the following information in [Figure 9-14](#):

- **Name** (required) Enter the name of this new object group.
- **Description** (optional) Enter a description of this new object group.
- **PE Group Members** (optional) Click **Edit** and a list of the existing PEs appears. You can filter this list. From the selected PEs, select the check box(es) for the PE(s) you want to include in this group. Then click **OK**. You can repeat this procedure if you want to change your selection(s). The **Interface Members** column will be empty. All existing interfaces for each of the PE Groups in the **Name** column will default to be members of the group unless you select only a subset. To limit the interfaces and select a subset of interfaces, click a PE Group in the **Name** column. You receive a list of all the interfaces for that PE from which you can individually select only the interfaces you want to associate with that PE Group. Then click **OK**. You return to [Figure 9-14](#), “Create/Edit Object Group Window,” and the **Name** and selected **Interface Members** for each PE Group Member appear. If no entries exist in the **Interface Members** column for both **PE Group Members** and **CE Group Members**, the default is all existing interfaces for both (if any exist).
- **CE Group Members** (optional) Click **Edit** and a list of the existing CEs appears. You can filter this list. From the selected CEs, select the check box(es) for the CE(s) you want to include in this group. Then click **OK**. You can repeat this procedure if you want to change your selection(s). The **Interface Members** column is empty. All existing interfaces for each of the CE Groups in the **Name** column default to be members of the group unless you select only a subset. To limit the interfaces and select a subset of interfaces, click a CE Group in the **Name** column. You receive a list of all the interfaces for that CE from which you can individually select only the interfaces you want to associate with that CE Group. Then click **OK**. You return to [Figure 9-14](#), “Create/Edit Object Group Window,” and the **Name**, and selected **Interface Members** for each CE Group Member appear. If no entries exist in the **Interface Members** column for both **CE Group Members** and **PE Group Members**, the default is all existing interfaces for both (if any exist).

- **NPC Group Members** (optional) Click **Edit** and a list of the existing NPCs appears. You can filter this list. From the selected NPCs, select the check box(es) for the NPC(s) you want to select to own this role. Then click **OK**. You can repeat this procedure if you want to change your selection(s). You return to [Figure 9-14](#), “Create/Edit Object Group Window,” and the **Name** for each NPC Group Member appears.

**Step 4** Click **Save**. [Figure 9-14](#) reappears with the new object group listed.

## Edit

The **Edit** button, located at the bottom of [Figure 9-14](#), allows a user with the required privileges to edit object group-specific information. Follow these steps:

- Step 1** Navigate **Administration > Security > Object Groups**.
- Step 2** Select the check box for the row of the object group you want to edit.
- Step 3** Click the **Edit** button and a window appears as shown in [Figure 9-14](#), with the object group chosen specified in the **Name** field.
- Step 4** Enter the desired information for the object group, as specified in [Step 3](#) of the “Create” section on [page 9-17](#).
- Step 5** Click **Save**. [Figure 9-14](#) reappears with the edited object groups listed.

## Delete

The **Delete** button, located at the bottom of [Figure 9-14](#), allows a user with the required privileges to delete object group-specific information. Follow these steps:

- Step 1** Navigate **Administration > Security > Object Groups**.
- Step 2** Select the check box(es) for the row(s) of the object group(s) you want to delete.
- Step 3** Click the **Delete** button and a window as shown in [Figure 9-15](#), “Delete Object Groups Confirm Delete,” appears.

**Figure 9-15** Delete Object Groups Confirm Delete

Confirm Delete		
Showing 1 - 2 of 2 records		
#	Name	Description
1.	objgp2	
2.	objgp3	

Rows per page: All Go to page: 1 of 1 Go

Delete Cancel

- Step 4** Click **Delete** to continue with the process of deleting information for the specified object group(s). Otherwise click **Cancel**.
- Step 5** [Figure 9-14, “Create/Edit Object Group Window,”](#) reappears. If this was successful, the newly updated information appears and a Status box appears in the lower left corner of the window with a green check mark for **Succeeded**.
- 

## User Roles Design Example

This section gives an example situation, an illustration that shows this setup, and steps on how to setup this design:

- [Example, page 9-20](#)
- [Illustration of Setup, page 9-20](#)
- [Steps to Set Up Example, page 9-22](#)

### Example

This section explains an example data center for which the following sections, [“Illustration of Setup” section on page 9-20](#) and [“Steps to Set Up Example” section on page 9-22](#) give an illustration setup and steps, respectively.

Finance Customer XYZ built an MPLS network to connect its branch offices to its data center. Subsidiaries of XYZ are running different parts of the MPLS network. Each subsidiary uses a different BGP AS domain, which results in different Provider Administrative Domains (PADs) inside ISC.

Each subsidiary acts as a Provider and owns therefore its own Devices, like PE and CE devices, and should also own logical attributes inside ISC, like Regions, Sites, Customers, and VPNs. Therefore, the view of the devices for each subsidiary must be separated into PAD views. Thus, Provider A cannot manipulate or view the configuration files for devices of Provider B. Devices are not shared between PADs.


Inside a PAD, there are Customers with sites and VPNs with only local significance. Also, the IP addressing should be defined per PAD.

But there are also Customers that have sites in different PADs. This means that there is a need for Inter-AS VPNs. The Provider who owns the Customer should also have the right to share this Customer with other Providers. In this case, the VPNs and CERCs should be shared between the providers.

### Illustration of Setup

[Figure 9-16, “Contents in Example,”](#) shows the setup described in the [“Example” section on page 9-20](#).

Figure 9-16 Contents in Example



111821

## Steps to Set Up Example

This section explains the steps to create the example explained in the [“Example” section on page 9-20](#) and shown in the [“Illustration of Setup” section on page 9-20](#).

- 
- Step 1** Create the following Object Groups (see the [“Create” section on page 9-17](#), which is for the section [Object Groups](#)):
- P1PEGroup that has members PE111 and PE112
  - P2PEGroup that has members PE211 and PE212
  - C1CEGroup that has members CE111 and CE121
  - C2CEGroup that has members CE211 and CE221
  - C3CEGroup that has the member CE311
  - C2DeviceGroup that has members PE112, CE211, PE211, and CE221
  - C3DeviceGroup that has members PE212 and CE311.
- Step 2** Create the following User Roles that are associated with one or more groups created in [Step 1](#) (see the [“Create” section on page 9-11](#), which is for the section [User Roles](#)).
- P1DeviceGroupRole, associated with groups P1PEGroup, C1CEGroup, and C2CEGroup, and have the Modify and Delete permissions on for PE and Cpe.
  - P2DeviceGroupRole, associated with groups P2PEGroup, C2CEGroup, and C3CEGroup, and have the Modify and Delete permissions on for PE and Cpe.
  - C1DeviceGroupRole, associated with groups P1PEGroup, C1CEGroup, and have the Modify permission on for PE and the Modify and Delete permissions on for Cpe.
  - C2DeviceGroupRole, associated with group C2DeviceGroup, and have the Modify permission on for PE and the Modify and Delete permissions on for Cpe.
  - C3DeviceGroupRole, associated with group C3DeviceGroup, and have the Modify permission on for PE and the Modify and Delete permissions on for Cpe.
- Step 3** Create the following User Roles that have Customer View or Provider View, as explained in the [“User Roles” section on page 9-9](#).
- P1MplsRole, associated with Provider P1, and have permissions on Provider, Task, ISC Host, Mpls SR, Mpls Policy, NPC, and Probe. (Add Service, Template, and ServiceOrder if needed.)
  - P2MplsRole, associated with Provider P2, and have permissions on Provider, Task, ISC Host, Mpls SR, Mpls Policy, NPC, and Probe. (Add Service, Template, and ServiceOrder if needed.)
  - C1MplsRole, associated with Customer C1, and have permissions on Customer, Task, ISC Host, Mpls SR, Mpls Policy, NPC, and Probe. (Add Service, Template, and ServiceOrder if needed.)
  - C2MplsRole, associated with Customer C2, and have permissions on Customer, Task, ISC Host, Mpls SR, Mpls Policy, NPC, and Probe. (Add Service, Template, and ServiceOrder if needed.)
  - C3MplsRole, associated with Customer C3, and have permissions on Customer, Task, ISC Host, Mpls SR, Mpls Policy, NPC, and Probe. (Add Service, Template, and ServiceOrder if needed.)
- Step 4** Assign the User Roles defined in [Step 2](#) and [Step 3](#) to Users, as explained in the [“Users” section on page 9-2](#).
- User P1 has User Roles: P1DeviceGroupRole, P1MplsRole, C1MplsRole, and C2MplsRole.
  - User P2 has User Roles: P2DeviceGroupRole, P2MplsRole, C2MplsRole, and C3MplsRole.
  - User C1 has User Roles: C1DeviceGroupRole and C1MplsRole.




- User C2 has User Roles: C2DeviceGroupRole and C2MplsRole.
- User C3 has User Roles: C3DeviceGroupRole and C3MplsRole.

## Control Center

This section explains how to view and change the properties in the Dynamic Component Properties Library (DCPL); how to view status information about a host, servers, the WatchDog, and logs; how to remotely install and uninstall a Processing server, Collection server, or Interface server; how to define collection zones; and how to install license keys.

Navigate **Administration > Control Center** and you go to the default page of **Hosts** in the TOC, as shown in [Figure 9-17](#), “**Control Center > Hosts**.”

**Figure 9-17** **Control Center > Hosts**



From **Administration > Control Center**, you have the following three choices in the TOC:

- [Hosts, page 9-23](#) **Hosts** allows you to manage the various servers.
- [Collection Zones, page 9-30](#) **Collection Zones** are the means of associating collection servers with network devices.
- [Licensing, page 9-32](#) **Licensing** is where you install license keys, which is the only way to access services and APIs.

## Hosts

Navigate **Administration > Control Center > Hosts**.

A window as shown in [Figure 9-17](#) appears.



### Note

Only the **Install** and **Logs** buttons are enabled by default when there is no host selected. When one or more hosts are selected by selecting the check box(es), the Install and Logs buttons are disabled and the other buttons are enabled.

Click any of the buttons and proceed as follows:

- [Details, page 9-24](#) Available only when one host system is chosen.
- [Config, page 9-25](#) Available only when one or more host systems are chosen.
- [Servers, page 9-26](#) Available only when one or more host systems are chosen.

- [Watchdog, page 9-27](#) Available only when one or more host systems are chosen.
- [Install, page 9-28](#) Available only when no host system selections are made.
- [Uninstall, page 9-29](#) Available only when one host system is chosen.
- [Logs, page 9-29](#) Available only when no host system selections are made.

## Details

For details about a chosen host, follow these steps:

- Step 1** Choose a host by selecting the check box to the left of the host name and then click the **Details** button.
- Step 2** You receive a window as shown in [Figure 9-18, “Host Details.”](#) This shows the details about the chosen host.

**Figure 9-18 Host Details**

Host Details

Host: efgh-ultra10.cisco.com	
<b>General</b>	
Active:	Yes
Image:	isc3.0-20030406.00.Q
Registered Date:	May 21 03:29:10 PDT
UnRegistered Date:	
Install Location:	/disk2/opt/iscadm/isc3
Install Time:	2003-03-19 16:59:07.
<b>Locations</b>	
Server Logs:	/disk2/opt/iscadm/isc3
Task Logs:	/disk2/opt/iscadm/isc3
Temporary:	/disk2/opt/iscadm/isc3
<b>Disk Stats</b>	
Path:	/disk2/opt/iscadm/isc3
Total Disk Space:	19146 MB
Free Disk Space:	12810 MB; 66% Free
Path:	/disk2/opt/iscadm/isc3
Total Disk Space:	19146 MB
Free Disk Space:	12810 MB; 66% Free
<b>Health Stats</b>	
Last Heartbeat:	
Last Heartbeat Status:	
Last Heartbeat Duration:	
<b>Collection Zones</b>	
<input type="text"/>	
<input type="button" value="OK"/>	

- Step 3** Click **OK** and you return to [Figure 9-17](#).

## Config


To view or change the Dynamic Component Properties Library (DCPL) properties, which replaces the csm.properties file for VPNSC, follow these steps:


**Note**


csm.properties in VPNSC cannot be migrated to DCPL settings in ISC.

- Step 1** From [Figure 9-17 on page 9-23](#), select a check box next to a host name for which you want to know the existing properties and then click the **Config** button.
- Step 2** A window as shown in [Figure 9-19, “Properties,”](#) appears. It is a list of all the folders with all the properties. See [Appendix C, “Property Settings”](#) for a list of all the properties with explanations, defaults, and ranges/rules. If you don’t know the property name, you can use a key word and do a Find on the pdf version of this appendix.

**Figure 9-19 Properties**



- Step 3** Click the + sign to expand each folder. The result could be more subfolders and the final level is the property name.
- Step 4** Position the mouse over the folder or property name and you see a description.
- Step 5** Click on an entry to get details and instructions on how to change the value, as shown in the example in [Figure 9-20, “Properties Detail Example.”](#)

**Figure 9-20 Properties Detail Example**

- Step 6** For each property that can be modified, you can modify the value and click **Set Property**. If when making your modifications, you want to return to the previous settings, click **Reset Property**.
- Step 7** After making all the changes you choose in each of the specific properties, you can click **Create Version** to create a new version of these properties. This feature gives you the option of saving multiple property sets for future use.
- Step 8** To view the values of previous versions of property sets, click the drop-down list in **Version** and select any version you choose.
- Step 9** When you click **Set to Latest** after selecting a version in [Step 8](#), this version is dated as the most current.
- Step 10** To return, click to the navigation path you want to use next.

## Servers

To view the status information about the servers, follow these steps:

- Step 1** From [Figure 9-17 on page 9-23](#), select a check box next to a host name for which you want to know the server statistics and then click the **Servers** button.
- Step 2** A window as shown in [Figure 9-21](#), “**Servers**,” appears.

**Figure 9-21 Servers**

#	<input type="checkbox"/>	Name	State	Generation	Start Time	PID	Successful Heartbeats	Missed Heartbeats
1.	<input type="checkbox"/>	worker	started	1	Oct 27 04:20:03 PM PDT	23146	15994	0
2.	<input type="checkbox"/>	dispatcher	started	2	Oct 27 04:24:16 PM PDT	23166	16136	0
3.	<input type="checkbox"/>	discovery	started	1	Oct 27 04:20:04 PM PDT	23150	16080	0
4.	<input type="checkbox"/>	lockmanager	started	1	Oct 27 04:20:03 PM PDT	23147	16181	0
5.	<input type="checkbox"/>	nspoller	started	1	Oct 27 04:19:58 PM PDT	0	15964	0
6.	<input type="checkbox"/>	scheduler	started	1	Oct 27 04:22:21 PM PDT	23165	16212	0
7.	<input type="checkbox"/>	httpd	started	2	Oct 27 04:24:19 PM PDT	23167	16173	0
8.	<input type="checkbox"/>	dbpoller	started	1	Oct 27 04:19:58 PM PDT	0	16000	0
9.	<input type="checkbox"/>	cnsserver	started	1	Oct 27 04:20:04 PM PDT	23151	16225	0

Showing 1 - 9 of 9 records

Rows per page: 10 Go to page: 1 of 1 Go

Start Stop Restart Logs OK

- Step 3** Select any one check box next to the server you want to address and you have access to **Start**, **Stop**, **Restart**, and **Logs**. When you click on a specific server name or the Logs button, you get a list of server logs. If you then click on the log name for which you want details, the log viewer appears. You can filter this information in the log viewer. After you complete the task of your choice, you return to [Figure 9-21](#).
- Step 4** You can click a different server and click the button for the process of your choice. Or you can unclick the server choice and click **OK**.
- Step 5** After you click **OK** in [Figure 9-21](#), you return to [Figure 9-17 on page 9-23](#).

## Watchdog

To view the log information about WatchDog, follow these steps:

- Step 1** From [Figure 9-17 on page 9-23](#), select a check box next to a host name for which you want to know the WatchDog logs and then click the **Watchdog** button.
- Step 2** A window as shown in [Figure 9-22](#), “**WatchDog Logs**,” appears.

**Figure 9-22 WatchDog Logs**

Name	Size	Last Modified
watchdog.0	300721	Thursday, October 27, 2005 4:26:26 PM PDT

OK

- Step 3** Click on a specific WatchDog log name in the **Name** column to get the contents of that log. You can filter the information in this log. Click **OK** to return to [Figure 9-22](#).
- Step 4** You can repeat the process in [Step 3](#) or click **OK** to return to [Figure 9-17 on page 9-23](#).

## Install

To remotely install the **Processing Server**, **Collection Server**, or **Interface Server**, follow these steps:



### Note

Telnet and ftp *must* be available on both the Master and remote server.



### Note

In this remote install, you *must* accept the default values, similar to the **express** install. If you want to do a **custom** install, it is only available through the installation procedure explained in the “Installing ISC” section of Chapter 2 of *Cisco IP Solution Center Installation Guide, 4.1*

- Step 1** From [Figure 9-17 on page 9-23](#), be sure that no check boxes are selected and then click the **Install** button.
- Step 2** A window as shown in [Figure 9-23](#), “Install ISC Host,” appears.

**Figure 9-23** *Install ISC Host*

- Step 3** Provide the following information in [Figure 9-23](#).
- **Device Host Name** (required)
  - **ISC User** (required) This same user *must* be created on the remote server.



### Note

Be sure you have 1 GB of disk space available in the ISC User’s home directory.

- **ISC User Password** (required)
- **Role** Accept the default of **Process Server** or click the drop-down list and choose the **Collection Server** or **Interface Server** option.

- **Install Location** (required)
- **Root Password** (optional) To auto start ISC on a remote server, the root password is required.

**Step 4** Click the **Install** button.

**Step 5** The result is an Install Log.

## Uninstall

To remotely uninstall the Processing Server, Collection Server, or Interface Server, follow these steps:

**Step 1** From [Figure 9-17 on page 9-23](#), select a check box next to a hostname for which you want to uninstall and then click the **Uninstall** button.

**Step 2** A window as shown in [Figure 9-24](#), “Remote Uninstall,” appears.

**Figure 9-24 Remote Uninstall**

ISC User :

ISC User Password :

**Step 3** Provide the following information in [Figure 9-24](#).

- **ISC User** (required)
- **ISC User Password** (required)

**Step 4** Click the **Uninstall** button.

**Step 5** The result is an Uninstall Log.

## Logs

To view install and uninstall logs for the Master and remotely installed server, follow these steps:

**Step 1** From [Figure 9-17 on page 9-23](#), be sure that no check boxes are selected.

**Step 2** Click the **Logs** drop-down list and select **Install** or **Uninstall**.

**Step 3** The window that appears is the log of installations or uninstallations, dependent on your selection in [Step 2](#).

**Step 4** Click the link in the **Name** column to view the detailed log information.

**Step 5** Click **OK** to return to the window in [Step 3](#).

**Step 6** Click **OK** again to return to [Figure 9-17 on page 9-23](#).

## Collection Zones

Navigate **Administration > Control Center**.


A collection zone is a geographical grouping of devices. Each collection zone is associated with exactly one Collection server that collects data from its devices. However, a Collection server can service multiple collection zones. For example, if you initially create several collection zones and have them all serviced by the Master server, then as the number of devices in each zone grows, you can install additional Collection servers and assign some of the zones to them.

When you install a new Collection server or Processing server, the system creates a new collection zone with the same name as the server. This functionality is for your convenience. You can delete this collection zone if this does not fit your distribution environment setup.

To define collection zones, follow these steps:

- Step 1** From the Control Center, choose **Collection Zones** from the TOC in the left column, and a window as shown in [Figure 9-25](#), “[Choose Control Center > Collection Zones](#)” appears.

**Figure 9-25** Choose Control Center > Collection Zones



- Step 2** To **Create** a collection zone, proceed to [Step 3](#). To **Edit** a collection zone, proceed to [Step 6](#). To **Delete** a collection zone, proceed to [Step 8](#). To display the **Devices**, proceed to [Step 11](#).
- Step 3** From [Figure 9-25](#), without selecting any check boxes, click the **Create** button.
- Step 4** A window as shown in [Figure 9-26](#), “[Create Collection Zone](#),” appears.



**Figure 9-26 Create Collection Zone**

**Create Collection Zone**

Name \* :

Description: Created on Sat Nov 19 00:11:15 PST 2005  
By efgh-ultra.cisco.com

Collection Host: efgh-ultra.cisco.com ▼

Save Cancel

Note: \* - Required Field

149155

Fill in the following information:

- **Name** (required)
- **Description** (optional) This is automatically filled in with the creation statistics: date, time, and creator. You can overwrite this information, add to it, or delete it altogether.
- **Collection Host** (default host appears) Click the drop-down list if you want to select a different collection host.

- Step 5** Click **Save**. [Figure 9-25](#) reappears, the newly created collection zone is added, and a Status appears with a green check mark for **Succeeded**. You can repeat [Step 3](#) to [Step 5](#) to create another collection zone. For **Edit**, proceed to [Step 6](#). For **Delete**, proceed to [Step 8](#). To display the **Devices**, proceed to [Step 11](#).
- Step 6** To edit a collection zone, in [Figure 9-25](#), select the check box for the collection zone you want to edit and then click the **Edit** button.
- Step 7** A window as shown in [Figure 9-26](#) appears. Follow the instructions in [Step 4](#) and [Step 5](#).
- Step 8** To delete a collection zone, in [Figure 9-25](#), select one or more check boxes for the collection zone(s) you want to delete. Then click the **Delete** button.
- Step 9** A Confirm Delete window appears, to give you a chance to click **Cancel** and not delete, or to click **OK** and delete.
- Step 10** [Figure 9-25](#) reappears and the collection zone is removed. You can repeat [Step 8](#) and [Step 9](#) to delete more collection zones, you can proceed to [Step 3](#) to create a collection zone, you can proceed to [Step 6](#) to edit a collection zone, or you can proceed to [Step 11](#) to display and assign devices.
- Step 11** To display, add, or delete devices, in [Figure 9-25](#), select a check box for the desired collection zone. Then click the **Devices** button.
- Step 12** A window appears as shown in [Figure 9-27](#), “[Collection Zone Devices](#).” This window shows the current devices assigned to the selected collection zone.

**Figure 9-27** Collection Zone Devices

Collection Zone Devices

Show Devices with Any matching \*

Showing 1-1 of 1 records

#	<input type="checkbox"/>	Device Name	Collection Zone Name	IP Address	Role	Type
1.	<input type="checkbox"/>	newdevice1	null		CE	IE2100

Rows per page: 10

- Step 13** To add a device, click **Add**; to delete devices, select the devices you want to delete from those shown and click **Delete** (this happens automatically with no chance to reconsider, but you can add it back in with another **Add** process); to accept what is listed, click **OK**; or to cancel, click **Cancel**.
- Step 14** If you click **Add**, you get a window with all the devices in the database. You can filter the list and from the listed choices you can select one or more devices to add to the selected collection zone. Then click **Select**.
- Step 15** [Figure 9-27](#) reappears with the updated device information for the selected collection zone.
- Step 16** When [Figure 9-27](#) has all the devices you want, click **OK** and [Figure 9-25](#) reappears with the updated information.

## Licensing

Navigate **Administration > Control Center**.




### Note

To enable Traffic Engineering Management (TEM), you must install a permanent license file. You must replace the `<install_directory>/thirdparty/parc/installed/data/system.properties` file with the `<distribution_directory>/permLic_system.properties` file. For example:

```
cp permLic_system.properties <install_directory>/thirdparty/parc/installed/data/system.properties
```

To install license keys, follow these steps:

- Step 1** From **Control Center**, choose **Licensing** from the TOC in the left column, as shown in [Figure 9-28](#), “[Choose Control Center > Licensing](#).”

**Figure 9-28** Choose Control Center > Licensing

**Step 2** From the **Installed Licenses** table, click the **Install** button, as shown in Figure 9-29, “**Installed Licenses**.” The Installed Licenses table explains the current statistics. The columns of information tell the **Type** of license keys you have installed (ACTIVATION, API-L2VPN, API-L3MPLS, L2VPN, L3MPLS/VPN, MPLSDIAG, QOS, TE, TE/BRG, TE/RG, VPLS, VPN); the **Size**, which is valid for the **ACTIVATION** (licensed maximum global count of services), **TE** (number of TE-enabled nodes), or the **VPN** (maximum number of VPNs licensed); the **Usage**, which gives the number currently used for the rows; and the **Date Updated**, which reflects the refresh of the license usage (on an hourly basis, by default).

**Note**

When you purchase Traffic Engineering Management (TEM), you automatically receive **TE**, **TE/BRG**, and **TE/RG** licenses and an unlimited VPN license. All of these licenses *must* be installed to use the TEM function. The **TE** license serves as an activation license for the maximum number of TE-enabled nodes to be managed by TEM; the **TE/RG** license enables primary tunnel placement; and the **TE/BRG** license enables the Fast ReRoute (FRR) protection function.

**Note**

Click **Refresh** to give the most current status.

**Figure 9-29** Installed Licenses

Installed Licenses			
Type	Size	Usage	Date Updated
ACTIVATION	25		2005-11-18 23:42
API-L2VPN			2005-11-18 23:42
API-L3MPLS			2005-11-18 23:42
L2VPN			2005-11-18 23:42
L3MPLS/VPN			2005-11-18 23:42
MPLSDIAG			2005-11-18 23:42
QOS			2005-11-18 23:42
TE	25		2005-11-18 23:42
TE/BRG			2005-11-18 23:42
TE/RG			2005-11-18 23:42
VPLS			2005-11-18 23:42
VPN	50	6	2005-11-18 23:42

149156

**Step 3** In the resulting window, as shown in Figure 9-30, “**Enter License Key**,” enter a **License Key** that you received on your *Right to Use* paperwork with your product.

**Figure 9-30** Enter License Key

**Install a License Key**

License Key \* :

Save Cancel

Note: \* - Required Field

- Step 4** Click **Save**. Your newly installed license appears in an updated version of the Installed License table, as shown in [Figure 9-29](#), “Installed Licenses.”
- Step 5** Repeat [Step 2](#), [Step 3](#), and [Step 4](#) for each of the *Right to Use* documents shipped with your product.

**Note**

When you receive multiple *Right to Use* documents to upgrade either the ACTIVATION License, which activates and sets the maximum global count of the services, or VPN licenses, which activates and set the maximum number of VPNs, be sure to enter the licenses in the correct order. For example, if you are upgrading from 500 to 3000 global count of the services and there are two steps to get there, enter the license to upgrade from 500 to 1500 and then the license key to upgrade from 1500 to 3000.

## Active Users

This section explains how to communicate with active users.

Navigate **Administration > Active Users** and follow these steps:

- Step 1** After you navigate **Administration > Active Users**, a window that shows the currently logged users appears, as shown in [Figure 9-31](#), “Active Users.”

**Figure 9-31** Active Users

**Active Users**

Show Active Users with User ID matching \* Find

Showing 1 - 1 of 1 record

#	User ID	Device Host Name	Login Time	Last Access Time
1.	admin	efgh-ultra.cisco.com	8:41:53 PM PST 11/18/05	12:33:52 AM PST 11/19/05

Rows per page: 10 Go to page: 1 of 1 Go

Auto Refresh: ☒ Disconnect

- Step 2** In [Figure 9-31](#), if you have the privileges of **SysAdmin** or **UserAdmin**, you can disconnect one or more users. Select the check box next to each user you want to disconnect. Then click the **Disconnect** button at the bottom of the window.

**Caution**

The current login sessions for the disconnected users are terminated and their work is lost.

- Step 3** To exit this list of all active users, choose another feature from the main product tabs.

## User Access Log

This section shows a detailed report of every activity by every user.

Navigate **Administration > User Access Log** and follow these steps:

- Step 1** After you navigate **Administration > User Access Log**, a window appears as shown in [Figure 9-31](#), “[Active Users](#).”

**Figure 9-32 User Access Log Viewer with Simple Filter**

User Access Log Viewer

Simple Filter

Advanced Filter

Find

Filter By:

Date

Matches:

\*

Showing 1 - 10 of 246 records

#	Date	Time	User Name	Origin Host	Action	Object	Severity	Activity	Message
1.	2005/11/18	23:34:49	backendadm		Logon	User	INFO	SecurityActivity	Login successfully.
2.	2005/11/18	23:30:56	backendadm		Logon	User	INFO	SecurityActivity	Login successfully.
3.	2005/11/18	22:53:43	admin	efgh-ultra.cisco.com	Delete	Role	INFO	SecurityActivity	Role newrole1 (id=265810285) is deleted.
4.	2005/11/18	22:49:15	admin	efgh-ultra.cisco.com	Create	Role	INFO	SecurityActivity	Role newrole1 (id=265810285) is created.
5.	2005/11/18	22:10:38	admin	efgh-ultra.cisco.com	Create	Group	INFO	SecurityActivity	Group newgroup1 (id=1203533294) is created.
6.	2005/11/18	21:46:26	admin	efgh-ultra.cisco.com	Modify	Role	INFO	SecurityActivity	Role SysAdminRole (id=-1234592039) is modified.
7.	2005/11/18	21:46:25	admin	efgh-ultra.cisco.com	Create	User	INFO	SecurityActivity	User new1 (id=1794273524) is created.
8.	2005/11/18	21:45:22	admin	efgh-ultra.cisco.com	Delete	User	INFO	SecurityActivity	User new1 (id=1794273524) is deleted.
9.	2005/11/18	21:44:59	admin	efgh-ultra.cisco.com	Modify	Role	INFO	SecurityActivity	Role SysAdminRole (id=-1234592039) is modified.
10.	2005/11/18	21:44:58	admin	efgh-ultra.cisco.com	Create	User	INFO	SecurityActivity	User new1 (id=1794273524) is created.

Rows per page:

10

Go to page:

1

of 25

Go

149159

All the log information about user actions appears.

**Note**

The types of activities or objects to be logged can be configured. This can be done directly through SQL. By default, security-related activities and activities on objects listed in the Role editor are logged.

- Step 2** The default **Simple Filter** radio button is selected. To filter using the **Simple Filter**, continue with [Step 3](#). To filter using **Advanced Filter**, proceed to [Step 5](#).
- Step 3** To filter the information with **Simple Filter**, keep the **Simple Filter** radio button selected and from **Filter By**, choose: **Date**, **User Name**, **Origin Host**, **Action**, **Severity**, or **Activity** (also column names). For **Matches**, enter the beginning characters of what you want to match followed by \*. Then click **Find**. The result is that only the log information matching the entered filter appears.
- Step 4** To exit this log report, choose another feature from the main product tabs.
- Step 5** To filter the information with **Advanced Filter**, click the **Advanced Filter** radio button. A window as shown in [Figure 9-33](#), “**User Access Log Viewer with Advanced Filter**,” appears.

**Figure 9-33** *User Access Log Viewer with Advanced Filter*

**User Access Log Viewer**

☐ Simple Filter ☒ Advanced Filter Find

Date:  Action:

User Name:  Severity:

Device Host Name:  Activity:

Service Requests Select/Deselect

Showing 1 - 10 of 246 records

#	Date	Time	User Name	Origin Host	Action	Object	Severity	Activity	Message
1.	2005/11/18	23:34:49	backendadm		Logon	User	INFO	SecurityActivity	Login successfully.
2.	2005/11/18	23:30:56	backendadm		Logon	User	INFO	SecurityActivity	Login successfully.
3.	2005/11/18	22:53:43	admin	efgh-ultra.cisco.com	Delete	Role	INFO	SecurityActivity	Role newrole1 (id=265810285) is deleted.
4.	2005/11/18	22:49:15	admin	efgh-ultra.cisco.com	Create	Role	INFO	SecurityActivity	Role newrole1 (id=265810285) is created.
5.	2005/11/18	22:10:38	admin	efgh-ultra.cisco.com	Create	Group	INFO	SecurityActivity	Group newgroup1 (id=1203533294) is created.
6.	2005/11/18	21:46:26	admin	efgh-ultra.cisco.com	Modify	Role	INFO	SecurityActivity	Role SysAdminRole (id=-1234592039) is modified.
7.	2005/11/18	21:46:25	admin	efgh-ultra.cisco.com	Create	User	INFO	SecurityActivity	User new1 (id=1794273524) is created.
8.	2005/11/18	21:45:22	admin	efgh-ultra.cisco.com	Delete	User	INFO	SecurityActivity	User new1 (id=1794273524) is deleted.
9.	2005/11/18	21:44:59	admin	efgh-ultra.cisco.com	Modify	Role	INFO	SecurityActivity	Role SysAdminRole (id=-1234592039) is modified.
10.	2005/11/18	21:44:58	admin	efgh-ultra.cisco.com	Create	User	INFO	SecurityActivity	User new1 (id=1794273524) is created.

Rows per page:  Go to page:  of 25 Go

All the log information about user actions appears.

- Step 6** Enter filter information you want to match in one or more of the following categories and then click **Find**.



**Note**

When you choose multiple filters, the log results that appear are only the ones that match all the specified filter information.

- **Date** Enter the beginning characters of the date you want to view followed by a \*, in the format given in the **Date** column.
- **User Name** Enter the beginning characters of the specific **User Name** you want to view followed by a \*.

- **Device Host Name** Enter the beginning characters of the specific **Host Name** you want to view followed by a \*.
  - **Action** Click the drop-down list and choose from: **UNKNOWN; View; Create; Modify; Delete; Logon; Logoff; Session Timeout**. If you decide not to use this filter, just keep \*.
  - **Severity** Click the drop-down list and choose from: **UNKNOWN; INFO; WARNING; ERROR**. If you decide not to use this filter, just keep \*.
  - **Activity** Click the drop-down list and choose from: **UNKNOWN; SecurityActivity; or UserActivity**. The result is that only the log information matching the entered filter appears.
- Step 7** **Service Requests** has a selection of **Select/Deselect**. Click this and you receive a list of Service Requests in the system from which you can select check box(es) for the User Access Log to handle. Then click the **Select** button. These Service Requests then appear on [Figure 9-33](#).
- Step 8** To exit this log report, choose another feature from the main product tabs.


## Manage TIBCO Rendezvous

The only reason you would ever use this functionality is if you change the TIBCO ports for TIBCO Rendezvous Agent (rva) or TIBCO Rendezvous Routing Daemon (rvrd) after installation. The changes being made here only affect the topology tool, a Java WebStart application.

Navigate **Administration > Manage TIBCO Rendezvous** and follow these steps:

- Step 1** After you navigate **Administration > Manage TIBCO Rendezvous**, a window appears as shown in [Figure 9-34](#), “**TIBCO Rendezvous**.”

**Figure 9-34** *TIBCO Rendezvous*



95362

- Step 2** From [Figure 9-34](#), click **connection**, as described in [Step 3](#); and click **change state**, as described in [Step 4](#). These are choices in the left column of [Figure 9-34](#).
- Step 3** In [Figure 9-34](#), when you click **connection**, a window such as [Figure 9-35](#), “**Connection Configuration**,” appears.

**Figure 9-35 Connection Configuration**

Connection Configuration	
Accept Client Connections on Listen Port:	7600
<b>TIB/Rendezvous Daemon Connection:</b>	
service:	7530
network:	
daemon:	
<input type="button" value="Submit"/> <input type="button" value="Reset"/>	

95361

If you must change the **rva** port number from the existing value, change the **Accept Client Connections on Listen Port:** field to your new rva port number for ISC. If you must change the **rvrd** port number from the existing value, change the **service** field to your new rvrd port number for ISC. Then click **Submit**. Then [Figure 9-35](#) returns with the new value and a note that says “Configuration change will take effect after RVA is re-activated. To re-activate RVA set it into idle state and then back to active state.”

- Step 4** In [Figure 9-34](#), click **change state**, follow the instructions, and you complete this functionality.
- Step 5** From a terminal window, change to the **bin** directory of your ISC installation, such as **/opt/isc-4.1/bin**
- Step 6** Source the ISC environment:
- C Shell - use the command **source ./vpnenv.csh**
  - K Shell or Bash - use the command **./vpnenv.sh**
- Step 7** To start the script, at the command line type **updateWebStartJars**.
- Step 8** The next time you start a Java WebStart, such as the topology tool, these changes are in effect.





## ISC XML Reference

This appendix contains an alphabetical listing of the XML rules, tags, and attributes that are used in the XML files used for ISC Discovery.

For a detailed description of the XML files and XML examples, see the “Service Inventory > Discovery” chapter at the following URL.

[\(URL to be provided\)](#)

**Table A-1**      *ISC XML Rules, Tags, and Attributes*

Tag	Description
<b>&lt;as-number&gt;</b>	Specifies the autonomous system (AS) number for the provider. The AS number can be an integer between 1 and 65535.
<b>&lt;CDP&gt;</b>	<p>Starts a <b>&lt;CDP&gt;</b> tag. The <b>&lt;CDP&gt;</b> tag specifies an seed IP address and a hop count.</p> <p>The <b>&lt;CDP&gt;</b> tag must contain the following attributes:</p> <ul style="list-style-type: none"><li>• <b>ipaddress</b></li><li>• <b>hop</b></li></ul>
<b>&lt;connection&gt;</b>	<p>Starts a <b>&lt;connection&gt;</b> tag. The <b>&lt;connection&gt;</b> tag must specify the following attributes:</p> <ul style="list-style-type: none"><li>• <b>discovery-protocol</b></li><li>• <b>fromDevice</b></li><li>• <b>FromIP</b></li><li>• <b>FromInterface</b></li><li>• <b>toDevice</b></li><li>• <b>toIP</b></li><li>• <b>toIF</b></li></ul>

Table A-1 ISC XML Rules, Tags, and Attributes (continued)

Tag	Description
<b>&lt;create-customer&gt;</b>	<p>Starts a <b>create-customer</b> rule. The <b>create-customer</b> rule creates a region object. the create-customer rule must contain the following tags:</p> <ul style="list-style-type: none"> <li>• <b>&lt;customer-name&gt;</b></li> <li>• <b>&lt;create-site&gt;</b></li> </ul>
<b>&lt;create-provider&gt;</b>	<p>Starts a <b>create-provider</b> rule. The create-provider rule creates a service provider object.</p> <p>The <b>create-provider</b> rule must contain the following tags:</p> <ul style="list-style-type: none"> <li>• <b>&lt;provider-name&gt;</b></li> <li>• <b>&lt;as-number&gt;</b></li> <li>• <b>&lt;create-region&gt;</b></li> </ul>
<b>&lt;create-region&gt;</b>	<p>Starts a <b>create-region</b> rule. The <b>create-region</b> rule creates a region object. The <b>create-region</b> rule must contain a <b>region-name</b> tag.</p>
<b>&lt;create-site&gt;</b>	<p>Starts a <b>create-site</b> rule. The create-site rule must contain a <b>&lt;site-name&gt;</b> tag.</p>
<b>&lt;customer-name&gt;</b>	<p>Specifies a customer name. Required within the <b>create-customer</b> rule.</p>
<b>&lt;device&gt;</b>	<p>Starts a <b>&lt;device&gt;</b> tag. The <b>&lt;device&gt;</b> tag must contain the following tags:</p> <ul style="list-style-type: none"> <li>• <b>&lt;device-name&gt;</b></li> <li>• <b>&lt;ip-address&gt;</b></li> </ul> <p>The following tags are optional within the <b>&lt;device&gt;</b> tag:</p> <ul style="list-style-type: none"> <li>• <b>&lt;system-object-id&gt;</b></li> <li>• <b>&lt;snmp-info&gt;</b></li> </ul>
<b>&lt;device-name&gt;</b>	<p>Specifies the name of the device. Required within the <b>&lt;device&gt;</b> tag.</p>
<b>&lt;DISCOVERY_METHOD&gt;</b>	<p>Starts a <b>&lt;DISCOVERY_METHOD&gt;</b> tag. The <b>&lt;DISCOVERY_METHOD&gt;</b> tag must contain a <b>&lt;CDP&gt;</b> tag.</p>
<b>discovery-protocol</b>	<p>Specifies the Discovery protocol used to discover the network topology. Normally, this is “CDP.”</p>
<b>fromDevice</b>	<p>Specifies the name of the device from which the Named Physical Circuit starts. Required attribute for the <b>&lt;connection&gt;</b> tag.</p>
<b>FromInterface</b>	<p>Specifies the name of the device interface from which the Named Physical Circuit starts. Required attribute for the <b>&lt;connection&gt;</b> tag.</p>

Table A-1 ISC XML Rules, Tags, and Attributes (continued)

Tag	Description
<b>FromIP</b>	Specifies the management IP address of the device from which the Named Physical Circuit starts. Required attribute for the <b>&lt;connection&gt;</b> tag.
<b>hop</b>	Specifies the number of hops from the device identified by the <b>ipaddress</b> attribute to go in discovering devices. Required attribute for the <b>&lt;CDP&gt;</b> tag.
<b>ipaddress</b>	Specifies the IP address of a seed device. Required attribute for the <b>&lt;CDP&gt;</b> tag.
<b>&lt;ip-address&gt;</b>	Specifies the IP address of the device. Required within the <b>&lt;device&gt;</b> tag.
<b>&lt;provider-name&gt;</b>	Specifies the name of the provider.
<b>&lt;region-name&gt;</b>	Specifies the name of a region.
<b>&lt;ro-community&gt;</b>	Specifies the level of SNMP access for the device. Normally, this should be “public.” Required within the <b>&lt;snmp-info&gt;</b> tag.
<b>&lt;site-name&gt;</b>	Specifies a site name.
<b>&lt;snmp-info&gt;</b>	Specifies SNMP information for the device. The <b>&lt;snmp-info&gt;</b> tag must contain a <b>&lt;ro-community&gt;</b> tag. Optional within the <b>&lt;device&gt;</b> tag.
<b>&lt;system-object-id&gt;</b>	(optional) Can be included to specify the SNMP Object ID (OID) for the device. If this is provided, it is specified within the <b>&lt;device&gt;</b> tag.
<b>toDevice</b>	Specifies the name of the device to which the Named Physical Circuit connects. Required attribute for the <b>&lt;connection&gt;</b> tag.
<b>toIF</b>	Specifies the device interface on the device to which the Named Physical Circuit connects. Required attribute for the <b>&lt;connection&gt;</b> tag.
<b>toIP</b>	Specifies the management IP address of the device from which the Named Physical Circuit connects. Required attribute for the <b>&lt;connection&gt;</b> tag.





## Cisco CNS IE2100 Appliances

Cisco IP Solution Center (ISC) supports the Cisco CNS IE2100 Device Access Protocol for communication with any Cisco IOS device, such as uploading a configuration file from a device, downloading a configlet to a device, or executing a command on a device and obtaining a result. ISC also supports CNS Plug-and-Play.

To use the Cisco CNS IE2100 functionality on ISC, you must first set up the Cisco CNS IE2100 appliance and the ISC workstation as explained in an appendix in [Cisco IP Solution Center Installation Guide, 4.1](#).

This appendix includes the following sections. Implement these sections in sequence:



### Note

The “[Using Plug-and-Play](#)” section on page B-7 is optional.

1. [Creating a Cisco CNS IE2100 Appliance](#), page B-1
2. [Creating a Cisco IOS Device Using the Cisco CNS Device Access Protocol](#), page B-3
3. [Using Plug-and-Play](#), page B-7

## Creating a Cisco CNS IE2100 Appliance


ISC supports multiple Cisco CNS IE2100 appliances. To create a Cisco CNS IE2100 appliance, follow these steps:



### Note

For more information, see the [Devices](#) section of [Chapter 3, “Service Inventory — Inventory and Connection Manager.”](#)

- Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Devices**.
- Step 2** A window appears as shown in [Figure B-1, “Devices Window.”](#)

**Figure B-1**      **Devices Window**

**Step 3** Click the **Create** button.

**Step 4** From the **Create** menu, click **IE2100**.

A window appears as shown in [Figure B-2](#), “Create IE2100 Device Window”.

**Figure B-2**      **Create IE2100 Device Window**

The screenshot shows the 'Create IE2100 Device Window' dialog box. It has a 'General' tab with the following fields:

- Device Host Name \* (required field)
- Device Domain Name
- Description
- IP Address

At the bottom right, there are 'Save' and 'Cancel' buttons. A note at the bottom left states: 'Note: \* - Required Field'.

**Step 5** Enter the **Device Host Name** and if applicable, the **IE2100 Device Domain Name**. The **Description** field is optional. If the Cisco CNS IE2100 appliance is not registered with DNS, then you *must* enter the **IP Address** of the Cisco CNS IE2100 appliance. Click **Save**.

[Figure B-1](#) reappears with the IE2100 listed as a device.

# Creating a Cisco IOS Device Using the Cisco CNS Device Access Protocol

Each Cisco CNS IE2100 appliance can serve multiple Cisco IOS devices. A Cisco IOS device can only be served by one Cisco CNS IE2100 appliance. To create a Cisco IOS device using the Cisco CNS Device Access Protocol, follow these steps:

**Note**

For more information, see the [Devices](#) section of [Chapter 3, “Service Inventory — Inventory and Connection Manager.”](#)

**Step 1** Navigate **Service Inventory > Inventory and Connection Manager > Devices**.

**Step 2** A window appears as shown in [Figure B-1, “Devices Window.”](#)

**Step 3** Click the **Create** button.

**Step 4** From the **Create** menu, click **Cisco Device**.

A window appears as shown in [Figure B-3, “Create Cisco Device Window.”](#)

**Figure B-3** Create Cisco Device Window

General	
Device Host Name :	<input type="text"/>
Device Domain Name:	<input type="text"/>
Description:	<input type="text"/>
Collection Zone:	None ▾
Management IP Address:	<input type="text"/>
Interfaces:	<input type="button" value="Edit"/>
Associated Groups	<input type="button" value="Edit"/>
Login and Password Information	
Login User:	<input type="text"/>
Login Password:	<input type="text"/>
Verify Login Password:	<input type="text"/>
Enable User:	<input type="text"/>
Enable Password:	<input type="text"/>
Verify Enable Password:	<input type="text"/>
Device and Configuration Access Information	
Terminal Session Protocol:	Default (Telnet) ▾
Config Access Protocol:	Default (Terminal) ▾
OS:	IOS ▾
SNMP Version:	Default (SNMP v1/v2c) ▾
SNMP v1/v2c	
Community String RO:	<input type="text"/>
Community String RW:	<input type="text"/>
Additional Properties:	<input type="button" value="Show"/>
<input type="button" value="Save"/> <input type="button" value="Cancel"/>	

**Step 5** In the **General** section, enter the **Device Host Name** and **Device Domain Name**.

For **CNS Device Access Protocol**, you do not need to define the parameters in the **Login User** and **Login Password** sections.

For the **Device and Configuration Access Information** section, you must select **CNS** for the **Terminal Session Protocol**.

For the **Device and Configuration Access Information** section, the only valid **OS** selection is **IOS**. **IOS\_XR** is not supported for Cisco CNS IE2100 appliances with ISC.



- Step 6** Click the **Show** button for **Additional Properties** at the bottom of the window and this window expands to add the additional information that is shown in [Figure B-4](#), “Cisco Device Additional Properties,” appears.

**Figure B-4** Cisco Device Additional Properties

Additional Properties:		Hide
<b>SNMP v3</b>		
SNMP Security Level:	Default (No Authentication/No Encryption) ▾	
Authentication User Name:	<input type="text"/>	
Authentication Password:	<input type="text"/>	
Verify Authentication Password:	<input type="text"/>	
Authentication Algorithm:	None ▾	
Encryption Password:	<input type="text"/>	
Verify Encryption Password:	<input type="text"/>	
Encryption Algorithm:	None ▾	
<b>Terminal Server and CNS Options</b>		
Terminal Server:	None ▾	
Port:	<input type="text" value="0"/>	
Fully Managed:	<input type="checkbox"/>	
Device State:	ACTIVE ▾	
CNS Identification:	<input type="text"/>	
Device Event Identification:	CNS_ID ▾	
Most recent CNS event:	None ▾	
IE2100:	None ▾	
CNS Software Version:	1.4 ▾	
CNS Device Transport:	HTTP ▾	
<b>Device Platform Information</b>		
Platform:	<input type="text"/>	
Software Version:	<input type="text"/>	
Image Name:	<input type="text"/>	
Serial Number:	<input type="text"/>	
Device Owner's Email Address:	<input type="text"/>	
		Save Cancel

Note: \* - Required Field

149196

**Step 7** The following steps pertain to the **Terminal Server** and **CNS Options** section.

**Step 8** Select the **Fully Managed** check box if you want the device to become a fully managed device. For fully managed devices, ISC sends e-mail notifications upon receipt of device configuration changes originated outside ISC and schedules enforcement audit tasks upon detection of possible intrusion.



**Note**

Be sure to set the DCPL parameters for e-mail and Fully Managed, as explained in the “[Config](#)” section on page 9-25. Navigate **Administration > Control Center**. Select a Host and then click **Config**. Then in the TOC in the left column, be sure to enter appropriate information in the following fields: **SYSTEM > email > from**; **SYSTEM > email > smtpHost**; **SYSTEM > fullyManaged > auditableCommandsFileLocation** (if information is not given here, all commands are audited); **SYSTEM > fullyManaged > enforcementAuditScript**; and **SYSTEM > fullyManaged > externalEventsEmailRecipients**.



**Note**

Verify that the **cns config notify** command is configured for the IOS device. This command ensures that configuration change events, which are the basis of the fully-managed feature, are sent out on the event bus. If this command is not configured on the device, the fully-managed feature will not work, because there will be no config-changed events reaching ISC.

**Step 9** Specify the **Device State**, as follows:

- Select **ACTIVE** (the default) if the router is physically present on the network.
- Select **INACTIVE** if the router is not yet physically present on the network.

**Step 10** Specify the **Device Event Identification**, as follows:

- Select **HOST\_NAME** if the **Device Host Name** as defined in [Step 5](#) is to be used as the **CNS Identification** for this device.
- Select **CNS\_ID** if the device CNS Identification string is other than the **Device Host Name**.
- If you have selected **CNS\_ID** as the **Device Event Identification**, you must enter the **CNS Identification** parameter in the field labeled **CNS Identification**. This must be a unique argument. It is used to create the device in the corresponding Cisco CNS IE2100 repository and to listen to events pertaining to this device.



**Note**

Verify that the **cns id string {CNS\_ID} event** command is configured for the IOS device. If this command is not present on the device, the IE2100 will not send out any events on the bus using this CNS ID, and hence communication with the device will fail.

**Step 11** Select the Cisco CNS **IE2100** appliance that serves this Cisco IOS device. Select one entry from the drop-down list of IE2100 devices already defined in the repository.

**Step 12** Use the drop-down list for **CNS Software Version** to choose the version of Cisco CNS Configuration Engine that manages the IOS device (1.3, 1.3.1, 1.3.2, 1.4, or 1.5).

**Step 13** Use the drop-down list for **CNS Device Transport** to choose HTTP or HTTPS as the transport mechanism used by ISC to create, delete, or edit devices in the IE2100 repository. If HTTPS is used, the Cisco CNS Configuration Engine must be running in secure mode.

**Step 14** Click **OK**. [Figure B-1](#) reappears with the Cisco IOS device listed.

# Using Plug-and-Play

ISC supports the Plug-and-Play device configuration through a Cisco CNS IE2100 appliance. ISC supports devices not physically present on the network.

The procedures for using Plug-and-Play when the Cisco IOS device is not physically present on the network vary depending on whether there is an initial configuration file for the device.

Follow these steps if the Cisco IOS device *does not* have an initial configuration file:

- 
- |               |                                                                                                                                                                                                                  |
|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Step 1</b> | Create a Cisco IOS Device as described in the “ <a href="#">Creating a Cisco IOS Device Using the Cisco CNS Device Access Protocol</a> ” section.                                                                |
| <b>Step 2</b> | Define the Cisco IOS device properties as shown in <a href="#">Figure B-4</a> .<br><br>Be sure to specify the <b>Device State</b> as <b>INACTIVE</b> because the device is not physically present on the network |
| <b>Step 3</b> | Click <b>Save</b> .<br><br>A Cisco IOS Device entry is created in the ISC repository and in the corresponding Cisco CNS IE2100 appliance repository.                                                             |
- 

Follow this step if the Cisco IOS device *does* have an initial configuration file:

- 
- |               |                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                              |
|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Step 1</b> | Import the initial configuration file into ISC using the Inventory Manager functionality, explained in <a href="#">Chapter 3, “Service Inventory — Inventory and Connection Manager.”</a> in this manual.<br><br>Be sure to specify the <b>Device State</b> as <b>INACTIVE</b> because the device is not physically present on the network.<br><br>The Inventory Manager create a Cisco IOS Device entry in the ISC repository. Also, it creates an entry in the corresponding Cisco CNS IE2100 repository, and associates the specified initial configuration file with this new device in the Cisco CNS IE2100 repository. |
|---------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
- 

You can provision the newly created inactive Cisco IOS Device for different services. Because the device is not physically present on the network, ISC saves the configlets associated with these services in its repository and tries to download them to the device only after the device has come up. Until the device is physically present on the network, the service request goes into the **WAIT\_DEPLOY** state. The service requests are explained in the user guides for each of the services.

After the device comes up and connects to its corresponding Cisco CNS IE2100 appliance, the device retrieves and applies its initial configuration if there is one waiting for it in the Cisco CNS IE2100 repository.

ISC detects that the device has come onto the network and performs the following actions:

- Changes the Cisco IOS Device state from **INACTIVE** to **ACTIVE**.  
ISC performs a collect config of the IOS device and stores it in the ISC repository.
- Verifies whether any ISC service has been waiting for this device to come up and tries to download the corresponding configlets to the device to complete the service request.





## Property Settings

To navigate to the properties, known as Dynamic Component Properties Library (DCPL), navigate to the tab **Administration > Control Center > Hosts**. Then select a check box for a specific host and click the **Config** button.



**Note**

More details about this are explained in the [“Config” section on page 9-25](#).

When you click on the folder or subfolder, it expands to more subfolders or eventually to the property itself. Then you receive an explanation, default values, and in some cases range and rules. This table can help you understand all the properties available at a glance. The properties are listed alphabetically. When a / ends an entry, this means it can be expanded further. Also, if you are searching for a property and do not know the name, you can use some key words and do a Find on the pdf version.

**Table C-1**      **DCPL Properties**

Property	Default Value	Range/Rules	Explanation
<b>AutoDiscovery Properties:</b>			Controls the operation of Autodiscovery.
/DiscoveryTemplateFolder	/Discovery	string	Template folder under which the templates to be discovered for MPLS VPN Discovery will reside.
/performTemplateDiscovery	false	The valid values are <b>true</b> and <b>false</b> .	With this flag, the user can control the template discovery. For performance reasons, if the template discovery is not desired this should be set to false.
<b>Cleanup Properties:</b>			Cleans up various system resources such as log files and temporary files.
/Cleanup/TaskLogs/			This component cleans up old TaskLogs.
maxAgeInHours	168	integer	Maximum age of the TaskLogs in hours. TaskLogs older than this age will be deleted during the next cleanup cycle. Set to 0 to disable this feature.
sleepIntervalInHours	24	integer, 1-1000 hours	Time in hours for taskLog cleanup service to sleep between clean up cycles.
/Cleanup/TempFiles/			This component cleans up old temporary files.

**Table C-1** *DCPL Properties (continued)*

maxAgeInHours	168	integer	Maximum age of the temporary files in hours. Temporary files older than this age will be deleted during the next cleanup cycle. Set to 0 to disable this feature.
sleepIntervalInHours	24	integer, 1-1000 hours	Time in hours for tempFile cleanup service to sleep between clean up cycles.
/Cleanup/logLevel	CONFIG	selection	This log Level is used only if there is no log Level defined for a component. The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
<b>DCS Properties:</b>			Device Configuration Service. This component corresponds to a library that is used by ISC to communicate with network devices using protocols such as telnet, ssh, tftp, and so forth.

**Table C-1**      **DCPL Properties (continued)**

/DCS/CATWarningExpressions		string	<p>CatOS (Catalyst switch) warning expressions that can be safely ignored; case insensitive; . matches any char except newline, * means zero or more, + means one or more, ? means zero or one.</p> <p>All regular expressions except the last one should have a \$ at the end of the regular expression.</p> <p>^.??.??.??.??.?-[5-7]- \$</p> <p>Adding vlans .* to allowed list.\$</p> <p>already allowed on the trunk\$</p> <p>CDP disabled on port.*\$</p> <p>Dot1q tunnel feature disabled.*\$</p> <p>Dot1q tunnel feature set to.*\$</p> <p>Jumbo frames enabled on port .*\$</p> <p>Jumbo frames disabled.*\$</p> <p>Layer 2 protocol tunneling enabled.*\$</p> <p>Layer 2 protocol tunneling disabled.*\$</p> <p>Packets on native vlan will be tagged on .*\$</p> <p>Port .* enabled\$</p> <p>Removing Vlan.*\$</p> <p>Secured .* cleared from\$</p> <p>.?security level for .* changed to\$</p> <p>.*successful\$</p> <p>This command will deactivate.*\$</p> <p>VLAN Mod/Ports.*\$</p> <p>VTP advertisements transmitting temporarily stopped.*\$</p> <p>VLAN .* modified*\$</p> <p>VLAN .*Mod/Ports .*\$</p>
/DCS/FTP/			FTP Settings.
ftpPassword		string	Password for FTP server login, used by DCS and GTL.
ftpRootDirectory		string	FTP root directory, used by DCS and GTL.
ftpServer		string	FTP Server host name or IP address, used by DCS and GTL.
ftpSubDirectory		string	FTP sub directory, used by DCS and GTL.
ftpUsername		string	Username for FTP server login, used by DCS and GTL.

**Table C-1**      **DCPL Properties (continued)**

DCS/IOSUsePrimaryWarningExprOnly	false	The valid values are <b>true</b> and <b>false</b> .	If <b>true</b> , DCS uses only the primary warning expression list, specified in DCS/IOSWarningExpressions. If <b>false</b> , DCS uses the primary list specified in DCS/IOSWarningExpressions for add and modify operations and uses the list specified in DCS/IOSWarningExpressionsRemoveCfg during delete (decommissioning) operations.
----------------------------------	-------	-----------------------------------------------------	--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------



Table C-1 DCPL Properties (continued)

/DCS/IOSWarningExpressions		string	<p>IOS warning expressions that can be safely ignored; case insensitive; . matches any char except newline, * means zero or more, + means one or more, ? means zero or one.</p> <p>All regular expressions except the last one should have a \$ at the end of the regular expression.</p> <p>%Aborting Save. Compress the config\$</p> <p>. *Access Rules Download Complete\$</p> <p>% Access VLAN does not exist.\$</p> <p>Address aliases with.*\$</p> <p>% All RSA Keys will be removed.\$</p> <p>% All router certs issued using these keys will also be removed.*\$</p> <p>% Already found same .* statement in this profile\$</p> <p>% A profile is deemed incomplete until it has match identity statements\$</p> <p>. *certificate accepted\$</p> <p>Certificate request sent\$</p> <p>.?Changes to the System MTU will not take effect until the next reload.*\$</p> <p>CNS config partial agent is running already\$</p> <p>% Configuration buffer full, can't add command.*\$</p> <p>. *Crypto EzVPN does not exist.*\$</p> <p>Enter configuration commands, one per line\$ Explicit Path name .*\$</p> <p>% Generating .* bit RSA keys\$</p> <p>Global .* will be Port Address Translated.*\$ Global Ethernet MTU is set to.*\$</p> <p>If the interface doesn't support baby giant frames.*\$</p> <p>Increasing .* burst size to\$</p> <p>% Interface .* IP address .* removed due to enabling VRF\$</p> <p>% Interface .* IP address .* removed due to disabling VRF\$</p> <p>% IP addresses from all interfaces in VRF .*have been removed\$</p>
----------------------------	--	--------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

Table C-1 DCPL Properties (continued)

/DCS/IOSWarningExpressions (Continued)		string	<p>% IP routing table V.* does not exist. Create first\$</p> <p>% IP routing table g.*does not exist. Create first\$</p> <p>% No CEF interface information\$</p> <p>%No matching route to delete\$</p> <p>%Translation not found\$</p> <p>. *Not all config may be removed and may reappear after reactivating\$</p> <p>^%.*?NOTE:\$</p> <p>OSPF: Unrecognized virtual interface . * Treat it as loopback stub route\$</p> <p>outside interface address added\$</p> <p>% Profile already contains this keyring\$</p> <p>%PVC is already defined\$</p> <p>Restarting RADIUS authentication service on port . *</p> <p>\$ Restarting RADIUS accounting service on port . *\$</p> <p>Redundant . * statement\$</p> <p>security level for . * changed to\$</p> <p>. *Service policy . * is already attached\$</p> <p>% Signature RSA Keys not found in configuration.\$</p> <p>. *success\$</p> <p>The . *command will also show the fingerprint\$ %The static routes in . * with outgoing interface . * will be removed\$</p> <p>Unable to disable parser cache\$</p> <p>% Unknown VPN\$ . *</p> <p>Unknown VRF specified\$</p> <p>% VRF . * does not exist or does not have a RD\$</p> <p>.?warning.*</p>
DCS/IOSWarningExpressionsExitCfgMode		string	<p>IOS warning expressions that can be safely ignored when exiting config term mode; regular expression must match whole warning message; for messages that wrap more than one line replace line terminations (CR and/or LF chars) with a single space character; replace each variable field with the meta-character sequence \\S+ that will match a single group of non-whitespace chars; literals are case insensitive; use \$ to separate entries.</p>

**Table C-1** DCPL Properties (continued)

DCS/IOSWarningExpressionsRemoveCfg		string	IOS warning expressions that can be safely ignored during decommissioning; case insensitive; . matches any char except newline, * means zero or more, + means one or more, ? means zero or one.
/DCS/RCP/			RCP Settings.
rcpDirectory	/tmp	string	Directory to use for uploaded/downloaded config files.
/DCS/SSH/			SSH Client Settings.
overWriteSSHKeys	true	The valid values are <b>true</b> and <b>false</b> .	Overwrite SSH Keys: If <b>true</b> , will allow new keys to overwrite existing keys in the key file for a given host. If <b>false</b> , an error will be displayed if host sent key does not match the server sent key.
sshEncryptionCipher	3DES->DES	selection	Cipher to use for SSH Encryption/Decryption; requires restart on change. Values: 3DES->DES first tries 3DES then if not available falls back to DES; 3DES, only tries 3DES; DES, only tries DES.
/DCS/TFTP/			TFTP Settings.
tftpCreateFileOnServerBeforeUpload	true	The valid values are <b>true</b> and <b>false</b> .	Some TFTP servers require a file to exist on the server with write access before a TFTP client can upload it. This is sometimes called write-replace or overwrite mode. Other TFTP servers require a that a file NOT exist, this is sometimes called write-create or no overwrite mode. When <b>true</b> , DCS will create the file on the TFTP server before uploading device configuration.
tftpRootDirectory	/tftpboot	string	TFTP Root Directory used by DCS and GTL.
tftpServerIPAddress		string	TFTP Server host name or IP Address used by DCS and GTL.
tftpSubDirectory		string	TFTP Sub Directory used by DCS and GTL.
/DCS/XR			IOS-XR properties.
WarningExpressions			IOS-XR warning expressions that can be safely ignored; case insensitive; . matches any character except newline, * means zero or more, + means one or more, ? means zero or one.
commitConfigTimeout	120	integer, 30-600	Maximum time in seconds to commit config target buffer to running config.

**Table C-1 DCPL Properties (continued)**

maxRetriesEnterCfgExcIMode	3	integer, 0-10	Maximum number of times to retry entering configure exclusive mode. 0 = no retries. Retry delay interval is fixed at 30 seconds.
/DCS/allowCommandDownloadOnError	false	The valid values are <b>true</b> and <b>false</b> .	Continue command download on error.
/DCS/cnsEventTimeout	120	integer, 0-120 seconds	CNS event wait time in seconds
/DCS/configUploadTimeout	300	integer, 60-900	Maximum time in seconds to wait for a device configuration to be uploaded.
/DCS/logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/DCS/maxDeviceConnectCompleteTime	60	integer, 15-600 seconds	Maximum time in seconds to wait for a terminal session connection to a device.
/DCS/maxDeviceConnectRetryCount	3	integer, 0-5	Maximum number of times to retry connecting to a device when the maxDeviceConnectCompleteTime expires. 0= no retries.
/DCS/maxOperationTimeout	30	integer, 5-300 minutes	Maximum time in minutes to wait for a device operation to complete.
/DCS/maxPromptTimeout	60	integer, 15-300 seconds	Maximum time in seconds to wait for a prompt during a terminal session with a device.
/DCS/maxSocketReadTimeout	30	integer, 10-300 seconds	Maximum time in seconds to wait for data on a socket connection read operation.
/DCS/misc			Miscellaneous settings.
allowPromptCharsInBanner	false	The valid values are <b>true</b> and <b>false</b> .	Controls if prompt characters, such as # and >, are allowed in banners. If <b>true</b> , a minimum of 2 seconds (default of loginSocketReadTimeout) is added to each login. Note that selecting this option requires “aaa authentication attempts login n” to be set to a minimum of 2.

Table C-1 DCPL Properties (continued)

loginSocketReadTimeout	2	integer, 1-45	Number of seconds to WAIT for a login authentication username or password prompt. Applicable if DCS\misc\allowPromptCharsInBanner is <b>true</b> . Increasing this value slows down device logins and counts against DCS\maxDeviceConnectCompleteTime who's default is 60 seconds.
readBufferSize	32	integer, 4-96	Size in KBytes of the buffers used while reading device input streams with telnet and SSH. Increasing size might improve performance. Decrease size if there are memory issues.
<b>DeploymentFlow Property:</b>			Deployment flow Component: Used to create a flow of different types of steps such as mpls and qos.
/DeploymentFlow/logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
<b>Discovery Properties:</b>			ISC auto discovery framework.
/Discovery/MetroEServices			Metro Ethernet services discovery.
meConfigParsingRegistry		string	List of handlers to be invoked at collect config time for Metro Ethernet services.
meDiscoverIntraPopVPWS	false	The valid values are <b>true</b> and <b>false</b> .	Set this to <b>true</b> if local switched VPWS services are to be discovered. Do this only if you wish to discover VPWS services switched at NPE. If not, set this to <b>false</b> for performance reasons.
/Discovery/Workflow			ISC auto discovery workflow.
CollectConfig			
logHandler	com.cisco.vpnsc. discovery.util. DiscoveryLog Handler	string	A custom handler for default collect config step log.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).

**Table C-1 DCPL Properties (continued)**

DeviceDiscovery			Device discovery component.
logHandler	com.cisco.vpnsc. discovery.util. DiscoveryLog Handler	string	A custom handler for device discovery step log.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
L2VpnServiceDiscovery			L2 service discovery component.
logHandler	com.cisco.vpnsc. discovery.util. DiscoveryLog Handler	string	A custom handler for metro Ethernet service discovery step log.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
MplsServiceDiscovery			MPLS service discovery component.
logHandler	com.cisco.vpnsc. discovery.util. DiscoveryLog Handler	string	A custom handler for MPLS VPN service discovery step log.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
NPCDiscovery			NPC discovery component.
logHandler	com.cisco.vpnsc. discovery.util. DiscoveryLog Handler	string	A custom handler for default NPC discovery step log.

**Table C-1** DCPL Properties (continued)

logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
RoleAssignment			Role discovery component.
logHandler	com.cisco.vpnsc. discovery.util. DiscoveryLog Handler	string	A custom handler for role assignment step log.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/Discovery/configs.location	<vpnsc_tmp>/ Discovery/ configs		The directory name where the temporary device configurations are stored during the collect config process.
/Discovery/logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/Discovery/logHandler	com.cisco.vpnsc. discovery.util. DiscoveryLog Handler	string	A custom handler for default discovery logs.
/Discovery/logLocation	vpnsc_tmp>/ Discovery/ logs	string	The directory name where discovery logs files are kept.
/Discovery/restart	false	The valid values are <b>true</b> and <b>false</b> .	With this property, you can clear out all network objects from the repository that were created by the Discovery process and you can restart the Discovery process. Be very cautious in setting this value to <b>true</b> .
/Discovery/tmpdir	<vpnsc_tmp> /Discovery	string	A directory to store the temporary results of the discovery process.

**Table C-1 DCPL Properties (continued)**

<b>DistributionFramework Properties:</b>			Distribution Framework. This component handles the distribution of work (jobs) between different servers in a ISC distributed installation.
/DistributionFramework/Dispatcher/			Service that dispatches jobs to workers.
DefaultUnitDuration	1000	integer	The unit duration (in milliseconds) used to estimate jobs without a profile.
PingInterval	1000	integer	The interval (in ms) dispatcher pings the workers to get the load.
ProcessorEpsilon	10	integer	If two processors differ in usage by an amount less than this, they are considered identical from the point of view of the load balancer.
ProfileUpdateThreshold	10	integer	The percent change of a profile that triggers an update of the dispatcher.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/DistributionFramework/NamingHost	<master_server>	string	The hostname or ip address of the name server.
/DistributionFramework/NamingPort	<naming_port>	string	The port of the name server.
/DistributionFramework/RemoteUtil/			Layer abstracting the remote call functionality.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/DistributionFramework/ServiceLauncher/			Manages the execution of multiple services in the same VM.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).



**Table C-1** *DCPL Properties (continued)*

/DistributionFramework/ThreadPool/			Thread pool component used by the worker to execute jobs.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/DistributionFramework/Worker/			Worker.
Groups		string	The groups this worker belongs to. This property is deprecated because groups are stored in the database rather than being provided by the worker.
ThreadPoolSize	100	integer, 25-250	The maximum number of threads. Set it to 0 to allow the pool to use as many thread as necessary.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
<b>GSAM Property:</b>			Generic Service Access Model to get an XML dump from the repository for the provisioning driver.
/GSAM/logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
<b>GTL Properties:</b>			Generic Transport Layer. This library provides an API to different jobs (such as provisioning, collection etc.) to access Device Configuration Service (DCS). The jobs do not interface with DCS directly (to access the devices), but work with the API provided by GTL.
/GTL/CSL/			Configuration Services Layer
ios/			IOS related properties.

**Table C-1 DCPL Properties (continued)**

cmdsRequiringDelay		string	List of the IOS commands that execute asynchronously and require time to be processed before they are reflected in the running configuration. Matching rules: case insensitive, .matches any char except newline, * means zero or more, + means one or more, ? means zero or one.
delayAfterDownloadingCmd		command name: integer, 0-1800 seconds	List of the IOS commands that require a delay after they are downloaded using a terminal session protocol, such as Telnet. The character ; delimits the list elements. The IOS command in each list element must be followed by the character : followed by a maximum integer of 1800, which indicates the number of seconds to delay, thus indicating 0-1800 seconds (0-30 minutes). The command matching rules: case insensitive, .matches any char except newline, * means zero or more, + means one or more, ? means zero or one. The default is a blank field.
delayBeforeDownloadingCmd			List of the IOS commands that require a delay before they are downloaded using a terminal session protocol, such as Telnet. The character ; delimits the list elements. The IOS command in each list element must be followed by the character : followed by a maximum integer of 1800, which indicates the number of seconds to delay, thus indicating 0-1800 seconds (0-30 minutes). The command matching rules: case insensitive, .matches any char except newline, * means zero or more, + means one or more, ? means zero or one.
delayBeforeUpload		integer, 0-30 seconds	The delay in seconds to wait after downloading a configlet that contains asynchronous commands before uploading the new configuration.
delayBeforeWriteMem	0	integer, 0-300 seconds	The delay in seconds to wait after downloading a configlet before performing a write memory command.
/GTL/device-config-access-protocol	1	integer, 1-3	Protocol to use for device configuration uploads and downloads. 1= TERMINAL (Use the device-terminal-session-protocol for config access) 2= TFTP 3= FTP.
/GTL/device-terminal-session-protocol	1	integer, 1-2	Protocol to use for device terminal sessions. 1= TELNET 2= SSH.

**Table C-1** *DCPL Properties (continued)*

/GTL/echo-mode	false	The valid values are <b>true</b> and <b>false</b> .	Flag indicating whether to run GTL in <b>ECHO</b> mode or <b>DCS</b> mode.
/GTL/ios/			IOS related GTL properties.
copy-running-to-startup	true	The valid values are <b>true</b> and <b>false</b> .	Flag indicating whether to copy running config to startup config when downloading configlets. Write Mem flag.
/GTL/logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GTL/pix/			PIX related properties.
copy-running-to-startup	true	The valid values are <b>true</b> and <b>false</b> .	Flag indicating whether to copy running config to startup config when downloading configlets. Write Mem flag.
<b>GUI Properties:</b>			The component for GUI-based properties.
/GUI/Common/			Generic GUI component. Use it if you do not have any specific component requirements, such as security or L2VPN.
logLevel	FINE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GUI/L2VPN/			L2VPN related GUI component. Use it with L2VPN related operations only.
logLevel	SEVERE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GUI/MPLSOAM/			The MPLS OAM component.

**Table C-1** *DCPL Properties (continued)*

logLevel	FINEST	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GUI/MplsVPN/			MPLS VPN related GUI component. Use it with MPLS VPN related operations only.
logLevel	SEVERE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GUI/Performance/			For monitoring GUI performance.
logLevel	INFO	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
GUI/Ping			Ping related GUI component. Use it with Ping related operations only.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GUI/QoS/			QoS related GUI component. Use it with QoS related operations only.

**Table C-1** DCPL Properties (continued)

logLevel	SEVERE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
sendAuditEvent	true	The valid values are <b>true</b> and <b>false</b> .	Set true to enable sending audit event for this service.
/GUI/Security/			Security related component. This is to be used for security purposes only.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GUI/Topology/			Component related to the web start topology application.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GUI/VPLS/			VPLS related GUI component. Use it with VPLS related operations only.
logLevel	SEVERE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/GUI/srRefreshRate	30000	integer	The refresh rate (in milliseconds) for the SR List screen.
/GUI/workflowSteps	<vpnsc_home>/etc/workflowSteps.csv	string	The pre-defined workflow steps.

**Table C-1 DCPL Properties (continued)**

/GUI/workflows	<vpnsc_home>/etc/workflows.csv	string	The pre-defined workflows.
<b>JavaWebStart Properties</b>			Java Web Start components.
/JavaWebStart/InventoryManager/			Component to create and manage Devices.
MaxDevicesPerSaveTransaction	25	integer, 1-500	Specifies the maximum number of devices per transaction when performing save operation.
/JavaWebStart/TaskManager/			Component to create and monitor scheduled tasks.
MaxDevicesPerCollectionTask	25	integer, 1-500	Specifies the maximum number of devices per Collect Config task. More devices can be specified for a single task and they will be managed as such from a user perspective. However, there may be more than on Collect Config task created and executed in the repository.
<b>Logging Properties:</b>			This contains different properties needed by the logging framework. There are a set of default values for logging parameters. These values can be overridden for a specific server.
/Logging/Defaults/			This contains the default values for the logging framework.
logFileNumber	2	integer, 1-10	Maximum number of log files for a process. Each of these files can be of size <b>logFileSize</b> . When the maximum number for log files is reached for a process, the log files are rotated by deleting the oldest log file for that process.
logFileSize	2000000	integer, 1000000-10000000 bytes	Size in bytes of a single log file for a process. Each process will have a number of log files (see <b>logFileNumber</b> property), where each of these files can grow to this size.
logFormatter	java.util.logging.XMLFormatter	string	Class name for the default formatter of log records.

**Table C-1** DCPL Properties (continued)

logLevel	CONFIG	selection	NOTE: This log Level is used only if there is no log Level defined for a component. The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
logLocation	<vpnsc_tmp>	string	The directory name where log files are kept.
/Logging/TaskLogs/			This contains logging properties for task logs.
logLocation	<vpnsc_tmp>/TaskLogs	string	The directory name where all the task logs are kept.
<b>Provisioning Properties:</b>			Contains properties and components for service provisioning like MPLS VPNs.
/Provisioning/Engine/			Contains properties for the XML driven provisioning engine.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
serviceSchema	service.xsd	string	Specifies the XML schema definition file for defining new services.
/Provisioning/NOM/			Network Object Model for parsing and delta generation of configs.
DocumentBuilderFactory/			This contains the properties for the DOM builder factory.
ignoreComments	true	The valid values are <b>true</b> and <b>false</b> .	Flag.
ignoreWhiteSpace	false	The valid values are <b>true</b> and <b>false</b> .	Flag for DOM builder factory.
validation	false	The valid values are <b>true</b> and <b>false</b> .	Flag for validation of xml files.
catSyntaxFile	catSyntax.xml	string	Contains the XML for Catalyst command syntax.

**Table C-1 DCPL Properties (continued)**

iosSyntaxFile	iosSyntax.xml	string	Contains the xml syntax for IOS command.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/Provisioning/PasswordManagement/			User generated Password generation
PasswordFormula/			User generated Password formula generation class
class		string	User generated class file
/Provisioning/ProvDrv/			Contains properties for the XML driven provisioning ProvDrv.
AuditJITUpload	true	The valid values are <b>true</b> and <b>false</b> .	If the value of this property is set to <b>false</b> , the provisioning server does NOT upload a copy of the configuration file from the routers when it processes the Service Request for auditing purpose. Instead, it uses copies of the configuration files that were collected and stored in the Repository earlier. If the value of this property is set to <b>true</b> , the provisioning server uploads a copy of the configuration file from the routers when it processes the Service Request for auditing purpose. The default value of this property is <b>true</b> .
CleanStagedConfigletWhenForceDeploy	false	The valid values are <b>true</b> and <b>false</b> .	If this value is <b>true</b> , when a service request is force deployed, the staged configlet is removed before provisioning. If this value is the default of <b>false</b> , the staged configlet is considered as part of the base configuration during provisioning.
DownloadTemplateToUnmanagedDevice	false	The valid values are <b>true</b> and <b>false</b> .	If this value is <b>true</b> , for an unmanaged device, ISC attempts to download just the template. The configlet generated by the provision is not part of the download. By default, this value is <b>false</b> and then there is no attempt to download to an unmanaged device.



**Table C-1** DCPL Properties (continued)

MaxNumberOfDevicesPerDownload	100	integer	ISC will try to bundle as much devices as possible during a download attempt. This value set the max number of devices allowed during such an attempt. If the number of devices exceeds this limit, multiple download attempts will take place. You should decrease this limit if the download involves many devices with huge configlets in order to conserve memory usage.
ProvisionJITUpload	true	The valid values are <b>true</b> and <b>false</b> .	If the value of this property is set to <b>false</b> , the provisioning server does NOT upload a copy of the configuration file from the routers when it processes the Service Request for provisioning purpose. Instead, it uses copies of the configuration files that were collected and stored in the Repository earlier. If the value of this property is set to <b>true</b> , the provisioning server uploads a copy of the configuration file from the routers when it processes the Service Request for provisioning purpose.
SaveConfigletsFromAllSRs	true	The valid values are <b>true</b> and <b>false</b> .	If the value of this property is set to true, for each device in a SR, the provisioning server will save the configlet contributed from all SRs that are processed in the same provisioning run. If the value is set to false, only the configlet contributed by the current SR is saved for this device in this SR even though this same device may be in multiple SRs that are processed by the same provisioning run.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/Provisioning/Service/			Contains different services and their properties.
QoS/			QoS Provisioning Service related properties section.

Table C-1 DCPL Properties (continued)

enableLogging	true	The valid values are <b>true</b> and <b>false</b> .	When the value is the default of <b>true</b> , debugging of logging is enabled for this service.  When the value is <b>false</b> , debugging of logging is not enabled for this service.
managementLanAddress	0.0.0.0/0	string	Management LAN address in the format of a.b.c.d/x. This will become the default value in QoS Policy's TrafficClassification's Mgmt_lan_addr_mask field.
platform/ CISCO_ROUTER/			Used by ProvDrv.
serviceBladeClass	com.cisco.vpnsc. prov.qos. ServiceBlade. QoSServiceBlade	string	Identifies ServiceBlade class name for ProvDrv.
sendAuditEvent	true	The valid values are <b>true</b> and <b>false</b> .	Set <b>true</b> to enable sending audit event for this service.
TE/			Traffic Engineering Provisioning Service related properties section.
enableLogging	true	The valid values are <b>true</b> and <b>false</b> .	When the value is the default of <b>true</b> , debugging of logging is enabled for this service.  When the value is <b>false</b> , debugging of logging is not enabled for this service.
platform/ CISCO_ROUTER/			Used by ProvDrv
serviceBladeClass	com.cisco.vpnsc. prov.te. ServiceBlade. TeServiceBlade	string	Identifies ServiceBlade class name for ProvDrv.
sendAuditEvent	true	The valid values are <b>true</b> and <b>false</b> .	Set <b>true</b> to enable sending audit event for this service.
Uds/			User defined services.
platform/ CISCO_ROUTER/			Service platform Cisco router
serviceBladeClass	com.cisco.vpnsc. prov.uds.Uds ServiceBlade	string	Uds Service Blade.
l2vpn/			MPLS Layer 2 VPN Provisioning.

Table C-1 DCPL Properties (continued)

DownloadWeights/			Specifies the download weights for different devices in an L2VPN service request. The higher the weight, the sooner we download to that device. By default the weights are set to 0, so that all devices get downloaded at the same time during service deployment.
weightForCE	0	integer	Download weight for CE devices.
weightForPE	0	integer	Download weight assigned to PE devices.
weightForPE_CLE	0	integer	download weight for PE_CLE devices.
platform/			Contains properties for L2VPN for different platforms.
CATOS/			Service blade parameters for CATOS.
serviceBladeClass	com.cisco.vpnsc. prov.l2vpn.L2VPNServiceBlade	string	ServiceBladeClass location.
CISCO_ROUTER/			IOS.
serviceBladeClass	com.cisco.vpnsc. prov.l2vpn.L2VPNServiceBlade	string	ServiceBladeClass location.
dataFileSchema	l2vpnData.xsd	string	Layer 2 VPN Data File schema.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
parseConfigAfterProvisioning	false	The valid values are <b>true</b> and <b>false</b> .	This property controls the parsing of the configuration file after the provisioning is completed in order to make sure that device inventory is in sync with network.
saveDebugData	true	The valid values are <b>true</b> and <b>false</b> .	If this property is set to <b>true</b> , whenever an SR is provisioned, the uploaded config files and input XML data are saved to a temporary directory for debugging purposes.
sendAuditEvent	true	The valid values are <b>true</b> and <b>false</b> .	Set true to enable sending audit event for this service.
serviceFile	l2vpnService.xml	string	Layer 2 VPN Service definition file.

**Table C-1** DCPL Properties (continued)

logLevel/	SEVERE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
mpls/			Contains properties for MPLS/BGP Layer 3 VPN service.
DownloadWeights/			Specifies the download weights for different devices in an MPLS-VPN service request. The higher the weight, the sooner we download to that device. By default the weights are set to 0, so that all devices get downloaded at the same time during service deployment.
weightForCE	0	integer	Download weight for CE devices.
weightForMVRFC	0	integer	Download weight for MVRFC. The higher the weight the sooner we download to this device while deploying a service request.
weightForPE	0	integer	Download weight assigned to PE devices.
weightForPE_CLE	0	integer	Download weight for PE_CLE devices.
platform/			Platform related classes.
CATOS/			Service blade parameters for CATOS.
serviceBladeClass	com.cisco.vpnsc. prov.mpls.MplsS erviceBlade	string	ServiceBladeClass location.
CISCO_ROUTER			IOS.
serviceBladeClass	com.cisco.vpnsc. prov.mpls.MplsS erviceBlade	string	ServiceBladeClass location
allowOverwriteManualAssigned Address	false	The valid values are <b>true</b> and <b>false</b> .	Allow manually-assigned IP address in Service Request overwrite the pre-existing interface IP address. <b>False</b> means if an MPLS service request tries to provision a manually-assigned IP address to an interface that already has a different IP address on it, ISC detects that and reports the error. <b>True</b> means ISC allows the new IP address to overwrite the existing IP address.

**Table C-1** DCPL Properties (continued)

allowShared VLAN Modification	false	The valid values are <b>true</b> and <b>false</b> .	For residential services, if the flag is on, <b>true</b> , shared VLAN attributes are available for modify in edit mode. If the flag is off, <b>false</b> , attributes are in read only mode.
auditIpAddressViaUnnumbered	false	The valid values are <b>true</b> and <b>false</b> .	When the value is the default of <b>false</b> , the auditor only looks for the IP address of a provisioned interface. When the value is <b>true</b> , the auditor tries to match the IP address of the unnumbered interface, if one exists.
auditMaxrouteThreshold	true	The valid values are <b>true</b> and <b>false</b> .	When the value is the default of <b>true</b> ,
dataFileSchema	l3vpnData.xsd	string	Specifies the schema for the data XML file for MPLS/BGP layer3 VPNs.
forceRemoveNonBroadcastStatic RouteOnPE	false	The valid values are <b>true</b> and <b>false</b> .	The default value is <b>false</b> . When the value is set to <b>true</b> , ISC removes the non-broadcast type static route command that has a pre-existing long syntax, even if the command was not provisioned by ISC. The non-broadcast type static route command is removed from a PE router prior to provisioning. Long syntax contains both an outgoing interface name and a next hop IP address.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
parseConfigAfterProvisioning	false	The valid values are <b>true</b> and <b>false</b> .	This property controls the parsing of the configuration file after the provisioning is completed in order to make sure that device inventory is in sync with network.
passIpAddressAuditWhenNoAddress Detected	false	The valid values are <b>true</b> and <b>false</b> .	Pass the IP address command auditing if uploaded router config does not contain an IP address. This is to prevent the audit failure from appended template blob overwriting the provisioned IP address command.

**Table C-1 DCPL Properties (continued)**

reapplyIpAddress	false	The valid values are <b>true</b> and <b>false</b> .	Re-apply the same IP address to the interface when decommission a service request. This option is only applicable to manually-assigned IP addresses. It does not work for automatically-assigned IP addresses. When this property is in effect, the interface negate command will not be generated.
removeSubInterface	true	The valid values are <b>true</b> and <b>false</b> .	Removing the ISC generated subinterface commands in decommission service requests.
saveDebugData	true	The valid values are <b>true</b> and <b>false</b> .	If this property is set to <b>true</b> , whenever an SR is provisioned, the uploaded config files and input XML data are saved to a temporary directory for debugging purposes.
sendAuditEvent	true	The valid values are <b>true</b> and <b>false</b> .	Set true to enable sending audit event for this service.
serviceFile	l3vpnService.xml	string	Specifies the XML file containing the service definition for MPLS/BGP layer3 VPNs. The schema for this file is specified by Provisioning.Engine.serviceSchema
skipAddressValidationOnUnmanaged CE	false	The valid values are <b>true</b> and <b>false</b> .	When the value is <b>false</b> , the IP addresses between a PE and an unmanaged CE are validated to ensure they are in the same subnetwork and valid host addresses. When the value is <b>true</b> , this validation is by-passed.
useNextHopAddressForStaticRoutes	false	The valid values are <b>true</b> and <b>false</b> .	For Static Routes, use local router outbound interface or IP address of the next hop to reach the destination network.
useOnlyExtraCEloopbackForGrey AccessList	false	The valid values are <b>true</b> and <b>false</b> .	With Extra CE loopback, the user can select this option to add only the loopback address instead of the interface ip address and extra CE loopback.
shared/			Properties shared by MPLS VPN, L2VPN and VPLS.
FeatureQuery/			ISC components that check if certain features are available for certain devices based on their software version and platform information.

**Table C-1** *DCPL Properties (continued)*

enableValidation	true	The valid values are <b>true</b> and <b>false</b> .	If enabled, FeatureQuery will check if the features are available based on the feature matrix and device OS version (IOS Version or PIX Version). If disabled it will assume that all features are available on all platforms (should be used for testing only).
actionTakenOnUNIVlanList	prune	string	Action taken when switch port <b>allowed vlan</b> cmd is absent for ERS service.
overwriteInterfaceDescription	true	The valid values are <b>true</b> and <b>false</b> .	By default, ISC generates a <b>description</b> subcommand for all the physical interfaces it provisioned. Set this property to false if this behavior is not desirable. This property does not apply to logical interfaces or other CLI objects that have a <b>description</b> subcommand (Ex. crypto map entries, gre Interfaces, etc.)
transferUNIDescToVlanName	false	The valid values are <b>true</b> and <b>false</b> .	Controls provisioning of the VLAN name on the PE-POP. If set to <b>true</b> , the VLAN name is assigned from the description for the UNI. If set to the default of <b>false</b> , no VLAN name is assigned.
vpls/			Contains properties for Virtual Private LAN Service.
DownloadWeights/			Specifies the download weights for different devices in an MPLS VPN service request. The higher the weight, the sooner we download to that device. By default the weights are set to 0, so that all devices get downloaded at the same time during service deployment.
weightForCE	0	integer	Download weight for CE devices.
weightForPE	0	integer	Download weight assigned to PE devices.
weightForPE_CLE	0	integer	Download weight for PE_CLE devices.
dataFileSchema	vplsData.xsd	string	Specifies the schema for the data XML file for VPLS.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).

**Table C-1 DCPL Properties (continued)**

parseConfigAfterProvisioning	false	The valid values are <b>true</b> and <b>false</b> .	This property controls the parsing of the configuration file after the provisioning is completed to make sure that device inventory is in sync with network.
platform/			Platform related classes.
CATOS/			Service blade parameters for CATOS.
serviceBladeClass	com.cisco.vpnsc. prov.vpls. VplsService Blade	string	ServiceBladeClass location.
CISCO_ROUTER/			IOS.
serviceBladeClass	com.cisco.vpnsc. prov.vpls. VplsService Blade	string	ServiceBladeClass location.
saveDebugData	true	The valid values are <b>true</b> and <b>false</b> .	If this property is set to <b>true</b> , whenever an SR is provisioned, the uploaded config files and input XML data are saved to a temporary directory for debugging purposes.
sendAuditEvent	true	The valid values are <b>true</b> and <b>false</b> .	Set <b>true</b> to enable sending audit event for this service.
serviceFile	vplsService.xml	string	Specifies the XML file containing the service definition for VPLS. The schema for this file is specified by Provisioning.Engine.serviceSchema.
<b>SLA Properties:</b>			Service Level Agreement. This component deals with creating SAA probes between different devices and to collect/aggregate the data corresponding to those probes, in order to provide different SLA reports.
/SLA/copyRunningToStartup	true	The valid values are <b>true</b> and <b>false</b> .	If <b>true</b> and if showInRunningConfig is <b>true</b> - the running configuration will be copied to startup after the router SA Agent configuration has been changed.
/SLA/daysToKeepDailyStats	365	integer, 30-3650 days	Specifies how many days should the SLA database keep the daily statistics. Specifying a low number keeps the database small but you will not be able to access daily reports beyond this period.



**Table C-1** DCPL Properties (continued)

/SLA/daysToKeepHourlyStats	60	integer, 7-1000 days	Specifies how many days should the SLA database keep the hourly statistics. Specifying a low number keeps the database small but you will not be able to access hourly reports beyond this period.
/SLA/logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/SLA/rowAgeOut	3600	integer, 0-2073600 seconds	The time after which a probe is completely removed after its life is over. In seconds.
/SLA/showInRunningConfig	true	The valid values are <b>true</b> and <b>false</b> .	If true, the configured SLAs appear in the router's running configuration.
<b>SYSTEM Properties:</b>			The properties common to all sub-systems in ISC can be found under this component. Most of the values here are set at the time of installation.
/SYSTEM/app_dir	<vpnsc_home>	string	Location of the ISC installation.
/SYSTEM/ciscoURL	http://www.cisco.com	string	The Cisco URL.
/SYSTEM/databaseServer	<db_server>	string	The database server fully qualified name.
/SYSTEM/email/			Properties related to e-mails sent out by ISC.
from	<mailfrom>	string	The <b>from</b> field in the e-mail header of the mails sent out by ISC.
smtpHost	<mailhost>	string	The server using which e-mail messages from ISC should be sent out.
/SYSTEM/fullyManaged/			Properties related to e-mails sent out by ISC in case of fully managed devices.
auditableCommandsFileLocation		string	This property specifies the full path to the file containing the list of prefixes of auditable commands used in the Fully Managed feature.
enforcementAuditScript		string	Script to be invoked when failure of enforcement audit is detected.
externalEventsEmailRecipients	<mailto>	string	The comma or space separated list of email addresses to which notification should be sent out when receiving a config-change event originated outside ISC.

**Table C-1 DCPL Properties (continued)**

/SYSTEM/license/			Properties related to ISC Licensing.
emailRecipients	<mailto>	string	The comma separated list of e-mail addresses to which the License Threshold e-mails should be sent out.
refreshInterval	1	integer, 1-24 hours	License refresh interval in hours.
threshold	90	integer, 1-100%	VPN and ACTIVATION Threshold in percent for e-mail notification.
/SYSTEM/masterServer	<master_server>	string	The master server fully qualified name.
/SYSTEM/maxTaskLimit	500	integer	maxTaskLimit.
/SYSTEM/role	master	string	Identifies the role in the distribution system. Possible values are: master ps (processing server) cs (collection server) is (interface server).
/SYSTEM/tibco/			TIBCO related properties.
port	<tibco_port>	integer	The port on which TIBCO Rendezvous listens for events.
prefix	cisco.vpncs.	string	Prefix for all TIBCO messages originating from ISC.
rva-http-port	<rva_http_port>	integer	The http port for TIBCO Rendezvous agent web interface.
rva-port	<rva_port>	integer	The port on which TIBCO Rendezvous agent listens for events.
/SYSTEM/tmpdir	<vpncs_tmp>	string	Location for temporary files.
<b>Scheduler Properties:</b>			Scheduler reads the task repository and schedules tasks on every minute boundary. Each scheduled task is passed to Task manager for execution.
/Scheduler/logLevel	CONFIG	selection	The log Level indicates the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).

**Table C-1 DCPL Properties (continued)**

/Scheduler/syncInterval	5	integer, 0-10 minutes	When scheduler starts up for the first time, it reads all the scheduling information from the task repository. After that, it depends on the events generated by task repository for receiving changes to the scheduling information. It can also periodically synchronize with the task repository by re-reading it at regular intervals. This property specifies, in minutes, that interval. If the value for the interval is 0, scheduler will not synchronize with the task repository and only depends on the events.
<b>Services Property</b>			Common services.
/Services/common/allowForcePurge	true	The valid values are <b>true</b> and <b>false</b> .	With the default value of <b>true</b> , you can force purge a Service Request. If the value is <b>false</b> , you cannot force purge a Service Request.
<b>SnmpService Properties:</b>			The Snmp Service package provides APIs to perform SNMP get() and set() operations.
/SnmpService/misc			Advanced settings.
enableDebug	false	The valid values are <b>true</b> and <b>false</b> .	Enables the AdventNet SNMP stack debug messages. Messages are written to the TaskLogs directory in files stdout and stderr. Warning: These log files grow quickly and are NOT managed by the ISC logger. Requires WatchDog restart.
rcvPktBuffSize	96	integer, 64-512	Buffer size in K bytes, for SNMP stack receive buffer.
/SnmpService/defaultSNMPVersion	1	integer, 1-2	The default SNMP version used to connect to Cisco router. Used if the SNMP version is not specified per router. Valid Values: SNMPv1/SNMPv2c - 1 SNMPv3 - 2.
/SnmpService/defaultSecurityLevel	3	integer, 1-3	The default security level used to connect to Cisco router. Used if the security level is not specified per router. Values: authentication no encryption - 1 authentication encryption - 2 no authentication no encryption - 3.

**Table C-1 DCPL Properties (continued)**

/SnmpService/logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/SnmpService/maxTaskLimit	500	integer	maxTaskLimit
/SnmpService/retries	3	integer, 0-10	The number of retries to be used by the SNMP protocol.
/SnmpService/timeout	5	integer, 0-300 seconds	Timeout value to be used by the SNMP protocol. Unit: seconds
<b>TE Properties:</b>			Traffic Engineering Management (TEM) Properties
/TE/Deployment			Control the operation of TEM Provisioning
maxCacheSize	60	integer, >0	Maximum cache size.
oneDeviceEachTimeThreshold	500	integer, >0	When the total number of tunnels to be provisioned exceeds this threshold number, provision one device at a time.
partialConfigAudit	false	The valid values are <b>true</b> and <b>false</b> .	When the value is the default of <b>false</b> , the config audit is not limited. When the value is set to <b>true</b> , only a partial config audit (audit of only the PENDING tunnels) occurs for primary and backup tunnel deployment.
/TE/repository			TEM Repository-related Properties
checkPermissionEnabled	false	The valid values are <b>true</b> and <b>false</b> .	This property enables or disables Role-Based Access Control (RBAC) checking during particular TEM operations, such as topology population, discovery, and service deployment. When the value is the default of <b>false</b> , RBAC permission checking is not enabled. When the values is set to <b>true</b> , RBAC permission checking is enabled and performance degrades.
<b>TE Topology Properties:</b>			TEM Topology-related Properties
/TE Topology/TrafficData			Color Control for Traffic Data Displays
Green	0-25	integer, 0-100 (percentage)	Topology representations for a link performance utilization range, specified as a percentage (default: 0-25), are displayed in the color green.

**Table C-1** *DCPL Properties (continued)*

Orange	51-75	integer, 0-100 (percentage)	Topology representations for a link performance utilization range, specified as a percentage (default: 51-75), are displayed in the color orange.
Red	76-100	integer, 0-100 (percentage)	Topology representations for a link performance utilization range, specified as a percentage (default: 76-100), are displayed in the color red. Greater than 100% is also displayed in red.
Yellow	26-50	integer, 0-100 (percentage)	Topology representations for a link performance utilization range, specified as a percentage (default: 26-50), are displayed in the color yellow.
<b>TaskManager Properties:</b>			Task manager executes tasks that are scheduled by scheduler. Task execution consists of executing different actions that comprise the task. Task manager manages the dependencies between these actions.
/TaskManager/CollectConfig			The Collect Config task uploads the running configuration.
logLevel	CONFIG	selection	The log Level indicates the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/TaskManager/logLevel	CONFIG	selection	The log Level indicates the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
<b>VpnInvServer Properties:</b>			Corba Server for VpnInvServer IDL backward compatibility.
/VpnInvServer/logLevel	SEVERE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).

**Table C-1 DCPL Properties (continued)**

<b>aagent Properties:</b>			AAgent component related defines.
/aagent/defaultVersion	3.6.3	string	The default 3k firmware version for AAgent.
/aagent/directories/			Various directories for aagent.
dmd	<vpnsc_home>/resources/AAgent/DMDFiles	string	File path and name.
input	<vpnsc_home>/resources/java/classes/common/AAgent/com/cisco/vpnscagent	string	File path and name.
working	<vpnsc_home>/resources/java/archives	string	File path and name.
<b>cfr Properties:</b>			The Command Flow Runner component. This currently runs within the Tomcat server (in the ISC web application) and is responsible for running MPLSOAM troubleshooting workflows.
/cfr/LogHandler	com.cisco.mgmt.workflow.util.IscLogHandler		Set the CFR to use a custom handler for logging. The handler should log to a separate file and format the log messages using the java.util.logging.SimpleFormatter instead of the ISC default XML formatting.
/cfr/logLevel	INFO		The level of logging information the Command Flow Runner will log (it will log from the set level upwards). The logging levels are as defined in the java.util.logging package.
<b>lockmanager Properties:</b>			Component that handles device locking. When different jobs (such as provisioning) try to update the config on the device, they obtain <b>software</b> locks so that two different jobs do not update the config at the same time. LockManager provides a way to obtain and later release such software locks.

**Table C-1** DCPL Properties (continued)

/lockmanager/collectConfigLock	false	The valid values are <b>true</b> and <b>false</b> .	Determines if a software lock is to be applied to the devices in the CollectConfig task. If <b>true</b> , a software lock is applied to all devices prior to executing the CollectConfig operation, and is released upon completion of the CollectConfig operation. Note that a software lock is not applied to the optional device attributes and interfaces operations. This flag is read by the CollectConfig task upon execution.
/lockmanager/lockTimeoutInHours	8	integer, 1-168 hours	Timeout in hours for a lock held by a lock holder. If the lock holder does not free a lock within this time the lockmanager will automatically release the device lock.
/lockmanager/logLevel	SEVERE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
<b>nbi Properties:</b>			Northbound API (Nbi) component related defines.
/nbi/BackwardCompatible			Path for execQuery requests.
RecordNumber	false	The valid values are <b>true</b> and <b>false</b> .	For execQuery requests, the number embedded in the output class name include <b>Record</b> for the default, <b>false</b> , or <b>Record#1</b> for <b>true</b> .
/nbi/CompositeDir	<vpnsc_home>/resources/java/xml/com/cisco/vpnsc/repository/meta/xml/composite	string	Path to composite XML files. Do not change it or the composite meta XML files will not be backed up.
/nbi/CustomerReportMetaDir	<vpnsc_home>/resources/java/xml/com/cisco/vpnsc/repository/meta/xml	string	Path to user defined report meta XML files. Do not change it or the report meta XML files will not be backed up.
/nbi/Formatter	com.cisco.vpnsc.nbi.io.NbiSimpleFormatter	string	File path and name.

**Table C-1 DCPL Properties (continued)**

/nbi/Logger	com.cisco.vpnsc.nbi.util.NbiVpnscLogger	string	File path and name.
/nbi/MetaCheckInterval	300000	string	Set the time for next meta check to happen.
/nbi/MetaDir	<vpnsc_home>/resources/java/xml/com/cisco/vpnsc/repository/meta/xml	string	Path to meta XML files. Do not change it or the meta XML will not be backed up.
/nbi/ProvidedReportMetaDir	<vpnsc_home>/resources/java/xml/com/cisco/vpnsc/repository/meta/xml	string	Path to ISC provided report meta XML files. Do not change it or the report meta xml files will not be backed up.
/nbi/Reader	com.cisco.vpnsc.nbi.io.NbiSoapReader	string	File path and name.
/nbi/RequestParserMgr	com.cisco.vpnsc.nbi.parser.NbiRequestParserMgr	string	File path and name.
/nbi/SSLfilepath	<vpnsc_home>/bin/client.keystore	string	Path to client.keystore file for NBI SSL connections.
/nbi/SessionTimeout	1200000	string	Amount of time the session is valid.
/nbi/TransactionParser	com.cisco.vpnsc.nbi.parser.NbiWsdlParser	string	File path and name.
/nbi/Validation	true	The valid values are <b>true</b> and <b>false</b> .	Variable to enable validation of incoming Nbi API XML attributes.
/nbi/WaitTimeout	1200	integer	The time in seconds to wait for a Service Request to deploy.
/nbi/Writer/ SoapEncapsulation	false	The valid values are <b>true</b> and <b>false</b> .	SoapEncapsulation.
/nbi/Writer	com.cisco.vpnsc.nbi.io.NbiSoapWriter	string	File path and name.
/nbi/logHandler	com.cisco.vpnsc.nbi.util.VpnscLogHandler	string	Custom log handler for nbi. This handler allows NBI to use alternate formatter from default one used by rest of ISC. In this case, NBI defaults to using SimpleFormatter which dumps simple output as opposed to XML output.



**Table C-1** DCPL Properties (continued)

/nbi/logLevel	WARNING	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging pack age. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
<b>notification Properties:</b>			Event notification related defines.
/notification/Logger	com.cisco.vpnsc.nbi.util.NbiVpnscLogger	string	File path and name.
/notification/clientEnabled	false	The valid values are <b>true</b> and <b>false</b> .	Set to true for enabling the example event receiving servlet.
/notification/clientHost	<master_server>	string	TIBCO event client host.
/notification/clientMethod	/notification/servlet/eventListener	string	TIBCO event client method.
/notification/clientPort	<http_port>	string	TIBCO event client port.
/notification/clientRegFile	<vpnsc_home>/resources/nbi/notification/clientReg.txt	string	Client TIBCO event registration file name.
/notification/logFormatter	java.util.logging.SimpleFormatter	string	File path and name.
/notification/logHandler	com.cisco.vpnsc.nbi.util.VpnscLogHandler	string	Custom log handler.
/notification/logLevel	WARNING	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/notification/password	cisco	string	Both user name and password are same as the ones used for GUI login.
/notification/remotePassword		string	User password for remote system authentication, if required, for example, when LDAP is in use.
/notification/remoteUsername		string	User name for remote system authentication, if required, for example, when LDAP is in use.

**Table C-1 DCPL Properties (continued)**

/notification/username	admin	string	Both user name and password are the same as the ones used for GUI login.
<b>pal Properties:</b>			The PAL Device interaction component. This runs within the Tomcat server and is responsible for running device interaction for the CFR to run the OAM troubleshooting workflows.
/pal/failureScenario			The system parameter that represents the current failure scenario. For use with the Canned Response mechanism for testing.
/pal/logHandler	com.cisco.mgmt.workflow.util.IscLogHandler		Set the PAL to use a custom handler for logging. The handler should log to a separate file and will format the log messages using the java.util.logging.SimpleFormatter instead of the ISC default XML formatting.
/pal/logLevel	INFO		The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/pal/responseDir	/vob/ntg/dev/resources/pal/testnetwork		The base directory where the failure scenarios are held. Used by the canned response mechanism and transport for failure scenario testing.
<b>repository Properties:</b>			The component for Database related properties.
/repository/Concurrency/			To setup properties for re-try loop to avoid deadlock
NOICE_FACTOR	500	integer	Add random noise to each process that is being retried.
NO_OF_RETRIES	3	integer	Number of retries before throwing deadlock exception.
TIME_BASE	2	integer	The base number to calculate the wait time. For example, a value of 2 for this property and 3 retries means, the process will be retried every $2^0$ , $2^1$ , and $2^2$ seconds.
/repository/IPAddressPool/			IP Address Pool Constants.
AGE_TIME	1440	integer	The Aging interval for released IP Address, in minutes. The default is 24 hours (1440 minutes).

**Table C-1** DCPL Properties (continued)

releaseAndReuseAgedAddresses	true	The valid values are <b>true</b> and <b>false</b> .	The default value is <b>false</b> . When the value is set to <b>true</b> , the address will be released from the Aged Pool and moved to the Allocated pool when manually allocated.
/repository/common			Repository common constants.
MCAST_SUBSUME_ALL_SRS	true	The valid values are <b>true</b> and <b>false</b> .	This property set at <b>true</b> indicates that the user wants all the MPLS VPN links of a VPN to be subsumed when Multicast is enabled for that VPN.
/repository/deviceConfig/		null	Configuration file related properties.
maxVersions	10	integer, 1-50	Maximum number of configuration files to be stored per device in the repository before older versions automatically get purged.
/repository/mlshare/			Share directory for both MPLS and L2VPN.
logLevel	SEVERE	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/repository/persistence/			Properties for database.
Versions	5	integer	The number of maximum versions for a Versioning Persistent Objects.
catalog	directory	string	Catalog.
driver	<db_driver>	string	The class name for the driver.
initialConnections	1	integer, 1-20	Number of initial connections.
location	<repository_home>	string	The directory containing the repository.db and repository.log files.
password	sql	string	Password for opening a DB connection.
schema	DBA	string	Schema.
slaur	jdbc:sybase:Tds:<local_db_server>:<db_port_sla>/?JCONNECT_VERSION=5&serviceName=sla	string	The url for opening a JDBC connection to the SLA database.
url	<db_url>	string	The url for opening a JDBC connection.
username	dba	string	User id to open a db connection.
/repository/rbac/			The component for RBAC User Access Model, user Authentication.

**Table C-1 DCPL Properties (continued)**

checkCreatorPermissionEnabled	true	The valid values are <b>true</b> and <b>false</b> .	The creator of objects can give the permissions of Modify or Delete to others. If this flag is false, enable RBAC permission checkin.
checkPermissionEnabled	true	The valid values are <b>true</b> and <b>false</b> .	The creator of objects can give the permissions of Modify or Delete to others. If this flag is false, enable RBAC permission checkin.
enableAutologin	true	The valid values are <b>true</b> and <b>false</b> .	The property controls whether user may store login information in form of cookies on the computer from which the user connects. If enabled, automatic login, based on the cookie information is permitted. Also user is presented with a screen in which he or she can elect to store login information on the local user's computer. With this property set to false no autologin or options associated with it are available.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
partialQueryResultExpected	true	The valid values are <b>true</b> and <b>false</b> .	When checking Permission on a list of Persistent Objects, and the current user does not the specified permission to all the objects in the result list, partial results will be returned if this flag is true; Insufficient Permission exception will be generated if the flag is <b>false</b> .
webSessionTimeoutSec	1800	integer, 1 - 2,147,483,647	Timeout of inactive web client session in seconds. Default is 30 minutes.
/repository/ual/			User Access/Audit Log
cleanUALogs	true	The valid values are <b>true</b> and <b>false</b> .	whether to let system automatically clean up UAL log entries based on ual.maxAgeInDays.
maxAgeInDays	30	integer	Maximum age of the User Access/Audit Logs in days after which the UALog Cleanup Service will delete them. if 0 then UALogs deletion is disabled even if cleanUALogs is set to true.
<b>watchdog Properties:</b>			All the servers in ISC are launched and managed by the Watchdog.

**Table C-1** DCPL Properties (continued)

/watchdog/byRole/			This component contains the watchdog properties that based on the role of the host.
cs/			Watchdog properties for machine playing the role of a cs (Collection Server/Agent).
servers	httpd nspoller worker dbpoller	string	Names of the servers to be run.
db/			Watchdog properties for a machine playing the role of a db (DB server).
servers	dbpoller	string	The servers to be run on a installation with the role <b>db</b> .
is/			Watchdog properties for a machine playing the role of a Interface Server.
servers	httpd dbpoller	string	Names of servers to be run on an installation with role <b>is</b> .
master/			Watchdog properties of a machine playing the role of a master.
servers	httpd nspoller dbpoller dispatcher worker scheduler lockmanager cornerstonebridg e cnsserver	string	The servers to be run.
ps/			Watchdog properties for a machine playing the role of a ps (Processing Server/Agent).
servers	httpd nspoller worker dbpoller	string	Names of servers to be run.
/watchdog/criticalServers		string	If any of these servers enters the disabled state, then it would mean that the system is NOT healthy. If this value is null/empty then every single server is critical.
/watchdog/diskspace/			Contains properties related to disk space monitoring.
dirsToMonitor		string	The directories (and ultimately the disks that contain them) to be monitored.
disksToMonitor		string	The disks to be monitored for space constraints.
emailRecipients	<mailto>	string	The comma separated list of e-mail addresses to which the disk space related e-mails should be sent out.

**Table C-1 DCPL Properties (continued)**

highWatermark	<highwater>	string	High watermark for the directories (disks) being monitored. The value should be a number followed by a < (for percent) or m or M (for Mbytes). These values should correspond to the available/free space on the disk. If the available disk space stabilizes above this value (after falling below the low watermark), an e-mail is sent to the addresses specified in the property watchdog.diskspace.emailRecipients.
lowWatermark	<lowwater>	string	Low watermark for the directories (disks) being monitored. The value should be a number followed by a % (for percent) or m or M (for Mbytes). These values should correspond to the available/free space on the disk. If the available disk space falls below this value, an e-mail is sent to the addresses specified in the property watchdog.diskspace.emailRecipients.
sleepInterval	60000	integer, 30000-300000 milliseconds	Time between two status checks for disk space limits in milliseconds.
/watchdog/group/			Group.
database_users	scheduler httpd	string	The servers that access database.
/watchdog/groups	database_users	string	The space separated list of different groups in the system.
/watchdog/heartbeat/			Properties related to watchdog heartbeat mechanism are specified here.
period	120000	integer, 30000-86400000 milliseconds	The minimum time between each heartbeat request in milliseconds.
sendEvents	false	The valid values are <b>true</b> and <b>false</b> .	If set to true, watchdog sends out TIBCO events every time a heartbeat succeeds or fails. If set to false, no such events will be sent.
startDelay	5000	integer, 0-60000 milliseconds	Time to wait before making the first heartbeat request in milliseconds.
timeout	3000	integer, 1000-600000 milliseconds	The period of time before which response for heartbeat request should be received by the watchdog, in milliseconds.
wds/			Heartbeat properties for intra-watchdog communication.

**Table C-1** DCPL Properties (continued)

delay	5000	integer, 1000-60000 milliseconds	The period in between heartbeats. (from master watchdog to slave watchdog and vice-versa) in milliseconds.
initDelay	1000	integer, 1000-5000 milliseconds	The initial period of time for which the heartbeat thread waits before trying for a heartbeat after a watchdog registers with the MasterWatchdog, in milliseconds.
masterReconnectAttemptDelay	2000	integer, 100-60000 milliseconds	The sleep time between two successive attempts by a slave watchdog to reconnect to master watchdog, in milliseconds.
maxAllowedMisses	3	integer	The maximum number of consecutive misses that a watchdog should miss for the master to consider it inactive or unregistered.
maxAttemptsForMasterReconnect	500	integer	Once the slave watchdog loses connection with the master, it will try this many times to try and establish the connection. If it cannot re-establish a connection with the master even after making these many attempts, it shuts itself down. Between attempts, it sleeps <b>watchdog.heartbeat.wds.masterReconnectAttemptDelay</b> time. The value for this property should be specified in milliseconds. A value of 0 indicates that the slave watchdog has no upper limit on the number of reconnect attempts.
/watchdog/java/			Java.
flags	-XX:+UseAltSig s	string	Any other flags to be passed on to <b>java</b> .
vmtype	-server	string	The flag to be passed on to java (-server or -client).
/watchdog/logLevel	FINEST	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/watchdog/server/	httpd nspoller dbpoller dispatcher worker scheduler lockmanager cornerstonebridg e	string	Server.

**Table C-1 DCPL Properties (continued)**

cnsserver/			Monitors CNS events from IE2100 boxes. Communication between client and server is completely handled using TIBCO events.
heartbeat/			Heartbeat related properties.
startDelay	10000	integer, 0-60000 milliseconds	Time to wait before making the first heartbeat request in milliseconds.
timeout	3000	integer, 1000-600000 milliseconds	The period of time before which response for heartbeat request should be received by the watchdog, in milliseconds.
java/			Java attributes for this server.
flags		string	Any additional java flags specific to this server. If the value is changed, watchdog restart is required for the new value to take effect.
class	com.cisco.vpnsc. watchdog.servers .WDCnsServer	string	Heartbeat Handler - Checks for valid TIBCO Connection.
cmd	java com.cisco.vpnsc. cns.CnsServer	string	Implementation to monitor CNS events from IE2100 boxes.
dependencies	dbpoller	string	Dependencies.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
dbpoller/			This server keeps polling the database to see if it is functional.
class	com.cisco.vpnsc. watchdog.servers .WDDatabase	string	Name of class responsible for getting heartbeats.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
discovery/			Handles various ISC Discovery workflow related tasks.



**Table C-1**      **DCPL Properties (continued)**

class	com.cisco.vpnsc. discovery.engine. server.Discovery Server	string	Heartbeat Handler.
cmd	java com.cisco.vpnsc. discovery.engine. server. DiscoveryImpl	string	Implementation of the Discovery work interface.
dependencies	dbpoller	string	dependencies
heartbeat/			Heartbeat related properties.
startDelay	10000	integer, 0-60000 milliseconds	Time to wait before making the first heartbeat request in milliseconds.
timeout	3000	integer, 1000-60000 milliseconds	The period of time before which response for heartbeat request should be received by the watchdog, in milliseconds.
java/			Java attributes for this server
flags		string	Any additional java flags specific to this server. If the value is changed, watchdog restart is required for the new value to take effect.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
dispatcher/			Dispatcher service of the Distribution framework.
app_args	Dispatcher com.cisco.vpnsc. dist.vpnsc.Vpnsc DispatcherImpl	string	Args to the class that starts this service.
class	com.cisco.vpnsc. watchdog.servers. WDDispatcher	string	The class that proxies this service for the watchdog.
cmd	java com.cisco.vpnsc. watchdog.ext.Ser viceLauncherImp l	string	Command to start the server.
dependencies	dbpoller nspoller	string	The other services that this service depends on Heartbeat related properties.

**Table C-1 DCPL Properties (continued)**

heartbeat/			
startDelay	45000	integer, 0-60000 milliseconds	Time to wait before making the first heartbeat request in milliseconds.
timeout	3000	integer, 1000-60000 milliseconds	The period of time before which response for heartbeat request should be received by the watchdog, in milliseconds.
java/			Java attributes for this server
flags		string	Any additional java flags specific to this server. If the value is changed, watchdog restart is required for the new value to take effect.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
httpd/		httpd	httpd
class	com.cisco.vpnsc. watchdog.servers .WDHtpd	string	Class.
cmd	<vpnsc_home>/ bin/tomcat. sh start fg	string	The command to start httpd on this host.
dependencies	dbpoller	string	Dependencies.
dependenciesByRole/			Dependencies of httpd based on the role of installation (higher priority than normal <b>dependencies</b> )
cs		string	Dependencies on a CS.
ps		string	Dependencies on a PS.
heartbeat/			Heartbeat.
port	<http_port>	integer	The port on which httpd should run.
startDelay	45000	integer, 0-60000 milliseconds	Time to wait before making the first heartbeat request in milliseconds.
timeout	10000	integer, 1000-600000 milliseconds	The period of time before which response for heartbeat request should be received by the watchdog, in milliseconds.
url	http://localhost: <http_port>/isc/ about.htm	string	url

**Table C-1** *DCPL Properties (continued)*

logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
lockmanager/			Component that handles locking.
class	com.cisco.vpnsc. watchdog.servers .WDLockManager	string	Class that keeps track of lockmanager heartbeats.
cmd	java com.cisco.vpnsc. lockmanager.Lock ManagerImpl	string	Command that starts up the lockmanager.
dependencies	nspoller	string	Lock Manager depends on the NS.
heartbeat/			Heartbeat related properties.
startDelay	10000	integer, 0-60000 milliseconds	Time to wait before making the first heartbeat request in milliseconds.
timeout	3000	integer, 1000-600000 seconds	The period of time before which response for heartbeat request should be received by the watchdog, in milliseconds.
java/			Java attributes for this server.
flags		string	Any additional java flags specific to this server. If the value is changed, watchdog restart is required for the new value to take effect.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
maxQuickDieCount	3	integer	The maximum number of times a server can die consecutively without having a successful heartbeat. If this number is exceeded, the server is marked as disabled.
nspoller/			This server polls the NameServer to see if it is running.

**Table C-1 DCPL Properties (continued)**

class	com.cisco.vpnsc. watchdog.servers .WDNameServer	string	Class.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
scheduler/			Scheduler.
class	com.cisco.vpnsc. watchdog.servers .WDScheduler	string	Class.
cmd	java com.cisco.vpnsc. scheduler.Schedu ler	string	Command to start the scheduler.
dependencies	dbpoller worker	string	Dependencies.
heartbeat/			Heartbeat related properties.
startDelay	30000	integer, 0-60000 milliseconds	Time to wait before making the first heartbeat request in milliseconds.
timeout	3000	integer, 1000-600000 milliseconds	The period of time before which response for heartbeat request should be received by the watchdog, in milliseconds.
java/			Java attributes for this server.
flags		string	Any additional java flags specific to this server. If the value is changed, watchdog restart is required for the new value to take effect.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
startTimeout	240000	integer, 5000-600000	The timeout for the initial heartbeat response. The first heartbeat should happen within this time.
worker/			Worker service of the distribution framework.

**Table C-1 DCPL Properties (continued)**

app_args	Worker com.cisco.vpnsc. dist.WorkerImpl, com.cisco.vpnsc. sla.sql.SlaMainte nanceService, com.cisco.vpnsc. repository.ual.U ALCleanupServi ceImpl, com.cisco.vpnsc. license.LicenseS ynchronize, com.cisco.vpnsc. cleanup.TaskLog CleanupService, com.cisco.vpnsc. cleanup.TempFil eCleanupService, com.cisco.vpnsc. cleanup.Runtime TaskCleanupServ ice”	string	Arguments to the class specified in the <b>cmd</b> property.
class	com.cisco.vpnsc. watchdog.servers .WDWorker	string	The server class that proxies Worker service for the watchdog.
cmd	java com.cisco.vpnsc. watchdog.ext.Ser viceLauncherImp l	string	Command to start the worker.
dependencies	nspoller	string	Servers that have to be functioning for this server to function normally.
dependenciesByRole/			Dependencies of httpd based on the role of installation (higher priority than normal <b>dependencies</b> )
cs		string	Dependencies on a CS.
ps		string	Dependencies on a PS.
heartbeat/			Heartbeat related properties.
startDelay	45000	integer, 0-60000 milliseconds	Time to wait before making the first heartbeat request in milliseconds.
timeout	3000	integer, 1000-600000 milliseconds	The period of time before which response for heartbeat request should be received by the watchdog, in milliseconds.
java/			Java attributes for this server.

**Table C-1 DCPL Properties (continued)**

flags	-Xmx512m -Xbootclasspath/ p:<vpnsc_home> /thirdparty/jar/ AdventNetSnm p3_3.2.jar: <vpnsc_home>/ thirdparty/jar/ cryptix32.jar -Dcom.cisco. insmbu.template mgr.backend. PropFile= <vpnsc_home>/ resources/ templatesystem/ Template. properties	string	Any additional java flags specific to this server. If the value is changed, watchdog restart is required for the new value to take effect.
logLevel	CONFIG	selection	The log Level is the level at which logging is done for this component. These levels are identical to the logging levels defined for JDK1.4 logging package. The levels in descending order are: SEVERE (highest value) WARNING INFO CONFIG FINE FINER FINEST (lowest value).
/watchdog/serverStatus/			The properties related to the server status monitoring function provided by the watchdog are specified here.
emailRecipients	<mailto:Restart>	string	Comma separated list of e-mail addresses to which notices about server state changes should be e-mailed
stableTime	60000	integer, 20000-300000 milliseconds	Time in milliseconds that has to pass before a server's status can be considered stable (for the purpose of sending out a server status e-mail notification).
/watchdog/servers	httpd nspoller dbpoller dispatcher worker scheduler lockmanager cornerstonebridg e	string	Server.
/watchdog/waitDelay	3000	integer, 20000-300000 milliseconds	The time period for which the wait() calls in watchdog wait, before checking the wait condition, in milliseconds.
<b>xml Properties:</b>			The component for XML-based properties.

**Table C-1**      **DCPL Properties (continued)**

/xml/queries/			Properties for RepQueryLoader.
filepath	<vpnsc_home>/resources/java/xml/com/cisco/vpnsc/repository/Queries.xml	string	File path and name.







## GLOSSARY

---

### A

<b>access control list</b>	See <i>ACL</i> .
<b>ACL</b>	access control list. A list kept by routers to control access to or from the router for a number of services.
<b>antialiasing</b>	Algorithm used to smooth lines in a topology layout.
<b>API</b>	application programming interface. APIs are supplied as XML schema and CORBA IDL files to customers with Cisco VPN Solutions Center products. After compiling these IDL files to produce language-specific implementation files for the <i>target language</i> of your choosing, you can use these APIs to incorporate MPLS-VPN features in third-party client-application source code. The CORBA version is being deprecated from the product and will not be supported in subsequent versions.
<b>Application Programming Interface</b>	See <i>API</i> .
<b>area</b>	Segments and their attached devices. Areas are usually connected to other areas through routers, making up a single autonomous system. See also <i>AS</i> . See also <i>region</i> .
<b>AS</b>	Collection of networks under a common administration sharing a common routing strategy. Autonomous systems are subdivided by <i>areas</i> or <i>regions</i> . An autonomous system must be assigned a unique 16-bit number by the <i>IANA</i> . Specific to BGP for MPLS VPN Solutions.
<b>ASN</b>	autonomous system number.
<b>ATM</b>	Asynchronous Transfer Mode. The international standard for cell relay in which multiple service types (such as voice, video, or data) are conveyed in fixed-length (53-byte) cells. Fixed-length cells allow cell processing to occur in hardware, thereby reducing transit delays. ATM is designed to take advantage of high-speed transmission media, such as E3, SONET, and T3.
<b>ATMoMPLS</b>	Asynchronous Transfer Mode over Multi-Protocol Label Switching. A type of Layer 2 point-to-point connection running over an MPLS core.
<b>AToM</b>	Any Transport over MPLS.
<b>audit SR (TE)</b>	Tool for auditing the protection of protected TE elements using all existing backup tunnels and proposed changes.
<b>auto bandwidth / auto-bw</b>	A way to configure a tunnel for automatic bandwidth adjustment and to control the manner in which the bandwidth for a tunnel is adjusted.

---

**A**

**autonomous system** See [AS](#).

**autonomous system number** See *ASN*.

---

**B**

**backing store** Function that stores graphics content when moved to the background and regenerates it when moved to the foreground. This helps avoid superfluous refreshing.

**baseline** A set of data collected from targets. For example, the latest configuration files for a list of Cisco Routers, or the latest configuration files, IP unnumbered information, and PVC information for a list of Cisco Routers. MPLS VPN Solution software automatically maintains baselines that correspond to: 1) the latest PE configuration files in the Provider Administrative Domain (with one baseline per PAD); 2) the latest configuration files of the customer edge routers (CEs) and provider edge routers (PEs) in the virtual private networks (VPNs) that the customer has defined. MPLS VPN Solution uses these baselines to create audit and topology reports.

**BECN** backwards explicit congestion notification. This is a concept in Frame Relay networking.

**BGP** Border Gateway Protocol. An interdomain routing protocol designed for the global Internet. Exterior border gateway protocols (EBGPs) communicate among different autonomous systems. Interior border gateway protocols (IBGPs) communicate among routers within a single autonomous system.

**Border Gateway Protocol** See [BGP](#).

**border router** A router at the edge of a provider network that interfaces to another provider's border router using the EBGp protocol.

---

**C**

**CAR** Committed Access Rate. CAR is Cisco's traffic policing tool for instituting a QoS policy at the edge of a network. CAR allows you to identify packets of interest for classification with or without rate limiting. CAR allows you to define a traffic contract in routed networks.

**CDP** Cisco Discovery Protocol. A protocol that is used to discover IOS devices in a network. One of the choices of method for performing device discovery in the ISC Discovery process.

**CE** customer edge router. A CE is part of a customer network and interfaces to a provider edge router (PE). A CE can join any set of virtual private networks (VPNs). Each CE connects a customer site to a [PE](#), obtaining the [VPN](#) service for that [customer site](#), and belongs to exactly one customer. Each CE may have many [configlets](#) and may be configured by multiple service requests.

**CEF** Cisco express forwarding. A layer 3 switching technology inside a router. It defines the fastest method by which a Cisco router uses to forward packets from ingress to egress interfaces.

---

**C**

<b>CERC</b>	customer edge routing community. A component of a VPN that is configured for either full mesh or hub-and-spoke connectivity. A method (using route-target attributes) of describing how CEs in a VPN communicate with each other. CERCs organize a complex VPN into simpler subgroups. Each CERC belongs to one and only one VPN. CERCs can be used to describe the logical topology of the VPN itself.
<b>CERC membership</b>	Relationship between a VRF definition and a CERC. It dictates which <a href="#">CERC</a> a <a href="#">VRF definition</a> is joining and whether it is joining the CERC as either a hub or a spoke.
<b>CIM</b>	Common Information Model from the DMTF. Describes components of a managed environment using an object-oriented modeling approach.
<b>CIM-CX</b>	Common Information Model - Cisco eXtensions. A DMTF CIM-based model.
<b>CIR</b>	committed information rate. This is a concept in Frame Relay networking.
<b>Cisco Service Management</b>	See <a href="#">CSM</a> .
<b>committed access rate</b>	See <a href="#">CAR</a> .
<b>configlet</b>	A configuration fragment that can be downloaded to a CE or PE to modify its current IOS command-set configuration.
<b>conformant tunnel</b>	A well-behaved tunnel that meets the TE management paradigm of ISC. A conformant primary tunnel with zero hold and setup priorities is a managed tunnel.
<b>CORBA</b>	Common Object Request Broker Architecture.
<b>CSM</b>	Cisco Service Management System. The name of Cisco's large-picture project for service management. Many interdependent products fall within this project.
<b>customer</b>	Requests VPN service from a <a href="#">provider</a> . Each customer may own many customer sites.
<b>customer edge router</b>	See <a href="#">CE</a> .
<b>customer edge routing community</b>	See <a href="#">CERC</a> .
<b>customer network</b>	A network under the control of an end customer. The VPN connects the single customer network by connecting the isolated sites.
<b>customer site</b>	A set of IP systems with mutual IP connectivity between them without the use of a VPN. Each customer site belongs to exactly one customer. A customer site can contain any number of CEs.

---

**D**

<b>data-link connection identifier</b>	See <i>DLCI</i> .
<b>data model</b>	A concrete representation of an information model in terms appropriate to a specific data store and access technology.
<b>dCEF</b>	Distributed Cisco expressed forwarding routing. Enables distributed forwarding on versatile interface processors (VIPs).
<b>Device/Topology Based Discovery</b>	One of the methods available for performing ISC device discovery. The Device/Topology Discovery method uses an XML file that provides device names and IP addresses and another XML file that provides information on the interface connections between devices in the network topology.
<b>DHCP</b>	Dynamic Host Configuration Protocol.
<b>DLCI</b>	data-link connection identifier. A value that specifies a private virtual circuit (PVC) or a switched virtual circuit (SVC) in a Frame Relay network.
<b>DMTF</b>	Distributed Management Task Force.
<b>DNS</b>	Domain Naming System. System used in the Internet for translating names of network nodes into addresses.
<b>document type definition</b>	See <i>DTD</i> .
<b>Domain Naming System</b>	See <i>DNS</i> .
<b>double buffer</b>	Smooths the lines in the topology display when dragging elements.
<b>DRAM</b>	dynamic random-access memory. RAM that stores information in capacitors that must be periodically refreshed.
<b>DSCP</b>	Differentiated services code point. A field in the IPv4 ToS byte of the packet header that allows you classify packets into any of 64 classes.
<b>DTD</b>	document type definition.
<b>Dynamic Host Configuration Protocol</b>	See <i>DHCP</i> .
<b>dynamic path</b>	A dynamic path is provisioned by allowing the head router to find a path. The <b>dynamic</b> keyword is then provisioned to the routers.
<b>dynamic random-access memory</b>	See <i>DRAM</i> .

---

**E**

<b>EBGP</b>	exterior border gateway protocol. EBGP (see <a href="#">BGP</a> ) communicate among different network domains.
<b>egress</b>	Traffic leaving the network or device.
<b>E-LAN</b>	An Ethernet LAN Service Type representing a multipoint-to-multipoint Ethernet service in a Metro Ethernet network.
<b>E-Line</b>	An Ethernet Line Service Type representing a point-to-point Ethernet service in a Metro Ethernet network.
<b>EMS</b>	Ethernet Multipoint Service is a port-based multipoint-to-multipoint E-LAN service that is used for transparent LAN applications.
<b>EPL</b>	Ethernet Private Line is a port-based point-to-point E-Line service that maps Layer 2 traffic directly on to a TDM circuit.
<b>ERMS</b>	Ethernet Relay Multipoint Service is a multipoint-to-multipoint VLAN-based E-LAN service that is used primarily for establishing a multipoint-to-multipoint connection between customer routers.
<b>ERS</b>	Ethernet Relay Service is a point-to-point LAN-based E-Line service that is used primarily for establishing a point-to-point connection between customer routers.
<b>Ethernet LAN Service Type</b>	See <a href="#">E-LAN</a> .
<b>Ethernet Line Service Type</b>	See <a href="#">E-Line</a> .
<b>Ethernet Multipoint Service</b>	See <a href="#">EMS</a> .
<b>Ethernet Private Line</b>	See <a href="#">EPL</a> .
<b>Ethernet Relay Multipoint Service</b>	See <a href="#">ERMS</a> .
<b>Ethernet Relay Service</b>	See <a href="#">ERS</a> .
<b>Ethernet Virtual Connection</b>	See <a href="#">EVC</a> .
<b>Ethernet Wire Service</b>	See <a href="#">EWS</a> .
<b>EVC</b>	An Ethernet Virtual Connection in Metro Ethernet with an association of two or more UNIs that limits the exchange of service frames to UNIs within the EVC.
<b>EWS</b>	Ethernet Wire Service is a point-to-point port-based E-Line service that is used primarily to connect geographically remote LANs over a service provider network.

---

**E**

**Extensible Markup Language** See [XML](#).

**EWS** An Ethernet Wire Service is a point-to-point-based E-Line service that is used primarily to connect geographically remote LANs over a Service Provider network.

**exterior border gateway protocol** See [EBGP](#).

---

**F**

**Fast Re-Route (FRR) protection** Provides link protection to Label-Switched Paths (LSPs). This enables all traffic carried by LSPs that traverse a failed link to be rerouted around the failure.

**FRoMPLS** Frame Relay over Multi-Protocol Label Switching. A type of Layer 2 point-to-point connection running over an MPLS core.

---

**G**

**Gigabit Switch Router** See [GSR](#).

**global pool** The bandwidth of TE enabled interfaces is assigned a number of nested bandwidth pools. The global pool represents the total bandwidth that can be reserved out of the total link bandwidth.

**grooming** Grooming is a TE tool that works on the whole network to optimize the placement of existing managed tunnels. It is only available when no tunnel attributes have been changed.

**GSR** Gigabit Switch Router.

---

**H**

**hold priority** Priority associated with a Label-Switched Path (LSP) for the tunnel to determine if it should be preempted by other LSPs that are being signaled.

**Hyper text Transfer Protocol** See [HTTP](#).

**HTTP** Hyper text Transfer Protocol. An application protocol running on TCP/IP and the World Wide Web

**HTTPS** Secure HTTP. Secure HTTP (HTTPS) provides the capability to connect to the Cisco IOS HTTPS server securely. It uses Secure Sockets Layer (SSL) and Transport Layer Security (TLS) to provide device authentication and data encryption.

<b>IANA</b>	Internet Assigned Numbers Authority. Organization operated under the auspices of the ISOC as a part of the IAB. IANA delegates authority for IP address-space allocation and domain-name assignment to the InterNIC and other organizations. IANA also maintains a database of assigned protocol identifiers used in the TCP/IP stack, including BGP autonomous system numbers.
<b>IBGP</b>	interior border gateway protocol. IBGPs (see <a href="#">BGP</a> ) communicate among routers within a single network domain.
<b>ICMP</b>	Internet Control Message Protocol. Network layer Internet protocol that reports errors and provides other information relevant to IP packet processing.
<b>IDL</b>	Interface Definition Language. Generic language for describing <a href="#">APIs</a> for <a href="#">API</a> servers. IDL API files must be compiled using an IDL compiler from an approved CORBA vendor to produce language-specific API files in a CORBA-supported <a href="#">target language</a> . Using the generated target-language files you can add API-supported features to third-party client-application source code.
<b>information model</b>	An abstraction and representation of the entities in a managed environment - their properties, operations, and relationships. It is independent of any specific repository, application, protocol, or platform.
<b>ingress</b>	Traffic entering the network or device.
<b>Interface Definition Language</b>	See <a href="#">IDL</a> .
<b>interior border gateway protocol</b>	See <a href="#">IBGP</a> .
<b>Internet Control Message Protocol</b>	See <a href="#">ICMP</a> .
<b>internet-service provider</b>	See <a href="#">ISP</a> .
<b>inter-switch link</b>	See <a href="#">ISL</a> .
<b>IPv4</b>	Internet Protocol, version 4. A version of IP that support a 32-bit address space.
<b>IPv6</b>	Internet Protocol, version 6. A version of IP that support a 128-bit address space.
<b>ISC</b>	Cisco IP Solution Center.
<b>ISC Discovery</b>	An automated process that allows ISC to discover the devices in a MPLS VPN network or a L2VPN Metro Ethernet network.
<b>ISL</b>	Inter-Switch Link. Provider of internet access and services through single BGP autonomous system.
<b>ISP</b>	internet-service provider. Provider of internet access and services through single BGP autonomous system.

---

**L**

<b>L2VPN</b>	Layer 2 Virtual Private Network.
<b>L2TPv3</b>	Layer 2 Tunnel Protocol Version 3.
<b>label-switched path</b>	See <a href="#">LSP</a> .
<b>link speed factor</b>	TE multiplication factor to be applied to the link speed to determine the amount of bandwidth that must be protected.
<b>LSP</b>	Sequence of routers that cooperatively perform MPLS operations for a packet stream. The first router in an LSP is called the ingress router, and the last router in the path is called the egress router. An LSP is a point-to-point, half-duplex connection from the ingress router to the egress router. (The ingress and egress routers cannot be the same router.)

---

**M**

<b>managed tunnel</b>	The concept of managed tunnels is at the center of TE planning activities. A managed tunnel is a primary TE tunnel characterized by having a setup/hold priority of zero, a non-zero bandwidth, and a valid explicit path. A non-zero bandwidth is defined to be non-zero Resource Reservation Protocol (RSVP) bandwidth or non-zero maximum auto bandwidth if auto bandwidth is enabled.
<b>manage lock</b>	Whenever a task updates the TE database and it might affect the resource and hence the result of a tunnel computation, it locks the system before the update and releases it at completion of the update. Manage lock is a capability provided in the GUI to release the lock under error conditions.
<b>management information base</b>	See <i>MIB</i> .
<b>MCE</b>	Management Customer Edge Router. The MCE is a required element in some MPLS VPN topologies. The network management subnet, which consists of the MPLS VPN Solution and Cisco IP Manager workstations on a single local area network (LAN), connects directly to an MCE.
<b>Metro Ethernet</b>	Metro Ethernet services use Ethernet technology to deliver cost-effective, high-speed connectivity for metropolitan-area network (MAN) and wide-area network (WAN) applications.
<b>MIB</b>	management information base.
<b>MLPPP</b>	Multilink Point-to-Point Protocol. Method of splitting, recombining, and sequencing datagrams across multiple, logical data links.
<b>MPE</b>	Management Provider Edge Router. The MPE is an element in some MPLS VPN topologies. The network management subnet connect directly to an MCE, which in turn is connected to an MPE.
<b>MPLS</b>	multi protocol label switching. An emerging standard based on a Cisco Tag Switching technology.
<b>MPLS TE tunnel</b>	multiprotocol label switching traffic engineering (MPLS TE) tunnel. Can be a primary or a backup tunnel.



---

**M**

<b>MPLS VPN</b>	multi protocol label switching virtual private network. For MPLS VPN Solution, it is a set of <i>PEs</i> that are connected via a common “backbone” network to supply private IP interconnectivity between two or more <i>customer sites</i> for a given <i>customer</i> . Each VPN has a set of provisioning templates/policies ( <i>CERC</i> ) and can span multiple <i>Provider Administrative Domains</i> but has a default provider administrative domain for <i>RD</i> and <i>RT</i> auto-allocation purposes. CERCs in a VPN break down complex topology into multiple subgroups.
<b>multilink point-to-point protocol</b>	See MLPP.
<b>multipoint-to-multipoint</b>	In Metro Ethernet, a connection type consisting of single multipoint-to-multipoint Ethernet circuits provisioned between two or more UNIs.
<b>multi protocol label switching</b>	See <i>MPLS</i> .
<b>multi protocol label switching virtual private network</b>	See <i>MPLS VPN</i> .
<b>Multi-VRF CE</b>	multi-VPN routing and forwarding tables CE (MVRFCE) is a feature that provides for Layer 3 aggregation. Multiple CEs can connect to a single Multi-VRF CE (typically in an enterprise network); then the Multi-VRF CE connects directly to a PE.

---

**N**

<b>network</b>	In MPLS VPN Solution, a collection of targets with unique names.
<b>Network-facing Provider Edge</b>	See <i>N-PE</i> .
<b>network management subnet</b>	Consists of the MPLS VPN Solution and Cisco IP Manager workstations on a single LAN. The network management subnet connects directly to an MCE.
<b>non-conformant tunnel</b>	A TE tunnel, which might impact ISC TEM's ability to meet bandwidth guarantees. This could be due to unknown bandwidth requirements such as no max bandwidth configured for auto-bandwidth, potential for pre-emption, dynamic paths, etc. A zero priority unmanaged tunnel would also be a non-conformant tunnel.
<b>N-PE</b>	Network-facing Provider Edge within the Edge layer in a Metro Ethernet network.

---

**O**

**OSS** Operations Support System. Network management system supporting a specific management function, such as alarm surveillance and provisioning, in a carrier network.

**operations support system** See *OSS*.

---

**P**

**PAD** Provider Administrative Domain. Set of all PE devices in one BGP autonomous system. An administrative domain defined by an Internet Service Provider. The network owned by the PAD is called a backbone network. Each PAD includes a route distinguisher and route target and IP address pools. Each PAD can have any number of regions within it. If an ISP requires two AS numbers, it must consist of two provider administrative domains. Each provider administrative domain has regions that have a route distinguisher (*RD*), a route target (*RT*), and an IP address pool from which to automatically generate IP values during provisioning. Each provider administrative domain can have many *regions*.

**PE** provider edge router. A router at the edge of a provider network that interfaces to CE routers. Each PE belongs to exactly one *region* of a *Provider Administrative Domain* and connects to one or more *customer sites*. Each PE can have many *VRF* definitions and configlets, and each can be configured by many service requests.

**PE-AGG** Provider edge aggregation (PE-AGG) within the Aggregation layer in a Metro Ethernet network.

**permanent virtual circuit.** See *PVC*.

**Point-to-Point Ethernet** A network architecture delivered with the Cisco Metro Ethernet offering. It supports both EWS and ERS services.

**projection (topology map)** A map projection is a topology function, which maps a sphere onto a plane.

**propagation delay** The time it takes for traffic to travel along a link from the head interface to the tail interface.

**provider** A party supplying internet service for its *customer*. See also *ISP*.

**Provider Administrative Domain** See *PAD*.

**Provider edge aggregation** See *PE-AGG*.

**provider edge router** See *PE*.

---

**P**

<b>provider network</b>	A backbone network under the control of a service provider that provides transport services between customer sites.
<b>PVC</b>	permanent virtual circuit. This is applicable to Frame Relay and Asynchronous Transfer Mode.

---

**Q**

<b>QoS</b>	Quality of Service. The mechanisms that give network managers the ability to control the mix of bandwidth, delay, jitter, and packet loss in the network. QoS is not a device feature, it is an end-to-end system architecture.
<b>quality of Service</b>	See <i>QoS</i> .

---

**R**

<b>RD</b>	Route Distinguisher. A 64-bit value that is added to an IPv4 prefix to create a unique VPN prefix. Each VRF has an RD.
<b>region</b>	A group of provider edge routers (PEs) within a single BGP autonomous system. Provider Administrative Domains are divided into regions just as customers are divided into sites. Each region belongs to exactly one provider administrative domain and can have many PEs. Regions allow a provider to employ unique IP address pools in large geographical regions. Each region is represented in the VPN Inventory Repository by a Region object.
<b>Residual Bandwidth Reservation</b>	The discrepancy between bandwidth reservations discovered for each link and bandwidth reserved by tunnels that ISC is aware of.
<b>response time reporter</b>	Renamed to service assurance agent (SA Agent).
<b>RG</b>	The Route Generator is a placement tool used in ISC Traffic Engineering Management to achieve optimization and bandwidth protection in the network.
<b>RIP</b>	Routing Information Protocol. The simplest Interior Gateway Protocol (IGP) in the Internet.
<b>round-trip time</b>	See <a href="#">RTT</a> .
<b>route distinguisher</b>	See <a href="#">RD</a> .
<b>Route Generator</b>	See <a href="#">RG</a> .
<b>route target</b>	See <a href="#">RT</a> .
<b>Routing Information Protocol</b>	See <a href="#">RIP</a> .
<b>RT</b>	Route Target. A 64-bit value by which the IOS discriminates routes for route updates in VRFs.

---

**R**

<b>RTR</b>	Renamed to Service Assurance Agent (SA Agent).
<b>RTT</b>	Round-trip time. The total time required for a packet to traverse a network to its destination and back again.

---

**S**

<b>SA Agent</b>	Service Assurance Agent. SA Agent provides Round-Trip Time for various protocols: DHCP, DNS, HTTP, ICMP Echo, Jitter, TCP Connect, and UDP Echo.
<b>schema</b>	A set of data models that describe a set of objects to be managed.
<b>seed router</b>	The TE network discovery process uses a seed router as an initial communication point to discover the MPLS TE network topology.
<b>Service Assurance Agent</b>	See <a href="#">SA Agent</a> .
<b>service level agreement</b>	See <a href="#">SLA</a> .
<b>setup priority</b>	Priority used when signaling a Label-Switched Path (LSP) for the tunnel to determine which of the existing tunnels can be preempted.
<b>Shared-Risk Link Group</b>	See <a href="#">SRLG</a> .
<b>site</b>	A component of a customer. A collection of one or more customer edge routers (CEs).
<b>SLA</b>	Service Level Agreement. Service-Level Agreements (SLAs) are negotiated contracts between VPN providers and their subscribers. An SLA defines the criteria for the specific services that the subscriber expects the provider to deliver. The SLA is the only binding mechanism at the subscriber's disposal to ensure that the VPN provider delivers the services as agreed.
<b>SOAP</b>	A lightweight protocol for exchange of information in a decentralized, distributed environment. It is an XML based protocol that consists of three parts: an envelope that defines a framework for describing what is in a message and how to process it, a set of encoding rules for expressing instances of application-defined datatypes, and a convention for representing remote procedure calls and responses.
<b>SNMP</b>	Simple Network Management Protocol.
<b>SP</b>	Service Provider.
<b>SRLG</b>	In Traffic Engineering, a Shared-Risk Link Group (SRLG) identifies links with common physical characteristics that could fail as a group during a single failure event.
<b>Static route</b>	Route that is explicitly configured and entered into the routing table. Static routes take precedence over routes chosen by dynamic routing protocols.
<b>storm control</b>	Interface configuration settings to help prevent a UNI port from being disrupted by a broadcast, multicast, or unicast storm.

---

**S**

<b>sub pool</b>	The bandwidth of TE enabled interfaces is assigned a number of nested bandwidth pools. A sub pool is a bandwidth pool nested inside a global pool. Thus, if for example a primary tunnel reserves bandwidth from the sub pool, it will also reserve the same bandwidth from the global pool.
<b>system path</b>	An ISC system generated explicit path (immovable unless the tunnel is set to be reroutable). The first path has to be an explicit path.

---

**T**

<b>target</b>	Single device from which information may be collected. A target may be a router. Any device (customer edge router, provider edge router, or RMON probe) from which the MPLS VPN Solution software can collect information.
<b>target language</b>	<a href="#">CORBA</a> -supported programming language to be generated by the <a href="#">IDL</a> compiler based on the IDL <a href="#">API</a> files. The generated target-language files can then be used to incorporate API-supported features in third-party client-application source code. For a complete list of CORBA-supported target languages, see the Object Modeling Group web site.
<b>TCP</b>	Transmission Control Protocol. Connection-oriented transport layer protocol that provides reliable full-duplex data transmission.
<b>TE</b>	traffic engineering.
<b>TE discovery</b>	An ISC task used to populate the repository with the TE network element and data.
<b>TE explicit path</b>	A fixed path from a specific head to a specific destination device. Paths are defined between source and destination routers, possibly with one or more hops in between.
<b>TE functional audit</b>	A task that checks the Label-Switched Path (LSP) used on a router at a given moment against the LSP stored in the repository.
<b>TE link</b>	A link between two TE enabled interfaces.
<b>TEM</b>	Traffic Engineering Management is an ISC implementation of the Traffic Engineering (TE) technology.
<b>TE metric</b>	Metric used to override the Interior Gateway Protocol (IGP) administrative weight (cost) of a TE link.
<b>TE node</b>	A TE enabled node.
<b>TE policy</b>	A set of rules established for a tunnel to carry TE traffic.
<b>TE provider</b>	The TE provider is a concept designed to allow the network management application to manage many different operators simultaneously, each working on different networks.
<b>TE topology</b>	A TE topology provides a graphical representation of the various network elements in a TE network, such as devices, links, and tunnels.
<b>TE traffic admission</b>	Also referred to as tunnel admission. It is the first step towards enabling services on TE tunnels by assigning traffic to traffic-engineered tunnels.
<b>TE tunnel</b>	See MPLS TE tunnel.

---

**T**

<b>Transmission Control Protocol</b>	See <a href="#">TCP</a> .
<b>tunnel audit</b>	When any type of change to the TE network is required, whether tunnel or resource modifications, a tunnel audit is run to determine what inconsistencies the change might cause, if any.
<b>tunnel placement</b>	Tunnel placement is a TE tool for calculating optimal paths for new or changed tunnels in the existing network.
<b>tunnel repair</b>	As changes are made to bandwidth requirements or delay parameters of existing TE tunnels, tunnel placement can create inconsistencies. Tunnel repair is designed to address such inconsistencies. The objective of tunnel repair is to try to move as few existing tunnels as possible to accommodate the changes.

---

**U**

<b>UDP</b>	User Datagram Protocol. Connectionless transport layer protocol in the TCP/IP protocol stack. UDP is a simple protocol that exchanges datagrams without acknowledgments or guaranteed delivery, requiring that error processing and retransmission be handled by other protocols.
<b>unmanaged tunnel</b>	An unmanaged tunnel is any tunnel that is not managed. See managed tunnel.
<b>U-PE</b>	The User-facing Provider Edge within the Access layer in a Metro Ethernet network.
<b>User Datagram Protocol</b>	See <a href="#">UDP</a> .
<b>User-facing Provider Edge</b>	See <a href="#">U-PE</a> .
<b>user role</b>	A user role is a predefined or a user-specified role defining a set of permissions.

---

**V**

<b>VCI</b>	virtual channel identifier. Used in ATM networking concept.
<b>virtual channel identifier</b>	See <a href="#">VCI</a> .
<b>virtual LAN</b>	See <a href="#">VLAN</a> .
<b>virtual path identifier</b>	See <a href="#">VPI</a> .
<b>virtual private network</b>	See <a href="#">VPN</a> .
<b>VLAN</b>	virtual LAN. Group of devices on a LAN that are configured so they can communicate as if they were attached to the same wire, when in fact they are located on a number of different LAN segments.

---

**V**

<b>VLAN Translation</b>	A technique used to pass frames between subinterfaces with different VLAN IDs. This allows frames entering a device with one VLAN ID to exit with a different VLAN ID. VLAN translation provides flexibility in managing VLANs, as well as Metro Ethernet-related services. There are two types of VLAN translation—1 to 1 (1:1) and 2 to 1 (2:1).
<b>VoIP</b>	voice over internet protocol.
<b>VPI</b>	virtual path identifier. The VPI, together with the VCI, is used to identify the next destination of a cell as it passes through a series of ATM switches on its way to its destination.
<b>VPIM</b>	VPN Provisioning and Inventory Manager.
<b>VPLS</b>	Virtual Private LAN Service.
<b>VPN</b>	Virtual Private Network. A framework that provides private IP networking over a public infrastructure such as the Internet. In MPLS VPN Solution, a VPN is a set of customer sites that are configured to communicate through a VPN service. A VPN is a network in which two sites can communicate over the provider's network in a private manner; that is, no site outside the VPN can intercept their packets or inject new packets. The provider network is configured such that only one VPN's packets can be transmitted through that VPN—that is, no data can come in or out of the VPN unless it is specifically configured to allow it. There is a physical connection from the provider edge network to the customer edge network, so authentication in the conventional sense is not required. A VPN is a private network constructed within a public network infrastructure, such as the Internet. A VPN is a communications environment in which access is controlled to permit peer connections only within a defined community of interest, and is constructed through some form of partitioning of a common underlying communications medium, where this communications medium provides services to the network on a nonexclusive basis.
<b>VPN customer</b>	Owner of VPN.
<b>VPN routing/forwarding instance</b>	See <a href="#">VRF</a> .
<b>VRF definition</b>	The configuration information for a <a href="#">VPN routing/forwarding instance</a> ( <a href="#">VRF</a> ) table for <a href="#">PEs</a> that share a common route-target ( <a href="#">RT</a> ) signature. In the VPN inventory repository, a VRF definition is a template by which to define a VRF table in a <a href="#">PE</a> .
<b>VRF</b>	VPN routing/forwarding instance. A routing table that is populated with VPN routes. A VRF is an IOS route table instance for connecting a set of sites to a VPN service.

---

**W**

<b>WSDL</b>	Web Services Definition Language
-------------	----------------------------------

---

**X**

<b>XML</b>	Extensible Markup Language.
------------	-----------------------------

## V

<b>XML API</b>	A programmatic interface to ISC used by OSS systems. The XML API is implement in a SOAP over HTTP format and provides full ISC functionality.
<b>XML Schema</b>	A specific format (.xsd) to describe XML structures (for example, metadata).





---

## A

AAA server [1-11, 3-2, 3-140](#)  
aagent properties [C-34](#)  
about [1-6](#)  
access domain  
    create [3-121](#)  
access domains  
    creating [4-50](#)  
accessing reports [7-42](#)  
account [1-5](#)  
active users [1-16, 9-1, 9-34](#)  
admin [1-2](#)  
Administration [1-2, 1-3, 1-15, 9-1](#)  
advanced filter [9-36](#)  
advanced operation method [5-2](#)  
advanced task configuration method [7-3](#)  
append [5-6](#)  
as-number tag [4-19, A-1](#)  
assigning [3-33](#)  
audience [xxx](#)  
AutoDiscovery property [C-1](#)  
autonomous system number [4-19, A-1](#)  
auto refresh [1-8](#)

---

## B

background daemon [2-1](#)  
bootstrapping [2-1](#)  
Broken state [3-3](#)  
buckets [7-15](#)

---

## C

CDP button [4-28](#)  
CDP Discovery  
    verifying CDP is running [4-16](#)  
CDP tag [4-21](#)  
CERC [1-11, 3-132](#)  
    access [3-133](#)  
    delete [3-135](#)  
CERCs [3-2](#)  
CE roles  
    assigning [4-43](#)  
    DIRECT-CONNECTED-MGMT-HOST role [4-45](#)  
    DIRECT-CONNECTED-REGULAR role [4-45](#)  
    edit [4-45](#)  
    MANAGED-MGMT-LAN role [4-45](#)  
    MANAGED-REGULAR role [4-45](#)  
    MULTI-VRF role [4-45](#)  
    UNMANAGED [4-45](#)  
    UNMANAGED-MGMT-LAN role [4-45](#)  
    UNMANAGED-MULTI-VRF role [4-45](#)  
CE routing community [1-11, 3-2, 3-132](#)  
    access [3-133](#)  
    delete [3-135](#)  
cfr properties [C-34](#)  
Cisco MPLS Diagnostics Expert [1-3, 1-14, 8-1](#)  
Cleanup properties [C-1](#)  
closed state [3-3](#)  
CNS attributes  
    edit [4-35](#)  
CNS device access protocol [B-3](#)  
CNS IE2100 appliance [B-1](#)  
    create [B-1](#)

- cnsrserver server [2-10](#)
- collect config [7-3](#)
- Collect Config Task
  - creating and running [4-77](#)
- collection zones [1-16, 9-30](#)
- color coding [1-8](#)
- commands
  - startdb [2-1](#)
  - startns [2-2](#)
  - startwd [2-2](#)
  - stopall [2-3](#)
  - stopdb [2-3](#)
  - stopns [2-4](#)
  - stopwd [2-4](#)
  - watchdog [2-1](#)
  - wdclient [2-5](#)
- components, GUI [1-6](#)
- config audit [7-5](#)
- configuration collection [4-36](#)
- configuration files [3-6](#)
- configurations
  - view [6-3](#)
- configuration to display [5-8](#)
- connection tag [4-25](#)
- control center [1-16, 9-1, 9-23](#)
- conventions [xxxi](#)
- copy
  - users [9-5](#)
- cornerstone bridge server [2-10](#)
- CPE devices
  - configuring SSH connectivity [3-69](#)
- create [3-101](#)
  - template [6-5](#)
  - user groups [9-8](#)
  - user role [9-11, 9-17](#)
- create-customer tag [4-19, A-2](#)
- create data file [6-3, 6-14](#)
- create-provider rule [4-19, A-2](#)
- create-region rule [4-19, A-2](#)
- create-site rule [4-19, A-2](#)
- create template [6-3](#)
- customer [1-11, 3-2, 3-106](#)
  - access [3-106](#)
  - associating with devices [9-14](#)
  - create [3-107](#)
  - definition [9-10](#)
  - delete [3-109](#)
  - edit [3-108](#)
- customer context [1-6](#)
- customer-name tag [4-19, A-2](#)
- customer site
  - create [3-110](#)
- custom reports [7-46](#)

---

## D

- data file
  - delete [6-20](#)
  - edit [6-19](#)
- data file name [6-16](#)
- dbpoller server [2-10](#)
- DCPL properties [C-1](#)
  - aagent [C-34](#)
  - AutoDiscovery [C-1](#)
  - cfr [C-34](#)
  - Cleanup [C-1](#)
  - DCS [C-2](#)
  - DeploymentFlow [C-9](#)
  - Discovery [C-9](#)
  - DistributionFramework [C-12](#)
  - GSAM [C-13](#)
  - GTL [C-13](#)
  - GUI [C-15](#)
  - JavaWebStart [C-18](#)
  - lockmanager [C-34](#)
  - Logging [C-18](#)
  - nbi [C-35](#)
  - notification [C-37](#)

- pal [C-38](#)
- Provisioning [C-19](#)
- repository [C-38](#)
- Scheduler [C-30](#)
- Services [C-31](#)
- SLA [C-28](#)
- SnmpService [C-31](#)
- SYSTEM [C-29](#)
- TaskManager [C-33](#)
- TE [C-32](#)
- TE Topology [C-32](#)
- VpnInvServer [C-33](#)
- watchdog [C-40](#)
- xml [C-50](#)
- DCS properties [C-2](#)
- delete
  - template [6-3](#)
  - user groups [9-9](#)
  - user roles [9-16, 9-19](#)
  - users [9-6](#)
- deployed state [3-3](#)
- DeploymentFlow property [C-9](#)
- detailed reports [7-42](#)
- device [1-11, 3-2, 3-68](#)
  - copy [3-99](#)
  - creation [3-74](#)
  - delete [3-95](#)
  - deleting [4-55](#)
  - edit [3-92](#)
  - e-mail [3-105](#)
  - inserting into an NPC topology [4-55](#)
- device.xml file
  - description [4-22](#)
  - editing [4-24](#)
  - sample file [4-22](#)
- Device/Topology button [4-28](#)
- device access protocol [5-9](#)
- device assignment display
  - changing [4-38](#)
- device configuration, edit [3-96](#)
- device configuration manager [1-12, 5-7](#)
- device configurations
  - editing [4-31](#)
- device console [1-12, 5-1](#)
  - device configuration manager [5-7](#)
  - download commands [5-2](#)
  - download template [5-3](#)
  - EXEC commands [5-9](#)
  - reload [5-13](#)
- device discovery [4-26](#)
- device group [1-11, 3-2, 3-100, 3-101](#)
  - access [3-101](#)
  - delete [3-104](#)
  - edit [3-104](#)
- device-name tag [A-2](#)
  - XML tags
    - device-name tag [4-23](#)
- device owner, e-mail [3-98](#)
- device roles
  - general description [4-40](#)
- Devices File field [4-29](#)
- device tag [A-2](#)
- DHCP protocol [7-29](#)
- DIA-channelization template folder [6-22](#)
- Diagnostics Expert [1-3, 1-14](#)
- diagnostic tools [2-5](#)
- DIRECT-CONNECTED-MGMT-HOST role [4-45](#)
- DIRECT-CONNECTED-REGULAR role [4-45](#)
- disabled\_dependent state [2-10](#)
- disabled state [2-11](#)
- Discovery
  - configuration collection [4-36](#)
  - description of workflow
    - for ISC L2VPN Management [4-8](#)
    - for ISC MPLS VPN Management [4-8](#)
    - for MPLS Diagnostics expert [4-12](#)
  - device discovery [4-26](#)
  - L2VPN (Metro Ethernet) service discovery phase [4-65](#)

launching Discovery [4-27](#)  
 logs [4-4](#)  
 MPLS VPN service discovery phase [4-56](#)  
 NPC discovery phase [4-49](#)  
 overview [4-1](#)  
 preliminary steps [4-13](#)  
 process illustrated [4-2](#)  
 required XML files [4-17](#)  
 role assignment [4-36](#)  
 summary  
     for ISC MPLS VPN Management [4-6](#)  
     for MPLS Diagnostics Expert [4-10](#)  
 summary for ISC L2VPN Management [4-6](#)  
 summary of methods [4-2](#)  
 technical notes [4-3](#)  
 using Restart button [4-4](#)  
 using with Cisco ISC MPLS VPN Management [4-5](#)  
 using with ISC L2VPN Management [4-5](#)  
 using with ISC Traffic Engineering Management [4-6](#)  
 using with MPLS Diagnostics Expert [4-5](#)  
 discovery [1-12](#)  
 DISCOVERY\_METHOD tag [4-21, A-2](#)  
     XML tags  
         DISCOVERY\_METHOD [A-2](#)  
 Discovery properties [C-9](#)  
 discovery-protocol tag [4-25, A-2](#)  
 dispatcher server [2-10](#)  
 DistributionFramework properties [C-12](#)  
 DNS protocol [7-28](#)  
 documentation [xxix](#)  
 download commands [1-12, 5-2](#)  
 download template [1-12, 5-3](#)  
 download to running [5-9](#)  
 download to startup [5-9](#)  
 dynamic Java class type [6-13](#)  
 dynamic URL type [6-13](#)

---

## E

edit  
     device configurations [4-31](#)  
     user groups [9-8](#)  
     user roles [9-15, 9-19](#)  
     users [9-6](#)  
 editing [3-24](#)  
 editing XML files  
     inventory.xml [4-19](#)  
 edit template [6-3](#)  
 e-mail, device group [3-105](#)  
 e-mail device owner [3-98](#)  
 e-mailing reports [7-46](#)  
 enable traps [7-15](#)  
 end to end wire  
     editing VPN associated with [4-71](#)  
 examples template folder [6-22](#)  
 EXEC commands [1-12, 5-9](#)  
 exec time column [2-11](#)  
 exporting reports [7-45](#)

---

## F

failed audit state [3-3](#)  
 failed deploy state [3-3](#)  
 falling threshold [7-15](#)  
 filter [1-7](#)  
     advanced [9-36](#)  
     simple [9-36](#)  
 float type [6-10](#)  
 frequency [7-14](#)  
 fromDevice tag [4-25, A-2](#)  
 FromInterface tag [4-26, A-2](#)  
 FromIP tag [4-25, A-3](#)  
 ftp [5-9](#)  
 FTP protocol [7-27](#)  
 Full Mesh topology [4-58](#)  
 Functional state [3-3](#)

## G

gen column [2-11](#)  
 general device attributes  
   edit [4-34](#)  
 getting started [1-1](#)  
 glossary [GL-1](#)  
 go to page [1-7](#)  
 GSAM property [C-13](#)  
 GTL properties [C-13](#)  
 GUI components [1-6](#)  
 GUI properties [C-15](#)  
 GUI reports [7-42](#)

## H

header check box [1-7](#)  
 header row [1-7](#)  
 help [1-5](#)  
 Home screen [1-2, 1-3, 7-1, 8-1, 9-1](#)  
 hop tag [4-21, A-3](#)  
 hosts [1-16, 9-23](#)  
   config [9-25](#)  
   details [9-24](#)  
   servers [9-26](#)  
   Watchdog [9-27](#)  
 HTTP CoS report [7-40](#)  
 httpd server [2-10](#)  
 HTTP protocol [7-28](#)  
 HTTP report [7-39](#)  
 Hub and Spoke topology [4-58](#)

## I

ICMP Echo protocol [7-25](#)  
 icons [1-10](#)  
 IE2100 appliance  
   create [B-1](#)

## IM

  accessing IM [3-5](#)  
   assigning devices [3-33](#)  
   importing devices with configuration files [3-6](#)  
   launching IM [3-37](#)  
   opening customers [3-24](#)  
   opening devices [3-7](#)  
   opening providers [3-15](#)  
 importing devices with configuration files [3-6](#)  
 index [1-5](#)  
 installation  
   remote [9-28](#)  
 integer type [6-9](#)  
 inter-N-PE interfaces  
   edit [4-50](#)  
 introduction [1-1](#)  
 invalid state [3-3](#)  
 inventory.xml file  
   editing [4-17, 4-19](#)  
   sample file [4-18](#)  
   XML tags used [4-19](#)  
 Inventory and Connection Manager [1-11, 3-1](#)  
 Inventory File field [4-29](#)  
 Inventory Manager [3-1, 3-5](#)  
 inventory manager [1-11, 3-2](#)  
 IOS [3-69](#)  
 IP address  
   create [3-124](#)  
 IP address pool [3-122](#)  
 ip-address tag [4-23, A-3](#)  
 ipaddress tag [4-21, A-3](#)  
 IPv4 type [6-11](#)  
 ISC L2VPN Management  
   Discovery process for [4-5](#)  
 ISC Traffic Engineering Management  
   using Discovery with [4-6](#)

## J

JavaWebStart properties [C-18](#)  
 jitter CoS report [7-41](#)  
 jitter protocol [7-26](#)  
 jitter report [7-39](#)

## K

keep history [7-15](#)  
 keys [3-69](#)

## L

L2TPv3 functional audit [7-5](#)  
 L2VPN (Metro Ethernet) service discovery [4-65](#)  
 L2VPN (Metro Ethernet Discovery) button [4-29](#)  
 L2VPN functional audit [7-5](#)  
 L2VPN repository variables [6-23](#)  
 Layer 2 end to end wires  
   deleting [4-73](#)  
   joining [4-73](#)  
   splitting [4-72](#)  
   viewing [4-69](#)  
 Layer 2 services  
   deleting [4-69](#)  
   editing  
     grouped by VPN [4-68](#)  
   viewing  
     grouped by VPN [4-66](#)  
 Layer 2 VPLS links  
   deleting [4-76](#)  
   editing [4-75](#)  
   viewing [4-73](#)  
 Licenses  
   installing for Discovery [4-15](#)  
 licensing [1-16, 9-32](#)  
 Link QoS [1-13](#)  
 link QoS [6-1, 6-37](#)

links [1-3](#)  
 lockmanager properties [C-34](#)  
 lockmanager server [2-10](#)  
 Logging properties [C-18](#)  
 logout [1-6](#)  
 logs [9-29](#)  
   Discovery logs [4-4](#)  
 lost state [3-4](#)

## M

MANAGED-MGMT-LAN role [4-45](#)  
 MANAGED-REGULAR role [4-45](#)  
 manage TIBCO Rendezvous [1-16, 9-1, 9-37](#)  
 manual, objective [xxix](#)  
 manual organization [xxx](#)  
 maps [3-64](#)  
 maps, adding [3-68](#)  
 missed column [2-11](#)  
 Monitoring [1-3, 1-13, 7-1](#)  
 mouse terminology [xxxi](#)  
 MPLS Diagnostics Expert [1-3, 1-14, 8-1](#)  
   description of Discovery steps [4-12](#)  
   summary of Discovery steps [4-10](#)  
 MPLS functional audit [7-5](#)  
 MPLS repository variables [6-26](#)  
 MPLS VPN button [4-29](#)  
 MPLS VPN service discovery [4-56](#)  
 MPLS VPN view  
   filtering [4-58](#)  
 Multicast pool [3-122](#)  
   create [3-125](#)  
 MULTI-VRF role [4-45](#)

## N

name column [2-9](#)

**Named Physical Circuit 3-140**

- access 3-141
- create 3-142
- delete 3-145

**named physical circuit 1-11, 9-17****Named Physical Circuits 3-2****nbi properties C-35****network operations center 8-1****NOC 8-1****node locations 3-67****notification properties C-37****NPC 1-11, 3-140, 9-17**

- access 3-141
- adding a ring 4-54
- adding devices to an NPC 4-53
- create 3-142
- creating 4-52
- delete 3-145
- inserting a device 4-55
- inserting a ring 4-55

**NPC discovery 4-49**

- preliminary steps for Metro Ethernet network with Ethernet core 4-49

**NPC Topology File field 4-29****N-PE role 4-42****nspoller server 2-10****number of buckets 7-15**

---

**O****object groups 1-15****objective xxix****one-dimensional array 6-17****opening 3-24****opening customers with configuration 3-7****opening devices with configuration providers 3-7****opening providers with configuration 3-7, 3-15****operation method, advanced 5-2****operation method, simplified 5-2****orbd 2-2****organization of manual xxx**

---

**P****pal properties C-38****parent role**

- definition 9-9

**Partial Mesh topology 4-58****password attributes**

- setting 4-32

**password management 7-3****PE-AGG role 4-42****PE device**

- create 3-120

**PE devices**

- guidelines for device roles 4-40

**pending state 3-4****PE Region Name**

- assigning 4-41

**permission for others**

- definition 9-4

**permissions**

- user roles 9-9

**PE roles**

- assigning 4-40
- editing 4-42
- N-PE role 4-42
- PE-AGG role 4-42
- P role 4-42
- U-PE role 4-42

**pid column 2-11****ping 1-14, 7-1, 7-8****plug-and-play B-7****policies 1-13, 6-1****policy.xml file 4-20**

- editing 4-21

**Policy File field 4-28**

## POPs

choosing all the POPs [4-22](#)

precedence [7-14](#)

prepend [5-6](#)

printing reports [7-45](#)

probes [7-12](#)

create common parameters [7-13](#)

create from any SA agent device [7-15](#)

create from MPLS CPE [7-17](#)

create from MPLS PE or MVRP-CE [7-22](#)

delete [7-31](#)

details [7-30](#)

disable [7-34](#)

enable [7-32](#)

product categories [1-3](#)

product introduction [1-1](#)

product tabs [1-3](#)

P role [4-42](#)

properties [C-1](#)

aagent [C-34](#)

AutoDiscovery [C-1](#)

cfr [C-34](#)

Cleanup [C-1](#)

DCS [C-2](#)

DeploymentFlow [C-9](#)

Discovery [C-9](#)

DistributionFramework [C-12](#)

GSAM [C-13](#)

GTL [C-13](#)

GUI [C-15](#)

JavaWebStart [C-18](#)

lockmanager [C-34](#)

Logging [C-18](#)

nbi [C-35](#)

notification [C-37](#)

pal [C-38](#)

Provisioning [C-19](#)

repository [C-38](#)

Scheduler [C-30](#)

Services [C-31](#)

SLA [C-28](#)

SnmpService [C-31](#)

SYSTEM [C-29](#)

TaskManager [C-33](#)

TE [C-32](#)

TE Topology [C-32](#)

VpnInvServer [C-33](#)

watchdog [C-40](#)

xml [C-50](#)

protocol

DHCP [7-29](#)

DNS [7-28](#)

FTP [7-27](#)

HTTP [7-28](#)

ICMP Echo [7-25](#)

jitter [7-26](#)

TCP connect [7-25](#)

UDP Echo [7-26](#)

protocols [7-24](#)

provider [1-11, 3-2, 3-114](#)

access [3-115](#)

create [3-115](#)

definition [9-10](#)

delete [3-117](#)

edit [3-116](#)

provider-name tag [4-19, A-3](#)

provider region

create [3-118](#)

Provisioning properties [C-19](#)

---

## Q

QoS/L2/ATM template folder [6-22](#)

QoS/L2/FrameRelay template folder [6-22](#)

QoS repository variables [6-33](#)



## R

RD pool [3-122](#)  
     create [3-126](#)  
 recommendations, system [1-1](#)  
 region-name tag [4-19, A-3](#)  
 related documentation [xxix](#)  
 reload [1-12, 5-13](#)  
 remote installation [9-28](#)  
 remote uninstallation [9-29](#)  
 Rendezvous agent [9-37](#)  
 Rendezvous routing daemon [9-37](#)  
 reports [1-14, 7-1, 7-41](#)  
     accessing [7-42](#)  
     custom [7-46](#)  
     e-mailing [7-46](#)  
     exporting [7-45](#)  
     filters [7-43](#)  
     graphical user interface [7-42](#)  
     GUI [7-42](#)  
     layout [7-43](#)  
     output [7-44](#)  
     output fields [7-43](#)  
     printing [7-45](#)  
     running [7-43](#)  
     sorting [7-43](#)  
 Repository  
     copying empty Repository [4-15](#)  
     ensuring Repository is empty [4-15](#)  
 repository properties [C-38](#)  
 repository variables  
     L2VPN [6-23](#)  
     MPLS [6-26](#)  
     QoS [6-33](#)  
     VPLS [6-35](#)  
 requested state [3-4](#)  
 resource pool [1-11, 3-2, 3-122](#)  
     access [3-123](#)  
     delete [3-132](#)

resource pools  
     creating [4-50](#)  
 restart\_delay state [2-11](#)  
 Restart button [4-4](#)  
 retrieve device attributes [5-3, 5-7](#)  
 right to use [9-33](#)  
 ring  
     adding [4-54](#)  
     deleting [4-55](#)  
     inserting [4-55](#)  
 ro-community tag [4-24, A-3](#)  
 role assignment [4-36](#)  
 Route Distinguisher pool [3-122](#)  
     create [3-126](#)  
 Route Target pool [3-122](#)  
     create [3-126](#)  
 rows per page [1-7](#)  
 RT pool [3-122](#)  
     create [3-126](#)  
 running reports [7-43](#)  
 rva [9-37](#)  
 rvrd [9-37](#)

## S

SA agents, enabling [3-72](#)  
 sample topology.xml file [4-25](#)  
 sample XML file  
     inventory.sample.xml [4-19](#)  
 sample XML files  
     device.xml file [4-22](#)  
     policy.xml file [4-20](#)  
     topology.xml file [4-25](#)  
 Scheduler properties [C-30](#)  
 scheduler server [2-10](#)  
 Security [1-2](#)  
 security [1-15, 9-1](#)  
 seed device  
     choosing POPs [4-22](#)

- select & click go [6-7](#)
- select a version [5-8](#)
- server names [2-9](#)
- service deployment [7-3](#)
- Service Design [1-3, 1-12](#)
- service design [6-1](#)
- Service Inventory [1-3, 1-10](#)
  - device console [5-1](#)
- service level agreement [1-14, 7-1, 7-11](#)
  - HTTP CoS report [7-40](#)
  - HTTP report [7-39](#)
  - jitter CoS report [7-41](#)
  - jitter report [7-39](#)
  - setup [7-12](#)
  - summary CoS report [7-39](#)
  - summary report [7-36](#)
- service level agreement collection [7-3](#)
- service level agreement reports [7-35](#)
- Service Request [1-11](#)
- service request [3-2, 3-3](#)
  - states [3-3](#)
- service requests
  - editing [4-78](#)
- services
  - L2VPN [6-17](#)
  - MPLS [6-17](#)
  - QoS [6-17](#)
  - VPLS [6-17](#)
- Services property [C-31](#)
- shortcuts [1-3](#)
- show button [6-3](#)
- show data file matching [6-3](#)
- show template matching [6-3](#)
- simple filter [9-36](#)
- simplified operation method [5-2](#)
- simplified task configuration method [7-3](#)
- site-name tag [4-19, A-3](#)
- site of origin pool [3-122](#)
  - create [3-128](#)
- SLA [1-14, 7-1, 7-11](#)
  - HTTP CoS report [7-40](#)
  - HTTP report [7-39](#)
  - jitter CoS report [7-41](#)
  - jitter report [7-39](#)
  - setup [7-12](#)
  - summary CoS report [7-39](#)
  - summary report [7-36](#)
- SLA collection [7-3](#)
- SLA life [7-13](#)
- SLA properties [C-28](#)
- SLA reports [7-35](#)
- SNMP
  - setting up [3-70](#)
  - SNMPv1 [3-71](#)
  - SNMPv3 [3-71](#)
- snmp-info tag [4-24, A-3](#)
- SnmpService properties [C-31](#)
- Split VPN button [4-58](#)
- SSH
  - configuring for CPE devices [3-69](#)
  - configuring on Cisco routers [3-69](#)
- SSH connections, configuring [3-69](#)
- start\_depends state [2-10](#)
- startdb command [2-1, 2-2](#)
- started state [2-10](#)
- starting state [2-10](#)
- startns command [2-2](#)
- startwd [2-1](#)
- startwd command [2-2](#)
- state
  - Broken [3-3](#)
  - closed [3-3](#)
  - deployed [3-3](#)
  - disabled [2-11](#)
  - disabled\_dependent [2-10](#)
  - failed audit [3-3](#)
  - failed deploy [3-3](#)
  - Functional [3-3](#)

- invalid [3-3](#)
- lost [3-4](#)
- pending [3-4](#)
- requested [3-4](#)
- restart\_delay [2-11](#)
- start\_depends [2-10](#)
- started [2-10](#)
- starting [2-10](#)
- stop\_depends [2-10](#)
- stopped [2-10](#)
- stopping\_gently [2-10](#)
- stopping\_hard [2-10](#)
- Wait Deployed [3-4](#)
- state column [2-10](#)
- states of service requests [3-3](#)
- states transition diagram [3-4](#)
- stop\_depends state [2-10](#)
- stopall command [2-3](#)
- stopdb command [2-3](#)
- stopns command [2-3, 2-4](#)
- stopped state [2-10](#)
- stopping\_gently state [2-10](#)
- stopping\_hard state [2-10](#)
- stopwd command [2-4](#)
- string type [6-8, 6-9](#)
- sub-template type [6-12](#)
- success column [2-11](#)
- summary CoS report [7-39](#)
- summary report [7-36](#)
- system-object-id tag [4-23, A-3](#)
- SYSTEM properties [C-29](#)
- system recommendations [1-1](#)

## T

- tabs [1-3](#)
- task, creating new [7-3](#)
- task configuration method, advanced [7-3](#)
- task configuration method, simplified [7-3](#)
- task logs [7-7](#)
- Task Manager
  - starting [7-2](#)
- task manager [1-14, 7-1](#)
- TaskManager properties [C-33](#)
- tasks [7-2](#)
- task Service Requests [7-4](#)
- TCP connect protocol [7-25](#)
- TE discovery [7-3](#)
- TE functional audit [7-5](#)
- TE interface performance [7-3](#)
- TEM [1-11](#)
- TEM performance report [7-1, 7-41](#)
- template
  - delete [6-20](#)
  - edit [6-19](#)
- template datafile chooser [5-6](#)
- template examples [6-22](#)
- template name [6-6](#)
- templates [1-13, 6-1, 6-2](#)
  - data pane [6-3](#)
  - tree [6-3](#)
- TE performance report [1-14](#)
- TE properties [C-32](#)
- terminology [xxxi](#)
- TE Topology properties [C-32](#)
- tftp [5-9](#)
- threshold [7-14](#)
  - falling [7-15](#)
- TIBCO port
  - verifying unique TIBCO port [4-16](#)
- timeout [7-14](#)
- toDevice tag [4-26, A-3](#)
- toIF tag [A-3](#)
  - XML tags
    - toIF tag [4-26](#)
- toIP tag [4-26, A-3](#)
- topology [3-2, 3-36](#)
  - accessing [3-41](#)

- areas [3-42](#)
- conventions [3-39](#)
- filtering [3-60](#)
- introduction [3-37](#)
- logical view [3-49](#)
- maps [3-64](#)
- maps, adding [3-68](#)
- node locations [3-67](#)
- physical view [3-52](#)
- searching [3-63](#)
- view types [3-43](#)
- VPN view [3-44](#)
- topology.xml file
  - description [4-24](#)
  - editing [4-26](#)
- topology tool [1-11](#)
- TOS [7-14](#)
- TOS category [7-14](#)
- traffic engineering discovery [7-3](#)
- traffic engineering functional audit [7-5](#)
- traffic engineering interface performance [7-3](#)
- Traffic Engineering Management [1-11](#)
- traffic engineering management performance report [7-41](#)
- traps
  - disable [7-35](#)
  - enable [7-15, 7-33](#)
- two-dimensional array [6-18](#)
- type
  - dynamic Java class [6-13](#)
  - dynamic URL [6-13](#)
  - float [6-10](#)
  - integer [6-9](#)
  - IPv4 [6-11](#)
  - string [6-8, 6-9](#)
  - sub-template [6-12](#)
- typographical conventions [xxxii](#)

---

## U

- UDP Echo protocol [7-26](#)
- uninstallation
  - remote [9-29](#)
- UNMANAGED-MGMT-LAN role [4-45](#)
- UNMANAGED-MULTI-VRF role [4-45](#)
- UNMANAGED role [4-45](#)
- U-PE role [4-42](#)
- upload config after download [5-3, 5-7](#)
- upload to customer [5-5](#)
- upload to site [5-5](#)
- user
  - copy [9-5](#)
  - delete [9-6](#)
  - edit [9-6](#)
  - managing [9-2](#)
- user access log [1-16, 9-1, 9-35](#)
- user group
  - creating [9-8](#)
  - delete [9-9](#)
  - editing [9-8](#)
  - managing [9-7](#)
- user groups [1-15](#)
- user management
  - user groups [9-7](#)
  - user roles [9-9](#)
  - users [9-2](#)
- user role
  - create [9-11, 9-17](#)
  - customer [9-10](#)
  - delete [9-16, 9-19](#)
  - edit [9-15, 9-19](#)
  - managing [9-9](#)
  - parent role [9-9](#)
  - provider [9-10](#)
- User Roles [1-2](#)
- user roles [1-15](#)
  - design example [9-20](#)

users [1-15](#)

- assigned roles [9-5](#)
- group membership [9-5](#)
- permission for others [9-4](#)

users, active [9-34](#)

## V

validate [6-7](#)

variables [6-7](#)

VC ID pool

- create [3-130](#)

VC IP pool [3-122](#)

Verifying CDP is running [4-16](#)

view configurations [6-3](#)

VLAN ID pool [3-122](#)

VLAN pool

- create [3-130](#)

VPLS repository variables [6-35](#)

VPN [1-11, 3-2, 3-136](#)

- access [3-136](#)
- console, overview [1-2](#)
- create [3-137](#)
- creating [4-61](#)
- creating or modifying [4-61](#)
- delete [3-140](#)
- edit [4-63](#)
- splitting [4-58](#)
- viewing link details [4-63](#)

VpnInvServer properties [C-33](#)

## W

Wait Deployed state [3-4](#)

watchdog commands [2-1](#)

- startdb [2-1](#)
- startns [2-2](#)
- startwd [2-2](#)

- stopall [2-3](#)
- stopdb [2-3](#)
- stopns [2-4](#)
- stopwd [2-4](#)
- wdclient [2-5](#)

watchdog properties [C-40](#)

wdclient command [2-5](#)

wdclient disk subcommand [2-6](#)

wdclient groups subcommand [2-6](#)

wdclient group subcommand [2-6](#)

wdclient health subcommand [2-7](#)

wdclient -help [2-5](#)

wdclient hosts subcommand [2-7](#)

wdclient -master -help [2-5](#)

wdclient restart subcommand [2-8](#)

wdclient start subcommand [2-8](#)

wdclient status subcommand [2-9](#)

wdclient stop subcommand [2-11](#)

wdclient subcommands

- exec time column [2-11](#)
- gen column [2-11](#)
- missed column [2-11](#)
- name column [2-9](#)
- pid column [2-11](#)
- state column [2-10](#)
- success column [2-11](#)
- wdclient disk [2-6](#)
- wdclient group [2-6](#)
- wdclient groups [2-6](#)
- wdclient health [2-7](#)
- wdclient hosts [2-7](#)
- wdclient restart [2-8](#)
- wdclient start [2-8](#)
- wdclient status [2-9](#)
- wdclient stop [2-11](#)
- wdclient syshealth [2-12](#)

wdclient syshealth subcommand [2-12](#)

worker server [2-10](#)

## X

### XML files

- location of sample files [4-17](#)
- policy.xml file [4-20](#)
- required for Discovery [4-17](#)
- sample file [4-19](#)
- summary of files [4-17](#)
- topology.xml file [4-24](#)

### xml properties [C-50](#)

### XML rules

- create-provider [4-19, A-2](#)
- create-region [4-19, A-2](#)
- create-site [4-19, A-2](#)

### X ML tags

- FromInterface [4-26](#)

### XML tags

- as-number [4-19, A-1](#)
- CDP tag [4-21](#)
- connection tag [4-25](#)
- create-customer [4-19, A-2](#)
- customer-name [4-19, A-2](#)
- device-name tag [A-2](#)
- device tag [A-2](#)
- DISCOVERY\_METHOD [4-21, A-2](#)
- discovery-protocol [4-25, A-2](#)
- fromDevice [4-25, A-2](#)
- FromInterface [A-2](#)
- FromIP [4-25, A-3](#)
- hop tag [4-21, A-3](#)
- ip-address tag [4-23, A-3](#)
- ipaddress tag [4-21](#)
- provider-name [4-19, A-3](#)
- region-name [4-19, A-3](#)
- ro-community [4-24, A-3](#)
- site-name [4-19, A-3](#)
- snmp-info [4-24, A-3](#)
- system-object-id [4-23, A-3](#)
- toDevice [4-26, A-3](#)

toIF tag [A-3](#)

toIP [4-26, A-3](#)

XML tags ipaddress tag [A-3](#)