



## **Cluster Configuration and Administration Guide for Cisco Unity Connection**

Release 7.x  
Revised May 2009

### **Americas Headquarters**

Cisco Systems, Inc.  
170 West Tasman Drive  
San Jose, CA 95134-1706  
USA  
<http://www.cisco.com>  
Tel: 408 526-4000  
800 553-NETS (6387)  
Fax: 408 527-0883

Text Part Number: OL-17041-01

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE.

IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

CCDE, CCSI, CCENT, Cisco Eos, Cisco HealthPresence, the Cisco logo, Cisco Lumin, Cisco Nexus, Cisco Nurse Connect, Cisco Stackpower, Cisco StadiumVision, Cisco TelePresence, Cisco WebEx, DCE, and Welcome to the Human Network are trademarks; Changing the Way We Work, Live, Play, and Learn and Cisco Store are service marks; and Access Registrar, Aironet, AsyncOS, Bringing the Meeting To You, Catalyst, CCDA, CCDP, CCIE, CCIP, CCNA, CCNP, CCSP, CCVP, Cisco, the Cisco Certified Internetwork Expert logo, Cisco IOS, Cisco Press, Cisco Systems, Cisco Systems Capital, the Cisco Systems logo, Cisco Unity, Collaboration Without Limitation, EtherFast, EtherSwitch, Event Center, Fast Step, Follow Me Browsing, FormShare, GigaDrive, HomeLink, Internet Quotient, IOS, iPhone, iQuick Study, IronPort, the IronPort logo, LightStream, Linksys, MediaTone, MeetingPlace, MeetingPlace Chime Sound, MGX, Networkers, Networking Academy, Network Registrar, PCNow, PIX, PowerPanels, ProConnect, ScriptShare, SenderBase, SMARTnet, Spectrum Expert, StackWise, The Fastest Way to Increase Your Internet Quotient, TransPath, WebEx, and the WebEx logo are registered trademarks of Cisco Systems, Inc. and/or its affiliates in the United States and certain other countries.

All other trademarks mentioned in this document or website are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (0903R)

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

*Cluster Configuration and Administration Guide for Cisco Unity Connection Release 7.x*  
© 2009 Cisco Systems, Inc. All rights reserved.



# CONTENTS

## **Preface** v

Audience and Use	v
Documentation Conventions	vi
Cisco Unity Connection Documentation	vi
Obtaining Documentation and Submitting a Service Request	vi
Cisco Product Security Overview	vii

---

## **CHAPTER 1**

### **Configuring a Cisco Unity Connection Cluster** 1-1

Task List for Configuring a Cisco Unity Connection Cluster	1-1
Configuring the Cisco Unity Connection Cluster	1-1
Setting Up Alert Notification of Server Status Changes	1-2
Customizing Cluster Settings	1-3

---

## **CHAPTER 2**

### **Administering a Cisco Unity Connection Cluster** 2-1

Restarting the Cisco Unity Connection Servers in Any Order	2-1
Manually Changing Server Status	2-1
Stopping All Ports on a Server from Taking New Calls	2-3
Restarting All Ports on a Server to Take Calls	2-3
Shutting Down a Server	2-3

---

## **CHAPTER 3**

### **About a Cisco Unity Connection Cluster** 3-1

How a Cluster Works in Cisco Unity Connection	3-1
Licenses for a Cluster	3-2
About the Publisher Server	3-2
Server Status Functions in the Cluster	3-3
Server Assignments and Usage of Voice Messaging Ports	3-4
Requirements for a Cisco Unity Connection Cluster	3-6
Effects on Calls in Progress When Server Status Changes	3-7
Effects on Cisco Unity Connection Web Applications When Server Status Changes	3-7
Effects of Stopping a Critical Service on a Server	3-7
Effects of a Split-Brain Condition	3-8
Events When Server Status Changes	3-8

Automatic Change of Server Status Initiated by Server with Primary Status	3-8
Automatic Change of Server Status Initiated by Server with Secondary Status	3-9
Manual Change of Server Status Initiated by Administrator	3-9

---

**INDEX**



## Preface

---

This preface contains the following sections:

- [Audience and Use, page v](#)
- [Documentation Conventions, page vi](#)
- [Cisco Unity Connection Documentation, page vi](#)
- [Obtaining Documentation and Submitting a Service Request, page vi](#)
- [Cisco Product Security Overview, page vii](#)

## Audience and Use

The *Cluster Configuration and Administration Guide for Cisco Unity Connection* is intended for installers, system administrators, and technicians who are installing and configuring, customizing, or administering Cisco Unity Connection clusters.

The guide contains instructions for configuring and using a Connection cluster, as well as information on how a Connection cluster works. You configure a Connection cluster after installing the publisher server according to instructions in the *Installation Guide for Cisco Unity Connection*.

(For information on making changes to the Connection system configuration, refer to the *Reconfiguration and Upgrade Guide for Cisco Unity Connection Release 7.x* at [http://www.cisco.com/en/US/docs/voice\\_ip\\_comm/connection/7x/upgrade/guide/7xcucrux.html](http://www.cisco.com/en/US/docs/voice_ip_comm/connection/7x/upgrade/guide/7xcucrux.html).)

# Documentation Conventions

**Table 1** *Conventions in the Cluster Configuration and Administration Guide for Cisco Unity Connection*

Convention	Description
boldfaced text	Boldfaced text is used for: <ul style="list-style-type: none"> <li>Key and button names. (Example: Click <b>OK</b>.)</li> <li>Information that you enter. (Example: Enter <b>Administrator</b> in the User Name box.)</li> </ul>
< > (angle brackets)	Angle brackets are used around parameters for which you supply a value. (Example: In your browser, go to <b>https://&lt;Cisco Unity Connection server IP address&gt;/cuadmin</b> .)
- (hyphen)	Hyphens separate keys that must be pressed simultaneously. (Example: Press <b>Ctrl-Alt-Delete</b> .)
> (right angle bracket)	A right angle bracket is used to separate selections that you make in the navigation bar of Cisco Unity Connection Administration. (Example: In Cisco Unity Connection Administration, go to <b>Contacts &gt; System Contacts</b> .)

The *Cluster Configuration and Administration Guide for Cisco Unity Connection* also uses the following conventions:



## Note

Means reader take note. Notes contain helpful suggestions or references to material not covered in the document.



## Caution

Means reader be careful. In this situation, you might do something that could result in equipment damage or loss of data.

## Cisco Unity Connection Documentation

For descriptions and URLs of Cisco Unity Connection documentation on Cisco.com, refer to the *Documentation Guide for Cisco Unity Connection Release 7.x*. The document is shipped with Connection and is available at [http://www.cisco.com/en/US/docs/voice\\_ip\\_comm/connection/7x/roadmap/7xcucdg.html](http://www.cisco.com/en/US/docs/voice_ip_comm/connection/7x/roadmap/7xcucdg.html).

## Obtaining Documentation and Submitting a Service Request

For information on obtaining documentation, submitting a service request, and gathering additional information, see the monthly *What's New in Cisco Product Documentation*, which also lists all new and revised Cisco technical documentation, at:

<http://www.cisco.com/en/US/docs/general/whatsnew/whatsnew.html>

Subscribe to the *What's New in Cisco Product Documentation* as a Really Simple Syndication (RSS) feed and set content to be delivered directly to your desktop using a reader application. The RSS feeds are a free service and Cisco currently supports RSS Version 2.0.

## Cisco Product Security Overview

This product contains cryptographic features and is subject to United States and local country laws governing import, export, transfer and use. Delivery of Cisco cryptographic products does not imply third-party authority to import, export, distribute or use encryption. Importers, exporters, distributors and users are responsible for compliance with U.S. and local country laws. By using this product you agree to comply with applicable laws and regulations. If you are unable to comply with U.S. and local laws, return this product immediately

Further information regarding U.S. export regulations may be found at [http://www.access.gpo.gov/bis/ear/ear\\_data.html](http://www.access.gpo.gov/bis/ear/ear_data.html).





# CHAPTER 1

## Configuring a Cisco Unity Connection Cluster

---

This chapter contains the following sections:

- [Task List for Configuring a Cisco Unity Connection Cluster, page 1-1](#)
- [Configuring the Cisco Unity Connection Cluster, page 1-1](#)
- [Setting Up Alert Notification of Server Status Changes, page 1-2](#)
- [Customizing Cluster Settings, page 1-3](#)

## Task List for Configuring a Cisco Unity Connection Cluster



### Caution

Configure a Cisco Unity Connection cluster only after you have installed the publisher server and set up administrator workstations according to instructions in the *Installation Guide for Cisco Unity Connection Release 7.x*.

---

Do the following tasks in the order listed to configure a Cisco Unity Connection cluster correctly:

1. On the publisher server, configure the Connection cluster by adding the host name or IP address of the subscriber server and enable access to alert logs for when the publisher server is not functioning. See the [“Configuring the Cisco Unity Connection Cluster” section on page 1-1](#).
2. Set up alert notification of server status changes. See the [“Setting Up Alert Notification of Server Status Changes” section on page 1-2](#).
3. *Optional:* Adjust the cluster settings. See the [“Customizing Cluster Settings” section on page 1-3](#).
4. Continue with the next task in [“Part 3: Configuring the Cluster, and Installing and Configuring the Subscriber Connection Server”](#) in the [“Task List for Installing a Cisco Unity Connection 7.x System with a Connection Cluster Configured”](#) in the *Installation Guide for Cisco Unity Connection Release 7.x*.

## Configuring the Cisco Unity Connection Cluster

You configure the cluster after you have installed the publisher server.

Do the two procedures in this section in the order listed.

**Note**

The Cisco Unity Connection cluster feature is not supported for use with Cisco Unified Communications Manager Business Edition.

---

**To Configure the Cisco Unity Connection Cluster**


---

- Step 1** On the publisher server, log on to Cisco Unity Connection Administration.
  - Step 2** In Connection Administration, expand **System Settings**, then click **Cluster**.
  - Step 3** On the Find and List Servers page, click **Add New**.
  - Step 4** On the New Server Configuration page, in the Host Name/IP Address field, enter the host name or IP address of the second server in the cluster.
  - Step 5** *Optional:* In the MAC Address field, enter the MAC address of the second server.
  - Step 6** In the Description field, enter **Server 2** or another description for the second server.
  - Step 7** Click **Save**.
- 

---

**To Enable Access to Alert Logs for When the Publisher Server Is Not Functioning**


---

- Step 1** In Connection Administration, expand **System Settings**, then click **Service Parameters**.
  - Step 2** On the Service Parameters page, in the Server field, click the publisher server.
  - Step 3** In the Service field, click **Cisco AMC Service**.
  - Step 4** In the Failover Collector field, click the subscriber server.
  - Step 5** Click **Save**.
- 

## Setting Up Alert Notification of Server Status Changes

**Added May 2009**

We recommend that you configure the Cisco Unified Real-Time Monitoring Tool to send notifications for the following Cisco Unity Connection alerts:

- AutoFailbackFailed
- AutoFailbackSucceeded
- AutoFailoverFailed
- AutoFailoverSucceeded
- NoConnectionToPeer
- SbrFailed

For instructions on setting up alert notification for Connection alerts, see the “Working with Alerts” chapter (in the “Alerts” part) of the *Cisco Unified Real-Time Monitoring Tool Administration Guide* at [http://www.cisco.com/en/US/products/ps6509/prod\\_maintenance\\_guides\\_list.html](http://www.cisco.com/en/US/products/ps6509/prod_maintenance_guides_list.html).

# Customizing Cluster Settings

You can change the default cluster settings.

## To Customize Cluster Settings

- 
- Step 1** On the publisher server, log on to Cisco Unity Connection Administration.
- Step 2** In Connection Administration, expand **System Settings > Advanced**, then click **Cluster Configuration**.
- Step 3** On the Cluster Configuration page, change the settings as applicable:

<b>Deactivate server with Secondary status when replication is backlogged</b>	<p>When this check box is checked, a replication backlog condition causes the server with Secondary status to change to Deactivated.</p> <p>When this check box is unchecked, a replication backlog condition does not cause the server with Secondary status to change status.</p> <p>The default is unchecked.</p>
<b>Automatically change server status when the publisher server fails</b>	<p>When this check box is checked, a failure of the publisher server causes the server with Secondary status to change automatically to Primary.</p> <p>When this check box is unchecked, a failure of the publisher server does not cause the server with Secondary status to change status. The status of the server must be changed manually.</p> <p>The default is checked.</p>

- Step 4** Click **Save**.
-





## CHAPTER 2

# Administering a Cisco Unity Connection Cluster

This chapter contains the following sections:

- [Restarting the Cisco Unity Connection Servers in Any Order, page 2-1](#)
- [Manually Changing Server Status, page 2-1](#)
- [Stopping All Ports on a Server from Taking New Calls, page 2-3](#)
- [Restarting All Ports on a Server to Take Calls, page 2-3](#)
- [Shutting Down a Server, page 2-3](#)



**Note**

For information and instructions on removing or replacing a server in a cluster, and on adding a server to create a cluster, refer to the *Reconfiguration and Upgrade Guide for Cisco Unity Connection Release 7.x* at

[http://www.cisco.com/en/US/docs/voice\\_ip\\_comm/connection/7x/upgrade/guide/7xcucrux.html](http://www.cisco.com/en/US/docs/voice_ip_comm/connection/7x/upgrade/guide/7xcucrux.html).

## Restarting the Cisco Unity Connection Servers in Any Order

You can start clustered Cisco Unity Connection servers in any order. The necessary services will run on the servers with Primary status or Secondary status.

## Manually Changing Server Status

You can manually change the status of servers in the following ways:

- A server with Secondary status can be manually changed to Primary status. (For the server that originally had Primary status, this change automatically causes its status to change to Secondary.) See the “[To Manually Change a Server from Secondary Status to Primary Status](#)” procedure on [page 2-2](#).
- A server with Secondary status can be manually changed to Deactivated status. See the “[To Manually Change a Server from Secondary Status to Deactivated Status](#)” procedure on [page 2-2](#).
- A server with Deactivated status can be manually activated so that its status changes to Primary or Secondary, depending on the status of the other server. See the “[To Manually Activate a Server with Deactivated Status](#)” section on [page 2-2](#).

### To Manually Change a Server from Secondary Status to Primary Status

- 
- Step 1** Log on to Cisco Unity Connection Serviceability.
- Step 2** On the Tools menu, click **Cluster Management**.
- Step 3** On the Cluster Management page, under Server Manager, in the Change Server Status column for the server with Secondary status, click **Make Primary**.
- Step 4** When prompted to confirm changing the server status, click **OK**.
- The Server Status column displays the changed status when the change is complete.



**Note** The server that originally had Primary status automatically changes to Secondary status.

---

### To Manually Change a Server from Secondary Status to Deactivated Status

- 
- Step 1** Log on to the Real-Time Monitoring Tool (RTMT).
- Step 2** On the Cisco Unity Connection menu, click **Port Monitor**. The Port Monitor tool appears in the right pane.
- Step 3** In the Node field, click the server with Secondary status.
- Step 4** In the right pane, click **Start Polling**.
- Step 5** Note whether any voice messaging ports are currently handling calls for the server.
- Step 6** Log on to Cisco Unity Connection Serviceability.
- Step 7** On the Tools menu, click **Cluster Management**.
- Step 8** If no voice messaging ports are currently handling calls for the server, skip to [Step 9](#).  
If there are voice messaging ports that are currently handling calls for the server, on the Cluster Management page, under Change Port Status, click **Stop Taking Calls** for the server, then wait until RTMT shows that all ports for the server are idle.
- Step 9** On the Cluster Management page, under Server Manager, in the Change Server Status column for the server with Secondary status, click **Deactivate**.



**Caution** Deactivating a server will terminate all calls that the ports for the server are handling.

---

- Step 10** When prompted to confirm changing the server status, click **OK**.
- The Server Status column displays the changed status when the change is complete.
- 

### To Manually Activate a Server with Deactivated Status

- 
- Step 1** Log on to Cisco Unity Connection Serviceability.
- Step 2** On the Tools menu, click **Cluster Management**.
- Step 3** On the Cluster Management page, under Server Manager, in the Change Server Status column for the server with Deactivated status, click **Activate**.

- Step 4** When prompted to confirm changing the server status, click **OK**.  
The Server Status column displays the changed status when the change is complete.
- 

## Stopping All Ports on a Server from Taking New Calls

Do the procedure in this section to stop all ports on a server from taking any new calls. Calls in progress continue until the callers hang up.

**Tip**

Use the Port Monitor page in the Real-Time Monitoring Tool (RTMT) to determine whether any ports are currently handling calls for the server.

---

### To Stop All Ports on a Server from Taking New Calls

---

- Step 1** Log on to Cisco Unity Connection Serviceability.  
**Step 2** On the Tools menu, click **Cluster Management**.  
**Step 3** On the Cluster Management page, under Port Manager, in the Ports in Service column, click **Stop Taking Calls** for the server.
- 

## Restarting All Ports on a Server to Take Calls

Do the procedure in this section to let ports on a server take calls again after they were stopped.

### To Restart All Ports on a Server to Take Calls

---


- Step 1** Log on to Cisco Unity Connection Serviceability.  
**Step 2** On the Tools menu, click **Cluster Management**.  
**Step 3** On the Cluster Management page, under Port Manager, in the Ports in Service column, click **Take Calls** for the server.
- 

## Shutting Down a Server

When a Cisco Unity Connection server has Primary or Secondary status, it is handling voice messaging traffic and cluster replication. We do not recommend shutting down a Connection server while it has Primary or Secondary status because calls in progress and replication may be abruptly terminated.

If you want to shut down a server (for example, to perform maintenance), we recommend that you do the procedure in this section during nonbusiness hours when voice messaging traffic will be light. Note that the remaining server, if it has Primary or Secondary status, handles all system voice messaging functions and maintains the Connection database.

**To Shut Down a Server**

- 
- Step 1** On the server that will not be shut down, log on to Cisco Unity Connection Serviceability.
- Step 2** On the Tools menu, click **Cluster Management**.
- Step 3** On the Cluster Management page, locate the server that you want to shut down.
- Step 4** If the server that you want to shut down has Secondary status, skip to [Step 5](#).  
 If the server that you want to shut down has Primary status, change the status:
- In the Change Server Status column for the server with Secondary status, click **Make Primary**.
  - When prompted to confirm changing the server status, click **OK**.
  - Confirm that the Server Status column indicates that the server now has Primary status and that the server you want to shut down has Secondary status.
- Step 5** On the server with Secondary status (the one you want to shut down), change the status:
- Log on to the Real-Time Monitoring Tool (RTMT).
  - On the Cisco Unity Connection menu, click **Port Monitor**. The Port Monitor tool appears in the right pane.
  - In the Node field, click the server with Secondary status.
  - In the right pane, click **Start Polling**.
  - Note whether any voice messaging ports are currently handling calls for the server.
  - If no voice messaging ports are currently handling calls for the server, skip to [Step 5g](#).  
 If there are voice messaging ports that are currently handling calls for the server, on the Cluster Management page, under Change Port Status, click **Stop Taking Calls** for the server, then wait until RTMT shows that all ports for the server are idle.
  - On the Cluster Management page, under Server Manager, in the Change Server Status column for the server with Secondary status, click **Deactivate**.
- 
-  **Caution** Deactivating a server will terminate all calls that the ports for the server are handling.
- 
- When prompted to confirm changing the server status, click **OK**.
  - Confirm that the Server Status column indicates that the server now has Deactivated status.
- Step 6** Shut down the server that you deactivated.
- In Cisco Unity Connection Serviceability on the server that is running, the Server Status column shows that the server you shut down has Not Functioning status.
-



## CHAPTER 3

# About a Cisco Unity Connection Cluster

---

This chapter contains the following sections:

- [How a Cluster Works in Cisco Unity Connection, page 3-1](#)
- [Licenses for a Cluster, page 3-2](#)
- [About the Publisher Server, page 3-2](#)
- [Server Status Functions in the Cluster, page 3-3](#)
- [Server Assignments and Usage of Voice Messaging Ports, page 3-4](#)
- [Requirements for a Cisco Unity Connection Cluster, page 3-6](#)
- [Effects on Calls in Progress When Server Status Changes, page 3-7](#)
- [Effects on Cisco Unity Connection Web Applications When Server Status Changes, page 3-7](#)
- [Effects of Stopping a Critical Service on a Server, page 3-7](#)
- [Effects of a Split-Brain Condition, page 3-8](#)
- [Events When Server Status Changes, page 3-8](#)

## How a Cluster Works in Cisco Unity Connection

**Revised May 2009**

The Cisco Unity Connection cluster feature provides high availability voice messaging through two Connection servers that are configured in a cluster. Under normal conditions, the Connection servers are both active so that:

- The cluster can be assigned a DNS name that is shared by the Connection servers.
- Clients such as email applications and the web tools available through the Cisco Personal Communications Assistant (PCA) can connect to either Connection server.
- Phone systems can send calls to either Connection server.
- Incoming phone traffic load is balanced between the Connection servers by the phone system, PIMG/TIMG units, or other gateways that are required for the phone system integration.

Each server in the cluster is responsible for handling a share of the incoming calls for the cluster (answering phone calls and taking messages). The server with Primary status is responsible for the following functions:

- Homing and publishing the database and message store, which are both replicated to the other server.

- Sending message notifications and MWI requests (the Connection Notifier service is activated).
- Sending SMTP notifications and VPIM messages (the Connection Message Transfer Agent service is activated).

When one of the servers stops functioning (for example, when it is shut down for maintenance), the remaining server assumes responsibility for handling all incoming calls for the cluster. The remaining server also assumes responsibility for the database and message store, which are both replicated to the other server when the connection and its functionality are restored.

When the server that stopped functioning is able to resume its normal functions and is activated, it resumes responsibility for handling its share of incoming calls for the cluster.

To monitor the status of the servers, the Connection Server Role Manager service runs in Cisco Unity Connection Serviceability on both servers. This service performs the following functions:

- Starts the applicable services on each server, depending on server status.
- Determines whether critical processes (such as voice message processing, database replication, and message store replication) are functioning normally.
- Initiates changes to server status when the server with Primary status is not functioning or when critical services are not running.

Note the following limitations when the publisher server is not functioning:

- If the Connection cluster is integrated with an LDAP directory, directory synchronization does not occur, although authentication continues to work when only the subscriber server is functioning. When the publisher server is functioning again, directory synchronization resumes.
- If a Digital Network includes the Connection cluster, directory updates do not occur, although messages continue to be sent to and from the cluster when only the subscriber server is functioning. When the publisher server is functioning again, directory updates resume.

## Licenses for a Cluster

### Added May 2009

A Cisco Unity Connection cluster requires a license for each Connection server. The license that has the MAC address of the publisher server must be installed on the publisher server. The license that has the MAC address of the subscriber server must be installed on the subscriber server.

For information on managing licenses, see the “[Managing Licenses](#)” chapter of the *System Administration Guide for Cisco Unity Connection Release 7.x* at

[http://www.cisco.com/en/US/docs/voice\\_ip\\_comm/connection/7x/administration/guide/7xcucsagx.html](http://www.cisco.com/en/US/docs/voice_ip_comm/connection/7x/administration/guide/7xcucsagx.html).

## About the Publisher Server

The first Cisco Unity Connection server that is configured in the cluster is the publisher server. The Cluster Management page in Cisco Unity Connection Serviceability identifies the publisher server.

The publisher server assumes responsibility for publishing the database and message store when the cluster is functioning normally.

When the publisher server does not have Primary status (for example, when the administrator manually changes the status of the other server to Primary, which automatically changes the status of the publisher server to Secondary), the other server assumes responsibility for publishing the database and message store.

The publisher server cannot be removed from the cluster.

## Server Status Functions in the Cluster

**Revised May 2009**

Each server in the cluster has a status that appears on the Cluster Management page of Cisco Unity Connection Serviceability. The status indicates the functions that the server is currently performing in the cluster, as described in [Table 3-1](#).

**Table 3-1** *Server Status Functions in the Cisco Unity Connection Cluster*

Server Status	Functions in Connection Cluster
Primary	<ul style="list-style-type: none"> <li>• Publishes the database and message store, which are both replicated to the other server in the cluster.</li> <li>• Receives replicated data from the other server when that server is able to share its data.</li> <li>• Displays and accepts changes to the administrative interfaces (such as Connection Administration). This data is replicated to the other server in the cluster.</li> <li>• Answers phone calls and takes messages.</li> <li>• Sends message notifications and MWI requests (the Connection Notifier service is activated).</li> <li>• Sends SMTP notifications and VPIM messages (the Connection Message Transfer Agent service is activated).</li> <li>• Connects with clients such as email applications and the web tools available through the Cisco PCA.</li> <li>• When the cluster is functioning normally, the publisher server has Primary status.</li> </ul> <p><b>Note</b> A server with Primary status cannot be deactivated.</p>
Secondary	<ul style="list-style-type: none"> <li>• Receives replicated data from the server with Primary status. Data includes the database and message store.</li> <li>• Replicates data to the server with Primary status.</li> <li>• Displays and accepts changes to the administrative interfaces (such as Connection Administration). The data is replicated to the server with Primary status.</li> <li>• Answers phone calls and takes messages.</li> <li>• Connects with clients such as email applications and the web tools available through the Cisco PCA.</li> </ul> <p><b>Note</b> Only a server with Secondary status can be deactivated.</p>

**Table 3-1** *Server Status Functions in the Cisco Unity Connection Cluster (continued)*

Server Status	Functions in Connection Cluster
Deactivated	<ul style="list-style-type: none"> <li>Receives replicated data from the server with Primary status. Data includes the database and message store.</li> <li>Displays and accepts changes to the administrative interfaces (such as Connection Administration). The data is replicated to the server with Primary status.</li> <li>Does not answer phone calls or take messages.</li> <li>Does not connect with clients such as email applications and the web tools available through the Cisco PCA.</li> </ul>
Not Functioning	<ul style="list-style-type: none"> <li>Does not receive replicated data from the server with Primary status.</li> <li>Does not replicate data to the server with Primary status.</li> <li>Does not display the administrative interfaces (such as Connection Administration).</li> <li>Does not answer phone calls or take messages.</li> </ul> <p><b>Note</b> A server with Not Functioning status usually is shut down.</p>
Starting	<ul style="list-style-type: none"> <li>Receives replicated data from the server with Primary status. Data includes the database and message store.</li> <li>Replicates data to the server with Primary status.</li> <li>Does not answer phone calls or take messages.</li> </ul> <p><b>Note</b> This status lasts only a few minutes, after which the server takes the applicable status.</p>
Replicating Data	<ul style="list-style-type: none"> <li>Sends and receives data from the cluster.</li> <li>Temporarily does not answer phone calls or take messages.</li> <li>Temporarily does not connect with clients such as email applications and the web tools available through the Cisco PCA.</li> </ul> <p><b>Note</b> This status lasts only a few minutes, after which the previous status resumes for the server.</p>
Split Brain Recovery	<ul style="list-style-type: none"> <li><i>After detecting two servers with Primary status:</i> Assigns Primary status to the publisher server.</li> <li>Updates the database and message store on the server that is determined to have Primary status.</li> <li>Replicates data to the other server.</li> <li>Temporarily does not answer phone calls or take messages.</li> <li>Temporarily does not connect with clients such as email applications and the web tools available through the Cisco PCA.</li> </ul> <p><b>Note</b> This status lasts only a few minutes, after which the previous status resumes for the server.</p>

## Server Assignments and Usage of Voice Messaging Ports

### Revised May 2009

In a Cisco Unity Connection cluster, the servers share the same phone system integrations. Each server is responsible for handling a share of the incoming calls for the cluster (answering phone calls and taking messages).

Depending on the phone system integration, each voice messaging port is either assigned to a specific server or used by both servers. [Table 3-2](#) describes the port assignments.

**Table 3-2** *Server Assignments and Usage of Voice Messaging Ports in the Cisco Unity Connection Cluster*

Integration Type	Server Assignments and Usage of Voice Messaging Ports
Integration by Skinny Client Control Protocol (SCCP) with Cisco Unified Communications Manager or Cisco Unified Communications Manager Express	<ul style="list-style-type: none"> <li>• The phone system is set up with twice the number of SCCP voice mail port devices that are needed to handle the voice messaging traffic. (For example, if 16 voice mail port devices are needed to handle all voice messaging traffic, 32 voice mail port devices must be set up on the phone system.)</li> <li>• In Cisco Unity Connection Administration, the voice messaging ports are configured so that half the number of the ports set up on the phone system are assigned to each server in the cluster. (For example, each server in the cluster has 16 voice messaging ports.)</li> <li>• On the phone system, a line group, hunt list, and hunt group are configured so that the subscriber server will answer most incoming calls for the cluster.</li> <li>• If one of the servers stops functioning (for example, when it is shut down for maintenance), the remaining server assumes responsibility for handling all incoming calls for the cluster.</li> <li>• When the server that stopped functioning is able to resume its normal functions and is activated, it resumes responsibility for handling its share of incoming calls for the cluster.</li> </ul>
Integration through a SIP Trunk with Cisco Unified Communications Manager or Cisco Unified Communications Manager Express	<ul style="list-style-type: none"> <li>• In Cisco Unity Connection Administration, half the number of voice messaging ports that are needed to handle voice messaging traffic are assigned to each server in the cluster. (For example, if 16 voice messaging ports are needed to handle all voice messaging traffic for the cluster, each server in the cluster is assigned 8 voice messaging ports.)</li> <li>• On the phone system, a route group, route list, and route pattern are configured to distribute calls equally to both servers in the cluster.</li> <li>• If one of the servers stops functioning (for example, when it is shut down for maintenance), the remaining server assumes responsibility for handling all incoming calls for the cluster.</li> <li>• When the server that stopped functioning is able to resume its normal functions and is activated, it resumes responsibility for handling its share of incoming calls for the cluster.</li> </ul>

**Table 3-2** *Server Assignments and Usage of Voice Messaging Ports in the Cisco Unity Connection Cluster*

Integration Type	Server Assignments and Usage of Voice Messaging Ports
Integration through PIMG/TIMG units	<ul style="list-style-type: none"> <li>• The number of ports set up on the phone system is the same as the number of voice messaging ports on each server in the cluster so that the servers share all the voice messaging ports. (For example, if the phone system is set up with 16 voice messaging ports, each server in the cluster must have the same 16 voice messaging ports.)</li> <li>• On the phone system, a hunt group is configured to distribute calls equally to both servers in the cluster.</li> <li>• The PIMG/TIMG units are configured to balance the voice messaging traffic between the servers.</li> <li>• If one of the servers stops functioning (for example, when it is shut down for maintenance), the remaining server assumes responsibility for handling all incoming calls for the cluster.</li> <li>• When the server that stopped functioning is able to resume its normal functions and is activated, it resumes responsibility for handling its share of incoming calls for the cluster.</li> </ul>
Other integrations that use SIP	<ul style="list-style-type: none"> <li>• In Cisco Unity Connection Administration, half the number of voice messaging ports that are needed to handle voice messaging traffic are assigned to each server in the cluster. (For example, if 16 voice messaging ports are needed to handle all voice messaging traffic for the cluster, each server in the cluster has 8 voice messaging ports.)</li> <li>• On the phone system, a hunt group is configured to distribute calls equally to both servers in the cluster.</li> <li>• If one of the servers stops functioning (for example, when it is shut down for maintenance), the remaining server assumes responsibility for handling all incoming calls for the cluster.</li> <li>• When the server that stopped functioning is able to resume its normal functions, it resumes responsibility for handling its share of incoming calls for the cluster.</li> </ul>

## Requirements for a Cisco Unity Connection Cluster

For current Cisco Unity Connection cluster requirements, refer to *System Requirements for Cisco Unity Connection Release 7.x* at

[http://www.cisco.com/en/US/docs/voice\\_ip\\_comm/connection/7x/requirements/7xcucsysreqs.html](http://www.cisco.com/en/US/docs/voice_ip_comm/connection/7x/requirements/7xcucsysreqs.html).

## Effects on Calls in Progress When Server Status Changes

When the status of a Cisco Unity Connection server changes, the effects on calls in progress depend on the final status of the server that is handling a call and on the condition of the network. [Table 3-3](#) describes the effects.

**Table 3-3** *Effects on Calls in Progress When Server Status Changes*

Status Change	Effects
Primary to Secondary	When the status change is initiated manually, calls in progress are not affected.  When the status change is automatic, effects on calls in progress depend on the critical service that stopped.
Secondary to Primary	When the status change is initiated manually, calls in progress are not affected.  When the status change is automatic, effects on calls in progress depend on the critical service that stopped.
Secondary to Deactivated	Calls in progress are dropped.  To prevent dropped calls, on the Cluster Management page in Cisco Unity Connection Serviceability, click Stop Taking Calls for the server, wait until all calls have ended, and deactivate the server.
Primary or Secondary to Replicating Data	Calls in progress are not affected.
Primary or Secondary to Split Brain Recovery	Calls in progress are not affected.

If network connections are lost, then calls in progress may be dropped, depending on the nature of the network problem.

## Effects on Cisco Unity Connection Web Applications When Server Status Changes

Normal functioning of the following web applications are not affected when the server status changes:

- Cisco Unity Connection Administration
- Cisco Unity Connection Serviceability
- Cisco Unity Connection web tools accessed through the Cisco PCA (the Cisco Unity Assistant, the Cisco Unity Inbox, and the Cisco Unity Personal Call Transfer Rules web tools)

## Effects of Stopping a Critical Service on a Server

**Revised May 2009**

Critical services are necessary for the normal functioning of the Cisco Unity Connection system. The effects of stopping a critical service depend on the server and its status. [Table 3-4](#) describes the effects.

**Table 3-4** *Effects of Stopping a Critical Service on a Server*

Server	Effects
Publisher	<ul style="list-style-type: none"> <li>When the server has Primary status, stopping a critical service in Cisco Unity Connection Serviceability causes the server status to change to Secondary and degrades the ability of the server to function normally. The status of the subscriber server changes to Primary if it does not have the Disabled or Not Functioning status.</li> <li>When the server has Secondary status, stopping a critical service in Cisco Unity Connection Serviceability degrades the ability of the server to function normally. The status of the servers does not change.</li> </ul>
Subscriber	When the server has Primary status, stopping a critical service in Cisco Unity Connection Serviceability degrades the ability of the server to function normally. The status of the servers does not change.

## Effects of a Split-Brain Condition

### Revised May 2009

When the servers in a Cisco Unity Connection cluster have Primary status at the same time (for example, when the servers have lost their connection with each other), both servers handle incoming calls (answer phone calls and take messages), send message notifications, send MWI requests, and accept changes to the administrative interfaces (such as Connection Administration). However, the servers do not replicate the database and message store to each other and do not receive replicated data from each other.

When the connection between the servers is restored, the status of the servers temporarily changes to Split Brain Recovery while the data is replicated between the servers and MWI settings are coordinated. When the recovery process is complete, the publisher server has Primary status and the other server has Secondary status.

## Events When Server Status Changes

This section describes the events that take place when server status changes in the following situations:

- [Automatic Change of Server Status Initiated by Server with Primary Status, page 3-8](#)
- [Automatic Change of Server Status Initiated by Server with Secondary Status, page 3-9](#)
- [Manual Change of Server Status Initiated by Administrator, page 3-9](#)

## Automatic Change of Server Status Initiated by Server with Primary Status

### Revised May 2009

1. The Connection Server Role Manager service on the server with Primary status detects an unrecoverable failure (for example, the database fails or a critical service is stopped).
2. The Connection Server Role Manager service on the server with Primary status notifies the Connection Server Role Manager service on the other server to change its status.
3. The Connection Server Role Manager service on both servers posts alarms that it is initiating a change of status.

4. The Connection Server Role Manager service on the server with Primary status sets its status in the database to Secondary.
5. The Connection Server Role Manager service on the other server (the server that originally had Secondary status) sets its status in the database to Primary.
6. The Connection Server Role Manager service on the server that now has Primary status starts the critical services on that server.
7. The data connector detects the changed server status and sets the connections to use the database on the server that now has Primary status.
8. If possible, database and message store replication continues between the servers.
9. The Connection Server Role Manager service on the server that now has Primary status posts an alarm that the change of status is complete.

## Automatic Change of Server Status Initiated by Server with Secondary Status

1. The Connection Server Role Manager service on the server with Secondary status does not receive contact from the Connection Server Role Manager service on the server with Primary status.
2. The Connection Server Role Manager service on the server with Secondary status confirms its network connection by pinging the local host and other known remote servers.
3. If the network connection is confirmed, the Connection Server Role Manager service on the server with Secondary status posts an alarm that it is initiating a change of status.  
  
If the network connection is not available, the status does not change and the remaining events do not occur.
4. The Connection Server Role Manager service on the server with Secondary status sets its status in the database to Primary.
5. The Connection Server Role Manager service on the server that now has Primary status starts the critical services on that server.
6. The data connector detects the changed status and sets the connections to use the database on the server that now has Primary status.
7. If possible, database and message store replication continues between the servers.
8. The Connection Server Role Manager service on the server that now has Primary status posts an alarm that the change of status is complete.

## Manual Change of Server Status Initiated by Administrator

### Revised May 2009

1. In Cisco Unity Connection Serviceability, the administrator manually initiates a change of server status.
2. The Connection Server Role Manager service on the server with Secondary status notifies the Connection Server Role Manager service on the server with Primary status to initiate change of status.
3. The Connection Server Role Manager service on the both servers posts alarms that the change of status is being initiated.
4. The Connection Server Role Manager service on the server with Primary status sets its status in the database to Secondary.

5. The Connection Server Role Manager service on the other server (the server that originally had Secondary status) sets its status in the database to Primary.
6. The Connection Server Role Manager service on the server that now has Primary status starts the critical services on that server.
7. The data connector detects the changed status and sets the connections to use the database on the server that now has Primary status.
8. Database and file replication continues between the servers.
9. The Connection Server Role Manager service on the server that now has Primary status posts an alarm that the change of status is complete.



## INDEX

---

### A

- activating server with Deactivated status [2-1](#)
- alerts, setting up notification of server status changes [1-2](#)
- automatic status changes
  - by server with Primary, events [3-8](#)
  - by server with Secondary, events [3-9](#)

---

### C

- calls in progress, effects of changing server status [3-7](#)
- changing
  - cluster settings [1-3](#)
  - server status, manually [2-1](#)
  - server with Secondary status to Deactivated [2-1](#)
  - server with Secondary status to Primary [2-1](#)
- cluster, how it works [3-1](#)
- Cluster Configuration page, changing settings [1-3](#)
- configuring
  - task list [1-1](#)
  - the cluster [1-1](#)
- Connection Server Role Manager service, about [3-2](#)
- critical service, effects of stopping [3-7](#)
- customizing cluster settings [1-3](#)

---

### D

- database replication [3-1](#)

---

### E

- effects
  - of a split-brain condition [3-8](#)
  - of stopping a critical service [3-7](#)
  - on calls in progress when server status changes [3-7](#)
  - on web applications when server status changes [3-7](#)
- events when server status changes [3-8](#)

---

### M

- manual status changes, events [3-9](#)
- message store replication [3-1](#)
- monitoring server status [3-2](#)

---

### N

- notification of server status change alerts, setting up [1-2](#)

---

### P

- ports
  - assignments of voice messaging to each server [3-4](#)
  - restarting to take calls [2-3](#)
  - stopping from taking new calls [2-3](#)
- publisher server, about [3-2](#)

---

### R

- replication
  - of database and message store [3-1](#)
  - of voice messages [3-1](#)
- requirements for a cluster [3-6](#)

restarting all ports to take calls [2-3](#)

## S

### servers

- assignments of voice messaging ports [3-4](#)
- cluster requirements [3-6](#)
- configuring the cluster [1-1](#)
- effects on calls in progress when status changes [3-7](#)
- events when status changes [3-8](#)
- manually changing status [2-1](#)
- order for starting [2-1](#)
- publisher, about [3-2](#)
- shutting down [2-3](#)
- status functions in cluster [3-3](#)
- status monitoring [3-2](#)

server status changes, setting up notification of [1-2](#)

settings, customizing cluster [1-3](#)

setting up notification of server status change alerts [1-2](#)

shutting down servers [2-3](#)

split-brain condition, effects of [3-8](#)

starting servers, order [2-1](#)

### status

- automatic change by server with Primary, events [3-8](#)
- automatic change by server with Secondary, events [3-9](#)
- Deactivated, activating manually [2-1](#)
- events when server changes [3-8](#)
- manual change, events [3-9](#)
- of servers [3-2](#)
- Secondary to Deactivated, changing manually [2-1](#)
- Secondary to Primary, changing manually [2-1](#)
- server, functions in cluster [3-3](#)

stopping a critical service, effects of [3-7](#)

stopping all ports from taking new calls [2-3](#)

## V

voice message replication [3-1](#)

voice messaging ports, assignments to each server [3-4](#)

## W

web applications, effects on when server status changes [3-7](#)

## T

task list for configuring cluster [1-1](#)