



# CHAPTER 4

## Settings

---

Use the Settings options to display and change IP settings, host settings, and Network Time Protocol (NTP) settings.

This chapter contains the following sections:

- [IP Settings, page 4-1](#)
- [NTP Servers, page 4-1](#)
- [SMTP Settings, page 4-2](#)
- [Time Settings, page 4-2](#)

## IP Settings

**Revised July 8, 2009**

For information on changing the IP address of a Cisco Unity Connection server, see the “[Changing the IP Addresses of Cisco Unity Connection 7.x Servers](#)” chapter of the *Reconfiguration and Upgrade Guide for Cisco Unity Connection Release 7.x* at

[http://www.cisco.com/en/US/docs/voice\\_ip\\_comm/connection/7x/upgrade/guide/7xcucrug050.html](http://www.cisco.com/en/US/docs/voice_ip_comm/connection/7x/upgrade/guide/7xcucrug050.html).

## NTP Servers

Ensure that external NTP server is stratum 9 or higher (1-9). To add, delete, or modify an external NTP server, follow this procedure:



### Note

You can only configure the NTP server settings on the first node or publisher.

### Procedure

- 
- Step 1** From the Cisco Unified Communications Operating System Administration window, navigate to **Settings>NTP Servers**.
- The NTP Server Settings window displays.
- Step 2** You can add, delete, or modify an NTP server:
- To delete an NTP server, check the check box in front of the appropriate server and click **Delete**.

- To add an NTP server, click **Add**, enter the hostname or IP address, and then click **Save**.
- To modify an NTP server, click the IP address, modify the hostname or IP address, and then click **Save**.

**Note**

Any change that you make to the NTP servers can take up to 5 minutes to complete. Whenever you make any change to the NTP servers, you must refresh the window to display the correct status.

**Step 3** To refresh the NTP Server Settings window and display the correct status, choose **Settings>NTP**.

**Note**

After deleting, modifying, or adding the NTP server, you must restart all other nodes in the cluster for the changes to take affect.

## SMTP Settings

The SMTP Settings window allows you to view or set the SMTP hostname and indicates whether the SMTP host is active.

**Tip**

If you want the system to send you e-mail, you must configure an SMTP host.

To access the SMTP settings, follow this procedure:

**Procedure**

**Step 1** From the Cisco Unified Communications Operating System Administration window, navigate to **Settings>SMTP**.

The SMTP Settings window displays.

**Step 2** Enter or modify the SMTP hostname or IP address.

**Step 3** Click **Save**.

## Time Settings

To manually configure the time, follow this procedure:

**Note**

Before you can manually configure the server time, you must delete any NTP servers that you have configured. See [NTP Servers](#) for more information.

### Procedure

- 
- Step 1** From the Cisco Unified Communications Operating System Administration window, navigate to **Settings > Time**.
- Step 2** Enter the date and time for the system.
- Step 3** Click **Save**.
- Step 4** On a Cisco Unity Connection server, if you changed the date or if you changed the time by more than two minutes, use the CLI command **utils system restart** to restart the server.
-

