



## CHAPTER 2

# Using Alarms in Version 8.x

---

This chapter provides information on using alarms in Cisco Unity Connection Serviceability and contains the following sections:

- [Understanding Alarms in Version 8.x, page 2-1](#)
- [Alarm Definitions in Version 8.x, page 2-1](#)
- [Viewing Alarm Definitions in Version 8.x, page 2-2](#)
- [Alarm Configurations in Version 8.x, page 2-2](#)

## Understanding Alarms in Version 8.x

Cisco Unity Connection Serviceability alarms provide information on runtime status and the state of the system, so you can troubleshoot problems that are associated with the system. For example, you can use alarms to determine whether there are any ports enabled to set MWIs. Alarm information includes the catalog, name, severity, explanation, recommended action, routing list, and parameters.

You can enable or disable alarms to appear as syslog messages on the local server or on a remote server that you specify. You can also set the severity level that you want to appear.

You use the trace and log central option in the Real-Time Monitoring Tool (RTMT) to collect alarms. You use the SysLog Viewer in RTMT to view alarms.

## Alarm Definitions in Version 8.x

Alarm definitions describe alarm messages—what they mean and how to recover from them.

You search the Alarm Message Definitions page for alarm information. When you select an alarm, a description of the alarm information and a recommended action appears on the Alarm Information page. To help with troubleshooting, the definitions include the alarm name, description, severity, explanation, recommended action, routing list, and parameters.

## Viewing Alarm Definitions in Version 8.x

You can search for and view alarm definitions in *Alarm Message Definitions for Cisco Unity Connection Release 8.0* at

[http://www.cisco.com/en/US/docs/voice\\_ip\\_comm/connection/8x/alarm\\_messages/80cucalarmmsgdefs.html](http://www.cisco.com/en/US/docs/voice_ip_comm/connection/8x/alarm_messages/80cucalarmmsgdefs.html).

## Alarm Configurations in Version 8.x

This section describes how to enable and disable alarms. Do the applicable procedure.

### To Enable Alarms in Version 8.x

- 
- Step 1** In Cisco Unity Connection Serviceability, select **Alarm > Configurations**.
- Step 2** In the Alarm Configurations window, do the applicable action:
- To enable the system to log the alarms in the application logs area in the SysLog Viewer, under Local Syslogs, check the **Enable Alarm** check box.
  - To enable the system to store the alarms on a remote syslog server, under Remote Syslogs, check the **Enable Alarm** check box and, in the Server Name field, enter the IP address or host name of the remote syslog server.
- Step 3** Under the syslog for which you have enabled alarms, in the Alarm Event Level field, select the severity level that you want.
- Step 4** Select **Save**.
- 

### To Disable Alarms in Version 8.x

- 
- Step 1** In Cisco Unity Connection Serviceability, select **Alarm > Configurations**.
- Step 2** In the Alarm Configurations window, uncheck the applicable **Enable Alarm** check box.
- Step 3** Select **Save**.
-