



Last Updated: April 16, 2010

ip domain-name

ip name-server

ip domain-name

To specify the local messaging gateway's domain name, use the **ip domain-name** command in Cisco Unified Messaging Gateway (Cisco UMG) configuration mode. To clear the configuration, use the **no** form of this command.

ip domain-name *company.com*

no ip domain-name *company.com*

Syntax Description	<i>company.com</i>	Domain name for local Cisco UMG.
---------------------------	--------------------	----------------------------------

Command Default	None
------------------------	------

Command Modes	Cisco UMG configuration (config)
----------------------	----------------------------------

Command History	Cisco UMG Version	Modification
	1.0	This command was introduced.

Examples The following example illustrates the use of the **ip domain-name** command:

```
umg-1# config t
umg-1(config)# ip domain-name mycompany.com
umg-1(config)# ip name-server dns1.mycompany.com
umg-1(config)# end
umg-1# show hosts
Hostname:      umg-1
Domain:       mycompany.com
[...]
umg-1#
```

Related Commands	Command	Description
	show hosts	Displays details for the current configuring messaging gateway.

ip name-server

To specify the local messaging gateway's domain name server, use the **ip name-server** command in Cisco Unified Messaging Gateway (Cisco UMG) configuration mode. To clear the configuration, use the **no** form of this command.

ip name-server *a.b.c.d*

no ip name-server *a.b.c.d*

Syntax Description	<i>a.b.c.d</i>	Domain name server for local Cisco UMG.
---------------------------	----------------	---

Command Default	None
------------------------	------

Command Modes	Cisco UMG configuration (config)
----------------------	----------------------------------

Command History	Cisco UMG Version	Modification
	1.0	This command was introduced.

Usage Guidelines	A domain name server is optional unless you have Avaya Interchange, in which case it is mandatory for failover support.
	Cisco UMG supports up to 4 domain name servers.

Examples	The following example illustrates the use of the ip name-server command:
-----------------	---

```
umg-1# config t
umg-1(config)# ip domain-name mycompany.com
umg-1(config)# ip name-server dns1.mycompany.com
umg-1(config)# end
umg-1# show hosts
Hostname:      umg-1
Domain:       mycompany.com
[...]
umg-1#
```

Related Commands	Command	Description
	show hosts	Displays details for the current configuring messaging gateway.
	show messaging-gateway	Displays all Cisco UMGs including the peer messaging gateways and the current configuring messaging gateway.

