



Last Updated: November 17, 2010

ip domain-name

ip name-server

ip domain-name

To specify the local messaging gateway's domain name, use the **ip domain-name** command in Cisco UMG configuration mode. To clear the configuration, use the **no** form of this command.

ip domain-name *dns-server-domain-name*

no ip domain-name *company.com*

Syntax Description

dns-server-domain-name Domain name for local Cisco UMG.

Command Modes

Cisco UMG configuration (config)

Command History

Cisco UMG Version

Modification

1.0

This command was introduced.

Examples

The following example illustrates the use of the **ip domain-name** command:

```
umg-1# config t
umg-1(config)# ip domain-name mycompany.com
umg-1(config)# ip name-server dns1.mycompany.com
umg-1(config)# end
umg-1# show hosts
Hostname:      umg-1
Domain:       mycompany.com
[...]
umg-1#
```

Related Commands

Command

Description

[show hosts](#)

Displays details for the current configuring messaging gateway.

ip name-server

To specify the local messaging gateway's domain name server, use the **ip name-server** command in Cisco UMG configuration mode. To clear the configuration, use the **no** form of this command.

ip name-server *a.b.c.d*

no ip name-server *a.b.c.d*

Syntax Description	<i>a.b.c.d</i>	Domain name server for local Cisco UMG.
---------------------------	----------------	---

Command Modes	Cisco UMG configuration (config)
----------------------	----------------------------------

Command History	Cisco UMG Version	Modification
	1.0	This command was introduced.

Usage Guidelines	A domain name server is optional unless you have Avaya Interchange, in which case it is mandatory for failover support.
	Cisco UMG supports up to four domain name servers.

Examples	The following example illustrates the use of the ip name-server command:
-----------------	---

```
umg-1# config t
umg-1(config)# ip domain-name mycompany.com
umg-1(config)# ip name-server dns1.mycompany.com
umg-1(config)# end
umg-1# show hosts
Hostname:      umg-1
Domain:       mycompany.com
[...]
umg-1#
```

Related Commands	Command	Description
	show hosts	Displays details for the current configuring messaging gateway.
	show messaging-gateway	Displays all Cisco UMGs including the peer messaging gateways and the current configuring messaging gateway.

