



Configuring Domain Name Settings

Perform the following tasks from the Domain Name Settings page:

- Specify the domain and hostname in which Cisco Unified SRSV is located. See [Changing a DNS](#).
- Add DNS servers. See [Adding a DNS Server](#).
- Delete DNS servers. See [Removing a DNS Server](#).

Changing a DNS

Use this procedure to change the DNS servers if their names or IP addresses have changed since running the Setup Wizard.

Before You Begin

Gather the following information:

- The hostname of Cisco Unified SRSV system.
- The domain name and IP address of the DNS server.

Procedure

- Step 1** Log in to the [Cisco UMG GUI](#). See the [Logging In to the Cisco UMG Graphical User Interface \(GUI\)](#) module.
- Step 2** Choose **System > Domain Name Settings**.
The system displays the Domain Name Settings page.
- Step 3** Enter the hostname of the server that stores the Cisco Unified SRSV system application files.
- Step 4** Enter the domain name of the server.
- Step 5** Click **Apply**.
-

What To Do Next

Save and then reload the configuration. See the [Saving the Cisco Unified Messaging Gateway Configuration](#) and [Reloading the Cisco Unified Messaging Gateway Configuration](#) sections.

Adding a DNS Server

Enter additional DNS servers as alternate server destinations, to be used if the system cannot access the primary domain name server.

Procedure

- Step 1** Log in to the [Cisco UMG GUI](#). See the [Logging In to the Cisco UMG Graphical User Interface \(GUI\) module](#).
 - Step 2** Choose **System > Domain Name Settings**.
The system displays the Domain Name Settings page.
 - Step 3** Click **Add**.
The system displays the Add a DNS server page.
 - Step 4** Enter the IP address of the DNS server.
 - Step 5** Click **Add**.
-

What To Do Next

Save and then reload the configuration. See the [Saving the Cisco Unified Messaging Gateway Configuration](#) and [Reloading the Cisco Unified Messaging Gateway Configuration](#) sections.

Removing a DNS Server

Procedure

- Step 1** Log in to the [Cisco UMG GUI](#). See the [Logging In to the Cisco UMG Graphical User Interface \(GUI\) module](#).
 - Step 2** Choose **System > Domain Name Settings**.
The system displays the Domain Name Settings page.
 - Step 3** Check the checkbox next to the DNS server that you want to delete.
 - Step 4** Click **Delete**.
 - Step 5** At the prompt, click **OK**.
-

What To Do Next

Save and then reload the configuration. See the [Saving the Cisco Unified Messaging Gateway Configuration](#) and [Reloading the Cisco Unified Messaging Gateway Configuration](#) sections.